

# Innovatrics ANSI/ISO Generator & Matcher

### **Table of Contents**

Overview	1
Fingerprint Image Data	2
Matching Scores	3
Library Functions	4
Init, Terminate and other General Functions	4
IEngine_Init Function	4
IEngine_Terminate Function	4
IEngine_GetVersion Function	5
IEngine_GetErrorMessage Function	5
IEngine_GetImageQuality Function	5
IEngine_SetLicenseContent Function	6
Conversion Functions	6
ANSI_ConvertToISO Function	7
ANSI_RemoveMinutiae Function	7
IEngine_ConvertBMP Function	3
IEngine_ConvertTemplate Function	Ş
IEngine_ConvertIso19794_4ToRaw Function	9
IEngine_ConvertRawToIso19794_4 Function	10
IEngine_LoadBMP Function	11
IEngine_MakeBMP Function	12
ISO_CARD_CC_ConvertToISO Function	13
ISO_CARD_CC_GetMinutiaeData Function	13
ISO_ConvertToANSI Function	14
ISO_ConvertToISOCardCC Function	15
ISO_RemoveMinutiae Function	15
Template Extraction and Matching Functions	16
ANSI_CreateTemplate Function	16
ANSI_CreateTemplateEx Function	17
ANSI_VerifyMatch Function	18
ANSI_VerifyMatchEx Function	19
ISO_CreateTemplate Function	20
ISO_CreateTemplateEx Function	21
ISO_VerifyMatch Function	22
ISO_VerifyMatchEx Function	22

remplate manipulation Functions	23
ANSI_DrawMinutiae Function	24
ANSI_GetFingerView Function	24
ANSI_GetMinutiae Function	25
ANSI_GetTemplateParameter Function	26
ANSI_MergeTemplates Function	26
ANSI_LoadTemplate Function	27
ANSI_SaveTemplate Function	27
ANSI_SetTemplateParameter Function	28
ISO_DrawMinutiae Function	29
ISO_GetFingerView Function	29
ISO_GetMinutiae Function	30
ISO_GetTemplateParameter Function	30
ISO_LoadTemplate Function	31
ISO_MergeTemplates Function	32
ISO_SaveTemplate Function	32
ISO_SetTemplateParameter Function	33
Types, Structures, Enumerations	34
IENGINE_TEMPLATE_PARAMETER Enumeration	34
IENGINE_TEMPLATE_FORMAT Enumeration	35
IENGINE_FINGER_POSITION Enumeration	35
IENGINE_IMPRESSION_TYPE Enumeration	35
IENGINE_VERSION Structure	36
IENGINE_MINUTIAE Structure	36
IENGINE_SORT_ORDER Enumeration	37
Constants	38
IENGINE_MIN_IMAGE_HEIGHT Macro	38
IENGINE_MAX_IMAGE_HEIGHT Macro	38
IENGINE_MIN_IMAGE_WIDTH Macro	38
IENGINE_MAX_IMAGE_WIDTH Macro	38
IENGINE_MAX_ANSI_TEMPLATE_SIZE Macro	39
IENGINE_MAX_ISO_TEMPLATE_SIZE Macro	39
Error Codes	40

Index a

### 1 Overview

The Innovatrics ANSI/ISO Generator & Matcher is a standard windows dll library designed to

- generate ANSI/INCITS 378 and ISO/IEC 19794-2 compliant templates
- match ANSI/INCITS 378 and ISO/IEC 19794-2 compliant templates

Innovatrics ANSI/ISO Generator takes as input raw fingerprint images and transforms them to ANSI/ISO compliant templates. Innovatrics ANSI/ISO Matcher takes as input two ANSI/ISO compliant templates and returns corresponding similarity score.

The API of the library is based on MINEX API specifications designed by NIST.

All functions from this library are thread-safe.

### 2

### 2 Fingerprint Image Data

The Generator takes as input fingerprint supplied to the SDK in uncompressed raw 8-bit (one byte per pixel) grayscale format. The recorded order of the scan image is illustrated in figure 1. The origin is the upper left corner of the image. The x-coordinate (horizontal) position shall increase positively from the origin to the right side of the image. The y-coordinate (vertical) position shall increase positively from the origin to the bottom of the image.




Figure 1 - Order of scanned images

Raw 8-bit grayscale images are canonically encoded. The minimum value that will be assigned to a "black" pixel is zero. The maximum value that will be assigned to a "white" pixel is 255. Intermediate gray levels will have assigned values of 1- 254. The pixels are stored left to right, top to bottom, with one 8-bit byte per pixel. The number of bytes in an image is equal to its height multiplied by its width as measured in pixels; there is no header. The image height and width in pixels will be supplied to the SDK as supplemental information.

The resolution of images supplied to the Generator should be 500 DPI. The dimensions of the fingerprint images may vary from 150 to 1000 pixels in width, and 166 to 1000 pixels in height.

The Generator contains functions for converting from standard uncompressed BMP image format to the raw format described above.

### 3

### 3 Matching Scores

Similarity scores returned by matching functions (ANSI\_VerifyMatch ( see page 18), ANSI\_VerifyMatchEx ( see page 19), ISO\_VerifyMatch ( see page 22), ISO\_VerifyMatchEx ( see page 22)) are integer values ranging from 0 to 100000. Higher score means higher similarity of compared templates, lower score means lower similarity. When deciding whether two fingerprint templates are from the same finger (matching fingers), one has to compare matching score to a similarity threshold. Threshold defines False Accept Rate (FAR) and False Reject Rate (FRR) of the application. Higher threshold means higher FRR and lower FAR, lower threshold means lower FRR but higher FAR. Recommended setting for a standard biometric application is a similarity threshold corresponding to False Accept Rate from 1:1000 to 1:10000. The table below shows different thresholds and observed FAR and FRR rates. This table was generated using a sample database of 500 DPI images from optical sensors.

Threshold	False Accept Rate (FAR)	False Reject Rate (FRR)
9500	1% (1:100)	0.09%
11600	0.1% (1:1.000)	0.25%
13700	0.01% (1:10.000)	0.55%
15650	0.001% (1:100.000)	0.9%
17750	0.0001% (1:10^6)	1.45%

### **4 Library Functions**

### 4.1 Init, Terminate and other General Functions

### **Functions**

	Name	Description
<b>≡♦</b>	IEngine_Init ( <b>万</b> see page 4)	Initializes the library
<b>≡∳</b>	IEngine_Terminate (᠌ see page 4)	Terminates the use of the library
<b>≡∳</b>	IEngine_GetVersion (	Returns the library version
<b>≡♦</b>	IEngine_GetErrorMessage (☐ see page 5)	Returns human understandable error message
<b>≡∳</b>	IEngine_GetImageQuality (☑ see page 5)	Returns quality of a fingerprint image
<b>≡♦</b>	IEngine_SetLicenseContent (☐ see page 6)	Activates the library with a license key

### 4.1.1 IEngine\_Init Function

Initializes the library

#### C++

IENGINE\_API int IEngine\_Init();

### Description

This function initializes and checks the integrity of the library and verifies the validity of the license. It should be called prior to any other function from the library.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occurred.
IENGINE_E_BADLICENSE	Provided license is not valid, or no license was found.

### **Related Topics**

IEngine\_Terminate (☐ see page 4), IEngine\_GetVersion (☐ see page 5)

### 4.1.2 IEngine\_Terminate Function

Terminates the use of the library

### C++

IENGINE\_API int IEngine\_Terminate();

### Description

This function releases all resources allocated by the library. It should be called as the very last function of the library.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occurred.

### **Related Topics**

IEngine\_Init ( see page 4)

### 4.1.3 IEngine\_GetVersion Function

Returns the library version

#### C++

```
IENGINE_API int IEngine_GetVersion(IENGINE_VERSION * version);
```

### Description

This function returns the version number of the library

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### Version

[out] Pointer to the structure where the library version will be stored

### 4.1.4 IEngine\_GetErrorMessage Function

Returns human understandable error message

### C++

```
IENGINE_API char * IEngine_GetErrorMessage(int errcode);
```

### Description

This function returns error message string corresponding to the specified error code.

### **Parameters**

int erroode

[in] Error code to be translated into error message

### Related Topics

Error Codes (2 see page 40)

### 4.1.5 IEngine\_GetImageQuality Function

Returns quality of a fingerprint image

### C++

```
IENGINE_API int IEngine_GetImageQuality(int width, int height, const BYTE * rawImage, int *
quality);
```

### **Description**

This function returns quality of the input fingerprint image. Image quality number is calculated in accordance with the general guidelines contained in Section 2.1.42 of ANSI/INCITS 358 standard.

### **Parameters**

```
int width
```

[in] The number of pixels indicating the width of the image

int height

[in] The number of pixels indicating the height of the image

const BYTE \* rawImage

[in] Pointer to the uncompressed raw image for template creation

int \* quality

[out] Fingerprint image quality, the output range is from 0 (lowest quality) to 100 (highest quality)

### 4.1.6 IEngine\_SetLicenseContent Function

Activates the library with a license key

### C++

IENGINE\_API int IEngine\_SetLicenseContent(const unsigned char \* licenseContent, int length);

### Description

Use this function if you want to avoid storing license files on filesystem. This prevents a potential hacker to steal your license file information.

#### **Parameters**

```
const unsigned char * licenseContent
[in] License information as provided by Innovatrics
int length
[in] Total length of license data
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADLICENSE	Invalid license data

### 4.2 Conversion Functions

### **Functions**

	Name	Description
<b>∉</b> ∳	ANSI_ConvertToISO ( see page 7)	Converts ANSI/INCITS 378 compliant template to ISO/IEC 19794-2 compliant template
<b>=♦</b>	ANSI_RemoveMinutiae (☐ see page 7)	Removes minutiae points from an ANSI template
<b>≡</b>	IEngine_ConvertBMP (  see page 8)	Reads bmp image from memory and converts it to raw 8-bit format
<b>≡</b>	IEngine_ConvertTemplate (☑ see page 9)	Converts between different template formats.
<b>=</b> ♦	IEngine_ConvertIso19794_4ToRaw (☐ see page 9)	Converts ISO 19794-4 format into raw image format.
<b>≡</b>	IEngine_ConvertRawToIso19794_4 (☐ see page 10)	Converts raw image into ISO 19794-4 format.
<b>≡</b>	IEngine_LoadBMP ( see page 11)	Loads bmp image from file and converts it to raw 8-bit format
<b>≡</b>	IEngine_MakeBMP (☐ see page 12)	Converts raw image into grayscale bmp image
<b>≡</b>	ISO_CARD_CC_ConvertToISO ( see page 13)	Converts an ISO Compact Card template into regular ISO template
<b>≟</b> ∳	ISO_CARD_CC_GetMinutiaeData ( see page 13)	Returns data from ISO Compact Card template corresponding to encoded minutiae block (template without header and footer)
<b>≟</b>	ISO_ConvertToANSI ( see page 14)	Converts ISO/IEC 19794-2 compliant template to ANSI/INCITS 378 compliant template
<b>=♦</b>	ISO_ConvertToISOCardCC ( see page 15)	Converts a regular ISO template to ISO Compact Card template format (ISO Compact Size Finger Minutiae Format)
<b>=♦</b>	ISO_RemoveMinutiae ( see page 15)	Removes minutiae points from an ISO template

### 4.2.1 ANSI\_ConvertToISO Function

Converts ANSI/INCITS 378 compliant template to ISO/IEC 19794-2 compliant template

#### C++

```
IENGINE_API int ANSI_ConvertToISO(const BYTE * ansiTemplate, int * length, BYTE *
isoTemplate);
```

### Description

This function converts an input ANSI/INCITS 378 compliant template to an output ISO/IEC 19794-2 compliant template. Templates with multiple finger views are supported by this function.

#### **Parameters**

```
const BYTE * ansiTemplate
[in] Reference ANSI/INCITS 378 template
int * length
[in/out] On input specifies the length of allocated data space (in bytes) pointed by isoTemplate pointer. On return, specifies the size of converted ISO template.

BYTE * isoTemplate
[out] Pointer to memory space where the resulting ISO/IEC 19794-2 compliant template will be written.
```

#### Returns

If isoTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to isoTemplate. If isoTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and isoTemplate are returned.

#### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	The input templates is not valid ANSI/INCITS 378 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### 4.2.2 ANSI\_RemoveMinutiae Function

Removes minutiae points from an ANSI template

### C++

```
IENGINE_API int ANSI_RemoveMinutiae(const BYTE * inTemplate, int maximumMinutiaeCount, int
* length, BYTE * outTemplate);
```

### Description

This function limits maximal number of minutiae points contained in an ANSI/INCITS 378 compliant fingerprint template. If the input template contains more minutiae points than the provided limit, extra minutae point are removed from the template. The truncation is made by peeling off minutiae that are farthest from the point of gravity of the minutiae set.

### **Parameters**

```
const BYTE * inTemplate
[in] Reference ANSI/INCITS 378 template
int maximumMinutiaeCount
[in] The maximal number of minutiae that will be stored in the output template. If current minutiae count is less or equal to this limit, the output template will be a copy of the input template.
int * length
```

[in/out] On input specifies the length of allocated data space (in bytes) pointed by outTemplate pointer. On return, specifies the size of truncated template

[out] Pointer to memory space where the resulting truncated ANSI/INCITS 378 compliant template will be stored

### Returns

If outTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to outTemplate. If outTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and outTemplate are returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### 4.2.3 IEngine\_ConvertBMP Function

Reads bmp image from memory and converts it to raw 8-bit format

### C++

```
IENGINE_API int IEngine_ConvertBMP(const BYTE * bmpImage, int * width, int * height, BYTE *
rawImage, int * length);
```

### Description

This function reads bmp image encoded in a byte array and converts it to raw 8-bit format as described in paragraph Fingerprint Image Data (2) see page 2)

### **Parameters**

```
const BYTE * bmpImage

[in] Pointer to the image in BMP format stored in the memory
int * width

[out] On return, contains the width of converted image
int * height

[out] On return, contains the height of converted image

BYTE * rawImage

[out] Pointer to memory space where raw image will be written
int * length
```

[in/out] On input, length parameter is interpreted as the total size of allocated memory pointed by rawlmage parameter. On return, this parameter will be equal to the total size of the image after conversion to raw format.

### Returns

If rawImage is NULL or if length parameter is less then the size of the input image after conversion to 8-bit raw format, length parameter will be set to the required length of rawImage array.

If rawImage is not NULL and if length is greater or equal to the total memory size required to store the input image in 8-bit raw format, input bmp image will be converted to 8-bit raw image format and written into memory space pointed by rawImage parameter.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADFORMAT	Unsupported image format.
IENGINE_E_FILE	Error occured while opening/reading file.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Related Topics**

IEngine\_LoadBMP (☐ see page 11), IEngine\_MakeBMP (☐ see page 12)

### 4.2.4 IEngine\_ConvertTemplate Function

Converts between different template formats.

#### $C^{++}$

```
IENGINE_API int IEngine_ConvertTemplate(IENGINE_TEMPLATE_FORMAT inputTemplateType, BYTE *
inputTemplate, IENGINE_TEMPLATE_FORMAT outputTemplateType, int * length, BYTE *
outputTemplate);
```

### Description

This function converts an input template to an equivalent template in a format specified by user. Templates with multiple finger views are supported by this function. When converting to ILO\_SID\_TEMPLATE format, all "fixed" values are set according to the specification (see http://www.ilo.org/public/english/dialogue/sector/papers/maritime/sid0002.pdf Annex B for more details). Similarly, the resulting template will always have two fingers. If the input template contains only one (or none) fingerview, the resulting ILO SID template will have one (or two) "unenrolled" fingers with finger quality set to 0x65 (enrollment failed due to a physical disability).

#### **Parameters**

```
IENGINE_TEMPLATE_FORMAT inputTemplateType

[in] Specifies the format of the input template

BYTE * inputTemplate

[in] Reference template

IENGINE_TEMPLATE_FORMAT outputTemplateType

[in] Specifies the format of the output template

int * length

[in/out] On input specifies the length of allocated data space (in
```

[in/out] On input specifies the length of allocated data space (in bytes) pointed by outputTemplate pointer. On return, specifies the size of the template after conversion.

BYTE \* outputTemplate

[out] Pointer to memory space where the resulting template will be written.

### Returns

If outputTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to outputTemplate. If outputTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and outputTemplate are returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	The input templates is not valid or has a different format as specified.
IENGINE_E_BADPARAM	Invalid input parameter provided (invalid template format?)
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### 4.2.5 IEngine\_ConvertIso19794\_4ToRaw Function

Converts ISO 19794-4 format into raw image format.

### C++

```
IENGINE_API int IEngine_ConvertIso19794_4ToRaw(const unsigned char * isoFingerImage, unsigned int isoImageLength, int * width, int * height, unsigned char * fingerPosition, unsigned char * imageFormat, unsigned int * dpiX, unsigned int * dpiY, unsigned char * rawImage, int * rawImageLength);
```

### Description

This function takes as input image stored in ISO 19794-4 format and converts it into raw format.

#### **Parameters**

```
const unsigned char * isoFingerImage
 [in] Pointer to ISO 19794-4 image data
unsigned int isoImageLength
 [in] Indicates length of input data
int * width
 [out] The number of pixels indicating the width of the image as stored in ISO 19794-4 header.
int * height
 [out] The number of pixels indicating the height of the image as stored in ISO 19794-4 header.
unsigned char * fingerPosition
 [out] Indicates finger position as stored in ISO 19794-4 header.
unsigned char * imageFormat
 [out] Indicates in which format is image data stored.
unsigned int * dpiX
 [out] Horizontal resolution of the input image as stored in ISO 19794-4 header.
unsigned int * dpiY
 [out] Vertical resolution of the input image as stored in ISO 19794-4 header.
```

unsigned char \* rawImage

[out] Pointer where output raw data will be stored. The size of memory pointed by this parameter has to be at least equal to the value of the rawImageLength parameter.

compressionRate

[in] Indicates compression rate to be used in case of WSQ or JPEG2000 formats. For other formats, this parameter is ignored.

length

[in/out] Pointer where output image (after background removal) will be stored. The size of memory pointed by this parameter has to be at least width\*height bytes.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occurred.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### 4.2.6 IEngine\_ConvertRawTolso19794\_4 Function

Converts raw image into ISO 19794-4 format.

### C++

```
IENGINE_API int IEngine_ConvertRawToIso19794_4(const unsigned char * rawImage, int width, int height, unsigned char fingerPosition, unsigned char imageFormat, unsigned int dpiX, unsigned int dpiY, unsigned char * outData, int compressionRate, int * length);
```

### Description

This function takes as input raw image, encodes this image in format specified and embeds it into ISO 19794-4 format.

### **Parameters**

```
const unsigned char * rawImage
[in] Pointer to the uncompressed raw image
int width
```

```
[in] The number of pixels indicating the width of the image
```

int height

[in] The number of pixels indicating the height of the image

unsigned char fingerPosition

[in] Indicates finger position. This information will be stored in the header of resulting ISO 19794-4 image data

unsigned int dpiX

[in] Indicates horizontal resolution of the input image. This information will be stored in the header of resulting ISO 19794-4 image data

unsigned int dpiY

[in] Indicates vertical resolution of the input image. This information will be stored in the header of resulting ISO 19794-4 image data

unsigned char \* outData

[out] Pointer where output ISO 19794-4 image data will be stored. The size of memory pointed by this parameter has to be at least equal to the value of the length parameter.

int compressionRate

[in] Indicates compression rate to be used in case of WSQ or JPEG2000 formats. For other formats, this parameter is ignored.

int \* length

[in/out] Pointer where output image (after background removal) will be stored. The size of memory pointed by this parameter has to be at least width\*height bytes.

#### **Return Values**

Return Values	Description
IENGINE_OK	No error occurred.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### 4.2.7 IEngine\_LoadBMP Function

Loads bmp image from file and converts it to raw 8-bit format

### C++

```
IENGINE_API int IEngine_LoadBMP(const char * filename, int * width, int * height, BYTE *
rawImage, int * length);
```

### Description

This function reads bmp image contained in a file and converts it to raw 8-bit format as described in paragraph Fingerprint Image Data ( see page 2)

### **Parameters**

```
const char * filename
[in] Name of the file containing the input bmp image
int * width
[out] On return, contains the width of converted image
int * height
[out] On return, contains the height of converted image

BYTE * rawImage
[out] Pointer to memory space where raw image will be written
int * length
```

[in/out] On input, length parameter is interpreted as the total size of allocated memory pointed by rawlmage parameter. On return, this parameter will be equal to the total size of the image after conversion to raw format.

### Returns

If rawImage is NULL or if length parameter is less then the size of the input image after conversion to 8-bit raw format, length parameter will be set to the required length of rawImage array.

If rawlmage is not NULL and if length is greater or equal to the total memory size required to store the input image in 8-bit raw format, input bmp image will be converted to 8-bit raw image format and written into memory space pointed by rawlmage parameter.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADFORMAT	Unsupported image format.
IENGINE_E_FILE	Error occured while opening/reading file.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Related Topics**

IEngine\_ConvertBMP (☐ see page 8), IEngine\_MakeBMP (☐ see page 12)

### 4.2.8 IEngine\_MakeBMP Function

Converts raw image into grayscale bmp image

### C++

```
IENGINE_API int IEngine_MakeBMP(int width, int height, const BYTE * rawImage, BYTE *
bmpImageData, int * length);
```

### Description

This function converts 8-bit raw image with specified dimensions into corresponding bmp grayscale image. The input raw 8-bit format is described in paragraph Fingerprint Image Data (28 see page 2)

### **Parameters**

```
int width
[in] Width of the input raw image
int height
[in] Height of the input raw image
const BYTE * rawImage
[in] Pointer to raw image data
BYTE * bmpImageData
[out] Pointer to memory space where bmp image will be stored
int * length
```

[in/out] On input, length parameter is interpreted as the total size of allocated memory pointed by bmpImageData parameter. On return, this parameter will be equal to the total size of the raw image after conversion to bmp format.

### Returns

If bmpImageData is NULL or if length parameter is less then the size of the input image after conversion to bmp format, length parameter will be set to the required length of bmpImageData array.

If bmpImageData is not NULL and if length is greater or equal to the total memory size required to store the input image in bmp format, input raw image will be converted to bmp image and written into memory space pointed by bmpImageData parameter.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADFORMAT	Unsupported image format.
IENGINE_E_FILE	Error occured while opening/reading file.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Related Topics**

IEngine\_ConvertBMP (☐ see page 8), IEngine\_LoadBMP (☐ see page 11)

### 4.2.9 ISO\_CARD\_CC\_ConvertToISO Function

Converts an ISO Compact Card template into regular ISO template

#### C++

```
IENGINE_API int ISO_CARD_CC_ConvertToISO(const BYTE * isoCCTemplate, int * length, BYTE *
isoTemplate);
```

### Description

This function takes as input a Finger Minutiae Compact Card Format template (ISO\_CARD\_CC template) and converts it into ISO/IEC 19794-2 compliant fingerprint template. An ISO\_CARD\_CC template is defined in ISO/IEC 19794-2 standard, under paragraph 8. In ISO\_CARD\_CC template, each minutiae point is encoded in 3 bytes (instead of 6 bytes used in regular ISO template).

#### **Parameters**

```
const BYTE * isoCCTemplate
[in] ISO Compact Card template
int * length
[in/out] On input specifies the length of allocated data space (in bytes) pointed by isoTemplate pointer. On return, specifies the size of the resulting ISO template

BYTE * isoTemplate
[out] Pointer to memory space where the resulting ISO template will be stored
```

#### Returns

If isoTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to isoTemplate. If isoTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and isoTemplate are returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Related Topics**

ISO\_ConvertToISOCardCC ( see page 15)

### 4.2.10 ISO\_CARD\_CC\_GetMinutiaeData Function

Returns data from ISO Compact Card template corresponding to encoded minutiae block (template without header and footer)

### 2++

```
IENGINE_API int ISO_CARD_CC_GetMinutiaeData(const BYTE * isoCCTemplate, int *
minutiaeCount, BYTE * minutiaeData, int * minutiaeDataSize);
```

### Description

This function takes as input a Finger Minutiae Compact Card Format template (ISO\_CARD\_CC template) and returns data corresponding to encoded minutiae only (all data other then template header and footer, finger view header and extended data such as ridge count or zonal quality data). If input template contains multiple views, minutiae data for first view are returned.

### **Parameters**

```
const BYTE * isoCCTemplate
 [in] ISO Compact Card template
int * minutiaeCount
 [out] Number of minutiae contained in the input template (in the first finger view)
```

BYTE \* minutiaeData

[out] Pointer to memory space where the memory block with encoded minutiae will be stored. Memory has to be initialized before calling this function. Maximum possible size of returned minutiae data is 256\*3 bytes.

int \* minutiaeDataSize

[out] Size of written minutiaeData block.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Related Topics**

ISO\_ConvertToISOCardCC ( see page 15)

### 4.2.11 ISO\_ConvertToANSI Function

Converts ISO/IEC 19794-2 compliant template to ANSI/INCITS 378 compliant template

```
IENGINE_API int ISO_ConvertToANSI(const BYTE * isoTemplate, int * length, BYTE *
ansiTemplate);
```

### Description

This function converts an input ISO/IEC 19794-2 compliant template to an output ANSI/INCITS 378 compliant template. Templates with multiple finger views are supported by this function.

### **Parameters**

```
const BYTE * isoTemplate
 [in] Reference ISO/IEC 19794-2 template
```

[in/out] On input specifies the length of allocated data space (in bytes) pointed by ansiTemplate pointer. On return, specifies the size of converted ANSI template.

BYTE \* ansiTemplate

[out] Pointer to memory space where the resulting ANSI/INCITS 378 compliant template will be written.

### Returns

If ansiTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to ansiTemplate. If ansiTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and ansiTemplate are returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	The input templates is not valid ISO/IEC 19794-2 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### 4.2.12 ISO\_ConvertToISOCardCC Function

Converts a regular ISO template to ISO Compact Card template format (ISO Compact Size Finger Minutiae Format)

#### C++

IENGINE\_API int ISO\_ConvertToISOCardCC(const BYTE \* isoTemplate, int maximumMinutiaeCount,
IENGINE\_SORT\_ORDER minutiaeOrder, IENGINE\_SORT\_ORDER minutiaeSecondaryOrder, int \* length,
BYTE \* isoCCTemplate);

### **Description**

This function takes as input an ISO/IEC 19794-2 compliant fingerprint template and converts it into Finger Minutiae Compact Card Format template (ISO\_CARD\_CC template). An ISO\_CARD\_CC template is defined in ISO/IEC 19794-2 standard, under paragraph 8. In ISO\_CARD\_CC template, each minutiae point is encoded in 3 bytes (instead of 6 bytes used in regular ISO template). This function can also truncate minutiae points, if the number of minutiae points in the template is too big. You may also specify desired minutiae order in which minutiae points should be stored in the template.

#### **Parameters**

```
const BYTE * isoTemplate
```

[in] Reference ISO/IEC 19794-2 template

int maximumMinutiaeCount

[in] The maximal number of minutiae that will be stored in the output template. See ISO\_RemoveMinutiae ( see page 15) for details about truncation algorithm.

IENGINE\_SORT\_ORDER minutiaeOrder

[in] Defines the primary ordering criteria for minutiae

IENGINE\_SORT\_ORDER minutiaeSecondaryOrder

[in] Defines the secondary ordering criteria for minutiae (used when primary ordering criteria gives equality)

int \* length

[in/out] On input specifies the length of allocated data space (in bytes) pointed by isoCCTemplate pointer. On return, specifies the size of the resulting ISO Compact Card template

BYTE \* isoCCTemplate

[out] Pointer to memory space where the resulting ISO Compact Card template will be stored

### Returns

If isoCCTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to isoCCTemplate. If isoCCTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and isoCCTemplate are returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Related Topics**

ISO\_RemoveMinutiae ( see page 15), ISO\_CARD\_CC\_ConvertToISO ( see page 13)

### 4.2.13 ISO\_RemoveMinutiae Function

Removes minutiae points from an ISO template

### C++

 ${\tt IENGINE\_API} \ \ \textbf{int} \ \ {\tt ISO\_RemoveMinutiae} (\textbf{\textit{const}} \ \ {\tt BYTE} \ \ ^* \ \ {\tt inTemplate}, \ \ \textbf{\textit{int}} \ \ {\tt maximumMinutiaeCount}, \ \ \textbf{\textit{int}} \ \ ^*$ 

length, BYTE \* outTemplate);

### Description

This function limits maximal number of minutiae points contained in an ISO/IEC 19794-2 compliant fingerprint template. If the input template contains more minutiae points than the provided limit, extra minutae point are removed from the template. The truncation is made by peeling off minutiae that are farthest from the point of gravity of the minutiae set.

#### **Parameters**

const BYTE \* inTemplate

[in] Reference ISO/IEC 19794-2 template

int maximumMinutiaeCount

[in] The maximal number of minutiae that will be stored in the output template. If current minutiae count is less or equal to this limit, the output template will be a copy of the input template.

int \* length

[in/out] On input specifies the length of allocated data space (in bytes) pointed by outTemplate pointer. On return, specifies the size of truncated template

BYTE \* outTemplate

[out] Pointer to memory space where the resulting truncated ISO/IEC 19794-2 compliant template will be stored

#### Returns

If outTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to outTemplate. If outTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and outTemplate are returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

## 4.3 Template Extraction and Matching Functions

### **Functions**

	Name	Description
<b>≡</b>	ANSI_CreateTemplate (☐ see page 16)	Creates ANSI/INCITS 378 compliant template
<b>=♦</b>	ANSI_CreateTemplateEx (  see page 17)	Creates ANSI/INCITS 378 compliant template, stores intermediate images
<b>=♦</b>	ANSI_VerifyMatch (☐ see page 18)	Compares two ANSI/INCITS 378 compliant templates
<b>≡</b>	ANSI_VerifyMatchEx (  see page 19)	Compares specified finger views from ANSI/INCITS 378 compliant templates
<b>≡</b>	ISO_CreateTemplate (⊿ see page 20)	Creates ISO/IEC 19794-2 compliant template
<b>=♦</b>	ISO_CreateTemplateEx (☐ see page 21)	Creates ISO/IEC 19794-2 compliant template, stores intermediate images
<b>≡</b>	ISO_VerifyMatch ( see page 22)	Compares two ISO/IEC 19794-2 compliant templates
<b>=♦</b>	ISO_VerifyMatchEx ( see page 22)	Compares specified finger views from ISO/IEC 19794-2 compliant templates

### 4.3.1 ANSI\_CreateTemplate Function

Creates ANSI/INCITS 378 compliant template

### C++

IENGINE\_API int ANSI\_CreateTemplate(int width, int height, const BYTE \* rawImage, BYTE \*
ansiTemplate);

### Description

This function takes a raw image as input and generates the corresponding ANSI/INCITS 378 compliant fingerprint template. The memory for the template is allocated before the call (i.e., ANSI\_CreateTemplate does not handle the memory allocation for the template parameter).

#### **Parameters**

```
int width
```

[in] The number of pixels indicating the width of the image

int hoight

[in] The number of pixels indicating the height of the image

const BYTE \* rawImage

[in] Pointer to the uncompressed raw image for template creation

BYTE \* ansiTemplate

[out] Pointer to memory space where the processed template will be written. Memory should be allocated before calling this function. The maximal size of generated template is 1568 bytes.

#### Returns

On success, ANSI/INCITS 378 compliant template is written to memory space pointed by ansiTemplate. Returned template contains default values in Record header and Finger View header. You may use ANSI\_SetTemplateParameters in order to specify non-default values for Record header and Finger View header. To detect total length of created template, you may call function ANSI\_GetTemplateParameter ( see page 26) with PARAM\_TEMPLATE\_SIZE argument.

On failure, NULL template is returned.

#### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADIMAGE	Image size is not in supported range.
IENGINE_E_BLANKIMAGE	Image is blank or contains non-recognizable fingerprint. (Fail to enroll)
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

NULL templates are defined as containing the Record header and Finger View header only, with zero minutiae information (i.e. Number of Minutiae shall be set to 0). Thus, it is a 32 byte template (26-byte Record Header + 4-byte Finger View header + 2 bytes for the Extended Data Block length which is 0x0000).

### **Related Topics**

ANSI\_SetTemplateParameter ( see page 28), ANSI\_GetTemplateParameter ( see page 26)

### 4.3.2 ANSI\_CreateTemplateEx Function

Creates ANSI/INCITS 378 compliant template, stores intermediate images

### C++

IENGINE\_API int ANSI\_CreateTemplateEx(int width, int height, const BYTE \* rawImage, BYTE \*
ansiTemplate, const char \* skeletonImageFile, const char \* binarizedImageFile, const char \*
minutiaeImageFile);

### Description

This function takes a raw image as input and generates the corresponding ANSI/INCITS 378 compliant fingerprint template. It optionally stores intermediate images produced during the extraction phase. The memory for the template is allocated before the call (i.e., ANSI\_CreateTemplate ( see page 16) does not handle the memory allocation for the template parameter).

### **Parameters**

```
int width
```

[in] The number of pixels indicating the width of the image

int height

[in] The number of pixels indicating the height of the image

```
const BYTE * rawImage
```

[in] Pointer to the uncompressed raw image for template creation

```
BYTE * ansiTemplate
```

[out] Pointer to memory space where the processed template will be written. Memory should be allocated before calling this function. The maximal size of generated templates is 1568 bytes.

```
const char * skeletonImageFile
```

[in] Specifies the filename of bmp image where the fingerprint skeleton image will be saved. If this parameter is NULL, no skeleton image is saved.

```
const char * binarizedImageFile
```

[in] Specifies the filename of bmp image where the fingerprint binary image will be saved. If this parameter is NULL, no binary image is saved.

```
const char * minutiaeImageFile
```

[in] Specifies the filename of bmp image where the minutiae image will be saved (original fingerprint with all detected minutiae). If this parameter is NULL, no minutiae image is saved.

#### Returns

On success, ANSI/INCITS 378 compliant template is written to memory space pointed by ansiTemplate. Returned template contains default values in Record header and Finger View header. You may use ANSI\_SetTemplateParameters in order to specify non-default values for Record header and Finger View header.

On failure, NULL template is returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADIMAGE	Image size is not in supported range.
IENGINE_E_BLANKIMAGE	Image is blank or contains non-recognizable fingerprint. (Fail to enroll)
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

NULL templates are defined as containing the Record header and Finger View header only, with zero minutiae information (i.e. Number of Minutiae shall be set to 0). Thus, it is a 32 byte template (26-byte Record Header + 4-byte Finger View header + 2 bytes for the Extended Data Block length which is 0x0000).

### **Related Topics**

ANSI\_SetTemplateParameter (≥ see page 28)

### 4.3.3 ANSI\_VerifyMatch Function

Compares two ANSI/INCITS 378 compliant templates

### C++

```
IENGINE_API int ANSI_VerifyMatch(const BYTE * probeTemplate, const BYTE * galleryTemplate,
int maxRotation, int * score);
```

### Description

This function compares two ANSI/INCITS 378 compliant templates and outputs a match score. The score returned is an integer value ranging from 0 to 100000 which represents the similarity of original fingerprint images corresponding to compared templates. See topic Matching Scores ( see page 3) for more details.

### **Parameters**

```
const BYTE * probeTemplate
[in] ANSI/INCITS 378 template
const BYTE * galleryTemplate
[in] ANSI/INCITS 378 template
int maxRotation
[in] Maximal considered rotation between two fingerprint images. Valid range is between 0 and 180.
int * score
[out] On return, contains match score
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	At least one the input template is not valid ANSI/INCITS 378 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLTEMPLATE	At least one of the input templates is NULL (contains no finger view)
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

#### Notes

Comparison in which either template is NULL template will result in match score equal to 0. If any input template contains multiple finger views only the first finger view (finger view with the lowest index number) is used for comparison. Use ANSI\_VerifyMatchEx ( see page 19) for comparing templates with multiple views.

### **Related Topics**

ANSI\_VerifyMatchEx ( see page 19)

### 4.3.4 ANSI\_VerifyMatchEx Function

Compares specified finger views from ANSI/INCITS 378 compliant templates

### C++

```
IENGINE_API int ANSI_VerifyMatchEx(const BYTE * probeTemplate, int probeView, const BYTE *
galleryTemplate, int galleryView, int maxRotation, int * score);
```

### **Description**

This function compares given finger views from ANSI/INCITS 378 compliant templates and outputs a match score. The score returned is an integer value ranging from 0 to 100000 which represents the similarity of original fingerprint images corresponding to compared finger views. See topic Matching Scores ( see page 3) for more details.

### **Parameters**

```
const BYTE * probeTemplate
[in] ANSI/INCITS 378 template
int probeView
[in] Index number of the compared finger view from probe template. 0 is the first index number, 1 the second, etc.
const BYTE * galleryTemplate
[in] ANSI/INCITS 378 template
int galleryView
[in] Index number of the compared finger view from gallery template. 0 is the first index number, 1 the second, etc.
int maxRotation
[in] Maximal considered rotation between two fingerprint images. Valid range is between 0 and 180.
int * score
[out] On return, contains match score
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Specified finger view does not exist in the given template.
IENGINE_E_BADTEMPLATE	At least one the input template is not valid ANSI/INCITS 378 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLTEMPLATE	At least one of the input templates is NULL (contains no finger view)
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

Comparison in which either template is NULL template will result in match score equal to 0.

### **Related Topics**

ANSI\_VerifyMatch ( see page 18), ANSI\_GetTemplateParameter ( see page 26)

### 4.3.5 ISO\_CreateTemplate Function

Creates ISO/IEC 19794-2 compliant template

### C++

```
IENGINE_API int ISO_CreateTemplate(int width, int height, const BYTE * rawImage, BYTE *
isoTemplate);
```

### Description

This function takes a raw image as input and generates the corresponding ISO/IEC 19794-2 compliant fingerprint template. The memory for the template is allocated before the call (i.e., ISO\_CreateTemplate does not handle the memory allocation for the template parameter).

### **Parameters**

```
int width
```

[in] The number of pixels indicating the width of the image

int height

[in] The number of pixels indicating the height of the image

const BYTE \* rawImage

[in] Pointer to the uncompressed raw image for template creation

BYTE \* isoTemplate

[out] Pointer to memory space where the processed template will be written. Memory should be allocated before calling this function. The maximal size of generated template is 1566 bytes.

### Returns

On success, ISO/IEC 19794-2 compliant template is written to memory space pointed by isoTemplate. Returned template contains default values in Record header and Finger View header. You may use ISO\_SetTemplateParameters in order to specify non-default values for Record header and Finger View header. To detect total length of created template, you may call function ISO\_GetTemplateParameter ( see page 30) with PARAM\_TEMPLATE\_SIZE argument.

On failure, *NULL template* is returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADIMAGE	Image size is not in supported range.
IENGINE_E_BLANKIMAGE	Image is blank or contains non-recognizable fingerprint. (Fail to enroll)
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

NULL templates are defined as containing the Record header and Finger View header only, with zero minutiae information (i.e. Number of Minutiae shall be set to 0). Thus, it is a 30 byte template (24-byte Record Header + 4-byte Finger View header + 2 bytes for the Extended Data Block length which is 0x0000).

### **Related Topics**

ISO\_SetTemplateParameter ( see page 33), ISO\_GetTemplateParameter ( see page 30)

### 4.3.6 ISO\_CreateTemplateEx Function

Creates ISO/IEC 19794-2 compliant template, stores intermediate images

#### C++

```
IENGINE_API int ISO_CreateTemplateEx(int width, int height, const BYTE * rawImage, BYTE *
isoTemplate, const char * skeletonImageFile, const char * binarizedImageFile, const char *
minutiaeImageFile);
```

### Description

This function takes a raw image as input and generates the corresponding ISO/IEC 19794-2 compliant fingerprint template. It optionally stores intermediate images produced during the extraction phase. The memory for the template is allocated before the call (i.e., ISO\_CreateTemplate ( see page 20) does not handle the memory allocation for the template parameter).

#### **Parameters**

```
int width
```

[in] The number of pixels indicating the width of the image

int height

[in] The number of pixels indicating the height of the image

const BYTE \* rawImage

[in] Pointer to the uncompressed raw image for template creation

BYTE \* isoTemplate

[out] Pointer to memory space where the processed template will be written. Memory should be allocated before calling this function. The maximal size of generated templates is 1566 bytes.

```
const char * skeletonImageFile
```

[in] Specifies the filename of bmp image where the fingerprint skeleton image will be saved. If this parameter is NULL, no skeleton image is saved.

const char \* binarizedImageFile

[in] Specifies the filename of bmp image where the fingerprint binary image will be saved. If this parameter is NULL, no binary image is saved.

const char \* minutiaeImageFile

[in] Specifies the filename of bmp image where the minutiae image will be saved (original fingerprint with all detected minutiae). If this parameter is NULL, no minutiae image is saved.

### Returns

On success, ISO/IEC 19794-2 compliant template is written to memory space pointed by isoTemplate. Returned template contains default values in Record header and Finger View header. You may use ISO\_SetTemplateParameters in order to specify non-default values for Record header and Finger View header.

On failure, *NULL template* is returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADIMAGE	Image size is not in supported range.
IENGINE_E_BLANKIMAGE	Image is blank or contains non-recognizable fingerprint. (Fail to enroll)
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

NULL templates are defined as containing the Record header and Finger View header only, with zero minutiae information (i.e. Number of Minutiae shall be set to 0). Thus, it is a 30 byte template (24-byte Record Header + 4-byte Finger View header + 2 bytes for the Extended Data Block length which is 0x0000).

### **Related Topics**

ISO\_SetTemplateParameter ( see page 33)

### 4.3.7 ISO\_VerifyMatch Function

Compares two ISO/IEC 19794-2 compliant templates

### C++

```
IENGINE_API int ISO_VerifyMatch(const BYTE * probeTemplate, const BYTE * galleryTemplate,
int maxRotation, int * score);
```

### Description

This function compares two ISO/IEC 19794-2 compliant templates and outputs a match score. The score returned is an integer value ranging from 0 to 100000 which represents the similarity of original fingerprint images corresponding to compared templates. See topic Matching Scores ( see page 3) for more details.

#### **Parameters**

```
const BYTE * probeTemplate
[in] ISO/IEC 19794-2 template
const BYTE * galleryTemplate
[in] ISO/IEC 19794-2 template
int maxRotation
[in] Maximal considered rotation between two fingerprint images. Valid range is between 0 and 180.
int * score
[out] On return, contains match score
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	At least one the input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLTEMPLATE	At least one of the input templates is NULL (contains no finger view)
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

Comparison in which either template is NULL template will result in match score equal to 0. If any input template contains multiple finger views only the first finger view (finger view with the lowest index number) is used for comparison. Use ISO\_VerifyMatchEx ( see page 22) for comparing templates with multiple views.

### **Related Topics**

ISO\_VerifyMatchEx ( see page 22)

### 4.3.8 ISO\_VerifyMatchEx Function

Compares specified finger views from ISO/IEC 19794-2 compliant templates

### C++

IENGINE\_API int ISO\_VerifyMatchEx(const BYTE \* probeTemplate, int probeView, const BYTE \*
galleryTemplate, int galleryView, int maxRotation, int \* score);

### Description

This function compares given finger views from ISO/IEC 19794-2 compliant templates and outputs a match score. The score returned is an integer value ranging from 0 to 100000 which represents the similarity of original fingerprint images corresponding to compared finger views. See topic Matching Scores ( see page 3) for more details.

#### **Parameters**

```
const BYTE * probeTemplate
[in] ISO/IEC 19794-2 template
int probeView
[in] Index number of the compared finger view from probe template. 0 is the first index number, 1 the second, etc.
const BYTE * galleryTemplate
[in] ISO/IEC 19794-2 template
int galleryView
[in] Index number of the compared finger view from gallery template. 0 is the first index number, 1 the second, etc.
int maxRotation
[in] Maximal considered rotation between two fingerprint images. Valid range is between 0 and 180.
int * score
[out] On return, contains match score
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Specified finger view does not exist in the given template.
IENGINE_E_BADTEMPLATE	At least one the input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLTEMPLATE	At least one of the input templates is NULL (contains no finger view)
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input parameter provided.

### **Notes**

Comparison in which either template is NULL template will result in match score equal to 0.

### **Related Topics**

ISO\_VerifyMatch ( see page 22), ISO\_GetTemplateParameter ( see page 30)

### 4.4 Template Manipulation Functions

### **Functions**

	Name	Description
<b>≡</b>	ANSI_DrawMinutiae (  see page 24)	Returns bmp image with minutiae points marked over given fingerprint
<b>≡</b>	ANSI_GetFingerView ( see page 24)	Returns specified finger view from ANSI/INCITS 378 compliant template
<b>≡</b>	ANSI_GetMinutiae ( <b>I</b> see page 25)	Returns minutiae stored in ANSI/INCITS 378 compliant template
<b>≡</b>	ANSI_GetTemplateParameter (  see page 26)	Get specific template parameters
<b>≟</b>	ANSI_MergeTemplates (☐ see page 26)	Combines finger views from two ANSI/INCITS 378 templates into one common template
<b>≡</b>	ANSI_LoadTemplate ( see page 27)	Loads ANSI/INCITS 378 compliant template from file
<b>≡</b>	ANSI_SaveTemplate ( <b>I</b> see page 27)	Stores ANSI/INCITS 378 compliant template to file
<b>≡</b>	ANSI_SetTemplateParameter (	Set specific template parameter
<b>≡</b>	ISO_DrawMinutiae ( see page 29)	Returns bmp image with minutiae points marked over given fingerprint
<b>≡</b>	ISO_GetFingerView (  see page 29)	Returns specified finger view from ISO/IEC 19794-2 compliant template

<b>=♦</b>	ISO_GetMinutiae ( <b>I</b> see page 30)	Returns minutiae stored in ISO/IEC 19794-2 compliant template
<b>≡</b>	ISO_GetTemplateParameter (☐ see page 30)	Get specific template parameters
<b>=</b> ♦	ISO_LoadTemplate (  see page 31)	Loads ISO/IEC 19794-2 compliant template from file
<b>⊕</b> ∳	ISO_MergeTemplates (☐ see page 32)	Combines finger views from two ISO/IEC 19794-2 templates into one common template
<b>=</b> ♦	ISO_SaveTemplate (  see page 32)	Stores ISO/IEC 19794-2 compliant template to file
<b>≡</b>	ISO_SetTemplateParameter ( see page 33)	Set specific template parameter

### 4.4.1 ANSI\_DrawMinutiae Function

Returns bmp image with minutiae points marked over given fingerprint

#### C++

```
IENGINE_API int ANSI_DrawMinutiae(const BYTE * ansiTemplate, int width, int height,
unsigned char * inputImage, unsigned char * outputBmpImage, int * outputImageLength);
```

### Description

This function draws minutiae points associated with the given fingerprint template and returns the result as bmp image in memory. If inputImage is NULL, minutiae are drawn on a blank background, otherwise inputImage is used as background.

#### **Parameters**

```
const BYTE * ansiTemplate
[in] ANSI/INCITS 378 compliant fingerprint template
int width
[in] Width of inputImage, if inputImage is NULL, this value is ignored
int height
[in] Height of inputImage, if inputImage is NULL, this value is ignored
unsigned char * inputImage
[in] Raw image representing fingerprint from which fingerprint template was extracted
unsigned char * outputBmoImage
```

[out] A pointer to memory space where the resulting image will be stored. Resulting image will be stored in bmp format and its size will be specified in output/mageLength. If this value is NULL, image is not saved, only output/mageLength is set to required size.

int \* outputImageLength

[in/out] On input, this value should indicate total allocated size of outputBmpImage. On output, this value will be equal to total memory size required to store resulting bmp image

### Returns

If outputBmpImage is NULL or if outputImageLength is less than memory size of resulting bmp image, outputImageLength is set to total size (in bytes) of resulting bmp image Otherwise, outputImageLength is set to total size (in bytes) of resulting bmp image and bmp image is stored in memory space pointed by outputBmpImage. Resulting image is a color bmp image.

### **Return Values**

Return Values	Description
IEngine_ERRCODE_INVALID_DATA	indicates that the input template has not correct format or is damaged

### 4.4.2 ANSI\_GetFingerView Function

Returns specified finger view from ANSI/INCITS 378 compliant template

### C++

```
IENGINE_API int ANSI_GetFingerView(const BYTE * ansiTemplate, int fingerView, BYTE *
outTemplate);
```

### Description

This function reads specified finger view from given ANSI/INCITS 378 compliant template and returns new ANSI/INCITS 378

compliant template containing only single finger view. Record header of the new template is a copy of the record header of the input template.

### **Parameters**

```
const BYTE * ansiTemplate
[in] ANSI/INCITS 378 template
int fingerView
```

[in] Index number of the finger view that will be returned in the newly created template. 0 is the first index number, 1 the second, etc.

BYTE \* outTemplate

[out] Pointer to memory space where the resulting ANSI/INCITS 378 template containing the specified finger view will be written. The maximal size of such template is 1568 bytes.

### **Returns**

On success, ANSI/INCITS 378 compliant template containing single finger view is written to memory space pointed by outTemplate. Returned template contains same values in Record header as the input template.

#### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Specified finger view does not exist in the given template.
IENGINE_E_BADTEMPLATE	The input template is not valid ANSI/INCITS 378 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLTEMPLATE	The input template is NULL (contains no finger view)
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### **Related Topics**

ANSI\_MergeTemplates (≥ see page 26)

[out] Minutiae count contained within the input template

### 4.4.3 ANSI\_GetMinutiae Function

Returns minutiae stored in ANSI/INCITS 378 compliant template

### C++

```
IENGINE_API int ANSI_GetMinutiae(const BYTE * ansiTemplate, IENGINE_MINUTIAE minutiae[256],
int * minutiaeCount);
```

### Description

This function returns minutiae angles and minutiae positions stored in ANSI/INCITS 378 compliant template

### **Parameters**

```
const BYTE * ansiTemplate
  [in] ANSI/INCITS 378 template

IENGINE_MINUTIAE minutiae[256]
  [out] Initialized minutiae array with 256 elements (maximal minutiae count in ANSI/INCITS 378 template is 256). If null, minutiae points will not be returned.
int * minutiaeCount
```

### Returns

On success, minutiae and minutiaeCount are returned. If either of those parameter is NULL, the parameter is not returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ANSI/INCITS 378 template.

IENGINE\_E\_NULLTEMPLATE Input template is NULL (contains no finger view)

### 4.4.4 ANSI\_GetTemplateParameter Function

Get specific template parameters

#### C++

```
IENGINE_API int ANSI_GetTemplateParameter(const BYTE * ansiTemplate,
IENGINE_TEMPLATE_PARAMETER parameter, int * value);
```

### Description

This function retrieves the value of a specific template parameter stored in record header or in finger view header of the input ANSI/INCITS 378 template. If specified template contains multiple finger views, this function retrieves information related to the first finger view (finger view with the lowest index number).

#### **Parameters**

```
const BYTE * ansiTemplate
[in] ANSI/INCITS 378 template

IENGINE_TEMPLATE_PARAMETER parameter
[in] Contains the code of the template parameter
int * value
[out] On return, contains the value of the specified parameter
```

#### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Invalid parameter type provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ANSI/INCITS 378 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_NOTDEFINED	Specified parameter is not defined (NULL template?)

### **Related Topics**

ANSI\_SetTemplateParameter ( see page 28)

### 4.4.5 ANSI\_MergeTemplates Function

Combines finger views from two ANSI/INCITS 378 templates into one common template

### C++

```
IENGINE_API int ANSI_MergeTemplates(const BYTE * referenceTemplate, const BYTE *
addedTemplate, int * length, BYTE * outTemplate);
```

### Description

This function reads finger views from two ANSI/INCITS 378 templates and merges them into one resulting template. Each input template may contain zero, one or multiple finger views. Record header of the resulting template is copied from the record header of the reference template.

### **Parameters**

```
const BYTE * referenceTemplate
[in] Reference ANSI/INCITS 378 template
const BYTE * addedTemplate
[in] ANSI/INCITS 378 template. Finger views from this template will be combined with finger views from the reference template.
int * length
```

[in/out] On input specifies the length of allocated data space (in bytes) pointed by outTemplate pointer. On return, specifies the size of merged template containing all finger views.

BYTE \* outTemplate

[out] Pointer to memory space where the resulting ANSI/INCITS 378 compliant template containing all finger views from input templates will be written.

#### Returns

If outTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to outTemplate. If outTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and outTemplate are returned.

#### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	At least one of the input templates is not valid ANSI/INCITS 378 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### **Related Topics**

ANSI\_GetFingerView ( see page 24)

### 4.4.6 ANSI\_LoadTemplate Function

Loads ANSI/INCITS 378 compliant template from file

#### C++

IENGINE\_API int ANSI\_LoadTemplate(const char \* filename, BYTE \* ansiTemplate);

### Description

This function loads an ANSI/INCITS 378 compliant template from file

### **Parameters**

const char \* filename

[in] Name of the file where the template will be saved

BYTE \* ansiTemplate

[out] Pointer to memory space where the ANSI/INCITS 378 compatible template will be loaded. Memory should be allocated before calling this function. The maximal size of ANSI/INCITS template is 1568 bytes.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ANSI/INCITS 378 template.
IENGINE_E_FILE	Error occured while opening/reading file.

### **Related Topics**

### 4.4.7 ANSI\_SaveTemplate Function

Stores ANSI/INCITS 378 compliant template to file

### C++

IENGINE\_API int ANSI\_SaveTemplate(const char \* filename, const BYTE \* ansiTemplate);

### Description

This function stores the input ANSI/INCITS 378 compliant template to a file

### **Parameters**

```
const char * filename
[in] Name of the file where the input template will be saved
const BYTE * ansiTemplate
[in] ANSI/INCITS 378 template
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ANSI/INCITS 378 template.
IENGINE_E_FILE	Error occured while opening/reading file.

### **Related Topics**

ANSI\_SetTemplateParameter ( see page 28)

### 4.4.8 ANSI\_SetTemplateParameter Function

Set specific template parameter

#### C++

```
 \begin{tabular}{ll} {\tt IENGINE\_API} & {\tt int} & {\tt ANSI\_SetTemplateParameter(BYTE * ansiTemplate, IENGINE\_TEMPLATE\_PARAMETER parameter, int value); \end{tabular}
```

### Description

This function modifies the information concerning specific template parameters stored in record header or in finger view header of an ANSI/INCITS 378 template. If specified template contains multiple finger views, this function modifies the first finger view (finger view with the lowest index number).

### **Parameters**

```
BYTE * ansiTemplate
[in/out] On input, this parameter should contain a valid ANSI/INCITS 378 template. On return, the original template is modified - .

IENGINE_TEMPLATE_PARAMETER parameter
[in] Contains the code of the template parameter to be set.

int value
[in] Contains the value for the specified parameter
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Invalid parameter type provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ANSI/INCITS 378 template.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADVALUE	Invalid value provided.
IENGINE_E_READONLY	Specified parameter cannot be modified.
IENGINE_E_NOTDEFINED	Specified parameter is not defined (NULL template?)

### **Related Topics**

ANSI\_GetTemplateParameter ( see page 26)

### 4.4.9 ISO\_DrawMinutiae Function

Returns bmp image with minutiae points marked over given fingerprint

#### C++

```
IENGINE_API int ISO_DrawMinutiae(const BYTE * isoTemplate, int width, int height, unsigned
char * inputImage, unsigned char * outputBmpImage, int * outputImageLength);
```

### Description

This function draws minutiae points associated with the given fingerprint template and returns the result as bmp image in memory. If inputImage is NULL, minutiae are drawn on a blank background, otherwise inputImage is used as background.

#### **Parameters**

```
const BYTE * isoTemplate
[in] ISO/IEC 19794-2 compliant fingerprint template
int width
[in] Width of inputImage, if inputImage is NULL, this value is ignored
int height
[in] Height of inputImage, if inputImage is NULL, this value is ignored
unsigned char * inputImage
[in] Raw image representing fingerprint from which fingerprint template was extracted
unsigned char * outputBmpImage
[out] A pointer to memory space where the resulting image will be stored. Resulting image will be stored in bmp format and its size will be specified in outputImageLength. If this value is NULL, image is not saved, only outputImageLength is set to required size.
int * outputImageLength
[in/out] On input, this value should indicate total allocated size of outputBmpImage. On output, this value will be equal to total memory size required to store
```

### Returns

If outputBmpImage is NULL or if outputImageLength is less than memory size of resulting bmp image, outputImageLength is set to total size (in bytes) of resulting bmp image Otherwise, outputImageLength is set to total size (in bytes) of resulting bmp image and bmp image is stored in memory space pointed by outputBmpImage. Resulting image is a color bmp image.

### **Return Values**

resulting bmp image

Return Values	Description
IEngine_ERRCODE_INVALID_DATA	indicates that the input template has not correct format or is damaged

### 4.4.10 ISO\_GetFingerView Function

Returns specified finger view from ISO/IEC 19794-2 compliant template

### C++

```
IENGINE_API int ISO_GetFingerView(const BYTE * isoTemplate, int fingerView, BYTE *
outTemplate);
```

### Description

This function reads specified finger view from given ISO/IEC 19794-2 compliant template and returns new ISO/IEC 19794-2 compliant template containing only single finger view. Record header of the new template is a copy of the record header of the input template.

### **Parameters**

```
const BYTE * isoTemplate
[in] ISO/IEC 19794-2 template
int fingerView
```

[in] Index number of the finger view that will be returned in the newly created template. 0 is the first index number, 1 the second, etc.

BYTE \* outTemplate

[out] Pointer to memory space where the resulting ISO/IEC 19794-2 template containing the specified finger view will be written. The maximal size of such template is 1566 bytes.

#### Returns

On success, ISO/IEC 19794-2 compliant template containing single finger view is written to memory space pointed by outTemplate. Returned template contains same values in Record header as the input template.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Specified finger view does not exist in the given template.
IENGINE_E_BADTEMPLATE	The input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLTEMPLATE	The input template is NULL (contains no finger view)
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### **Related Topics**

ISO\_MergeTemplates ( see page 32)

### 4.4.11 ISO\_GetMinutiae Function

Returns minutiae stored in ISO/IEC 19794-2 compliant template

#### C++

```
IENGINE_API int ISO_GetMinutiae(const BYTE * isoTemplate, IENGINE_MINUTIAE minutiae[256],
int * minutiaeCount);
```

### Description

This function returns minutiae angles and minutiae positions stored in ISO/IEC 19794-2 compliant template

### **Parameters**

```
const BYTE * isoTemplate
[in] ISO/IEC 19794-2 template

IENGINE_MINUTIAE minutiae[256]
```

[out] Initialized minutiae array with 256 elements (maximal minutiae count in ISO/IEC 19794-2 template is 256). If null, minutiae points will not be returned.

int \* minutiaeCount

[out] Number of minutiae contained in the input template

### Returns

On success, minutiae and minutiaeCount are returned. If either of those parameter is NULL, the parameter is not returned.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_NULLTEMPLATE	Input template is NULL (contains no finger view)

### 4.4.12 ISO\_GetTemplateParameter Function

Get specific template parameters

### C++

```
IENGINE_API int ISO_GetTemplateParameter(const BYTE * isoTemplate,
IENGINE_TEMPLATE_PARAMETER parameter, int * value);
```

### Description

This function retrieves the value of a specific template parameter stored in record header or in finger view header of the input ISO/IEC 19794-2 template. If specified template contains multiple finger views, this function retrieves information related to the first finger view (finger view with the lowest index number).

#### **Parameters**

```
const BYTE * isoTemplate
[in] ISO/IEC 19794-2 template

IENGINE_TEMPLATE_PARAMETER parameter
[in] Contains the code of the template parameter
int * value
[out] On return, contains the value of the specified parameter
```

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Invalid parameter type provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_NOTDEFINED	Specified parameter is not defined (NULL template?)

### **Related Topics**

ISO\_SetTemplateParameter ( see page 33)

### 4.4.13 ISO\_LoadTemplate Function

Loads ISO/IEC 19794-2 compliant template from file

### C++

```
IENGINE_API int ISO_LoadTemplate(const char * filename, BYTE * isoTemplate);
```

### Description

This function loads an ISO/IEC 19794-2 compliant template from file

### **Parameters**

```
const char * filename
  [in] Name of the file where the template will be saved
BYTE * isoTemplate
```

[out] Pointer to memory space where the ISO/IEC 19794-2 compatible template will be loaded. Memory should be allocated before calling this function. The maximal size of ISO/IEC 19794-2 template is 1566 bytes.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_FILE	Error occured while opening/reading file.

### **Related Topics**

ISO\_GetTemplateParameter ( see page 30)

### 4.4.14 ISO\_MergeTemplates Function

Combines finger views from two ISO/IEC 19794-2 templates into one common template

#### C++

```
IENGINE_API int ISO_MergeTemplates(const BYTE * referenceTemplate, const BYTE *
addedTemplate, int * length, BYTE * outTemplate);
```

### Description

This function reads finger views from two ISO/IEC 19794-2 templates and merges them into one resulting template. Each input template may contain zero, one or multiple finger views. Record header of the resulting template is copied from the record header of the reference template.

### **Parameters**

```
const BYTE * referenceTemplate
[in] Reference ISO/IEC 19794-2 template
const BYTE * addedTemplate
[in] ISO/IEC 19794-2 template.
[in] ISO/IEC 19794-2 template. Finger views from this template will be combined with finger views from the reference template.
int * length
[in/out] On input specifies the length of allocated data space (in bytes) pointed by outTemplate pointer. On return, specifies the size of merged template containing all finger views.
```

#### Poturne

BYTE \* outTemplate

If outTemplate parameter is NULL or if the size required to store the resulting template is more than the value specified by length parameter, total number of bytes required to store the resulting template is returned but no data is written to outTemplate. If outTemplate parameter is non-NULL and if the size required to store the resulting template is less or equal to the value specified by length parameter, both length parameter and outTemplate are returned.

[out] Pointer to memory space where the resulting ISO/IEC 19794-2 compliant template containing all finger views from input templates will be written.

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADTEMPLATE	At least one of the input templates is not valid ISO/IEC 19794-2 template.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_MEMORY	Memory allocation failed.
IENGINE_E_NULLPARAM	NULL input or output parameter provided.

### **Related Topics**

ISO\_GetFingerView ( see page 29)

### 4.4.15 ISO\_SaveTemplate Function

Stores ISO/IEC 19794-2 compliant template to file

### C++

```
IENGINE_API int ISO_SaveTemplate(const char * filename, const BYTE * isoTemplate);
```

### Description

This function stores the input ISO/IEC 19794-2 compliant template to a file

### **Parameters**

```
const char * filename
[in] Name of the file where the input template will be saved
```

const BYTE \* isoTemplate
[in] ISO/IEC 19794-2 template

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_INIT	Library was not initialized.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_FILE	Error occured while opening/reading file.

### **Related Topics**

ISO\_SetTemplateParameter ( see page 33)

### 4.4.16 ISO\_SetTemplateParameter Function

Set specific template parameter

### C++

IENGINE\_API int ISO\_SetTemplateParameter(BYTE \* isoTemplate, IENGINE\_TEMPLATE\_PARAMETER
parameter, int value);

### Description

This function modifies the information concerning specific template parameters stored in record header or in finger view header of an ISO/IEC 19794-2 template. If specified template contains multiple finger views, this function modifies the first finger view (finger view with the lowest index number).

#### **Parameters**

BYTE \* isoTemplate

[in/out] On input, this parameter should contain a valid ISO/IEC 19794-2 template. On return, the original template is modified - .

IENGINE\_TEMPLATE\_PARAMETER parameter

[in] Contains the code of the template parameter to be set.

int value

[in] Contains the value for the specified parameter

### **Return Values**

Return Values	Description
IENGINE_OK	No error occured.
IENGINE_E_BADPARAM	Invalid parameter type provided.
IENGINE_E_BADTEMPLATE	Input template is not valid ISO/IEC 19794-2 template.
IENGINE_E_NULLPARAM	NULL input parameter provided.
IENGINE_E_BADVALUE	Invalid value provided.
IENGINE_E_READONLY	Specified parameter cannot be modified.
IENGINE_E_NOTDEFINED	Specified parameter is not defined (NULL template?)

### **Related Topics**

ISO\_GetTemplateParameter ( see page 30)

### 5 Types, Structures, Enumerations

### **Enumerations**

Name	Description
IENGINE_TEMPLATE_PARAMETER (☐ see page 34)	Enumeration defining codes for parameters contained in ISO/IEC 19794-2 and ANSI/INCITS 378 compliant templates.
IENGINE_TEMPLATE_FORMAT (☐ see page 35)	Enumeration defining codes for different template formats
IENGINE_FINGER_POSITION (☐ see page 35)	Enumeration defining codes for different finger positions
IENGINE_IMPRESSION_TYPE ( see page 35)	Defines impression type of fingerprint image
IENGINE_SORT_ORDER ( see page 37)	Defines sort order of minutiae points

#### Structures

Name	Description
IENGINE_VERSION ( see page 36)	Structure representing the current version of the library
	Structure representing a particular minutia (distinctive fingerprint feature found in fingerprint skeleton, such as a bifurcation or an ending).

# 5.1 IENGINE\_TEMPLATE\_PARAMETER Enumeration

Enumeration defining codes for parameters contained in ISO/IEC 19794-2 and ANSI/INCITS 378 compliant templates.

### C++

```
typedef enum {
   PARAM_PRODUCT_OWNER = 0,
   PARAM_PRODUCT_VERSION = 1,
   PARAM_TEMPLATE_SIZE = 2,
   PARAM_CAPTURE_EQUIPMENT_COMPLIANCE = 3,
   PARAM_CAPTURE_EQUIPMENT_ID = 4,
   PARAM_FINGER_VIEW_COUNT = 5,
   PARAM_FINGER_POSITION = 10,
   PARAM_IMPRESSION_TYPE = 11,
   PARAM_FINGER_QUALITY = 12
} IENGINE_TEMPLATE_PARAMETER;
```

### **Members**

Members	Description	
PARAM_PRODUCT_OWNER = 0	Specifies the 'owner' of the encoding application. This value is read-only (cannot be used with IEngine_SetTemplateParameter function).	
PARAM_PRODUCT_VERSION = 1	Specifies the version of the encoding application. This value is read-only (cannot be used with IEngine_SetTemplateParameter function).	
PARAM_TEMPLATE_SIZE = 2	Specifies the total length of the template in bytes. This value is read-only (cannot be used with IEngine_SetTemplateParameter function).	
PARAM_CAPTURE_EQUIPMENT_COMPLIANCE = 3	Shall be a 4-bit value between 0 and 15, the most significant bit, if set to a 1, indicates that the equipment was cerified to comply with Appendix F (IAFIS Image Quality Specification, January 29, 1999) of FJIS-RS-0010, the Federal Bureau of Investigations's Electronic Fingerprint Transmission Specification. The other three bits are reserved for future compliance indicators. The default value for this parameter is 0.	
PARAM_CAPTURE_EQUIPMENT_ID = 4	Shall be recorded in twelve bits. A value of all zeros are acceptable and idicate that the capture equipment ID is unreported. In other case, the value of the field is determined by the vendor. The default value for this parameter is 0.	
PARAM_FINGER_VIEW_COUNT = 5	Specifies total number of finger views contained within given template. This value is read-only (cannot be used with IEngine_SetTemplateParameter function).	

PARAM_FINGER_POSITION = 10	Specifies the finger position of the encoded fingerprint. The values of different finger positions are defined in IENGINE_FINGER_POSITION ( see page 35) enum. The default value for this parameter is 0 (UNKNOWN_FINGER).
PARAM_IMPRESSION_TYPE = 11	Specifies the impression type of the encoded fingerprint. The values of different finger positions are defined in IENGINE_IMPRESSION_TYPE ( see page 35) enum. The default value for this parameter is 0 (TYPE_LIVE_SCAN_PLAIN).
PARAM_FINGER_QUALITY = 12	Specifies the quality of the encoded fingerprint. This quality number is an overall expression of the quality of the finger record, and represents quality of the original image. A value of 0 represents the lowest possible quality and the value 100 represents the highest possible quality. The numeric values in this field are set in accordance with the general guidelines contained in Section 2.1.42 of ANSI/INCITS 358. The default value for this parameter is 40 (fair quality).

# 5.2 IENGINE\_TEMPLATE\_FORMAT Enumeration

Enumeration defining codes for different template formats

```
C++
```

```
typedef enum {
  ANSI_TEMPLATE = 0,
  ISO_TEMPLATE = 1,
  ILO_SID_TEMPLATE = 2
} IENGINE_TEMPLATE_FORMAT;
```

### 5.3 IENGINE\_FINGER\_POSITION Enumeration

Enumeration defining codes for different finger positions

### C++

```
typedef enum {
  UNKNOWN_FINGER = 0,
  RIGHT_THUMB = 1,
  RIGHT_INDEX = 2,
  RIGHT_MIDDLE = 3,
  RIGHT_RING = 4,
  RIGHT_LITTLE = 5,
  LEFT_THUMB = 6,
  LEFT_INDEX = 7,
  LEFT_MIDDLE = 8,
  LEFT_RING = 9,
  LEFT_LITTLE = 10
} IENGINE_FINGER_POSITION;
```

### 5.4 IENGINE\_IMPRESSION\_TYPE Enumeration

Defines impression type of fingerprint image

### C++

```
typedef enum {
  TYPE_LIVE_SCAN_PLAIN = 0,
  TYPE_LIVE_SCAN_ROLLED = 1,
  TYPE_NONLIVE_SCAN_PLAIN = 2,
```

```
TYPE_NONLIVE_SCAN_ROLLED = 3,
TYPE_SWIPE = 4,
TYPE_LIVE_SCAN_CONTACTLESS = 9
} IENGINE_IMPRESSION_TYPE;
```

### 5.5 IENGINE\_VERSION Structure

Structure representing the current version of the library

### C++

```
typedef struct iengine_version {
  unsigned int Major;
  unsigned int Minor;
} IENGINE_VERSION;
```

### Description

Version definition contains major and minor number. The major number begins at 1 and is incremented by 1 for each major realease.

The minor number uses two digits to represent minor releases and revisions. The revision number is represented in the least significant digit. The more significant digits represent release minor version.

### **Example**

Version	Major number	Minor number
1.0	1	0
1.01	1	1
1.11	1	11
1.24	1	24

### 5.6 iengine\_version Structure

### 5.7 IENGINE\_MINUTIAE Structure

Structure representing a particular minutia (distinctive fingerprint feature found in fingerprint skeleton, such as a bifurcation or an ending).

### C++

```
typedef struct iengine_minutiae {
  BYTE angle;
  unsigned short x;
  unsigned short y;
  unsigned char type;
} IENGINE_MINUTIAE;
```

### Members

Members	Description
BYTE angle;	Minutia angle encoded in one byte. Valid range: 0-255.
unsigned short x;	Minutiae x coordinate as stored in the template.

unsigned short y;	Minutiae y coordinate as stored in the template.
unsigned char type;	Minutiae type (bifurcation/ending)

### 5.8 IENGINE\_SORT\_ORDER Enumeration

Defines sort order of minutiae points

### C++

```
typedef enum {
   SORT_NONE = 0,
   SORT_X_ASC = 1,
   SORT_X_DESC = 2,
   SORT_Y_ASC = 3,
   SORT_Y_DESC = 4
} IENGINE_SORT_ORDER;
```

### **Members**

Members	Description
SORT_NONE = 0	No ordering required.
SORT_X_ASC = 1	Cartesian x-coordinate is used for ordering, ascending order.
SORT_X_DESC = 2	Cartesian x-coordinate is used for ordering, descending order.
SORT_Y_ASC = 3	Cartesian y-coordinate is used for ordering, ascending order.
SORT_Y_DESC = 4	Cartesian y-coordinate is used for ordering, descending order.

### 5.9 iengine\_minutiae Structure

### **6 Constants**

#### **Macros**

Name	Description
IENGINE_MIN_IMAGE_HEIGHT (☐ see page 38)	Defines minimal height of accepted fingerprint images
IENGINE_MAX_IMAGE_HEIGHT (☑ see page 38)	Defines maximal height of accepted fingerprint images
IENGINE_MIN_IMAGE_WIDTH ( <b>I</b> see page 38)	Defines minimal width of accepted fingerprint images
IENGINE_MAX_IMAGE_WIDTH ( see page 38)	Defines maximal width of accepted fingerprint images
IENGINE_MAX_ANSI_TEMPLATE_SIZE ( see page 39)	Maximal size of generated ANSI/INCITS 378 template (with only one finger view)
IENGINE_MAX_ISO_TEMPLATE_SIZE ( see page 39)	Maximal size of generated ISO/IEC 19794-2 template (with only one finger view)

### 6.1 IENGINE\_MIN\_IMAGE\_HEIGHT Macro

Defines minimal height of accepted fingerprint images

C++

#define IENGINE\_MIN\_IMAGE\_HEIGHT 90

### 6.2 IENGINE\_MAX\_IMAGE\_HEIGHT Macro

Defines maximal height of accepted fingerprint images

C++

#define IENGINE\_MAX\_IMAGE\_HEIGHT 1800

### 6.3 IENGINE\_MIN\_IMAGE\_WIDTH Macro

Defines minimal width of accepted fingerprint images

C++

#define IENGINE\_MIN\_IMAGE\_WIDTH 90

### 6.4 IENGINE\_MAX\_IMAGE\_WIDTH Macro

Defines maximal width of accepted fingerprint images

C++

#define IENGINE\_MAX\_IMAGE\_WIDTH 1800

# **6.5 IENGINE\_MAX\_ANSI\_TEMPLATE\_SIZE Macro**

Maximal size of generated ANSI/INCITS 378 template (with only one finger view)

C++

#define IENGINE\_MAX\_ANSI\_TEMPLATE\_SIZE 1568

### 6.6 IENGINE\_MAX\_ISO\_TEMPLATE\_SIZE Macro

Maximal size of generated ISO/IEC 19794-2 template (with only one finger view)

C++

#define IENGINE\_MAX\_ISO\_TEMPLATE\_SIZE 1566

### **7 Error Codes**

Error	Error Code	Description
IENGINE_E_NOERROR	0	No error.
IENGINE_E_BADPARAM	1101	Invalid parameter type provided.
IENGINE_E_BLANKIMAGE	1114	Image is blank or contains non-recognizable fingerprint.
IENGINE_E_BADIMAGE	1115	Invalid image or unsupported image format.
IENGINE_E_FILE	1117	Error occured while opening/reading file.
IENGINE_E_INIT	1116	Library was not initialized.
IENGINE_E_MEMORY	1120	Memory allocation failed.
IENGINE_E_NULLPARAM	1121	NULL input parameter provided.
IENGINE_E_OTHER	1122	Other unspecified error.
IENGINE_E_BADFORMAT	1132	Unsupported format.
IENGINE_E_BADVALUE	1133	Invalid value provided.
IENGINE_E_BADLICENSE	1129	Provided license is not valid, or no license was found.
IENGINE_E_BADTEMPLATE	1135	Invalid template or unsupported template format.
IENGINE_E_READONLY	1136	Value cannot be modified
IENGINE_E_NOTDEFINED	1137	Value is not defined
IENGINE_E_NULLTEMPLATE	1138	Provided template is NULL (contains no finger view)

### 8 Symbol Reference

### 8.1 Functions

The following table lists functions in this documentation.

### 8.2 Macros

The following table lists macros in this documentation.

### 8.3 Structs, Records, Enums

The following table lists structs, records, enums in this documentation.

### Index

A

ANSI\_ConvertToISO function 7

ANSI\_CreateTemplate function 16

ANSI\_CreateTemplateEx function 17

ANSI\_DrawMinutiae function 24

ANSI\_GetFingerView function 24

ANSI\_GetMinutiae function 25

ANSI\_GetTemplateParameter function 26

ANSI\_LoadTemplate function 27

ANSI\_MergeTemplates function 26

ANSI\_RemoveMinutiae function 7

ANSI\_SaveTemplate function 27

ANSI\_SetTemplateParameter function 28

ANSI\_VerifyMatch function 18

ANSI\_VerifyMatchEx function 19

C

Constants 38

Conversion Functions 6

Е

Error Codes 40

E

Fingerprint Image Data 2

ı

IEngine\_ConvertBMP function 8

IEngine\_ConvertIso19794\_4ToRaw function 9

IEngine\_ConvertRawToIso19794\_4 function 10

IEngine\_ConvertTemplate function 9

IENGINE\_FINGER\_POSITION enumeration 35

IEngine\_GetErrorMessage function 5

IEngine\_GetImageQuality function 5

IEngine\_GetVersion function 5

IENGINE\_IMPRESSION\_TYPE enumeration 35

IEngine\_Init function 4

IEngine\_LoadBMP function 11

IEngine\_MakeBMP function 12

IENGINE\_MAX\_ANSI\_TEMPLATE\_SIZE macro 39

IENGINE\_MAX\_IMAGE\_HEIGHT macro 38

IENGINE\_MAX\_IMAGE\_WIDTH macro 38

IENGINE\_MAX\_ISO\_TEMPLATE\_SIZE macro 39

IENGINE\_MIN\_IMAGE\_HEIGHT macro 38

IENGINE\_MIN\_IMAGE\_WIDTH macro 38

IENGINE\_MINUTIAE structure 36

IEngine\_SetLicenseContent function 6

IENGINE\_SORT\_ORDER enumeration 37

IENGINE\_TEMPLATE\_FORMAT enumeration 35

IENGINE\_TEMPLATE\_PARAMETER enumeration 34

IEngine\_Terminate function 4

IENGINE\_VERSION structure 36

Init, Terminate and other General Functions 4

ISO\_CARD\_CC\_ConvertToISO function 13

ISO\_CARD\_CC\_GetMinutiaeData function 13

ISO\_ConvertToANSI function 14

ISO\_ConvertToISOCardCC function 15

ISO\_CreateTemplate function 20

ISO\_CreateTemplateEx function 21

ISO\_DrawMinutiae function 29

ISO\_GetFingerView function 29

ISO\_GetMinutiae function 30

ISO\_GetTemplateParameter function 30

ISO\_LoadTemplate function 31

ISO\_MergeTemplates function 32

ISO\_RemoveMinutiae function 15

ISO\_SaveTemplate function 32

ISO\_SetTemplateParameter function 33

ISO\_VerifyMatch function 22

ISO\_VerifyMatchEx function 22

L

Library Functions 4

M

Matching Scores 3

O

Overview 1

### T

Template Extraction and Matching Functions 16
Template Manipulation Functions 23
Types, Structures, Enumerations 34