# The PGE \*.LVLX file file specification

Created by Wohlstand (July, 17, 2014)

This is a text file which saves a level map. All parameters are written with having own markers per every field, and there are divided by data sections which are contains only items of defined type (blocks, background objects, NPC's, etc.).

### Introduction

### **Standart parameters:**

Standart size of one block
On screen can showing height
On screen can showing width
25 blocks
25 blocks

Big height of screen 600 pixels (19 blocks without 8 pixels)

Big width of screen 800 pixels (28 blocks) Small width of screen 512 pixels (16 blocks) Small height of screen 480 pixels (15 blocks)

# **Default section positions**

### (Section Center) Section (X and Y axis ranges)

-200000 **01** (-190000 : -219999) **02** (-170000 : -189999) -180000 **03** (-150000 : -189999) -160000 **04** (-130000 : -149999) -140000 **05** (-110000 : -129999) -120000 **06** (-90000 : -109999) -100000 **07** (-70000 : -89999) -80000 -60000 **08** (-50000 : -69999) **09** (-30000 : -49999) -40000 **10** (-10000 : -29999) -20000 0000 11 (9999 : -9999) 20000 **12** (10000 : 29999) **13** (30000 : 49999) 40000 -60000 **14** (50000 : 69999) **15** (70000 : 89999) 80000 **16** (90000 : 109999) 100000 **17** (100000 : 129999) 120000 **18** (130000 : 149999) 140000 **19** (150000 : 169999) 160000 180000 **20** (170000 : 189999) **21** (190000 : 209999) 200000


- The standard size of one section zone is 29999×29999 pixels
- Y is always equal to X as Section center coordinates
- where x=0 and y=0 is a center of 11'th section.

For converting from absolute coordinates to the relative of center by one section:

$$X_{n-section} = \bar{X}_{absolute} - X_{Current section center}$$
 $Y_{n-section} = Y_{absolute} - Y_{Current section center}$ 

The section size and position are defined by the position of each side of the section. height and width are calculated with a formula:

$$W = |L-R|$$
  $H = |T-B|$ 





# The coordinates of an object's placement is set concerning its upper left corner:

In this example, the mushroom's coordinates on the current section is: X=2150; Y=2600 and the block coordinates are: X=2150; Y=2632

#### Remember!

As the Y axis is turned to move an object down, it is necessary to add to the Y offset and to move up, it is necessary to subtract.





# **File Format Specification**

### The reference designations:

- standart parameter
- <u>currently not implemented or not used parameter</u>
- Comment title
- Comment description
- loop
- variable
- Special option, using only under special conditions, differently is absent
- File format version limit
- Data type

### File format version:

The version number of the file format defines data present or absent in the file.

#### **Sections**

Each data type separated by markers: started from line **DATA1** and closed with line **DATA1 END** 

### for example:

**SECTION** 

 $SC:1;L:-32445;R:-32436;T:-43623;B:-32677;MZ:43;MF:"test.ogg";BG:34; \leftarrow \textbf{some data SECTION\_END}$ 

## *List of available sections:*

Marker	Description
HEAD	File header
SECTION	Level sections
META_BOOKMARKS	Position bookmarks
STARTPOINT	Player's start points
BLOCK	Blocks present on the map
BGO	BGO present on the map
NPC	NPC present on the map
PHYSICS	Physical environment zones on the map
DOORS	Warps and doors available on the map
LAYERS	Layers
EVENTS	Action-styled events
EVENT	Sub-section of action-styled events, contains list of actions
EVENTS_CLASSIC	SMBX64-compatible classic events

#### Data

Each data entry have each line. Parameters separated with a semicolon ";". All parameters must have a markers. Marker and value separated by colon ":". Non-exist markers will be skipped. Not allowing to use parameters without markers. Data-type for each parameter defining by its internal. Data-types closed by its markers. Always possible add new marker with possible to save compatible with old versions.

# **Example of data entry:**

ID:24;X:-4146;Y:23566;V:-1;ZO:0;SP:-1;L:"Default"

Data types syntax:

Data types syntax.	vata types syntax.	
12345	unsigned int/long	
<del>-31414</del>	signed int/long	
13.45	unsigned float/double	
-34.772	signed float/double	
"Hello world"	string	
H48656c6c6f20776f726c64	hex encoded string	
[123,54,243,33]	int/long array	
["test", "cat", "dog"]	string array	
0/1	Boolean	
011011010	Boolean array	
B12FD24	Byte-encoded Boolean array	

# Also inside strings can be used sprcial safe constants:

\n	New line
\''	Safe Quotes
\\	Safe slash
\;	Semicolon
\:	colon
/[	
\]	
	Comma
\%	Percent

### User's variables:

@p@	Current character's name

# **Data markers**

### File header:

Marker	Description
TL	(string) Level title
SZ	(unsigned int) Number of stars
DL	(string) Target level to open when player will fail (all playable characters are dead)
DE	(unsigned int) Target level warp-ID (0 – regular entrance, >=1 – warp-ID of enter)
CN	(string) Game config key.
GS	(bool) Use episode global switches (switch states will be saved)
PS	(int) Physics type (Internal physics configuration ID)
CC	(bool array) Controls flags (allow/deny control features for whole level)
CT	(int) Start level with character ID ([-1] – last used character)
TL	(long) Time limit in seconds (0 - disabled)
TA	(int) Time limit type (Kill player, Trigger event)

# **Level Section:**

M 1	
Marker	Description
SC	(unsigned int) Number of section
L	(long) Left side position X
Τ	(long) Top side position Y
В	(long) Bottom side position Y
R	(long) Right side position X
MZ	(unsigned int) Internal music ID
MF	(string) Custom music relative file path
BG	(unsigned int) Internal background ID
<u>BF</u>	(string) Custom background relative file path
CS	(bool) Connect sides flag (horizontally)
CSV	(bool) Connect sides flag (vertically)
OE	(bool) Off-screen exit flag
SR	(bool) Right-way scroll only (No Turn-back)
SL	(bool) Right-way scroll only
SR	(bool) Left-way scroll only
SD	(bool) Up-way scroll only
SU	(bool) Down-way scroll only
<u>GR</u>	(int) Gravity Value
<u>WE</u>	(bool) Section wind flag
WD	(int) Section wind direction
<u>WF</u>	(int) Wind strength value
	(int) Weather effects
WT CC	(bool array) Controls flags (allow/deny control features for this section only)

# Position bookmarks:

Marker	Description
BM	(string) Bookmark title
X	(long) Position X
Y	(long) Position Y

# Players start points:

Marker	Description
ID	(unsigned int) Player ID

X	(long) Position X
Y	(long) Position Y
D	(int) Start direction

# **Blocks:**

Marker	Description
ID	(unsigned long) Block ID
X	(long) Position X
Y	(long) Position Y
W	(unsigned int) Width
Н	(unsigned int) Height
CN	(int) NPC Content (Negative value – coins number, Positive – NPC-ID)
IV	(bool) Invisible flag
SL	(bool) Slippery flag
LR	(string) Layer
ED	(string) Event slot "Destroyed"
EH	(string) Event slot "Hit"
EE	(string) Event slot "Layer is empry"
PTR	(string) Unique item pointer (Using only for item specific events)

**Background object:** 

Marker	Description
ID	(unsigned long) Background object ID
X	(long) Position X
Y	(long) Position Y
ZO	(double) Z-Offset
ZP	(int) Z-Position (Frg-2 / Frg / Default / Backgrnd / Backgrnd-2)
SP	(int) SMBX64 array sort priority (will used only on save into SMBX LVL file)
LR	(string) Layer
PTR	(string) Unique item pointer (Using only for item specific events)

**Non-Playable Characters:** 

Marker	Description
ID	(unsigned long) NPC ID
X	(long) Position X
Y	(long) Position Y
D	(int) Direction
S1	(long) Special option 1
ZP	(int) Z-Position (Frg-2 / Frg / Default / Backgrnd / Backgrnd-2)
S2	(long) Special option 2
GE	(bool) Generator flag
GT	(int) Generator type
GD	(int) Generator direction
GM	(unsigned int) Generator delay
GA	(double) Generator custom angle (applies if direction value is 0)
GB	(unsigned int) Generator number of branches (applies if direction value is 0)
GR	(double) Generator angle range (applies if direction value is 0)
GS	(double) Generator, custom initial NPC's speed (applies if direction value is 0)
MG	(string) NPC message
FD	(bool) Friendly flag
NM	(bool) Idle flag
BS	(bool) Boss algorithms

LR	(string) Layer
LA	(string) Attach layer
EA	(string) Event slot "Activate"
ED	(string) Event slot "Death/Take/Destroy"
ET	(string) Event slot "Talk"
EE	(string) Event slot "Layer is empty"
EG	(string) Event slot "Grab"
ЕО	(string) Event slot "Touch"
EF	(string) Event slot "Next frame" (trigger event every game logic loop)
PTR	(string) Unique item pointer (Using only for item specific events)

**Physical environment zones:** 

Marker	Description Description
ET	(unsigned int) Environment type
X	(long) Position X
Y	(long) Position Y
W	(unsigned int) Width
Н	(unsigned int) Height
FR	(double) Custom friction (Applying if "Custom Liquid" environment type is active)
AD	(double) Custom Acceleration direction (Degrees 0360, -1 means stream is off)
AC	(double) Custom Acceleration (Applying for "Custom Liquid")
MV	(double) Maximum velocity (Applying for "Custom Liquid")
EO	(string) Touch event
HN	(bool) Enable hurtful for NPC
HP	(bool) Enable hurtful for Player
HV	(int) Hurtful strength (<0 – health up, 0 – safe, 1 – damage, 2, fast damage, 10 – fataly [as lava])
ST	(bool) Stream (for example, wind or water stream)
ST SD	(int) Stream direction
SS	(int) Stream strenght
LR	(string) Layer
<u>PTR</u>	(string) Unique item pointer (Using only for item specific events)

# Doors:

Marker	Description
IX	(long) Entrance position X
IY	(long) Entrance position Y
OX	(long) Exit position X
OY	(long) Exit position Y
IL	(unsigned int) Entrance length
OL	(unsigned int) Exit length
IV	(bool) Vertical entrance flag
OV	(bool) Vertical Exit flag
DT	(unsigned int) Door type
ID	(unsigned int) Entrance direction
OD	(unsigned int) Exit direction
WX	(long) World map exit X
WY	(long) World map exit Y
LF	(string) Target level file
LI	(unsigned int) Target Door ID. 0 – enter by default start point
ET	(bool) Is a level entrance
EX	(bool) Is a level exit

SL	(unsigned int) Stars needed for entrance	
SM	(string) Stars needed message if not collected	
SH	(bool) Don't show number of stars in the target level	
NV	(bool) Deny vehicles flag	
AI	(bool) Allow items flag	
LC	(bool) Locked door flag	
LB	(bool) Locked door, bomb required, flag	
HS	(bool) Don't show next level entering scene flag	
AL	(bool) Allow items (inter-level)	
TW	(bool) Two-way door flag	
PT	(bool) Projectile exit	
LR	(string) Layer	
EE	(string) On-Enter event slot	
PTR	(string) Unique item pointer (Using only for item specific events)	

# **Layers:**

Marker	Description
LR	(string) Layer title
HD	(string) Hidden flag
LC	(string) Locked flag

### **Classic Events:**

Marker	Description
ET	(string) Title
MG	(string) Message text
SD	(unsigned int) Play sound ID
EG	(unsigned int) End Game algorithm
LH	(string array) hide layers
LS	(string array) show layers
LT	(string array) toggle layers
SM	(string array) Music section sets
SB	(string array) Background section sets
SS	(string array) Size section sets
TE	(string) Trigger event
TD	(unsigned int) Trigger delay
DS	(bool) Disable smoke
AU	(bool) Autostart event
PC	(bool array) Player's control hold keys
ML	(string) Movement layer
MX	(int) Movement layer speed X
MY	(int) Movement layer speed Y
AS	(int) Autoscroll section ID
AX	(int) Autoscroll speed X
AY	(int) Autoscroll speed Y

# **Action-styled events entries**

Action-styled events contains only single entry with one marker ET, what used as event title

# **Actions entries example**

ACT\_XXX:"TEXT" ← Single-parametric ACT\_XXX;ID:1;VL:"4564" ← Multi-parametric

DO\_XXX ← Action without parameters

### **Actions list:**

Show message: ACT MSG

Marker	Description
_	(string) MessageText

### Play sound: ACT SND

Marker	Description
-	(unsigned int) Play sound

# **Hold player's keys: ACT\_PCNT**

Marker	Description
-	(bool array) Hold control keys

# Reset player's hold keys: DO\_PCNT\_R

Marker	Description
-	-

**Hide layers: ACT LHIDE** 

Marker	Description
NS	(bool) without smoke effect
LS	(string array) layers

**Show layers: ACT LSHOW** 

Marker	Description
NS	(bool) without smoke effect
LS	(string array) layers

Toggle layers: ACT LTOGGLE

Marker	Description
NS	(bool) without smoke effect
LS	(string array) layers

Toggle layers: ACT LTOGGLE

	<u> </u>
Marker	Description
NS	(bool) without smoke effect
LS	(string array) layers

Change section music ID: ACT SETMUS

Marker	Description
SI	(unsigned int) Section ID
MZ	(unsigned long) Music ID

Change section custom music file field: ACT SETMUSF

Marker	Description
SI	(unsigned int) Section ID
MF	(string) Music file path

Change section background ID: ACT SETBG

Marker	Description
SI	(unsigned int) Section ID
BG	(unsigned long) Background ID

Change section custom background file field: ACT SETBGF

Marker	Description
SI	(unsigned int) Section ID
BF	(string) Background file path

Change section custom background file field: ACT SRESIZE

Marker	Description	
SI	(unsigned int) Section ID	
L	(long) left side position X	
T	(long) top side position Y	
В	(long) bottom side position Y	
R	(long) right side position X	

Reset music ID to default: ACT SMUS R

Marker	Description
-	(unsigned int) Section ID

Reset background ID to default: ACT SMUS R

Marker	Description
-	(unsigned int) Section ID

### Reset section size to default: ACT SSIZE R

Marker	Description
-	(unsigned int) Section ID

### Reset custom music file field to default: ACT SMUSF R

Marker	Description
-	(unsigned int) Section ID

### Reset custom background file field to default: ACT SMUSF R

Marker	Description
-	(unsigned int) Section ID

### Set event trigger: ACT TRIGGER

Marker	Description
TE	(string) Event title
TT	(unsigned int) Delay, d-seconds (1/10 sec)

### Set layer speed motion: ACT MOTEL

Marker	Description
LT	(string) Layer title
SX SY	(double) Speed X
SY	(double) Speed Y
AX	(unsigned double) Acceleration X
AY	(unsigned double) Acceleration Y

# Set event trigger: ACT\_AUTOSCRL

Marker	Description
SI	(string) Layer title
SX SY	(double) Speed X
SY	(double) Speed Y
AX AY	(unsigned double) Acceleration X
AY	(unsigned double) Acceleration Y

### **Delay next action: ACT\_DELAY\_NEXT**

Marker	Description
-	(long) Delay time, ms

# **Loop event X times: ACT\_LOOP**

Marker	Description
-	(long) Loop times

### **Loop event forever: ACT LOOP FOREVER**

Marker	Description
-	-

### Abort event loop: ACT LOOP ABORT

Marker	Description
-	(string) Name of event which in loop

**Change Item setting: ACT CHITEM** 

Marker	Description	
PTR	(string) Target Item pointer	
IT	(unsigned int) Item type	
S	(string) Setting name	
V	(string) Setting value	

### **Cut-scene mode Events**

**Loop event forever: ACT CUTSCENE** 

Marker	Description
-	(bool) Enable cut-scene mode (Stop any AI's algorithms)

Change Item setting: ACT\_CTRL\_NPC

Marker	Description
PTR	(string) Target Item pointer
S	(string) Command name (Move, talk msg, jump, teleport to, etc)
V	(string) Command value

Change Item setting: ACT\_CTRL\_PLAYER

Marker	Description
ID	(unsigned int) Playable character ID
S	(string) Command name (Move, talk msg, jump, teleport to, etc)
V	(string) Command value

# Global events and switches

Change Item setting: ACT GLOBAL EVENT DO

Change reem	Change from sevenge from _GEODITE_E (E.(1_DO	
Marker	Description	
Е	(string) Global event name	
S	(string) Command name (Move, talk msg, jump, teleport to, etc)	
V	(string) Command value	

Change Item setting: ACT\_GLOBAL\_SWITCH

Marker	Description
SN	(string) Global switch name
SW	(bool) Switch state