

Use statistics to monitor Hyper-V and SQL Server over SMB activity

ONTAP 9

NetApp May 20, 2022

This PDF was generated from https://docs.netapp.com/us-en/ontap/smb-hyper-v-sql/determine-statistics-objects-counters-task.html on May 20, 2022. Always check docs.netapp.com for the latest.

Table of Contents

Jse statistics to monitor Hyper-V and SQL Server over SMB activity	. 1
Determine which statistics objects and counters are available	. 1
Display SMB statistics	. 4

Use statistics to monitor Hyper-V and SQL Server over SMB activity

Determine which statistics objects and counters are available

Before you can obtain information about CIFS, SMB, auditing, and BranchCache hash statistics and monitor performance, you must know which objects and counters are available from which you can obtain data.

Steps

1. Set the privilege level to advanced:

set -privilege advanced

2. Perform one of the following actions:

If you want to determine	Enter
Which objects are available	statistics catalog object show
Specific objects that are available	statistics catalog object show object object_name
Which counters are available	statistics catalog counter show object object_name

See the man pages for more information about which objects and counters are available.

3. Return to the admin privilege level:

set -privilege admin

Examples

The following command displays descriptions of selected statistic objects related to CIFS and SMB access in the cluster as seen at the advanced privilege level:

```
cluster1::> set -privilege advanced
Warning: These advanced commands are potentially dangerous; use them only
when directed to do so by support personnel.
Do you want to continue? {y|n}: y
cluster1::*> statistics catalog object show -object audit
                                CM object for exporting audit ng
performance counters
cluster1::*> statistics catalog object show -object cifs
    cifs
                                The CIFS object reports activity of the
                                Common Internet File System protocol
cluster1::*> statistics catalog object show -object nblade cifs
    nblade cifs
                                The Common Internet File System (CIFS)
                                protocol is an implementation of the
Server
cluster1::*> statistics catalog object show -object smb1
                                These counters report activity from the
    smb1
SMB
                                revision of the protocol. For information
cluster1::*> statistics catalog object show -object smb2
                                These counters report activity from the
    smb2
                                SMB2/SMB3 revision of the protocol. For
                                . . .
cluster1::*> statistics catalog object show -object hashd
   hashd
                                The hashd object provides counters to
measure
                                the performance of the BranchCache hash
daemon.
cluster1::*> set -privilege admin
```

The following command displays information about some of the counters for the cifs object as seen at the advanced privilege level:



This example does not display all of the available counters for the cifs object; output is truncated.

cluster1::> set -privilege advanced Warning: These advanced commands are potentially dangerous; use them only when directed to do so by support personnel. Do you want to continue? {y|n}: y cluster1::*> statistics catalog counter show -object cifs Object: cifs Counter Description active searches Number of active searches over SMB and SMB2 auth_reject_too_many
Authentication refused after too many requests were made in rapid succession SMB and SMB2 path-based commands cluster2::> statistics start -object client -sample-id Object: client Counter Value ______ cifs ops 0 0 cifs read ops cifs read recv ops 0 cifs read recv size 0В cifs read size 0B 0 cifs write ops 0 cifs write recv ops cifs write recv size 0B cifs_write_size 0В instance name vserver 1:10.72.205.179 instance uuid 2:10.72.205.179 local ops 0 mount_ops 0 [...]

3

Display SMB statistics

You can display various SMB statistics to monitor performance and diagnose issues.

Steps

- 1. Use the statistics start and optional statistics stop commands to collect a data sample.
 - For more information about these commands, see the System Administration Reference.
- 2. Perform one of the following actions:

If you want to display statistics for	Enter the following command
All versions of SMB	statistics show -object cifs
SMB 1.0	statistics show -object smb1
SMB 2.x and SMB 3.0	statistics show -object smb2
CIFS subsystem of the node	statistics show -object nblade_cifs

See the man page for more information.

Copyright Information

Copyright © 2022 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system- without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.