libdwarf

Generated by Doxygen 1.9.8

1 /	A Consumer Library Interface to DWARF	1
	1.1 Suggestions for improvement are welcome	2
	1.2 Introduction	2
	1.3 Thread Safety	2
	1.4 Error Handling in libdwarf	3
	1.4.1 Error Handling at Initialization	3
	1.4.2 Error Handling Everywhere	4
	1.4.2.1 DW_DLV_OK	5
	1.4.2.2 DW_DLV_NO_ENTRY	5
	1.4.2.3 DW_DLV_ERROR	5
	1.4.2.4 Slight Performance Enhancement	5
	1.5 Extracting Data Per Compilation Unit	6
	1.6 Line Table Registers	6
	1.7 Reading Special Sections Independently	7
	1.8 Special Frame Registers	7
	1.9 .debug_pubnames etc DWARF2-DWARF4	8
	1.10 Reading DWARF with no object file present	9
	1.11 Section Groups: Split Dwarf, COMDAT groups	10
	1.12 Details on separate DWARF object access	12
	1.13 Linking against libdwarf.so (or dll or dylib)	13
	1.14 Linking against libdwarf.a	13
	1.15 Suppressing CRC calculation for debuglink	14
	1.16 dwsec_mmap	14
	1.17 Recent Changes	15
	WE and a second days BWARE	•
2,	JIT and special case DWARF	21
	2.1 Reading DWARF not in an object file	21
	2.1.1 Describing the Interface	23
	2.1.2 Describing A Section	
	2.1.3 Function Pointers	24
3 (dwarf.h	27
4 I	ibdwarf.h	29
5 c	checkexamples.c	31
6 7	Topic Index	33
	6.1 Topics	33
7 [Data Structure Index	35
	7.1 Data Structures	35
8 F	File Index	37
	8.1 File List	37

9 Topic Documentation	39
9.1 Basic Library Datatypes Group	39
9.1.1 Detailed Description	39
9.1.2 Typedef Documentation	39
9.1.2.1 Dwarf_Unsigned	39
9.1.2.2 Dwarf_Signed	39
9.1.2.3 Dwarf_Off	39
9.1.2.4 Dwarf_Addr	40
9.1.2.5 Dwarf_Bool	40
9.1.2.6 Dwarf_Half	40
9.1.2.7 Dwarf_Small	40
9.1.2.8 Dwarf_Ptr	40
9.2 Enumerators with various purposes	40
9.2.1 Detailed Description	41
9.2.2 Enumeration Type Documentation	41
9.2.2.1 Dwarf_Ranges_Entry_Type	41
9.2.2.2 Dwarf_Form_Class	41
9.3 Defined and Opaque Structs	42
9.3.1 Detailed Description	43
9.3.2 Typedef Documentation	43
9.3.2.1 Dwarf_Form_Data16	43
9.3.2.2 Dwarf_Sig8	43
9.3.2.3 Dwarf_Block	43
9.3.2.4 Dwarf_Locdesc_c	44
9.3.2.5 Dwarf_Loc_Head_c	44
9.3.2.6 Dwarf_Gnu_Index_Head	44
9.3.2.7 Dwarf_Dsc_Head	44
9.3.2.8 Dwarf_Frame_Instr_Head	44
9.3.2.9 dwarf_printf_callback_function_type	44
9.3.2.10 Dwarf_Str_Offsets_Table	45
9.3.2.11 Dwarf_Ranges	45
9.3.2.12 Dwarf_Regtable_Entry3	45
9.3.2.13 Dwarf_Regtable3	46
9.3.2.14 Dwarf_Error	46
9.3.2.15 Dwarf_Debug	47
9.3.2.16 Dwarf_Section	47
9.3.2.17 Dwarf_Die	47
9.3.2.18 Dwarf_Debug_Addr_Table	47
9.3.2.19 Dwarf_Line	47
9.3.2.20 Dwarf_Global	47
9.3.2.21 Dwarf_Type	47
9.3.2.22 Dwarf_Func	48

48
48
48
48
48
48
49
49
49
49
49
49
49
50
50
50
50
50
50
50
50
51
51
51
52
52
61
61
61
62
62
62
63
63
64
64
65
65
66
66
67
67

9.7.3.10 dwarf_get_tied_dbg()	68
9.8 Compilation Unit (CU) Access	69
9.8.1 Detailed Description	69
9.8.2 Function Documentation	69
9.8.2.1 dwarf_next_cu_header_e()	69
9.8.2.2 dwarf_next_cu_header_d()	71
9.8.2.3 dwarf_siblingof_c()	71
9.8.2.4 dwarf_siblingof_b()	72
9.8.2.5 dwarf_cu_header_basics()	72
9.8.2.6 dwarf_child()	73
9.8.2.7 dwarf_dealloc_die()	74
9.8.2.8 dwarf_die_from_hash_signature()	74
9.8.2.9 dwarf_offdie_b()	74
9.8.2.10 dwarf_find_die_given_sig8()	75
9.8.2.11 dwarf_get_die_infotypes_flag()	75
9.9 Debugging Information Entry (DIE) content	76
9.9.1 Detailed Description	77
9.9.2 Function Documentation	77
9.9.2.1 dwarf_die_abbrev_global_offset()	77
9.9.2.2 dwarf_tag()	78
9.9.2.3 dwarf_dieoffset()	78
9.9.2.4 dwarf_debug_addr_index_to_addr()	79
9.9.2.5 dwarf_addr_form_is_indexed()	79
9.9.2.6 dwarf_CU_dieoffset_given_die()	79
9.9.2.7 dwarf_get_cu_die_offset_given_cu_header_offset_b()	80
9.9.2.8 dwarf_die_CU_offset()	80
9.9.2.9 dwarf_die_CU_offset_range()	81
9.9.2.10 dwarf_attr()	81
9.9.2.11 dwarf_die_text()	82
9.9.2.12 dwarf_diename()	82
9.9.2.13 dwarf_die_abbrev_code()	82
9.9.2.14 dwarf_die_abbrev_children_flag()	83
9.9.2.15 dwarf_validate_die_sibling()	83
9.9.2.16 dwarf_hasattr()	84
9.9.2.17 dwarf_offset_list()	84
9.9.2.18 dwarf_get_die_address_size()	85
9.9.2.19 dwarf_die_offsets()	85
9.9.2.20 dwarf_get_version_of_die()	86
9.9.2.21 dwarf_lowpc()	86
9.9.2.22 dwarf_highpc_b()	86
9.9.2.23 dwarf_dietype_offset()	87
9.9.2.24 dwarf_bytesize()	87

9.9.2.25 dwarf_bitsize()	 . 88
9.9.2.26 dwarf_bitoffset()	 . 88
9.9.2.27 dwarf_srclang()	 . 89
9.9.2.28 dwarf_language_version_string()	 . 89
9.9.2.29 dwarf_arrayorder()	 . 89
9.10 DIE Attribute and Attribute-Form Details	 . 90
9.10.1 Detailed Description	 . 91
9.10.2 Function Documentation	 . 92
9.10.2.1 dwarf_attrlist()	 . 92
9.10.2.2 dwarf_hasform()	 . 92
9.10.2.3 dwarf_whatform()	 . 93
9.10.2.4 dwarf_whatform_direct()	 . 93
9.10.2.5 dwarf_whatattr()	 . 93
9.10.2.6 dwarf_formref()	 . 94
9.10.2.7 dwarf_global_formref_b()	 . 94
9.10.2.8 dwarf_global_formref()	 . 95
9.10.2.9 dwarf_formsig8()	 . 95
9.10.2.10 dwarf_formsig8_const()	 . 95
9.10.2.11 dwarf_formaddr()	 . 96
9.10.2.12 dwarf_get_debug_addr_index()	 . 96
9.10.2.13 dwarf_formflag()	 . 97
9.10.2.14 dwarf_formudata()	 . 97
9.10.2.15 dwarf_formsdata()	 . 97
9.10.2.16 dwarf_formdata16()	 . 98
9.10.2.17 dwarf_formblock()	 . 98
9.10.2.18 dwarf_formstring()	 . 99
9.10.2.19 dwarf_get_debug_str_index()	 . 99
9.10.2.20 dwarf_formexprloc()	 . 100
9.10.2.21 dwarf_get_form_class()	 . 100
9.10.2.22 dwarf_attr_offset()	 . 100
9.10.2.23 dwarf_uncompress_integer_block_a()	 . 101
9.10.2.24 dwarf_dealloc_uncompressed_block()	 . 101
9.10.2.25 dwarf_convert_to_global_offset()	 . 101
9.10.2.26 dwarf_dealloc_attribute()	 . 102
9.10.2.27 dwarf_discr_list()	 . 102
9.10.2.28 dwarf_discr_entry_u()	 . 103
9.10.2.29 dwarf_discr_entry_s()	 . 103
9.11 Line Table For a CU	 . 103
9.11.1 Detailed Description	 . 105
9.11.2 Function Documentation	 . 105
9.11.2.1 dwarf_srcfiles()	 . 105
9.11.2.2 dwarf_srclines_b()	 . 107

9.11.2.3 dwarf_srclines_from_linecontext())7
9.11.2.4 dwarf_srclines_two_level_from_linecontext())8
9.11.2.5 dwarf_srclines_dealloc_b())8
9.11.2.6 dwarf_srclines_table_offset())8
9.11.2.7 dwarf_srclines_comp_dir())9
9.11.2.8 dwarf_srclines_subprog_count())9
9.11.2.9 dwarf_srclines_subprog_data())9
9.11.2.10 dwarf_srclines_files_indexes()	10
9.11.2.11 dwarf_srclines_files_data_b()	11
9.11.2.12 dwarf_srclines_include_dir_count()	11
9.11.2.13 dwarf_srclines_include_dir_data()	12
9.11.2.14 dwarf_srclines_version()	12
9.11.2.15 dwarf_linebeginstatement()	13
9.11.2.16 dwarf_lineendsequence()	13
9.11.2.17 dwarf_lineno()	14
9.11.2.18 dwarf_line_srcfileno()	14
9.11.2.19 dwarf_line_is_addr_set()	14
9.11.2.20 dwarf_lineaddr()	15
9.11.2.21 dwarf_lineoff_b()	15
9.11.2.22 dwarf_linesrc()	16
9.11.2.23 dwarf_lineblock()	16
9.11.2.24 dwarf_prologue_end_etc()	16
9.11.2.25 dwarf_check_lineheader_b()	17
9.11.2.26 dwarf_print_lines()	18
9.11.2.27 dwarf_register_printf_callback()	18
9.12 Ranges: code addresses in DWARF3-4	19
9.12.1 Detailed Description	19
9.12.2 Function Documentation	19
9.12.2.1 dwarf_get_ranges_b()	19
9.12.2.2 dwarf_dealloc_ranges()	20
9.12.2.3 dwarf_get_ranges_baseaddress()	20
9.13 Rnglists: code addresses in DWARF5	21
9.13.1 Detailed Description	22
9.13.2 Function Documentation	22
9.13.2.1 dwarf_rnglists_get_rle_head()	22
9.13.2.2 dwarf_get_rnglists_entry_fields_a()	23
9.13.2.3 dwarf_dealloc_rnglists_head()	23
9.13.2.4 dwarf_load_rnglists()	24
9.13.2.5 dwarf_get_rnglist_offset_index_value()	24
9.13.2.6 dwarf_get_rnglist_head_basics()	25
9.13.2.7 dwarf_get_rnglist_context_basics()	25
9.13.2.8 dwarf_get_rnglist_rle()	26

9.14 Locations of data: DWARF2-DWARF5	26
9.14.1 Detailed Description	28
9.14.2 Function Documentation	28
9.14.2.1 dwarf_get_loclist_c()	28
9.14.2.2 dwarf_get_loclist_head_kind()	28
9.14.2.3 dwarf_get_locdesc_entry_d()	29
9.14.2.4 dwarf_get_locdesc_entry_e()	29
9.14.2.5 dwarf_get_location_op_value_c()	30
9.14.2.6 dwarf_loclist_from_expr_c()	31
9.14.2.7 dwarf_dealloc_loc_head_c()	31
9.14.2.8 dwarf_load_loclists()	32
9.14.2.9 dwarf_get_loclist_offset_index_value()	32
9.14.2.10 dwarf_get_loclist_head_basics()	33
9.14.2.11 dwarf_get_loclist_context_basics()	33
9.14.2.12 dwarf_get_loclist_lle()	34
9.15 .debug_addr access: DWARF5	34
9.15.1 Detailed Description	34
9.15.2 Function Documentation	34
9.15.2.1 dwarf_debug_addr_table()	34
9.15.2.2 dwarf_debug_addr_by_index()	35
9.15.2.3 dwarf_dealloc_debug_addr_table()	36
9.16 Macro Access: DWARF5	36
9.16.1 Detailed Description	37
9.16.2 Function Documentation	37
9.16.2.1 dwarf_get_macro_context()	37
9.16.2.2 dwarf_get_macro_context_by_offset()	38
9.16.2.3 dwarf_macro_context_total_length()	38
9.16.2.4 dwarf_dealloc_macro_context()	38
9.16.2.5 dwarf_macro_context_head()	39
9.16.2.6 dwarf_macro_operands_table()	39
9.16.2.7 dwarf_get_macro_op()	39
9.16.2.8 dwarf_get_macro_defundef()	10
9.16.2.9 dwarf_get_macro_startend_file()	11
9.16.2.10 dwarf_get_macro_import()	11
9.17 Macro Access: DWARF2-4	12
9.17.1 Detailed Description	12
9.17.2 Function Documentation	12
9.17.2.1 dwarf_find_macro_value_start()	12
9.17.2.2 dwarf_get_macro_details()	13
9.18 Stack Frame Access	13
9.18.1 Detailed Description	1 5
9.18.2 Function Documentation	16

9.18.2.1 dwarf_get_fde_list()	146
9.18.2.2 dwarf_get_fde_list_eh()	146
9.18.2.3 dwarf_dealloc_fde_cie_list()	147
9.18.2.4 dwarf_get_fde_range()	147
9.18.2.5 dwarf_get_fde_exception_info()	148
9.18.2.6 dwarf_get_cie_of_fde()	148
9.18.2.7 dwarf_get_cie_info_b()	148
9.18.2.8 dwarf_get_cie_index()	149
9.18.2.9 dwarf_get_fde_instr_bytes()	149
9.18.2.10 dwarf_get_fde_info_for_all_regs3_b()	150
9.18.2.11 dwarf_get_fde_info_for_all_regs3()	150
9.18.2.12 dwarf_get_fde_info_for_reg3_c()	151
9.18.2.13 dwarf_get_fde_info_for_reg3_b()	152
9.18.2.14 dwarf_get_fde_info_for_cfa_reg3_c()	152
9.18.2.15 dwarf_get_fde_info_for_cfa_reg3_b()	153
9.18.2.16 dwarf_get_fde_for_die()	153
9.18.2.17 dwarf_get_fde_n()	153
9.18.2.18 dwarf_get_fde_at_pc()	154
9.18.2.19 dwarf_get_cie_augmentation_data()	154
9.18.2.20 dwarf_get_fde_augmentation_data()	155
9.18.2.21 dwarf_expand_frame_instructions()	155
9.18.2.22 dwarf_get_frame_instruction()	156
9.18.2.23 dwarf_get_frame_instruction_a()	157
9.18.2.24 dwarf_dealloc_frame_instr_head()	157
9.18.2.25 dwarf_fde_section_offset()	158
9.18.2.26 dwarf_cie_section_offset()	158
9.18.2.27 dwarf_set_frame_rule_table_size()	158
9.18.2.28 dwarf_set_frame_rule_initial_value()	159
9.18.2.29 dwarf_set_frame_cfa_value()	159
9.18.2.30 dwarf_set_frame_same_value()	159
9.18.2.31 dwarf_set_frame_undefined_value()	160
9.19 Abbreviations Section Details	160
9.19.1 Detailed Description	161
9.19.2 Function Documentation	161
9.19.2.1 dwarf_get_abbrev()	161
9.19.2.2 dwarf_get_abbrev_tag()	162
9.19.2.3 dwarf_get_abbrev_code()	162
9.19.2.4 dwarf_get_abbrev_children_flag()	162
9.19.2.5 dwarf_get_abbrev_entry_b()	163
9.20 String Section .debug_str Details	163
9.20.1 Detailed Description	163
9.20.2 Function Documentation	164

9.20.2.1 dwarf_get_str()	164
9.21 Str_Offsets section details	164
9.21.1 Detailed Description	165
9.21.2 Function Documentation	165
9.21.2.1 dwarf_open_str_offsets_table_access()	165
9.21.2.2 dwarf_close_str_offsets_table_access()	165
9.21.2.3 dwarf_next_str_offsets_table()	166
9.21.2.4 dwarf_str_offsets_value_by_index()	166
9.21.2.5 dwarf_str_offsets_statistics()	167
9.22 Dwarf_Error Functions	167
9.22.1 Detailed Description	168
9.22.2 Function Documentation	168
9.22.2.1 dwarf_errno()	168
9.22.2.2 dwarf_errmsg()	168
9.22.2.3 dwarf_errmsg_by_number()	168
9.22.2.4 dwarf_error_creation()	169
9.22.2.5 dwarf_dealloc_error()	169
9.23 Generic dwarf_dealloc Function	169
9.23.1 Detailed Description	169
9.23.2 Function Documentation	170
9.23.2.1 dwarf_dealloc()	170
9.24 Access to Section .debug_sup	170
9.24.1 Detailed Description	171
9.24.2 Function Documentation	171
9.24.2.1 dwarf_get_debug_sup()	171
9.25 Fast Access to .debug_names DWARF5	171
9.25.1 Detailed Description	172
9.25.2 Function Documentation	172
9.25.2.1 dwarf_dnames_header()	172
9.25.2.2 dwarf_dealloc_dnames()	173
9.25.2.3 dwarf_dnames_abbrevtable()	173
9.25.2.4 dwarf_dnames_sizes()	174
9.25.2.5 dwarf_dnames_offsets()	174
9.25.2.6 dwarf_dnames_cu_table()	175
9.25.2.7 dwarf_dnames_bucket()	175
9.25.2.8 dwarf_dnames_name()	176
9.25.2.9 dwarf_dnames_entrypool()	176
9.25.2.10 dwarf_dnames_entrypool_values()	177
9.26 Fast Access to a CU given a code address	178
9.26.1 Detailed Description	179
9.26.2 Function Documentation	179
9.26.2.1 dwarf_get_aranges()	179

9.26.2.2 dwarf_get_arange()	179
9.26.2.3 dwarf_get_cu_die_offset()	180
9.26.2.4 dwarf_get_arange_cu_header_offset()	180
9.26.2.5 dwarf_get_arange_info_b()	180
9.27 Fast Access to .debug_pubnames and more	181
9.27.1 Detailed Description	182
9.27.2 Function Documentation	182
9.27.2.1 dwarf_get_globals()	182
9.27.2.2 dwarf_get_pubtypes()	183
9.27.2.3 dwarf_globals_by_type()	183
9.27.2.4 dwarf_globals_dealloc()	184
9.27.2.5 dwarf_globname()	184
9.27.2.6 dwarf_global_die_offset()	184
9.27.2.7 dwarf_global_cu_offset()	185
9.27.2.8 dwarf_global_name_offsets()	185
9.27.2.9 dwarf_global_tag_number()	185
9.27.2.10 dwarf_get_globals_header()	186
9.27.2.11 dwarf_return_empty_pubnames()	186
9.28 Fast Access to GNU .debug_gnu_pubnames	187
9.28.1 Detailed Description	187
9.28.2 Function Documentation	187
9.28.2.1 dwarf_get_gnu_index_head()	187
9.28.2.2 dwarf_gnu_index_dealloc()	188
9.28.2.3 dwarf_get_gnu_index_block()	188
9.28.2.4 dwarf_get_gnu_index_block_entry()	189
9.29 Fast Access to Gdb Index	189
9.29.1 Detailed Description	190
9.29.2 Function Documentation	191
9.29.2.1 dwarf_gdbindex_header()	191
9.29.2.2 dwarf_dealloc_gdbindex()	191
9.29.2.3 dwarf_gdbindex_culist_array()	192
9.29.2.4 dwarf_gdbindex_culist_entry()	192
9.29.2.5 dwarf_gdbindex_types_culist_array()	192
9.29.2.6 dwarf_gdbindex_types_culist_entry()	193
9.29.2.7 dwarf_gdbindex_addressarea()	193
9.29.2.8 dwarf_gdbindex_addressarea_entry()	194
9.29.2.9 dwarf_gdbindex_symboltable_array()	194
9.29.2.10 dwarf_gdbindex_symboltable_entry()	194
9.29.2.11 dwarf_gdbindex_cuvector_length()	195
9.29.2.12 dwarf_gdbindex_cuvector_inner_attributes()	195
9.29.2.13 dwarf_gdbindex_cuvector_instance_expand_value()	196
9.29.2.14 dwarf_gdbindex_string_by_offset()	196

9.30 Fast Access to Split Dwarf (Debug Fission)
9.30.1 Detailed Description
9.30.2 Function Documentation
9.30.2.1 dwarf_get_xu_index_header()
9.30.2.2 dwarf_dealloc_xu_header()
9.30.2.3 dwarf_get_xu_index_section_type()
9.30.2.4 dwarf_get_xu_hash_entry()
9.30.2.5 dwarf_get_xu_section_names()
9.30.2.6 dwarf_get_xu_section_offset()
9.30.2.7 dwarf_get_debugfission_for_die()
9.30.2.8 dwarf_get_debugfission_for_key()
9.31 Access GNU .gnu_debuglink, build-id
9.31.1 Detailed Description
9.31.2 Function Documentation
9.31.2.1 dwarf_gnu_debuglink()
9.31.2.2 dwarf_suppress_debuglink_crc()
9.31.2.3 dwarf_add_debuglink_global_path()
9.31.2.4 dwarf_crc32()
9.31.2.5 dwarf_basic_crc32()
9.32 Harmless Error recording
9.32.1 Detailed Description
9.32.2 Function Documentation
9.32.2.1 dwarf_get_harmless_error_list()
9.32.2.2 dwarf_set_harmless_error_list_size()
9.32.2.3 dwarf_insert_harmless_error()
9.33 Names DW_TAG_member etc as strings
9.33.1 Detailed Description
9.33.2 Function Documentation
9.33.2.1 dwarf_get_GNUIKIND_name()
9.33.2.2 dwarf_get_EH_name()
9.33.2.3 dwarf_get_FRAME_name()
9.33.2.4 dwarf_get_GNUIVIS_name()
9.33.2.5 dwarf_get_LLEX_name()
9.33.2.6 dwarf_get_MACINFO_name()
9.33.2.7 dwarf_get_MACRO_name()
9.33.2.8 dwarf_get_FORM_CLASS_name()
9.34 Object Sections Data
9.34.1 Detailed Description
9.34.2 Function Documentation
9.34.2.1 dwarf_get_die_section_name()
9.34.2.2 dwarf_get_die_section_name_b()
9.34.2.3 dwarf_get_real_section_name()

9.34.2.4 dwarf_get_frame_section_name()	215
9.34.2.5 dwarf_get_frame_section_name_eh_gnu()	215
9.34.2.6 dwarf_get_offset_size()	215
9.34.2.7 dwarf_get_address_size()	215
9.34.2.8 dwarf_get_line_section_name_from_die()	215
9.34.2.9 dwarf_get_section_info_by_name_a()	216
9.34.2.10 dwarf_get_section_info_by_name()	217
9.34.2.11 dwarf_get_section_info_by_index_a()	217
9.34.2.12 dwarf_get_section_info_by_index()	218
9.34.2.13 dwarf_machine_architecture_a()	218
9.34.2.14 dwarf_machine_architecture()	219
9.34.2.15 dwarf_get_section_count()	219
9.34.2.16 dwarf_get_section_max_offsets_d()	220
9.35 Section Groups Objectfile Data	220
9.35.1 Detailed Description	221
9.35.2 Function Documentation	221
9.35.2.1 dwarf_sec_group_sizes()	221
9.35.2.2 dwarf_sec_group_map()	222
9.36 LEB Encode and Decode	222
9.36.1 Detailed Description	222
9.37 Miscellaneous Functions	223
9.37.1 Detailed Description	223
9.37.2 Function Documentation	223
9.37.2.1 dwarf_package_version()	223
9.37.2.2 dwarf_set_stringcheck()	223
9.37.2.3 dwarf_set_reloc_application()	224
9.37.2.4 dwarf_record_cmdline_options()	224
9.37.2.5 dwarf_set_de_alloc_flag()	224
9.37.2.6 dwarf_library_allow_dup_attr()	225
9.37.2.7 dwarf_set_default_address_size()	225
9.37.2.8 dwarf_get_universalbinary_count()	226
9.37.3 Variable Documentation	226
9.37.3.1 dwarf_get_endian_copy_function	226
9.38 Determine Object Type of a File	227
9.38.1 Detailed Description	227
9.39 Section allocation: malloc or mmap	227
9.39.1 Detailed Description	227
9.39.2 Function Documentation	228
9.39.2.1 dwarf_set_load_preference()	228
9.39.2.2 dwarf_get_mmap_count()	228
9.40 Using dwarf_init_path()	229
9.41 Using dwarf_init_path_dl()	230

9.42 Using dwarf_attrlist()
9.43 Attaching a tied dbg
9.44 Detaching a tied dbg
9.45 Examining Section Group data
9.46 Using dwarf_siblingof_c()
9.47 Using dwarf_siblingof_b()
9.48 Using dwarf_child()
9.49 using dwarf_validate_die_sibling
9.50 Example walking CUs(e)
9.51 Example walking CUs(d)
9.52 Using dwarf_offdie_b()
9.53 Using dwarf_offset_given_die()
9.54 Using dwarf_attrlist()
9.55 Using dwarf_offset_list()
9.56 Documenting Form_Block
9.57 Using dwarf_discr_list()
9.58 Location/expression access
9.59 Reading a location expression
9.60 Using dwarf_srclines_b()
9.61 Using dwarf_srclines_b() and linecontext
9.62 Using dwarf_srcfiles()
9.63 Using dwarf_get_globals()
9.64 Using dwarf_globals_by_type()
9.65 Reading .debug_weaknames (nonstandard)
9.66 Reading .debug_funcnames (nonstandard)
9.67 Reading .debug_types (nonstandard)
9.68 Reading .debug_varnames data (nonstandard)
9.69 Reading .debug_names data
9.70 Reading .debug_macro data (DWARF5)
9.71 Reading .debug_macinfo (DWARF2-4)
9.72 Extracting fde, cie lists
9.73 Reading the .eh_frame section
9.74 Using dwarf_expand_frame_instructions
9.75 Reading string offsets section data
9.76 Reading an aranges section
9.77 Example getting .debug_ranges data
9.78 Reading gdbindex data
9.79 Reading gdbindex addressarea
9.80 Reading the gdbindex symbol table
9.81 Reading cu and tu Debug Fission data
9.82 Reading Split Dwarf (Debug Fission) hash slots
9.83 Reading high pc from a DIE

9.84 Reading Split Dwarf (Debug Fission) data	265
9.85 Retrieving tag,attribute,etc names	266
9.86 Using GNU debuglink data	266
9.87 Accessing accessing raw rnglist	267
9.88 Accessing rnglists section	269
9.89 Demonstrating reading DWARF without a file	269
9.90 A simple report on section groups	275
10 Data Structure Documentation	279
10.1 Dwarf_Block_s Struct Reference	279
10.2 Dwarf_Cmdline_Options_s Struct Reference	279
10.2.1 Detailed Description	279
10.3 Dwarf_Debug_Fission_Per_CU_s Struct Reference	280
10.4 Dwarf_Form_Data16_s Struct Reference	280
10.5 Dwarf_Macro_Details_s Struct Reference	280
10.5.1 Detailed Description	280
10.6 Dwarf_Obj_Access_Interface_a_s Struct Reference	281
10.7 Dwarf_Obj_Access_Methods_a_s Struct Reference	281
10.7.1 Detailed Description	281
10.8 Dwarf_Obj_Access_Section_a_s Struct Reference	282
10.9 Dwarf_Printf_Callback_Info_s Struct Reference	282
10.9.1 Detailed Description	282
10.10 Dwarf_Ranges_s Struct Reference	283
10.11 Dwarf_Regtable3_s Struct Reference	283
10.12 Dwarf_Regtable_Entry3_s Struct Reference	283
10.13 Dwarf_Sig8_s Struct Reference	283
11 File Documentation	285
12 checkexamples.c	287
12.1 /home/davea/dwarf/code/src/bin/dwarfexample/jitreader.c File Reference	287
12.2 /home/davea/dwarf/code/src/bin/dwarfexample/showsectiongroups.c File Reference	287
13 dwarf.h	289
13.1 dwarf.h	289
14 libdwarf.h	309
14.1 libdwarf.h	309
Index	345

Chapter 1

A Consumer Library Interface to DWARF

1.1 Suggestions for improvement are welcome
1.2 Introduction
1.3 Thread Safety
1.4 Error Handling in libdwarf
1.4.1 Error Handling at Initialization
1.4.2 Error Handling Everywhere
1.5 Extracting Data Per Compilation Unit
1.6 Line Table Registers
1.7 Reading Special Sections Independently
1.8 Special Frame Registers
1.9 .debug_pubnames etc DWARF2-DWARF4
1.10 Reading DWARF with no object file present
1.11 Section Groups: Split Dwarf, COMDAT groups
1.12 Details on separate DWARF object access
1.13 Linking against libdwarf.so (or dll or dylib)
1.14 Linking against libdwarf.a
1.15 Suppressing CRC calculation for debuglink
1.16 dwsec_mmap
1.17 Recent Changes

Author

David Anderson

Copyright

This work is licensed under the Creative Commons Attribution 4.0 International License. To view a copy of this license, visit http://creativecommons.org/licenses/by/4.0/ or send a letter to Creative Commons, PO Box 1866, Mountain View, CA 94042, USA.

Date

2025-04-02 v0.12.0

1.1 Suggestions for improvement are welcome.

Your thoughts on the document?

- A) Are the section and subsection titles on Main Page meaningful to you?
- B) Are the titles on the Modules page meaningful to you?

Anything else you find misleading or confusing? Send suggestions to (libdwarf-list (at) prevanders with final characters .org) Sorry about the simple obfuscation to keep bots away. It's actually a simple email address, not a list.

Thanks in advance for any suggestions.

1.2 Introduction

This document describes an interface to *libdwarf*, a library of functions to provide access to DWARF debugging information records, DWARF line number information, DWARF address range and global names information, weak names information, DWARF frame description information, DWARF static function names, DWARF static variables, and DWARF type information. In addition the library provides access to several object sections (created by compiler writers and for debuggers) related to debugging but not mentioned in any DWARF standard.

The DWARF Standard has long mentioned the "Unix International Programming Languages Special Interest Group" (PLSIG), under whose auspices the DWARF committee was formed around 1991. "Unix International" was disbanded in the 1990s and no longer exists.

The DWARF committee published DWARF2 July 27, 1993, DWARF3 in 2005, DWARF4 in 2010, and DWARF5 in 2017.

In the mid 1990s this document and the library it describes (which the committee never endorsed, having decided not to endorse or approve any particular library interface) was made available on the internet by Silicon Graphics, Inc.

In 2005 the DWARF committee began an affiliation with FreeStandards.org. In 2007 FreeStandards.org merged with The Linux Foundation. The DWARF committee dropped its affiliation with FreeStandards.org in 2007 and established the dwarfstd.org website.

See also

https://www.dwarfstd.org for current information on standardization activities and a copy of the standard.

1.3 Thread Safety

Libdwarf can safely open multiple Dwarf_Debug pointers simultaneously but all such Dwarf_Debug pointers must be opened within the same thread. And all *libdwarf* calls must be made from within that single (same) thread.

1.4 Error Handling in libdwarf

Essentially every *libdwarf* call could involve dealing with an error (possibly data corruption in the object file). Here we explain the two main approaches the library provides (though we think only one of them is truly appropriate except in toy programs). In all cases where the library returns an error code (almost every library function does) the caller should check whether the returned integer is DW_DLV_OK, DW_DLV_ERROR, or DW_DLV_NO_ENTRY and then act accordingly.

A) The recommended approach is to define a Dwarf Error and initialize it to 0.

```
Dwarf_Error error = 0;
```

Then, in every call where there is a Dwarf_Error argument pass its address. For example:

```
int res = dwarf_tag(die,DW_TAG_compile_unit,&error);
```

The possible return values to res are, in general:

```
DW_DLV_OK
DW_DLV_NO_ENTRY
DW_DLV_ERROR
```

If **DW_DLV_ERROR** is returned then error is set (by the library) to a pointer to important details about the error and the library will not pass back any data through other pointer arguments. If **DW_DLV_NO_ENTRY** is returned the error argument is ignored by the library and the library will not pass back any data through pointer arguments. If **DW_DLV_OK** is returned argument pointers that are defined as ways to return data to your code are used and values are set in your data by the library.

Some functions cannot possibly return some of these three values. As defined later for each function.

B) An alternative (not recommended) approach is to pass NULL to the error argument.

```
int res = dwarf_tag(die,DW_TAG_compile_unit,NULL);
```

If your initialization provided an 'errhand' function pointer argument (see below) the library will call errhand if an error is encountered. (Your errhand function could exit if you so choose.)

The the library will then return DW_DLV_ERROR, though you will have no way to identify what the error was. Could be a malloc fail or data corruption or an invalid argument to the call, or something else.

That is the whole picture. The library never calls exit() under any circumstances.

1.4.1 Error Handling at Initialization

Each initialization call (for example)

```
Dwarf_Debug dbg = 0;
const char *path = "myobjectfile";
char *true_path = 0;
unsigned int true_pathlen = 0;
Dwarf_Handler errhand = 0;
Dwarf_Ptr errarg = 0;
Dwarf_Error error = 0;
int res = 0;
res = dwarf_init_path(path, true_path, true_pathlen,
DW_GROUPNUMBER_ANY, errhand, errarg, &dbg, &error);
```

has two arguments that appear nowhere else in the library.

```
Dwarf_Handler errhand
Dwarf_Ptr errarg
```

For the recommended A) approach:

Just pass NULL to both those arguments. If the initialization call returns DW_DLV_ERROR you should then call dwarf_dealloc_error(dbg, error);

to free the Dwarf_Error data because dwarf_finish() does not clean up a dwarf-init error. This works even though dbg will be NULL.

For the **not recommended B)** approach:

Because dw_errarg is a general pointer one could create a struct with data of interest and use a pointer to the struct as the dw_errarg. Or one could use an integer or NULL, it just depends what you want to do in the Dwarf_Handler function you write.

If you wish to provide a dw_errhand, define a function (this first example is not a good choice as it terminates the application!).

and pass bad_dw_errhandler (as a function pointer, no parentheses).

The Dwarf_Ptr argument your error handler function receives is the value you passed in as dw_errarg, and can be anything, it allows you to associate the callback with a particular dwarf_init* call if you wish to make such an association.

By doing an exit() you guarantee that your application abruptly stops. This is only acceptable in toy or practice programs.

A better dw errhand function is

```
void my_dw_errhandler(Dwarf_Error error,Dwarf_Ptr ptr)
{
    /* Clearly one could write to a log file or do
        whatever the application finds useful. */
    printf("ERROR on %lx due to error 0x%lx %s\n",
            (unsigned long)ptr,
            (unsigned long)dwarf_errno(error),
            dwarf_errmsg(error));
}
```

because it returns rather than exiting. It is not ideal. The DW_DLV_ERROR code is returned from *libdwarf* and your code can do what it likes with the error situation. The library will continue from the error and will return an error code on returning to your @elibdwarf call ... but the calling function will not know what the error was.

```
Dwarf_Ptr x = address of some struct I want in the errhandler;
res = dwarf_init_path(...,my_dw_errhandler,x,...);
if (res == ...)
```

If you do not wish to provide a dw_errhand, just pass both arguments as NULL.

1.4.2 Error Handling Everywhere

So let us examine a simple case where anything could happen. We are taking the **recommended A)** method of using a non-null Dwarf_Error*:

1.4.2.1 DW_DLV_OK

When res == DW_DLV_OK newdie is a valid pointer and when appropriate we should do dwarf_dealloc_die(newdie). For other *libdwarf* calls the meaning depends on the function called, so read the description of the function you called for more information.

1.4.2.2 DW DLV NO ENTRY

When res == DW_DLV_NO_ENTRY then newdie is not set and there is no error. It means die was the last of a siblinglist. For other *libdwarf* calls the meaning depends on the function called, so read the description of the function you called for more information.

1.4.2.3 DW DLV ERROR

When res == DW_DLV_ERROR Something bad happened. The only way to know what happened is to examine the *error as in

```
int ev = dwarf_errno(*error);
or
char * msg = dwarf_errmsg(*error);
```

or both and report that somehow.

The above three values are the only returns possible from the great majority of *libdwarf* functions, and for these functions the return type is always **int** .

If it is a decently large or long-running program then you want to free any local memory you allocated and return res. If it is a small or experimental program print something and exit (possibly leaking memory).

```
If you want to discard the error report from the dwarf_siblingof_c() call then possibly do
dwarf_dealloc_error(dbg,*error);
*error = 0;
return DW_DLV_OK;
```

Except in a special case involving function dwarf_set_de_alloc_flag() (which you will not usually call), any dwarf_dealloc() that is needed will happen automatically when you call dwarf_finish().

1.4.2.4 Slight Performance Enhancement

Very long running library access programs using relevant appropriate dwarf_dealloc calls should consider calling dwarf_set_de_alloc_flag(0). Using this one could get a performance enhancement of perhaps five percent in *libdwarf* CPU time and a reduction in memory use.

Be sure to test using valgrind or -fsanitize to ensure your code really does the extra dwarf_dealloc calls needed since when using dwarf_set_de_alloc_flag(0) dwarf_finish() does only limited cleanup.

1.5 Extracting Data Per Compilation Unit

The library is designed to run a single pass through the set of Compilation Units (CUs), via a sequence of calls to dwarf_next_cu_header_e(). (dwarf_next_cu_header_d() is supported but its use requires that it be immediately followed by a call to dwarf_siblingof_b(). see dwarf_next_cu_header_d().)

Within a CU opened with dwarf_next_cu_header_e() do something (if desired) on the CU_DIE returned, and call dwarf_child() on the CU_DIE to begin recursing through all DIEs. If you save the CU_DIE you can repeat passes beginning with dwarf_child() on the CU_DIE, though it almost certainly faster to remember, in your data structures, what you need from the first pass.

The general plan:

```
create your local data structure(s)

A. Check your local data structures to see if you have what you need

B. If sufficient data present act on it, ensuring your data structures are kept for further use.

C. Otherwise Read a CU, recording relevant data in your structures and loop back to A.
```

For an example (best approach)

See also

Example walking CUs(e) or (second-best approach)

Example walking CUs(d) Write your code to record relevant (to you) information from each CU as you go so your code has no need for a second pass through the CUs. This is much much faster than allowing multiple passes would be.

1.6 Line Table Registers

Line Table Registers

Please refer to the DWARF5 Standard for details. The line table registers are named in Section 6.2.2 State Machine Registers and are not much changed from DWARF2.

Certain functions on Dwarf_Line data return values for these 'registers' as these are the data available for debuggers and other tools to relate a code address to a source file name and possibly also to a line number and column-number within the source file.

```
address
op_index
file
line
column
is_stmt
basic_block
end_sequence
prologue_end
epilogue_begin
isa
discriminator
```

1.7 Reading Special Sections Independently

DWARF defines (in each version of DWARF) sections which have a somewhat special character. These are referenced from compilation units and other places and the Standard does not forbid blocks of random bytes at the start or end or between the areas referenced from elsewhere.

Sometimes compilers (or linkers) leave trash behind as a result of optimizations. If there is a lot of space wasted that way it is quality of implementation issue. But usually the wasted space, if any, is small.

Compiler writers or others may be interested in looking at these sections independently so *libdwarf* provides functions that allow reading the sections without reference to what references them.

Abbreviations can be read independently

Strings can be read independently

String Offsets can be read independently

The addr table can be read independently

Those functions allow starting at byte 0 of the section and provide a length so you can calculate the next section offset to call or refer to.

Usually that works fine. If there is some random data somewhere outside of referenced areas or the data format is a gcc extension of an early DWARF version the reader function may fail, returning DW_DLV_ERROR. Such an error is neither a compiler bug nor a *libdwarf* bug.

1.8 Special Frame Registers

In dealing with .debug_frame or .eh_frame there are five values that must be set unless one has relatively few registers in the target ABI (anything under 188 registers, see dwarf.h DW FRAME LAST REG NUM for this default).

The requirements stem from the design of the section. See the DWARF5 Standard for details. The .debug_frame section is basically the same from DWARF2 on. The .eh_frame section is similar to .debug_frame but is intended to support exception handling and has fields and data not present in .debug_frame.

Keep in mind that register values correspond to columns in the theoretical fully complete line table of a row per pc and a column per register.

There is no time or space penalty in setting **Undefined_Value**, **Same_Value**, and **CFA_Column** much larger than the **Table Size**.

Here are the five values.

Table_Size: This sets the number of columns in the theoretical table. It starts at DW_FRAME_LAST_REG_NUM which defaults to 188. This is the only value you might need to change, given the defaults of the others are set reasonably large by default.

Undefined_Value: A register number that means the register value is undefined. For example due to a call clobbering the register. DW_FRAME_UNDEFINED_VAL defaults to 12288. There no such column in the table.

Same_Value: A register number that means the register value is the same as the value at the call. Nothing can have clobbered it. DW_FRAME_SAME_VAL defaults to 12289. There no such column in the table.

Initial_Value: The value must be either DW_FRAME_UNDEFINED_VAL or DW_FRAME_SAME_VAL to represent how most registers are to be thought of at a function call. This is a property of the ABI and instruction set. Specific frame instructions in the CIE or FDE will override this for registers not matching this value.

CFA_Column: A number for the CFA. Defined so we can use a register number to refer to it. DW_FRAME_CFA COL defaults to 12290. There no such column in the table. See libdwarf.h struct Dwarf_Regtable3_s member rt3_cfa_rule or function dwarf_get_fde_info_for_cfa_reg3_b() or function dwarf_get_fde_info_for_cfa_reg3_c() .

A set of functions allow these to be changed at runtime. The set should be called (if needed) immediately after initializing a Dwarf_Debug and before any other calls on that Dwarf_Debug. If just one value (for example, Table — _Size) needs altering, then just call that single function.

For the library accessing frame data to work properly there are certain invariants that must be true once the set of functions have been called.

REQUIRED:

```
Table_Size > the number of registers in the ABI.
Undefined_Value != Same_Value
CFA_Column != Undefined_value
CFA_Column != Same_value
Initial_Value == Same_Value ||
    (Initial_Value == Undefined_value)
Undefined_Value > Table_Size
Same_Value > Table_Size
CFA_Column > Table_Size
```

1.9 .debug_pubnames etc DWARF2-DWARF4

Each section consists of a header for a specific compilation unit (CU) followed by an a set of tuples, each tuple consisting of an offset of a compilation unit followed by a null-terminated namestring. The tuple set is ended by a 0,0 pair. Then followed with the data for the next CU and so on.

The function set provided for each such section allows one to print all the section data as it literally appears in the section (with headers and tuples) or to treat it as a single array with CU data columns.

Each has a set of 6 functions.

```
Section typename Standard
debug_pubnames Dwarf_Global DWARF2-DWARF4
debug_pubtypes Dwarf_Global DWARF3,DWARF4
```

These sections are accessed calling dwarf_globals_by_type() using type of DW_GL_GLOBALS or DW_GL_← PUBTYPES. Or call dwarf_get_pubtypes().

The following four were defined in SGI/IRIX compilers in the 1990s but were never part of the DWARF standard. These sections are accessed calling dwarf_globals_by_type() using type of DW_GL_FUNCS,DW_GL_← TYPES,DW_GL_VARS, or DW_GL_WEAKS.

It not likely you will encounter these four sections.

```
.debug_funcs
.debug_typenames
.debug_vars
.debug_weaks
```

1.10 Reading DWARF with no object file present

This most commonly happens with just-in-time compilation, and someone working on the code wants do debug this on-the-fly code in a situation where nothing can be written to disc, but DWARF can be constructed in memory.

For a simple example of this

See also

Demonstrating reading DWARF without a file.

But the libdwarf feature can be used in a wide variety of ways.

For example, the DWARF data could be kept in simple files of bytes on the internet. Or on the local net. Or if files can be written locally each section could be kept in a simple stream of bytes in the local file system.

Another example is a non-standard file system, or file format, with the intent of obfuscating the file or the DWARF.

For this to work the code generator must generate standard DWARF.

Overall the idea is a simple one: You write a small handful of functions and supply function pointers and code implementing the functions. These are part of your application or library, not part of *libdwarf*.

You set up a little bit of data with that code (all described below) and then you have essentially written the dwarf ← _init_path equivalent and you can access compilation units, line tables etc and the standard *libdwarf* function calls work.

Data you need to create involves these types. What follows describes how to fill them in and how to make them work for you.

```
typedef struct Dwarf_Obj_Access_Interface_a_s
   Dwarf_Obj_Access_Interface_a;
struct Dwarf_Obj_Access_Interface_a_s {
                                      ai object;
    const Dwarf_Obj_Access_Methods_a *ai_methods;
typedef struct Dwarf_Obj_Access_Methods_a_s
   Dwarf_Obj_Access_Methods_a
struct Dwarf_Obj_Access_Methods_a_s {
          (*om_get_section_info)(void* obj,
       Dwarf_Unsigned section_index,
       Dwarf_Obj_Access_Section_a* return_section,
       int* error);
    Dwarf Small
                     (*om_get_byte_order) (void* obj);
    Dwarf_Small
                    (*om_get_length_size)(void* obj);
                     (*om_get_pointer_size) (void* obj);
    Dwarf Small
    Dwarf_Unsigned (*om_get_filesize)(void* obj);
    Dwarf_Unsigned (*om_get_section_count)(void* obj);
    int
                     (*om_load_section)(void* obj,
        Dwarf_Unsigned section_index,
       Dwarf_Small** return_data, int* error);
                     (*om_relocate_a_section) (void* obj,
       Dwarf_Unsigned section_index,
       Dwarf_Debug dbg,
       int* error);
};
typedef struct Dwarf_Obj_Access_Section_a_s
    Dwarf_Obj_Access_Section_a
struct Dwarf_Obj_Access_Section_a_s {
    const char*
                  as_name;
    Dwarf_Unsigned as_type;
    Dwarf_Unsigned as_flags;
    Dwarf Addr
                  as_addr;
    Dwarf_Unsigned as_offset;
    Dwarf_Unsigned as_size;
    Dwarf_Unsigned as_link;
    Dwarf Unsigned as info:
    Dwarf_Unsigned as_addralign;
    Dwarf_Unsigned as_entrysize;
```

};

Dwarf_Obj_Access_Section_a: Your implementation of a **om_get_section_info** must fill in a few fields for *libdwarf*. The fields here are standard Elf, but for most you can just use the value zero. We assume here you will not be doing relocations at runtime.

as_name: Here you set a section name via the pointer. The section names must be names as defined in the DWARF standard, so if such do not appear in your data you have to create the strings yourself.

as_type: Fill in zero.
as_flags: Fill in zero.

as_addr: Fill in the address, in local memory, where the bytes of the section are.

as offset: Fill in zero.

as_size: Fill in the size, in bytes, of the section you are telling libdwarf about.

as_link: Fill in zero.
as_info: Fill in zero.
as_addralign: Fill in zero.
as_entrysize: Fill in one(1).

Dwarf Obj Access Methods a s: The functions we need to access object data from libdwarf are declared here.

In these function pointer declarations 'void *obj' is intended to be a pointer (the object field in Dwarf_Obj_Access Later Interface_s) that hides the library-specific and object-specific data that makes it possible to handle multiple object formats and multiple libraries. It is not required that one handles multiple such in a single *libdwarf* archive/shared-library (but not ruled out either). See dwarf_elf_object_access_internals_t and dwarf_elf_access.c for an example.

Usually the struct **Dwarf_Obj_Access_Methods_a_s** is statically defined and the function pointers are set at compile time.

The om_get_filesize member is new September 4, 2021. Its position is NOT at the end of the list. The member names all now have om prefix.

1.11 Section Groups: Split Dwarf, COMDAT groups

A typical executable or shared object is unlikely to have any section groups, and in that case what follows is irrelevant and unimportant.

COMDAT groups are defined by the Elf ABI and enable compilers and linkers to work together to eliminate blocks of duplicate DWARF and duplicate CODE.

Split Dwarf (sometimes referred to as Debug Fission) allows compilers and linkers to separate large amounts of DWARF from the executable, shrinking disk space needed in the executable while allowing full debugging (also applies to shared objects).

See the DWARF5 Standard, Section E.1 Using Compilation Units page 364.

To name COMDAT groups (defined later here) we add the following defines to libdwarf.h (the DWARF standard does not specify how to do any of this).

```
/* These support opening DWARF5 split dwarf objects and
    Elf SHT_GROUP blocks of DWARF sections. */
#define DW_GROUPNUMBER_ANY 0
#define DW_GROUPNUMBER_BASE 1
#define DW GROUPNUMBER DWO 2
```

The DW_GROUPNUMBER_ are used in *libdwarf* functions dwarf_init_path(), dwarf_init_path_dl() and dwarf_init_b(). In all those cases unless you know there is any complexity in your object file, pass in DW_ GROUPNUMBER_ANY.

To see section groups usage, see the example source:

See also

A simple report on section groups. Examining Section Group data

The function interface declarations:

See also

```
dwarf_sec_group_sizes
dwarf_sec_group_map
```

If an object file has multiple groups *libdwarf* will not reveal contents of more than the single requested group with a given dwarf_init_path() call. One must pass in another groupnumber to another dwarf_init_path(), meaning initialize a new Dwarf_Debug, to get *libdwarf* to access that group.

When opening a Dwarf Debug the following applies:

If DW_GROUPNUMBER_ANY is passed in *libdwarf* will choose either of DW_GROUPNUMBER_BASE(1) or DW ← _GROUPNUMBER_DWO (2) depending on the object content. If both groups one and two are in the object *libdwarf* will chose DW GROUPNUMBER_BASE.

If DW_GROUPNUMBER_BASE is passed in *libdwarf* will choose it if non-split DWARF is in the object, else the init call will return DW DLV NO ENTRY.

If DW_GROUPNUMBER_DWO is passed in *libdwarf* will choose it if .dwo sections are in the object, else the init will call return DW DLV NO ENTRY.

If a groupnumber greater than two is passed in *libdwarf* accepts it, whether any sections corresponding to that groupnumber exist or not. If the groupnumber is not an actual group the init will call return DW DLV NO ENTRY.

For information on groups "dwarfdump -i" on an object file will show all section group information **unless** the object file is a simple standard object with no .dwo sections and no COMDAT groups (in which case the output will be silent on groups). Look for **Section Groups data** in the dwarfdump output. The groups information will be appearing very early in the dwarfdump output.

Sections that are part of an Elf COMDAT GROUP are assigned a group number > 2. There can be many such COMDAT groups in an object file (but none in an executable or shared object). Each such COMDAT group will have a small set of sections in it and each section in such a group will be assigned the same group number by *libdwarf*.

Sections that are in a .dwp .dwo object file are assigned to DW_GROUPNUMBER_DWO,

Sections not part of a .dwp package file or a.dwo section, or a COMDAT group are assigned DW $_{\leftarrow}$ GROUPNUMBER BASE.

At least one compiler relies on relocations to identify COMDAT groups, but the compiler authors do not publicly document how this works so we ignore such (these COMDAT groups will result in *libdwarf* returning DW_DLV_
ERROR).

Popular compilers and tools are using such sections. There is no detailed documentation that we can find (so far) on how the COMDAT section groups are used, so *libdwarf* is based on observations of what compilers generate.

1.12 Details on separate DWARF object access

There are, at present, three distinct approaches in use to put DWARF information into separate objects to significantly shrink the size of the executable. All of them involve identifying a separate file.

Split Dwarf is one method. It defines the attribute **DW_AT_dwo_name** (if present) as having a file-system appropriate name of the split object with most of the DWARF.

The second is Macos dSYM. It is a convention of placing the DWARF-containing object (separate from the object containing code) in a specific subdirectory tree.

The third involves GNU debuglink and GNU debug_id. These are two distinct ways (outside of DWARF) to provide names of alternative DWARF-containing objects elsewhere in a file system.

If one initializes a Dwarf_Debug object with dwarf_init_path() or dwarf_init_path_dl() appropriately *libdwarf* will automatically open the alternate dSYM or debuglink/debug_id object on the object with most of the DWARF.

See also

```
https://sourceware.org/gdb/onlinedocs/gdb/Separate-Debug-Files.html
```

libdwarf provides means to automatically read the alternate object (in place of the one named in the init call) or to suppress that and read the named object file.

```
int dwarf_init_path(const char * dw_path,
char *
                  dw_true_path_out_buffer,
unsigned int
                  dw_true_path_bufferlen,
unsigned int.
                  dw groupnumber,
Dwarf_Handler
                  dw_errhand,
Dwarf_Ptr
                  dw_errarg,
Dwarf_Debug*
                  dw_dbg,
Dwarf_Error*
                  dw_error);
int dwarf_init_path_dl(const char *dw_path,
                * true path out buffer.
char
unsigned
                true_path_bufferlen,
unsigned
                groupnumber,
Dwarf_Handler
                errhand,
Dwarf_Ptr
                errarg,
Dwarf_Debug
                * ret_dbg,
                ** dl_path_array,
char
unsigned int
               dl path count,
unsigned char
                * path_source,
Dwarf_Error
                * error);
```

Case 1:

If $dw_true_path_out_buffer$ or $dw_true_path_bufferlen$ is passed in as zero then the library will not look for an alternative object.

Case 2:

If dw_true_path_out_buffer passes a pointer to space you provide and dw_true_path_bufferlen passes in the length, in bytes, of the buffer, libdwarf will look for alternate DWARF-containing objects. We advise that the caller zero all the bytes in dw true path out buffer before calling.

If the alternate object name (with its null-terminator) is too long to fit in the buffer the call will return DW_DLV_← ERROR with dw_error providing error code DW_DLE_PATH_SIZE_TOO_SMALL.

If the alternate object name fits in the buffer libdwarf will open and use that alternate file in the returned Dwarf_Dbg.

It is up to callers to notice that $dw_true_path_out_buffer$ now contains a string and callers will probably wish to do something with the string.

If the initial byte of *dw_true_path_out_buffer* is a non-null when the call returns then an alternative object was found and opened.

The second function, dwarf_init_path_dl(), is the same as dwarf_init_path() except the _dl version has three additional arguments, as follows:

Pass in NULL or *dw_dl_path_array*, an array of pointers to strings with alternate GNU debuglink paths you want searched. For most people, passing in NULL suffices.

Pass in dw_dl_path_array_size, the number of elements in dw_dl_path_array.

Pass in dw dl path source as NULL or a pointer to char. If non-null libdwarf will set it to one of three values:

- DW PATHSOURCE basic which means the original input dw path is the one opened in dw dbg.
- DW_PATHSOURCE_dsym which means a Macos dSYM object was found and is the one opened in dw_dbg. dw_true_path_out_buffer contains the dSYM object path.
- DW_PATHSOURCE_debuglink which means a GNU debuglink or GNU debug-id path was found and names the one opened in dw_dbg. dw_true_path_out_buffer contains the object path.

1.13 Linking against libdwarf.so (or dll or dylib)

If you wish to do the basic *libdwarf* tests and are linking against a shared library *libdwarf* you must do an install for the tests to succeed (in some environments it is not strictly necessary).

For example, if building with configure, do

make install make check

You can install anywhere, there is no need to install in a system directory! Creating a temporary directory and installing there suffices. If installed in appropriate system directories that works too.

When compiling to link against a shared library libdwarf you must not define LIBDWARF STATIC.

For examples of this for all three build systems read the project shell script ${\tt scripts/allsimplebuilds.sh}$

1.14 Linking against libdwarf.a

- · If you are building an application
- · And are linking your application against a static library libdwarf.a
- Then you must ensure that each source file compilation with an include of libdwarf.h has the macro LIBDWARF_STATIC defined to your source compilation.
- If *libdwarf* was built with zlib and zstd decompression library enabled you must add -lz -lzstd to the link line of the build of your application.

To pass **LIBDWARF_STATIC** to the preprocessor with Visual Studio:

- · Right click on a project name
- In the contextual menu, click on **Properties** at the very bottom.
- In the new window, double click on C/C++
- · On the right, click on Preprocessor definitions
- · There is a small down arrow on the right, click on it then click on Modify
- · Add LIBDWARF_STATIC to the values
- · Click on OK to close the windows

1.15 Suppressing CRC calculation for debuglink

GNU Debuglink-specific issue:

If GNU debuglink is present and considered by dwarf_init_path() or dwarf_init_path_dl() the library may be required to compute a 32bit crc (Cyclic Redundancy Check) on the file found via GNU debuglink.

See also

```
https://en.wikipedia.org/wiki/Cyclic_redundancy_check
```

For people doing repeated builds of objects using such the crc check is a waste of time as they know the crc comparison will pass.

For such situations a special interface function lets the dwarf_init_path() or dwarf_init_path_dl() caller suppress the crc check without having any effect on anything else in *libdwarf*.

It might be used as follows (the same pattern applies to dwarf_init_path_dl()) for any program that might do multiple dwarf_init_path() or dwarf_init_path() or dwarf_init_path() or dwarf_init_path().

```
int res = 0;
int crc_check= 0;

crc_check = dwarf_suppress_debuglink_crc(1);
res = dwarf_init_path(..usual arguments);
/* Reset the crc flag to previous value. */
dwarf_suppress_debuglink_crc(crc_check);
/* Now check res in the usual way. */
```

This pattern ensures the crc check is suppressed for this single dwarf_init_path() or dwarf_init_path_dl() call while leaving the setting unchanged for further dwarf_init_path() or dwarf_init_path_dl() calls in the running program.

1.16 dwsec_mmap

As of version 0.12.0 libdwarf allows callers to select mmap (instead of malloc/read) to access object section DWARF data. Even if mmap is selected it is possible libdwarf will chose to use malloc in specific cases.

If at library build time the required functions/header are not available the following will have no effect.

```
One way to select mmap is to call dwarf_set_load_preference(Dwarf_Alloc_Mmap);
```

Another way to select mmap is with an environment variable

so libdwarf will see the variable at runtime.

The environment variable overrides the function call.

Calling dwarf_set_load_preference(0) will return the current overall preference will return the current overall preference, an instance of

```
enum Dwarf_Sec_Alloc_Pref
```

The new function

```
dwarf_get_mmap_count(Dwarf_Debug dw_dbg)
```

returns the application count and size of allocations for DWARF sections from the open Dwarf_Debug pointer.

Each supported build environment has a new build option to prevent libdwarf from assuming that things in the build are always present.

1.17 Recent Changes 15

1.17 Recent Changes

We list these with newest first.

Changes 0.11.1 to 0.12.0

To optionally support mmap/munmap of object files sections we read we have added a function prototype for struct Dwarf_Obj_Access_Methods_a_s function om_load_section(). This will help when reading multi gigiabyte object files. And we added a function prototype for destructing the object specific data while removing library internal public functions.

If an application does not call any of the functions which are new in v0.12.0 then it will work without recompilation.

Any application calling the new functions (for example, v0.12.0 dwarfdump) will only work with a v0.12.0 libdwarf.

If one is calling dwarf_object_init_b() (almost no one ever calls this function) one is therefore instantiating struct Dwarf_Obj_Access_Methods_a_s oneself, you will surely find that your application will not work with libdwarf 0.
12.0. Moreover, recompilation will fail unless you update your source to add the two new pointers to your instantiation (typically just add two zeros or NULLs in that struct instance).

Added new API function dwarf_machine_architecture_a() which has an additional argument added to let dwarfdump create an better .text (etc) address-range for the object file being read for improved checking (fewer incorrect error reports) in dwarfdump -k output.

Up through December 2024 libdwarf could be made to be very very slow (Denial of Service) with calls with thousands of duplicate attributes in an abbreviation list of a specially constructed Compilation Unit.

Beginning 2025 by default that cannot happen as the library quickly notices and returns DW_DLV_ERROR with error details noted. Callers should check the return value and act appropriately, as always, when calling the library.

In case one has (and cannot fix) object files with duplicated attributes one can call a new API function : dwarf_library_allow_dup_attr(). The library defaults to false (0) meaning the checks are done in libdwarf by default. Pass non-zero value to allow duplicate attributes in a Debugging Information Entry through to callers.

Added the ability to select, at runtime, whether libdwarf will use malloc to load section content from an object file being read (previously the only option) or will use mmap instead.

If the build determines mmap is unavailble then malloc will be used.

Added API function dwarf_set_load_preference() giving callers the option to choose the default section load functions. Iibdwarf now recognizes the environment variable DWARF_WHICH_ALLOC to select whether the library uses mmap or malloc/read to load object section data, and the environment variable values 'DWARF_WHICH_ \leftarrow ALLOC=mmap' or 'DWARF_WHICH_ALLOC=malloc' are the only values recognized. A recognized environment variable overrides dwarf_set_load_preference() values. If the libdwarf build determines mmap is unavailble then only malloc will be used.

Added API function dwarf_get_mmap_count() giving callers the ability to determine what section loads were used and the total amount of section data loaded.

Added API function dwarf_get_LANGUAGE_name() to be able to easily get a string for DW_LNAME_Ada etc.

Added API function dwarf_language_version_string(). This returns information defined by DWARF 6 and useful in interpreting DWARF6 language-version strings based on a name accessed from DW AT language name attribute.

Changes 0.11.0 to 0.11.1

Corrected handling of DWARF5 .debug rnglists and .debug loclists. No API change, no incompatibilities.

Changes 0.10.1 to 0.11.0

Added function dwarf_get_ranges_baseaddress() to the api to allow dwarfdump and other library callers to easily derive the (cooked) address from the raw data in the DWARF2, DWARF3, DWARF4 .debug_ranges section. An example of use is in doc/checkexamples.c (see examplev).

Changes 0.9.2 to 0.10.1

Released 01 July 2024 (Release 0.10.0 was missing a CMakeLists.txt file and is withdrawn).

Added API function dwarf_get_locdesc_entry_e() to allow dwarfdump to report some data from .debug_loclists more completely – it reports a byte length of each loclist item. This is of little interest to anyone, surely. dwarf_get_locdesc_entry_d() is still what you should be using.

dwarf_debug_addr_table() now supports reading the DWARF4 GNU extension .debug_addr table.

A heuristic sanity check for PE object files was too conservative in limiting VirtualSize to 200MB. A library user has an exe with .debug_info size of over 200MB. Increased the limit to be 2000MB and changed the names of the errors for the three heuristic checks to include *HEURISTIC* so it is easier to know the kind of error/failure it is.

When doing a shared-library build with cmake we were not emitting the correct .so version names nor setting SONAME with the correct version name. This long-standing mistake is now fixed.

Changes 0.9.1 to 0.9.2

Version 0.9.2 released 2 April 2024

Vulnerabilities DW202402-001, DW202402-002, DW202402-003, and DW202403-001 could crash *libdwarf* given a carefully corrupted (fuzzed) DWARF object file. Now the library returns an error for these corruptions. DW_CFA in item incorrect spelling DW_CFA in item incorrect spelling.

Changes 0.9.0 to 0.9.1

Version 0.9.1 released 27 January 2024

The abbreviation code type returned by dwarf_die_abbrev_code() changed from int to Dwarf_Unsigned as abbrev codes are not constrained by the DWARF Standard.

The section count returned by dwarf_get_section_count() is now of type **Dwarf_Unsigned**. The previous type of **int** never made sense in *libdwarf*. Callers will, in practice, see the same value as before.

All type-warnings issued by MSVC have been fixed.

Problems reading Macho (Apple) relocatable object files have been fixed.

Each of the build systems available now has an option which eliminates *libdwarf* references to the object section decompression libraries. See the respective READMEs.

Changes 0.8.0 to 0.9.0

Version 0.9.0 released 8 December 2023

Adding functions (rarely needed) for callers with special requirements. Added dwarf_get_section_info_by_name_a() and dwarf_get_section_info_by_index_a() which add dw_section_flags pointer argument to return the object section file flags (whose meaning depends entirely on the object file format), and dw_section_offset pointer argument to return the object-relevant offset of the section (here too the meaning depends on the object format). Also added dwarf_machine_architecture() which returns a few top level data items about the object *libdwarf* has opened, including the 'machine' and 'flags' from object headers (all supported object types).

1.17 Recent Changes 17

This adds new library functions dwarf_next_cu_header_e() and dwarf_siblingof_c(). Used exactly as documented dwarf_next_cu_header_d() and dwarf_siblingof_b() work fine and continue to be supported for the forseeable future. However it would be easy to misuse as the requirement that dwarf_siblingof_b() be called immediately after a successful call to dwarf_next_cu_header_d() was never stated and that dependency was impossible to enforce. The dependency was an API mistake made in 1992.

So dwarf_next_cu_header_e() now returns the compilation-unit DIE as well as header data and dwarf_siblingof_c() is not needed except to traverse sibling DIEs. (the compilation-unit DIE by definition has no siblings).

Changes were required to support Mach-O (Apple) universal binaries, which were not readable by earlier versions of the library.

We have new library functions dwarf_init_path_a(), dwarf_init_path_dl_a(), and dwarf_get_universalbinary_count().

The first two allow a caller to specify which (numbering from zero) object file to report on by adding a new argument dw universalnumber. Passing zero as the dw universalnumber argument is always safe.

The third lets callers retrieve the number being used.

These new calls do not replace anything so existing code will work fine.

Applying the previously existing calls dwarf_init_path() dwarf_init_path_dl() to a Mach-O universal binary works, but the library will return data on the first (index zero) as a default since there is no dw_universalnumber argument possible.

For improved performance in reading Fde data when iterating though all usable pc values we add dwarf_get_fde_info_for_all_regs3_b(), which returns the next pc value with actual frame data. We retain dwarf_get_fde_info_for_all_regs3() so existing code need not change.

Changes 0.7.0 to 0.8.0

v0.8.0 released 2023-09-20

New functions dwarf_get_fde_info_for_reg3_c(), dwarf_get_fde_info_for_cfa_reg3_c() are defined. The advantage of the new versions is they correctly type the dw_offset argument return value as Dwarf_Signed instead of the earlier and incorrect type Dwarf_Unsigned.

The original functions dwarf_get_fde_info_for_reg3_b() and dwarf_get_fde_info_for_cfa_reg3_b() continue to exist and work for compatibility with the previous release.

For all open() calls for which the O_CLOEXEC flag exists we now add that flag to the open() call.

Vulnerabilities involving reading corrupt object files (created by fuzzing) have been fixed: DW202308-001 (ossfuzz 59576), DW202307-001 (ossfuzz 60506), DW202306-011 (ossfuzz 59950), DW202306-009 (ossfuzz 59755), DW202306-006 (ossfuzz 59727), DW202306-005 (ossfuzz 59717), DW202306-004 (ossfuzz 59695), DW202306-002 (ossfuzz 59519), DW202306-001 (ossfuzz 59597). DW202305-010 (ossfuzz 59478). DW202305-009 (ossfuzz 56451), DW202305-008 (ossfuzz 56451), DW202305-007 (ossfuzz 56474), DW202305-006 (ossfuzz 56472), DW202305-005 (ossfuzz 56462), DW202305-004 (ossfuzz 56446).

Changes 0.6.0 to 0.7.0

v0.7.0 released 2023-05-20

Elf section counts can exceed 16 bits (on linux see **man 5 elf**) so some function prototype members of struct **Dwarf_Obj_Access_Methods_a_s** changed. Specifically, om_get_section_info() om_load_section(), and om_counterelocate_a_section() now pass section indexes as Dwarf_Unsigned instead of Dwarf_Half. Without this change executables/objects with more than 64K sections cannot be read by *libdwarf*. This is unlikely to affect your code since for most users *libdwarf* takes care of this and dwarfdump is aware of this change.

Two functions have been removed from libdwarf.h and the library: dwarf_dnames_abbrev_by_code() and dwarf_← dnames_abbrev_form_by_index().

dwarf_dnames_abbrev_by_code() is slow and pointless. Use either dwarf_dnames_name() or dwarf_dnames_abbrevtable() instead, depending on what you want to accomplish.

dwarf_dnames_abbrev_form_by_index() is not needed, was difficult to call due to argument list requirements, and never worked.

Changes 0.5.0 to 0.6.0

v0.6.0 released 2023-02-20 The dealloc required by dwarf_offset_list() was wrong. The call could crash *libdwarf* on systems with 32bit pointers. The new and proper dealloc (for all pointer sizes) is dwarf_dealloc(dbg,offsetlistptr, ← DW_DLA_UARRAY);

A memory leak from dwarf_load_loclists() and dwarf_load_rnglists() is fixed and the libdwarf-regressiontests error that hid the leak has also been fixed.

A **compatibility** change affects callers of <code>dwarf_dietype_offset()</code>, which on success returns the offset of the target of the DW_AT_type attribute (if such exists in the Dwarf_Die). Added a pointer argument so the function can (when appropriate) return a FALSE argument indicating the offset refers to DWARF4 .debug_types section, rather than TRUE value when .debug_info is the section the offset refers to. If anyone was using this function it would fail badly (while pretending success) with a DWARF4 DW_FORM_ref_sig8 on a DW_AT_type attribute from the Dwarf_\top Die argument. One will likely encounter DWARF4 content so a single correct function seemed necessary. New regression tests will ensure this will continue to work.

A **compatibility** change affects callers of dwarf_get_pubtypes(). If an application reads .debug_pubtypes there is a **compatibility break**. Such applications must be recompiled with latest *libdwarf*, change Dwarf_Type declarations to use Dwarf_Global, and can only use the latest *libdwarf*. We are correcting a 1993 library design mistake that created extra work and documentation for library users and inflated the *libdwarf* API and documentation for no good reason.

The changes are: the data type Dwarf_Type disappears as do dwarf_pubtypename() dwarf_pubtype_die_offset(), dwarf_pubtype_cu_offset(), dwarf_pubtype_name_offsets() and dwarf_pubtypes_dealloc(). Instead the type is Dwarf_Global, the type and functions used for dwarf_get_globals(). The existing read/dealloc functions for Dwarf — Global apply to pubtypes data too.

No one should be referring to the 1990s SGI/IRIX sections .debug_weaknames, .debug_funcnames, .debug_ varnames, or .debug_typenames as they are not emitted by any compiler except from SGI/IRIX/MIPS in that period. There is (revised) support in *libdwarf* to read these sections, but we will not mention details here.

Any use of DW_FORM_strx3 or DW_FORM_addrx3 in DWARF would, in 0.5.0 and earlier, result in *libdwarf* reporting erroneous data. A copy-paste error in libdwarf/dwarf_util.c was noticed and fixed 24 January 2023 for 0.6.0. Bug **DW202301-001**.

Changes 0.4.2 to 0.5.0

v0.5.0 released 2022-11-22 The handling of the .debug_abbrev data in *libdwarf* is now more cpu-efficient (measurably faster) so access to DIEs and attribute lists is faster. The changes are library-internal so are not visible in the API.

Corrects CU and TU indexes in the .debug_names (fast access) section to be zero-based. The code for that section was previously unusable as it did not follow the DWARF5 documentation.

dwarf_get_globals() now returns a list of Dwarf_Global names and DIE offsets whether such are defined in the .debug_names or .debug_pubnames section or both. Previously it only read .debug_pubnames.

A new function, dwarf_global_tag_number(), returns the DW_TAG of any Dwarf_Global that was derived from the .debug_names section.

1.17 Recent Changes 19

Three new functions enable printing of the .debug_addr table. dwarf_debug_addr_table(), dwarf_debug_addr_by_index(), and dwarf_dealloc_debug_addr_table(). Actual use of the table(s) in .debug_addr is handled for you when an attribute invoking such is encountered (see DW_FORM_addrx, DW_FORM_addrx1 etc).

Added doc/libdwarf.dox to the distribution (left out by accident earlier).

Changes 0.4.1 to 0.4.2

0.4.2 released 2022-09-13. No API changes. No API additions. Corrected a bug in dwarf_tsearchhash.c where a delete request was accidentally assumed in all hash tree searches. It was invisible to *libdwarf* uses. Vulnerabilities DW202207-001 and DW202208-001 were fixed so error conditions when reading fuzzed object files can no longer crash *libdwarf* (the crash was possible but not certain before the fixes). In this release we believe neither *libdwarf* nor dwarfdump leak memory even when there are malloc failures. Any GNU debuglink or build-id section contents were not being properly freed (if malloced, meaning a compressed section) until 9 September 2022.

It is now possible to run the build sanity tests in all three build mechanisms (configure,cmake,meson) on linux, Mac OS, FreeBSD, and mingw msys2 (windows). *libdwarf* README.md (or README) and README.cmake document how to do builds for each supported platform and build mechanism.

Changes 0.4.0 to 0.4.1

Reading a carefully corrupted DIE with form DW_FORM_ref_sig8 could result in reading memory outside any section, possibly leading to a segmentation violation or other crash. Fixed.

See also

```
https://www.prevanders.net/dwarfbug.xml DW202206-001
```

Reading a carefully corrupted .debug_pubnames/.debug_pubtypes could lead to reading memory outside the section being read, possibly leading to a segmentation violation or other crash. Fixed.

See also

```
https://www.prevanders.net/dwarfbug.xml DW202205-001
```

libdwarf accepts DW_AT_entry_pc in a compilation unit DIE as a base address for location lists (though it will prefer DW_AT_low_pc if present, per DWARF3). A particular compiler emits DW_AT_entry_pc in a DWARF2 object, requiring this change.

libdwarf adds dwarf_suppress_debuglink_crc() so that library callers can suppress crc calculations. (useful to save the time of crc when building and testing the same thing(s) over and over; it just loses a little checking.) Additionally, *libdwarf* now properly handles objects with only GNU debug-id or only GNU debuglink.

dwarfdump adds --show-args, an option to print its arguments and version. Without that new option the version and arguments are not shown. The output of -v (--version) is a little more complete.

dwarfdump adds --suppress-debuglink-crc, an option to avoid crc calculations when rebuilding and rerunning tests depending on GNU .note.gnu.buildid or .gnu_debuglink sections. The help text and the dwarfdump.1 man page are more specific documenting --suppress-debuglink-crc and --no-follow-debuglink

Changes 0.3.4 to 0.4.0

Removed the unused Dwarf_Error argument from dwarf_return_empty_pubnames() as the function can only return DW_DLV_OK. dwarf_xu_header_free() renamed to dwarf_dealloc_xu_header(). dwarf_gdbindex_free() renamed to dwarf_dealloc_gdbindex(). dwarf_loc_head_c_dealloc_renamed to dwarf_dealloc_loc_head_c().

dwarf_get_location_op_value_d() renamed to dwarf_get_location_op_value_c(), and 3 pointless arguments removed. The dwarf_get_location_op_value_d version and the three arguments were added for DWARF5 in libdwarf-20210528 but the change was a mistake. Now reverted to the previous version.

The .debug_names section interfaces have changed. Added dwarf_dnames_offsets() to provide details of facts useful in problems reading the section. dwarf_dnames_name() now does work and the interface was changed to make it easier to use.

Changes 0.3.3 to 0.3.4

Replaced the groff -mm based libdwarf.pdf with a libdwarf.pdf generated by doxygen and latex.

Added support for the meson build system.

Updated an include in libdwarfp source files. Improved doxygen documentation of *libdwarf*. Now 'make check -j8' and the like works correctly. Fixed a bug where reading a PE (Windows) object could fail for certain section virtual size values. Added initializers to two uninitialized local variables in dwarfdump source so a compiler warning cannot not kill a –enable-wall build.

Added src/bin/dwarfexample/showsectiongroups.c so it is easy to see what groups are present in an object without all the other dwarfdump output.

Changes 20210528 to 0.3.3 (28 January 2022)

There were major revisions in going from date versioning to Semantic Versioning. Many functions were deleted and various functions changed their list of arguments. Many many filenames changed. Include lists were simplified. Far too much changed to list here.

JIT and special case DWARF

html 2

2.1 Reading DWARF not in an object file

If the DWARF you work with is in standard object files (Elf, PE, MacOS) then you can ignore this section entirely. All that this section describes is used, but it's already done for you in functions in the library:

See also

```
dwarf_init_path dwarf_init_path_dl
dwarf_init_b and
dwarf_finish .
```

This section describes how to use calls

See also

```
dwarf_object_init_b
dwarf_object_finish .
```

These functions are useful if someone is doing just-in-time compilation, and someone working on the code wants to debug this on-the-fly code in a situation where nothing can be written to disc, but DWARF can be constructed in memory.

For a simple example of this with DWARF in local arrays

See also

Demonstrating reading DWARF without a file.

But the libdwarf feature can be useful in a variety of circumstances.

For example, the DWARF data were kept in simple files of bytes on the internet. Or on the local net. Or if files can be written locally each section could be kept in a simple stream of bytes in the local file system.

Another example is a non-standard file system, or file format, with the intent of obfuscating the file or the DWARF.

For this to work the code generator must generate standard DWARF.

Overall the idea is a simple one: You write a small handful of functions and supply function pointers and code implementing the functions. These are part of your application or library, not part of *libdwarf*. Your code accesses the data in whatever way applies and you write code that provides the interfaces so standard *libdwarf* can access your DWARF content.

You set up a little bit of data with that code (described below) and then you have essentially written the dwarf_\circ
init_path equivalent and you can access compilation units, line tables etc and the standard *libdwarf* function calls simply work.

Data you need to create involves the following types. What follows describes how to fill them in and how to make them work for you.

```
typedef struct Dwarf_Obj_Access Interface a s
    Dwarf_Obj_Access_Interface_a;
struct Dwarf_Obj_Access_Interface_a_s {
                                      *ai object;
    const Dwarf_Obj_Access_Methods_a *ai_methods;
};
typedef struct Dwarf_Obj_Access_Methods_a_s
    Dwarf_Obj_Access_Methods_a
struct Dwarf_Obj_Access_Methods_a_s {
           (*om_get_section_info) (void* obj,
       Dwarf Half
                                   section_index,
       Dwarf_Obj_Access_Section_a* return_section,
       int
                                  * error);
    Dwarf_Small
                     (*om_get_byte_order)(void* obj);
    Dwarf_Small
                     (*om_get_length_size)(void* obj);
    Dwarf_Small
                     (*om_get_pointer_size) (void* obj);
    Dwarf_Unsigned (*om_get_filesize) (void* obj);
    Dwarf_Unsigned (*om_get_section_count)(void* obj);
                     (*om load section) (void* obj.
    int
       Dwarf Half
                     section index,
        Dwarf_Small** return_data,
                    (*om_relocate_a_section)(void* obj,
       Dwarf_Half section_index,
       Dwarf_Debug dbg,
                   *error);
};
typedef struct Dwarf_Obj_Access_Section_a_s
    Dwarf_Obj_Access_Section_a
struct Dwarf_Obj_Access_Section_a_s {
    const char*
                  as name:
    Dwarf_Unsigned as_type;
    Dwarf_Unsigned as_flags;
    Dwarf_Addr
                  as_addr;
    Dwarf_Unsigned as_offset;
    Dwarf_Unsigned as_size;
    Dwarf_Unsigned as_link;
    Dwarf Unsigned as info;
    Dwarf_Unsigned as_addralign;
    Dwarf_Unsigned as_entrysize;
};
```

2.1.1 Describing the Interface

struct struct Dwarf_Obj_Access_Interface_a_s

Your code must create and fill in this struct's two pointer members. Libdwarf needs these to access your DWARF data. You pass a pointer to this filled-in struct to **dwarf_object_init_b**. When it is time to conclude all access to the created Dwarf_Debug call **dwarf_object_finish**. Any allocations you made in setting these things up you must then free after calling **dwarf_object_finish**.

ai_object

Allocate a local struct (*libdwarf* will not touch this struct and will not know anything of its contents). You will need one of these for each Dwarf_Debug you open. Put a pointer to this into ai_object. Then fill in all the data you need to access information you will pass back via the ai_methods functions. In the description of the methods functions described later here, this pointer is named **obj**.

ai methods

Usually you allocate a static structure and fill it in with function pointers (to functions you write). Then put a pointer to the static structure into this field.

2.1.2 Describing A Section

Dwarf_Obj_Access_Section_a:

The set of fields here is a set that is sufficient to describe a single object section to *libdwarf*. Your implementation of a **om_get_section_info** must simply fill in a few fields (leaving most zero) for *libdwarf* for the section indexed. The fields here are standard Elf, and for most you can just fill in the value zero. For section index zero as_name should be set to an empty string (see below about section index numbers).

as_name: Here you set a section name via the pointer. The section names must be names as defined in the DWARF standard, so if such do not appear in your data you have to create the strings yourself.

as_type: Just fill in zero.

as_flags: Just fill in zero.

as_addr: Fill in the address, in local memory, where the bytes of the section are.

as_offset: Just fill in zero.

as_size: Fill in the size, in bytes, of the section you are telling libdwarf about.

as_link: Just fill in zero.

as_info: Just fill in zero.

as addralign:Just fill in zero.

as_entrysize: Just fill in one.

2.1.3 Function Pointers

struct Dwarf_Obj_Access_Methods_a_s:

The functions *libdwarf* needs to access object data are declared here. Usually the struct is statically defined and the function pointers are set at compile time. You must implement these functions based on your knowledge of how the actual data is represented and where to get it.

Each has a first-parameter of **obj** which is a struct you define to hold data you need to implement this set of functions. You refer to it When *libdwarf* calls your set of functions (these described now) it passes the ai_object pointer you provided to these functions as **obj** parameter.

This is the final part of your work for *libdwarf*. In the source file with your code you will be allocating data, making a provision for an array (real or conceptual) for per-section data, and returning values *libdwarf* needs. Note that the section array should include an index zero with all zero field values. That means interesting fields start with index one. This special case of index zero Elf is required and matches the standard Elf object format.

Notice that the **error** argument, where applicable, is an int*. Error codes passed back are DW_DLE codes and **dwarf_errmsg_by_number** may be used (by your code) to get the standard error string for that error.

om get section info

```
Get address, size, and name info about a section.
               - Your data
obj
section_index - Zero-based index.
return_section - Pointer to a structure in which
   section info will be placed. Caller must
    provide a valid pointer to a structure area.
    The structure's contents will be overwritten
   by the call to get_section_info.
              - A pointer to an integer in which an error
   code may be stored.
Return
              - Everything ok.
- Error occurred. Use 'error' to determine the
DW_DLV_ERROR
    @e libdwarf defined error.
DW_DLV_NO_ENTRY - No such section.
```

om_get_byte_order

This retrieves data you put into your ai object struct that you filled out.

```
Get from your @b ai_object whether the object file represented by this interface is big-endian (DW_END_big) or little endian (DW_END_little).

Parameters obj - Your data

Return Endianness of object, DW_END_big or DW_END_little.
```

om get length size

This retrieves data you put into your ai_object struct that you filled out.

```
Get the size of a length field in the underlying object file. @e libdwarf currently supports * 4 and 8 byte sizes, but may support larger in the future.

Perhaps the return type should be an enumeration?

Parameters
obj - Your data

Return
Size of length. Cannot fail.
```

om_get_pointer_size

This retrieves data you put into your ai_object struct that you filled out.

Get the size of a pointer field in the underlying object file.

```
@e libdwarf currently supports 4 and 8 byte sizes.
Perhaps the return type should be an enumeration?
Return
Size of pointer. Cannot fail. */
```

om_get_filesize

This retrieves data you put into your ai object struct that you filled out.

```
Parameters
obj - Your data

Return
Must return a value at least as large as any section @e libdwarf
might read. Returns a value that is a sanity check on
offsets @e libdwarf reads for this DWARF set. It need not be
a tight bound.
```

om_get_section_count

This retrieves data you put into your ai_object struct that you filled out.

```
Get the number of sections in the object file, including the index zero section with no content.

Parameters obj - Your data

Return

Number of sections.
```

om_load_section

This retrieves data you put into your **ai_object** struct that you filled out.

Get a pointer to an array of bytes that are the section content.

```
Get a pointer to an array of bytes that represent the section.

Parameters
obj - Your data
section_index - Zero-based section index.
return_data - Place the address of this section content into *return_data.
error - Pointer to an integer for returning libdwarf-defined error numbers.

Return
DW_DLV_OK - No error.
DW_DLV_ERROR - Error. Use 'error' to indicate a libdwarf-defined error number.
DW_DLV_NO_ENTRY - No such section. */
```

om_relocate_a_section

```
Leave this pointer NULL.
If relocations are required it is probably simpler
for you do to them yourself n your
implementation of @b om_load_section . Any relocations this function pointer
is to use must be in standard Elf
relocation (32 or 64 bit) form and must be
in an appropriately named Elf relocation section.
Parameters
obj - Your data
section_index - Zero-based index of the
    section to be relocated.
error - Pointer to an integer for returning libdwarf-defined
    error numbers.
Return
DW_DLV_OK - No error.
DW_DLV_ERROR - Error. Use 'error' to indicate
    a libdwarf-defined
error number.
DW_DLV_NO_ENTRY - No such section.
```

dwarf.h

dwarf.h contains all the identifiers such as DW_TAG_compile_unit etc from the various versions of the DWARF Standard beginning with DWARF2 and containing all later Dwarf Standard identifiers.

In addition, it contains all user-defined identifiers that we have been able to find.

All identifiers here are C defines with the prefix "DW_" .

28 dwarf.h

libdwarf.h

libdwarf.h contains all the type declarations and function function declarations needed to use the library. It is essential that coders include dwarf.h before including libdwarf.h.

All identifiers here in the public namespace begin with DW_ or Dwarf_ or dwarf_ . All function argument names declared here begin with dw_{-} .

30 libdwarf.h

checkexamples.c

checkexamples.c contains what user code should be. Hence the code typed in checkexamples.c is PUBLIC DO-MAIN and may be copied, used, and altered without any restrictions.

checkexamples.c need not be compiled routinely nor should it ever be executed.

To verify syntatic correctness compile in the libdwarf-code/doc directory with:

```
cc -c -Wall -00 -Wpointer-arith \
  -Wdeclaration-after-statement \
  -Wextra -Wcomment -Wformat -Wpedantic -Wuninitialized \
  -Wno-long-long -Wshadow -Wbad-function-cast \
  -Wmissing-parameter-type -Wnested-externs \
  -I../src/lib/libdwarf checkexamples.c
```

32 checkexamples.c

Topic Index

6.1 Topics

Here is a list of all topics with brief descriptions:

Basic Library Datatypes Group	 	 	 	39
Enumerators with various purposes	 	 	 	40
Defined and Opaque Structs	 	 	 	42
Default stack frame macros	 	 	 	51
DW_DLA alloc/dealloc typename&number	 	 	 	51
DW_DLE Dwarf_Error numbers	 	 	 	52
Libdwarf Initialization Functions				62
Compilation Unit (CU) Access				69
Debugging Information Entry (DIE) content	 	 	 	76
DIE Attribute and Attribute-Form Details	 	 	 	90
Line Table For a CU				103
Ranges: code addresses in DWARF3-4				119
Rnglists: code addresses in DWARF5				121
Locations of data: DWARF2-DWARF5				126
.debug_addr access: DWARF5	 	 	 	134
Macro Access: DWARF5				136
Macro Access: DWARF2-4				142
Stack Frame Access				143
Abbreviations Section Details				160
String Section .debug_str Details				163
Str_Offsets section details	 	 	 	164
Dwarf_Error Functions	 	 	 	167
Generic dwarf_dealloc Function	 	 	 	169
Access to Section .debug_sup	 	 	 	170
Fast Access to .debug_names DWARF5	 	 	 	171
Fast Access to a CU given a code address	 	 	 	178
Fast Access to .debug_pubnames and more	 	 	 	181
Fast Access to GNU .debug_gnu_pubnames				187
Fast Access to Gdb Index				189
Fast Access to Split Dwarf (Debug Fission)	 	 	 	197
Access GNU .gnu_debuglink, build-id	 	 	 	201
Harmless Error recording	 	 	 	206
Names DW_TAG_member etc as strings	 	 	 	208
Object Sections Data	 	 	 	212
Section Groups Objectfile Data	 	 	 	220

34 Topic Index

LEB Encode and Decode	22
Miscellaneous Functions	23
Determine Object Type of a File	27
Section allocation: malloc or mmap	27
Using dwarf_init_path()	29
Using dwarf_init_path_dl()	30
Using dwarf_attrlist()	31
Attaching a tied dbg	
Detaching a tied dbg	32
Examining Section Group data	32
Using dwarf_siblingof_c()	33
Using dwarf_siblingof_b()	
Using dwarf_child()	34
using dwarf_validate_die_sibling	35
Example walking CUs(e)	
Example walking CUs(d)	
Using dwarf_offdie_b()	
Using dwarf_offset_given_die()	
Using dwarf_attrlist()	
Using dwarf_offset_list()	
Documenting Form Block	
Using dwarf_discr_list()	
Location/expression access	
Reading a location expression	
Using dwarf_srclines_b()	
Using dwarf_srclines_b() and linecontext	
Using dwarf_srcfiles()	
Using dwarf_get_globals()	
Using dwarf_globals_by_type()	
Reading .debug_weaknames (nonstandard)	
Reading .debug_funcnames (nonstandard)	
Reading .debug_types (nonstandard)	
Reading .debug_varnames data (nonstandard)	
Reading .debug_names data	
Reading .debug_macro data (DWARF5)	
Reading .debug macinfo (DWARF2-4)	
Extracting fde, cie lists	
	.57 257
• -	
0 = 1 = =	58
	258
	60
1 0 0 0= 0	61
	62
0 0	63
5 5 7	63
3 3	64
	65
	65
	65
	66
	266
	67
0 0	69
	69
A simple report on section groups	75

Data Structure Index

7.1 Data Structures

Here are the data structures with brief descriptions:

Dwarf_Block_s	279
Dwarf_Cmdline_Options_s	279
Dwarf_Debug_Fission_Per_CU_s	280
Dwarf_Form_Data16_s	280
Dwarf_Macro_Details_s	280
Dwarf_Obj_Access_Interface_a_s	281
Dwarf_Obj_Access_Methods_a_s	281
Dwarf_Obj_Access_Section_a_s	282
Dwarf_Printf_Callback_Info_s	282
Dwarf_Ranges_s	283
Dwarf_Regtable3_s	283
Dwarf_Regtable_Entry3_s	283
Dwarf_Sig8_s	283

36 Data Structure Index

File Index

8.1 File List

Here is a list of all documented files with brief descriptions:

checkexamples.c	287
/home/davea/dwarf/code/src/bin/dwarfexample/jitreader.c	287
/home/davea/dwarf/code/src/bin/dwarfexample/showsectiongroups.c	287
/home/davea/dwarf/code/src/lib/libdwarf/dwarf.h	289
/home/dayea/dwarf/code/src/lib/libdwarf/libdwarf h	309

38 File Index

Topic Documentation

9.1 Basic Library Datatypes Group

Typedefs

- · typedef unsigned long long Dwarf Unsigned
- typedef signed long long Dwarf_Signed
- typedef unsigned long long Dwarf_Off
- typedef unsigned long long Dwarf_Addr
- typedef int Dwarf_Bool
- typedef unsigned short Dwarf_Half
- typedef unsigned char Dwarf_Small
- typedef void * Dwarf_Ptr

9.1.1 Detailed Description

9.1.2 Typedef Documentation

9.1.2.1 Dwarf_Unsigned

Dwarf_Unsigned

The basic unsigned data type. Intended to be an unsigned 64bit value.

9.1.2.2 Dwarf_Signed

Dwarf_Signed

The basic signed data type. Intended to be a signed 64bit value.

9.1.2.3 Dwarf_Off

Dwarf_Off

Used for offsets. It should be same size as Dwarf_Unsigned.

9.1.2.4 Dwarf_Addr

Dwarf_Addr

Used when a data item is a an address represented in DWARF. 64 bits. Must be as large as the largest object address size.

9.1.2.5 Dwarf_Bool

Dwarf_Bool

A TRUE(non-zero)/FALSE(zero) data item.

9.1.2.6 Dwarf Half

Dwarf_Half

Many libdwarf values (attribute codes, for example) are defined by the standard to be 16 bits, and this datatype reflects that (the type must be at least 16 bits wide).

9.1.2.7 Dwarf Small

Dwarf_Small

Used for small unsigned integers and used as Dwarf_Small* for pointers and it supports pointer addition and subtraction conveniently.

9.1.2.8 Dwarf Ptr

Dwarf_Ptr

A generic pointer type. It uses void * so it cannot be added-to or subtracted-from.

9.2 Enumerators with various purposes

Enumerations

- enum Dwarf_Ranges_Entry_Type { DW_RANGES_ENTRY , DW_RANGES_ADDRESS_SELECTION , DW_RANGES_END }
- enum Dwarf Form Class {

DW_FORM_CLASS_UNKNOWN = 0 , DW_FORM_CLASS_ADDRESS = 1 , DW_FORM_CLASS_BLOCK = 2 , DW_FORM_CLASS_CONSTANT = 3 ,

 $\label{eq:dw_form_class_exprloc} \mbox{DW_form_class_flag} = 5 \; , \\ \mbox{DW_form_class_lineptr} = 6 \; , \\ \mbox{DW_form_class_loclistptr} = 7 \; , \\ \mbo$

DW_FORM_CLASS_MACPTR = 8 , DW_FORM_CLASS_RANGELISTPTR =9 , DW_FORM_CLASS_← REFERENCE = 10 , DW_FORM_CLASS_STRING = 11 ,

DW_FORM_CLASS_FRAMEPTR = 12 , DW_FORM_CLASS_MACROPTR = 13 , DW_FORM_CLASS_← ADDRPTR = 14 , DW_FORM_CLASS_LOCLIST = 15 ,

 $\label{eq:class_loc_listsptr} \begin{subarray}{ll} DW_FORM_CLASS_LOCLISTSPTR = 16 \ , \ DW_FORM_CLASS_RNGLIST = 17 \ , \ DW_FORM_CLASS_RNGLISTSPTR = 18 \ , \ DW_FORM_CLASS_STROFFSETSPTR = 19 \ \} \\ \end{subarray}$

9.2.1 Detailed Description

9.2.2 Enumeration Type Documentation

9.2.2.1 Dwarf Ranges Entry Type

enum Dwarf_Ranges_Entry_Type

The dwr_addr1/addr2 data is either pair of offsets of a base pc address (DW_RANGES_ENTRY) or a base pc address (dwr_addr2 in DW_RANGES_ADDRESS_SELECTION) or both are zero(end of list, DW_RANGES_END) or both non-zero but identical (means an empty range, DW_RANGES_ENTRY). These are for use with DWARF 2,3,4.

DW_RANGES_ADDRESS_SELECTION should have been spelled DW_RANGES_BASE_ADDRESS. but it is not worth changing as it is widely used.

The DW_RANGES_ENTRY values are raw pc offset data recorded in the section, not addresses.

See also

Example getting .debug ranges data

Dwarf Ranges* apply to DWARF2,3, and 4. Not to DWARF5 (the data is different and in a new DWARF5 section).

9.2.2.2 Dwarf Form Class

enum Dwarf_Form_Class

The dwarf specification separates FORMs into different classes. To do the separation properly requires 4 pieces of data as of DWARF4 (thus the function arguments listed here). The DWARF4 specification class definition suffices to describe all DWARF versions. See section 7.5.4, Attribute Encodings. A return of DW_FORM_CLASS_UNKNOWN means the library could not properly figure out what form-class it is.

DW_FORM_CLASS_FRAMEPTR is MIPS/IRIX only, and refers to the DW_AT_MIPS_fde attribute (a reference to the .debug_frame section).

DWARF5: DW_FORM_CLASS_LOCLISTSPTR is like DW_FORM_CLASS_LOCLIST except that LOCLISTSPTR is always a section offset, never an index, and LOCLISTSPTR is only referenced by DW_AT_loclists_base. Note DW_FORM_CLASS_LOCLISTSPTR spelling to distinguish from DW_FORM_CLASS_LOCLISTPTR.

DWARF5: DW_FORM_CLASS_RNGLISTSPTR is like DW_FORM_CLASS_RNGLIST except that RNGLISTSPTR is always a section offset, never an index. DW_FORM_CLASS_RNGLISTSPTR is only referenced by DW_AT_ \leftarrow rnglists_base.

9.3 Defined and Opaque Structs

Data Structures

- struct Dwarf_Form_Data16_s
- struct Dwarf_Sig8_s
- · struct Dwarf Block s
- · struct Dwarf Printf Callback Info s
- struct Dwarf_Cmdline_Options_s
- struct Dwarf_Ranges_s
- struct Dwarf_Regtable_Entry3_s
- struct Dwarf Regtable3 s
- struct Dwarf Macro Details s
- struct Dwarf_Obj_Access_Section_a_s
- struct Dwarf_Obj_Access_Methods_a_s
- struct Dwarf_Obj_Access_Interface_a_s
- struct Dwarf_Debug_Fission_Per_CU_s

Typedefs

- typedef struct Dwarf_Form_Data16_s Dwarf_Form_Data16
- typedef struct Dwarf Sig8 s Dwarf Sig8
- typedef struct Dwarf_Block_s Dwarf_Block
- typedef struct Dwarf_Locdesc_c_s * Dwarf_Locdesc_c
- typedef struct Dwarf_Loc_Head_c * Dwarf_Loc_Head_c
- typedef struct Dwarf_Gnu_Index_Head_s * Dwarf_Gnu_Index_Head
- typedef struct Dwarf_Dsc_Head_s * Dwarf_Dsc_Head
- typedef struct Dwarf_Frame_Instr_Head_s * Dwarf_Frame_Instr_Head
- typedef void(* dwarf_printf_callback_function_type) (void *dw_user_pointer, const char *dw_linecontent)
- typedef struct Dwarf Cmdline Options s Dwarf Cmdline Options
- typedef struct Dwarf_Str_Offsets_Table_s * Dwarf_Str_Offsets_Table
- · typedef struct Dwarf Ranges s Dwarf Ranges
- typedef struct Dwarf Regtable Entry3 s Dwarf Regtable Entry3
- typedef struct Dwarf_Regtable3_s Dwarf_Regtable3
- typedef struct Dwarf_Error_s * Dwarf_Error
- typedef struct Dwarf_Debug_s * Dwarf_Debug
- typedef struct Dwarf_Section_s * Dwarf_Section
- typedef struct Dwarf_Die_s * Dwarf_Die
- typedef struct Dwarf_Debug_Addr_Table_s * Dwarf_Debug_Addr_Table
- typedef struct Dwarf_Line_s * Dwarf_Line
- typedef struct Dwarf_Global_s * Dwarf_Global
- typedef struct Dwarf_Type_s * Dwarf_Type
- typedef struct Dwarf_Func_s * Dwarf_Func
- typedef struct Dwarf Var s * Dwarf Var
- typedef struct Dwarf Weak s * Dwarf Weak
- typedef struct Dwarf_Attribute_s * Dwarf_Attribute
- typedef struct Dwarf Abbrev s * Dwarf Abbrev
- typedef struct Dwarf_Fde_s * Dwarf_Fde
- typedef struct Dwarf_Cie_s * Dwarf_Cie
- typedef struct Dwarf Arange s * Dwarf Arange
- typedef struct Dwarf_Gdbindex_s * Dwarf_Gdbindex
- typedef struct Dwarf Xu Index Header s * Dwarf Xu Index Header
- typedef struct Dwarf_Line_Context_s * Dwarf_Line_Context

- typedef struct Dwarf_Macro_Context_s * Dwarf_Macro_Context
- typedef struct Dwarf_Dnames_Head_s * Dwarf_Dnames_Head
- typedef void(* Dwarf_Handler) (Dwarf_Error dw_error, Dwarf_Ptr dw_errarg)
- typedef struct Dwarf_Macro_Details_s Dwarf_Macro_Details
- typedef struct Dwarf_Debug_Fission_Per_CU_s Dwarf_Debug_Fission_Per_CU
- typedef struct Dwarf_Obj_Access_Interface_a_s Dwarf_Obj_Access_Interface_a
- typedef struct Dwarf_Obj_Access_Methods_a_s Dwarf_Obj_Access_Methods_a
- typedef struct Dwarf_Obj_Access_Section_a_s Dwarf_Obj_Access_Section_a
- typedef struct Dwarf_Rnglists_Head_s * Dwarf_Rnglists_Head

Enumerations

• enum Dwarf_Sec_Alloc_Pref { Dwarf_Alloc_None =0 , Dwarf_Alloc_Malloc =1 , Dwarf_Alloc_Mmap =2 }

9.3.1 Detailed Description

9.3.2 Typedef Documentation

9.3.2.1 Dwarf Form Data16

Dwarf_Form_Data16

a container for a DW_FORM_data16 data item. We have no integer types suitable so this special struct is used instead. It is up to consumers/producers to deal with the contents.

9.3.2.2 Dwarf_Sig8

Dwarf_Sig8

Used for signatures where ever they appear. It is not a string, it is 8 bytes of a signature one would use to find a type unit.

See also

dwarf formsig8

9.3.2.3 Dwarf_Block

Dwarf_Block

Used to hold uninterpreted blocks of data. bl_data refers to on an uninterpreted block of data Used with certain location information functions, a frame expression function, expanded frame instructions, and DW_FORM_block functions.

See also

dwarf_formblock
Documenting Form_Block

9.3.2.4 Dwarf_Locdesc_c

Dwarf_Locdesc_c

Provides access to Dwarf_Locdesc_c, a single location description

9.3.2.5 Dwarf_Loc_Head_c

Dwarf_Loc_Head_c

provides access to any sort of location description for DWARF2,3,4, or 5.

9.3.2.6 Dwarf_Gnu_Index_Head

Dwarf_Gnu_Index_Head

A pointer to a struct Dwarf_Gnu_Index_Head_s for sections .debug_gnu_pubtypes or .debug_gnu_pubnames. These are not standard DWARF, and can appear with gcc -gdwarf-5

9.3.2.7 Dwarf_Dsc_Head

Dwarf_Dsc_Head

Access to DW_AT_discr_list array of discriminant values.

9.3.2.8 Dwarf_Frame_Instr_Head

Dwarf_Frame_Instr_Head

The basis for access to DWARF frame instructions (FDE or CIE) in full detail.

9.3.2.9 dwarf_printf_callback_function_type

dwarf_printf_callback_function_type

Used as a function pointer to a user-written callback function. This provides a detailed content of line table data.

The default contents of the callback data are all zero bytes. So no callbacks involving this data will be done.

See dwarf_register_printf_callback()

Parameters

	Passes your callback a pointer to space you allocated as an identifier of some kind in calling dwarf_register_printf_callback
dw_linecontent	Passes your callback null-terminated string with one line of detailed line table content.

9.3.2.10 Dwarf_Str_Offsets_Table

```
Dwarf_Str_Offsets_Table
```

Provides an access to the .debug_str_offsets section independently of other DWARF sections. Mainly of use in examining the .debug_str_offsets section content for problems.

9.3.2.11 Dwarf Ranges

Dwarf_Ranges

Details of of non-contiguous address ranges of DIEs for DWARF2, DWARF3, and DWARF4. Sufficient for older dwarf.

dwr_addr1 and dwr_addr2 in the struct are offsets from a base address in the CU involved. To calculate actual range pc addresses see the example:

See also

Example getting .debug_ranges data

9.3.2.12 Dwarf Regtable Entry3

Dwarf_Regtable_Entry3

For each index i (naming a hardware register with dwarf number i) the following is true and defines the value of that register:

```
If dw_regnum is Register DW_FRAME_UNDEFINED_VAL
    it is not DWARF register number but
    a place holder indicating the register
    has no defined value.
If dw_regnum is Register DW_FRAME_SAME_VAL
    it is not DWARF register number but
    a place holder indicating the register has the same
    value in the previous frame.
    DW_FRAME_UNDEFINED_VAL, DW_FRAME_SAME_VAL and
    DW_FRAME_CFA_COL are only present at libdwarf runtime.
    Never on disk.
    DW_FRAME_* Values present on disk are in dwarf.h
    Because DW_FRAME_SAME_VAL and DW_FRAME_UNDEFINED_VAL
    and DW_FRAME_CFA_COL are definable at runtime
    consider the names symbolic in this comment,
    not absolute.
Otherwise: the register number is a DWARF register number
    (see ABI documents for how this translates to hardware/
    software register numbers in the machine hardware)
    and the following applies:
In a cfa-defining entry (rt3_cfa_rule) the regnum is the
CFA 'register number'. Which is some 'normal' register, not DW_FRAME_CFA_COL, nor DW_FRAME_SAME_VAL, nor
DW_FRAME_UNDEFINED_VAL.
If dw_value_type == DW_EXPR_OFFSET (the only
possible case for dwarf2):
    If dw\_offset\_relevant is non-zero, then
        the value is stored at at the address
```

```
CFA+N where N (dw_offset) is a signed offset,
        (not unsigned) and must be cast to Dwarf_Signed
        before use.
        dw_regnum is the cfa register rule which means
        one ignores dw_regnum and uses the CFA appropriately.
        Rule: Offset(N)
    If dw_offset_relevant is zero, then the
        value of the register
        is the value of (DWARF) register number dw_regnum.
        Rule: register(R)
If dw_value_type == DW_EXPR_VAL_OFFSET
    the value of this register is CFA +N where
    N (dw_offset) is a signed offset (not unsigned)
    and must be cast to Dwarf_Signed before use.
   dw regnum is the cfa register rule which means
    one ignores dw_regnum and uses the CFA appropriately.
    Rule: val_offset(N)
If dw_value_type == DW_EXPR_EXPRESSION
    The value of the register is the value at the address
    computed by evaluating the DWARF expression E.
    Rule: expression(E)
    The expression E byte stream is pointed to by
   block.bl data.
   The expression length in bytes is given by
   block.bl_len.
If dw_value_type == DW_EXPR_VAL_EXPRESSION
   The value of the register is the value
    computed by evaluating the DWARF expression E.
    Rule: val_expression(E)
    The expression E byte stream is pointed to
   by block.bl_data.
    The expression length in bytes is given by
    block.bl_len.
Other values of dw_value_type are an error.
Note that this definition can only deal correctly
with register numbers that fit in a 16 bit
unsigned value. Removing this
restriction would force an incompatible
change to several functions in the libdwarf API.
```

9.3.2.13 Dwarf Regtable3

Dwarf_Regtable3

This structs provides a way for applications to select the number of frame registers and to select names for them.

rt3_rules and rt3_reg_table_size must be filled in before calling libdwarf. Filled in with a pointer to an array (pointer and array set up by the calling application) of rt3_reg_table_size Dwarf_Regtable_Entry3_s structs. libdwarf does not allocate or deallocate space for the rules, you must do so. libdwarf will initialize the contents rules array, you do not need to do so (though if you choose to initialize the array somehow that is ok: libdwarf will overwrite your initializations with its own).

Note that this definition can only deal correctly with register table size that fits in a 16 bit unsigned value.

9.3.2.14 Dwarf_Error

```
Dwarf_Error
Dwarf_Error error = 0;
dres = dwarf_siblingof_c(in_die,&return_sib, &error);
```

&error is used in calls to return error details when the call returns DW DLV ERROR.

9.3.2.15 Dwarf_Debug

Dwarf_Debug

An open Dwarf_Debug points to data that libdwarf maintains to support libdwarf calls.

9.3.2.16 Dwarf_Section

Dwarf_Section

An open Dwarf_Section points to data that libdwarf maintains to record object section data.

9.3.2.17 Dwarf_Die

Dwarf_Die

Used to reference a DWARF Debugging Information Entry.

9.3.2.18 Dwarf_Debug_Addr_Table

Dwarf_Debug_Addr_Table

Used to reference a table in section .debug_addr

9.3.2.19 Dwarf_Line

Dwarf_Line

Used to reference a line reference from the .debug line section.

9.3.2.20 Dwarf_Global

Dwarf_Global

Used to reference a reference to an entry in the .debug_pubnames section.

9.3.2.21 **Dwarf_Type**

Dwarf_Type

Before release 0.6.0 used to reference a reference to an entry in the .debug_pubtypes section (as well as the SGI-only extension .debug_types). However, we use Dwarf_Global instead now.

9.3.2.22 Dwarf_Func

Dwarf_Func

An SGI extension type which is no longer used at all. As of release 0.6.0 use Dwarf_Global instead.

9.3.2.23 Dwarf_Var

Dwarf_Var

An SGI extension type which is no longer used at all. As of release 0.6.0 use Dwarf_Global instead.

9.3.2.24 Dwarf_Weak

Dwarf_Weak

An SGI extension type which is no longer used at all. As of release 0.6.0 use Dwarf_Global instead.

9.3.2.25 Dwarf_Attribute

Dwarf_Attribute

Used to reference a Dwarf_Die attribute

9.3.2.26 Dwarf_Abbrev

Dwarf_Abbrev

Used to reference a Dwarf_Abbrev. Usually Dwarf_Abbrev are fully handled inside the library so one rarely needs to declare the type.

9.3.2.27 Dwarf_Fde

Dwarf_Fde

Used to reference .debug_frame or .eh_frame FDE.

9.3.2.28 Dwarf_Cie

Dwarf_Cie

Used to reference .debug_frame or .eh_frame CIE.

9.3.2.29 Dwarf_Arange

Dwarf_Arange

Used to reference a code address range in a section such as .debug_info.

9.3.2.30 Dwarf_Gdbindex

Dwarf_Gdbindex

Used to reference .gdb_index section data which is a fast-access section by and for gdb.

9.3.2.31 Dwarf_Xu_Index_Header

Dwarf_Xu_Index_Header

Used to reference .debug_cu_index or .debug_tu_index sections in a split-dwarf package file.

9.3.2.32 Dwarf_Line_Context

Dwarf_Line_Context

Used as the general reference line data (.debug_line).

9.3.2.33 Dwarf_Macro_Context

Dwarf_Macro_Context

Used as the general reference to DWARF5 .debug_macro data.

9.3.2.34 Dwarf_Dnames_Head

Dwarf_Dnames_Head

Used as the general reference to the DWARF5 .debug_names section.

9.3.2.35 Dwarf_Handler

Dwarf_Handler

Used in rare cases (mainly tiny programs) with dwarf_init_path() etc initialization calls to provide a pointer to a generic-error-handler function you write.

9.3.2.36 Dwarf_Macro_Details

Dwarf_Macro_Details

A handy short name for a Dwarf_Macro_Details_S struct.

9.3.2.37 Dwarf Debug Fission Per CU

Dwarf_Debug_Fission_Per_CU

A handy short name for a Dwarf_Debug_Fission_Per_CU_s struct.

9.3.2.38 Dwarf_Obj_Access_Interface_a

Dwarf_Obj_Access_Interface_a

Used for access to and setting up special data allowing access to DWARF even with no object files present

9.3.2.39 Dwarf_Obj_Access_Methods_a

Dwarf_Obj_Access_Methods_a

Used for access to and setting up special data allowing access to DWARF even with no object files present

9.3.2.40 Dwarf_Obj_Access_Section_a

Dwarf_Obj_Access_Section_a

Used for access to and setting up special data allowing access to DWARF even with no object files present. The fields match up with Elf section headers, but for non-Elf many of the fields can be set to zero.

9.3.2.41 Dwarf_Rnglists_Head

Dwarf_Rnglists_Head

Used for access to a set of DWARF5 debug_rnglists entries.

9.3.3 Enumeration Type Documentation

9.3.3.1 Dwarf Sec Alloc Pref

enum Dwarf_Sec_Alloc_Pref

Since

{0.12.0}

This is part of the allowance of mmap for loading sections of an object file.

The option of using mmap() only applies to Elf object files in this release.

See also

dwarf_set_load_preference()

9.4 Default stack frame macros

Macros

- #define DW DLX NO EH OFFSET (-1LL)
- #define DW_DLX_EH_OFFSET_UNAVAILABLE (-2LL)
- #define DW CIE AUGMENTER STRING V0 "z"
- #define DW REG TABLE SIZE DW FRAME LAST REG NUM
- #define DW FRAME REG INITIAL VALUE DW FRAME SAME VAL
- #define DW_EXPR_OFFSET 0 /* offset is from CFA reg */
- #define DW_EXPR_VAL_OFFSET 1
- #define DW_EXPR_EXPRESSION 2
- #define DW EXPR VAL EXPRESSION 3

9.4.1 Detailed Description

9.5 DW DLA alloc/dealloc typename&number

Macros

- #define DW_DLA_STRING 0x01 /* char* */
- #define DW DLA LOC 0x02 /* Dwarf Loc */
- #define DW_DLA_LOCDESC 0x03 /* Dwarf_Locdesc */
- #define DW_DLA_ELLIST 0x04 /* Dwarf_Ellist (not used)*/
- #define DW DLA BOUNDS 0x05 /* Dwarf Bounds (not used) */
- #define DW DLA BLOCK 0x06 /* Dwarf Block */
- #define DW_DLA_DEBUG 0x07 /* Dwarf Debug */
- #define DW_DLA_DIE 0x08 /* Dwarf_Die */
- #define DW DLA LINE 0x09 /* Dwarf Line */
- #define DW_DLA_ATTR 0x0a /* Dwarf_Attribute */
- #define DW_DLA_TYPE 0x0b /* Dwarf_Type (not used) */
- #define DW_DLA_SUBSCR 0x0c /* Dwarf_Subscr (not used) */
- #define DW_DLA_GLOBAL 0x0d /* Dwarf_Global */
- #define DW_DLA_ERROR 0x0e /* Dwarf_Error */
- #define DW DLA LIST 0x0f /* a list */
- #define DW_DLA_LINEBUF 0x10 /* Dwarf_Line* (not used) */
- #define DW DLA ARANGE 0x11 /* Dwarf Arange */
- #define DW DLA ABBREV 0x12 /* Dwarf Abbrev */
- #define DW_DLA_FRAME_INSTR_HEAD 0x13 /* Dwarf_Frame_Instr_Head */
- #define DW_DLA_CIE 0x14 /* Dwarf_Cie */
- #define DW_DLA_FDE 0x15 /* Dwarf_Fde */
- #define DW_DLA_LOC_BLOCK 0x16 /* Dwarf_Loc */
- #define **DW DLA FRAME OP** 0x17 /* Dwarf Frame Op (not used) */
- #define DW DLA FUNC 0x18 /* Dwarf Func */
- #define DW_DLA_UARRAY 0x19 /* Array of Dwarf_Off:Jan2023 */
- #define DW_DLA_VAR 0x1a /* Dwarf_Var */
- #define DW_DLA_WEAK 0x1b /* Dwarf_Weak */
- #define DW_DLA_ADDR 0x1c /* Dwarf_Addr sized entries */
- #define DW_DLA_RANGES 0x1d /* Dwarf_Ranges */
- #define DW DLA GNU INDEX HEAD 0x35
- #define DW_DLA_RNGLISTS_HEAD 0x36 /* .debug_rnglists DW5 */
- #define DW_DLA_GDBINDEX 0x37 /* Dwarf_Gdbindex */

- #define DW_DLA_XU_INDEX 0x38 /* Dwarf_Xu_Index_Header */
- #define DW_DLA_LOC_BLOCK_C 0x39 /* Dwarf_Loc_c*/
- #define DW_DLA_LOCDESC_C 0x3a /* Dwarf_Locdesc_c */
- #define DW DLA LOC HEAD C 0x3b /* Dwarf Loc Head c */
- #define DW DLA MACRO CONTEXT 0x3c /* Dwarf Macro Context */
- #define DW DLA DSC HEAD 0x3e /* Dwarf Dsc Head */
- #define DW_DLA_DNAMES_HEAD 0x3f /* Dwarf_Dnames_Head */
- #define DW DLA STR OFFSETS 0x40
- #define DW_DLA_DEBUG_ADDR 0x41

9.5.1 Detailed Description

These identify the various allocate/dealloc types. The allocation happens within libdwarf, and the deallocation is usually done by user code.

9.6 DW_DLE Dwarf_Error numbers

Macros

- #define DW DLE NE 0 /* no error */
- #define DW DLE VMM 1 /* dwarf format/library version mismatch */
- #define DW_DLE_MAP 2 /* memory map failure */
- #define DW_DLE_LEE 3 /* libelf error */
- #define DW_DLE_NDS 4 /* no debug section */
- #define DW_DLE_NLS 5 /* no line section */
- #define DW_DLE_ID 6 /* invalid descriptor for query */
- #define DW_DLE_IOF 7 /* I/O failure */
- #define DW_DLE_MAF 8 /* memory allocation failure */
- #define DW_DLE_IA 9 /* invalid argument */
- #define DW_DLE_MDE 10 /* mangled debugging entry */
- #define **DW DLE MLE** 11 /* mangled line number entry */
- #define DW DLE FNO 12 /* file not open */
- #define DW DLE FNR 13 /* file not a regular file */
- #define DW_DLE_FWA 14 /* file open with wrong access */
- #define DW_DLE_NOB 15 /* not an object file */
- #define DW_DLE_MOF 16 /* mangled object file header */
- #define DW_DLE_EOLL 17 /* end of location list entries */
- #define **DW_DLE_NOLL** 18 /* no location list section */
- #define DW_DLE_BADOFF 19 /* Invalid offset */
- #define DW_DLE_EOS 20 /* end of section */
- #define DW_DLE_ATRUNC 21 /* abbreviations section appears truncated*/
- #define **DW DLE BADBITC** 22 /* Address size passed to dwarf bad,*/
- #define DW DLE DBG ALLOC 23
- #define DW DLE FSTAT ERROR 24
- #define DW DLE FSTAT MODE ERROR 25
- #define DW DLE INIT ACCESS WRONG 26
- #define DW_DLE_ELF_BEGIN_ERROR 27
- #define DW_DLE_ELF_GETEHDR_ERROR 28
- #define DW_DLE_ELF_GETSHDR_ERROR 29
- #define DW DLE ELF STRPTR ERROR 30
- #define DW_DLE_DEBUG_INFO_DUPLICATE 31

- #define DW DLE DEBUG INFO NULL 32
- #define DW DLE DEBUG ABBREV DUPLICATE 33
- #define DW_DLE_DEBUG_ABBREV_NULL 34
- #define DW DLE DEBUG ARANGES DUPLICATE 35
- #define DW DLE DEBUG ARANGES NULL 36
- #define DW_DLE_DEBUG_LINE_DUPLICATE 37
- #define DW DLE DEBUG LINE NULL 38
- #define DW_DLE_DEBUG_LOC_DUPLICATE 39
- #define DW DLE DEBUG LOC NULL 40
- #define DW DLE DEBUG MACINFO DUPLICATE 41
- #define DW DLE DEBUG MACINFO NULL 42
- #define DW DLE DEBUG PUBNAMES DUPLICATE 43
- #define DW DLE DEBUG PUBNAMES NULL 44
- #define DW DLE DEBUG STR DUPLICATE 45
- #define DW_DLE_DEBUG_STR_NULL 46
- #define DW DLE CU LENGTH ERROR 47
- #define DW DLE VERSION STAMP ERROR 48
- #define DW DLE ABBREV OFFSET ERROR 49
- #define DW DLE ADDRESS SIZE ERROR 50
- #define DW DLE DEBUG INFO PTR NULL 51
- #define DW_DLE_DIE_NULL 52
- #define DW DLE STRING OFFSET BAD 53
- #define DW DLE DEBUG LINE LENGTH BAD 54
- #define DW_DLE_LINE_PROLOG_LENGTH_BAD 55
- #define DW DLE LINE NUM OPERANDS BAD 56
- #define DW_DLE_LINE_SET_ADDR_ERROR 57
- #define DW_DLE_LINE_EXT_OPCODE_BAD 58
- #define DW DLE DWARF LINE NULL 59
- #define DW DLE INCL DIR NUM BAD 60
- #define DW_DLE_LINE_FILE_NUM_BAD 61
- #define DW DLE ALLOC FAIL 62
- #define DW_DLE_NO_CALLBACK_FUNC 63
- #define DW_DLE_SECT_ALLOC 64
- #define DW_DLE_FILE_ENTRY_ALLOC 65
- #define DW_DLE_LINE_ALLOC 66
- #define DW_DLE_FPGM_ALLOC 67
- #define DW_DLE_INCDIR_ALLOC 68
- #define DW_DLE_STRING_ALLOC 69
- #define DW_DLE_CHUNK_ALLOC 70
- #define DW DLE BYTEOFF ERR 71
- #define DW DLE CIE ALLOC 72
- #define DW_DLE_FDE_ALLOC 73
- #define DW_DLE_REGNO_OVFL 74
- #define **DW_DLE_CIE_OFFS_ALLOC** 75
- #define **DW_DLE_WRONG_ADDRESS** 76
- #define DW_DLE_EXTRA_NEIGHBORS 77
- #define DW_DLE_WRONG_TAG 78
- #define DW DLE DIE ALLOC 79
- #define DW_DLE_PARENT_EXISTS 80
- #define DW_DLE_DBG_NULL 81
- #define DW DLE DEBUGLINE ERROR 82
- #define DW_DLE_DEBUGFRAME_ERROR 83
- #define DW DLE DEBUGINFO ERROR 84
- #define DW DLE ATTR ALLOC 85
- #define DW_DLE_ABBREV_ALLOC 86

- #define DW DLE OFFSET UFLW 87
- #define DW_DLE_ELF_SECT_ERR 88
- #define DW_DLE_DEBUG_FRAME_LENGTH_BAD 89
- #define DW DLE FRAME VERSION BAD 90
- #define DW_DLE_CIE_RET_ADDR_REG_ERROR 91
- #define DW_DLE_FDE_NULL 92
- #define DW DLE FDE DBG NULL 93
- #define DW_DLE_CIE_NULL 94
- #define DW_DLE_CIE_DBG_NULL 95
- #define DW DLE FRAME TABLE COL BAD 96
- #define DW_DLE_PC_NOT_IN_FDE_RANGE 97
- #define DW DLE CIE INSTR EXEC ERROR 98
- #define DW DLE FRAME INSTR EXEC ERROR 99
- #define DW DLE FDE PTR NULL 100
- #define DW_DLE_RET_OP_LIST_NULL 101
- #define DW DLE LINE CONTEXT NULL 102
- #define DW DLE DBG NO CU CONTEXT 103
- #define DW DLE DIE NO CU CONTEXT 104
- #define DW DLE FIRST DIE NOT CU 105
- #define DW DLE NEXT DIE PTR NULL 106
- #define DW_DLE_DEBUG_FRAME_DUPLICATE 107
- #define DW DLE DEBUG FRAME NULL 108
- #define DW DLE ABBREV DECODE ERROR 109
- #define DW_DLE_DWARF_ABBREV_NULL 110
- #define DW DLE ATTR NULL 111
- #define **DW_DLE_DIE_BAD** 112
- #define DW_DLE_DIE_ABBREV_BAD 113
- #define DW_DLE_ATTR_FORM_BAD 114
- #define **DW_DLE_ATTR_NO_CU_CONTEXT** 115
- #define DW_DLE_ATTR_FORM_SIZE_BAD 116
- #define DW_DLE_ATTR_DBG_NULL 117
- #define DW DLE BAD REF FORM 118
- #define DW_DLE_ATTR_FORM_OFFSET_BAD 119
- #define DW_DLE_LINE_OFFSET_BAD 120
- #define DW_DLE_DEBUG_STR_OFFSET_BAD 121
- #define DW_DLE_STRING_PTR_NULL 122
- #define DW_DLE_PUBNAMES_VERSION_ERROR 123
- #define DW DLE PUBNAMES LENGTH BAD 124
- #define DW DLE GLOBAL NULL 125
- #define DW DLE GLOBAL CONTEXT NULL 126
- #define DW DLE DIR INDEX BAD 127
- #define DW_DLE_LOC_EXPR_BAD 128
- #define DW_DLE_DIE_LOC_EXPR_BAD 129
- #define DW_DLE_ADDR_ALLOC 130
- #define **DW_DLE_OFFSET_BAD** 131
- #define **DW_DLE_MAKE_CU_CONTEXT_FAIL** 132
- #define DW DLE REL ALLOC 133
- #define DW DLE ARANGE OFFSET BAD 134
- #define DW_DLE_SEGMENT_SIZE_BAD 135
- #define DW_DLE_ARANGE_LENGTH_BAD 136
- #define DW DLE ARANGE DECODE ERROR 137
- #define DW_DLE_ARANGES_NULL 138
- #define DW_DLE_ARANGE_NULL 139
- #define **DW_DLE_NO_FILE_NAME** 140
- #define DW_DLE_NO_COMP_DIR 141

- #define DW DLE CU ADDRESS SIZE BAD 142
- #define DW_DLE_INPUT_ATTR_BAD 143
- #define DW_DLE_EXPR_NULL 144
- #define DW DLE BAD EXPR OPCODE 145
- #define DW_DLE_EXPR_LENGTH_BAD 146
- #define DW_DLE_MULTIPLE_RELOC_IN_EXPR 147
- #define DW_DLE_ELF_GETIDENT_ERROR 148
- #define DW_DLE_NO_AT_MIPS_FDE 149
- #define **DW_DLE_NO_CIE_FOR_FDE** 150
- #define DW DLE DIE ABBREV LIST NULL 151
- #define DW DLE DEBUG FUNCNAMES DUPLICATE 152
- #define DW DLE DEBUG FUNCNAMES NULL 153
- #define DW DLE DEBUG FUNCNAMES VERSION ERROR 154
- #define DW DLE DEBUG FUNCNAMES LENGTH BAD 155
- #define DW_DLE_FUNC_NULL 156
- #define DW DLE FUNC CONTEXT NULL 157
- #define DW DLE DEBUG TYPENAMES DUPLICATE 158
- #define DW DLE DEBUG TYPENAMES NULL 159
- #define DW DLE DEBUG TYPENAMES VERSION ERROR 160
- #define DW_DLE_DEBUG_TYPENAMES_LENGTH_BAD 161
- #define DW_DLE_TYPE_NULL 162
- #define DW DLE TYPE CONTEXT NULL 163
- #define DW DLE DEBUG VARNAMES DUPLICATE 164
- #define DW_DLE_DEBUG_VARNAMES_NULL 165
- #define DW_DLE_DEBUG_VARNAMES_VERSION_ERROR 166
- #define DW_DLE_DEBUG_VARNAMES_LENGTH_BAD 167
- #define DW DLE VAR NULL 168
- #define DW DLE VAR CONTEXT NULL 169
- #define DW DLE DEBUG WEAKNAMES DUPLICATE 170
- #define DW_DLE_DEBUG_WEAKNAMES_NULL 171
- #define DW DLE DEBUG WEAKNAMES VERSION ERROR 172
- #define DW DLE DEBUG WEAKNAMES LENGTH BAD 173
- #define DW_DLE_WEAK_NULL 174
- #define DW_DLE_WEAK_CONTEXT_NULL 175
- #define DW_DLE_LOCDESC_COUNT_WRONG 176
- #define DW_DLE_MACINFO_STRING_NULL 177
- #define DW DLE MACINFO STRING EMPTY 178
- #define DW DLE MACINFO INTERNAL ERROR SPACE 179
- #define DW DLE MACINFO MALLOC FAIL 180
- #define DW DLE DEBUGMACINFO ERROR 181
- #define DW DLE DEBUG MACRO LENGTH BAD 182
- #define DW_DLE_DEBUG_MACRO_MAX_BAD 183
- #define DW_DLE_DEBUG_MACRO_INTERNAL_ERR 184
- #define DW_DLE_DEBUG_MACRO_MALLOC_SPACE 185
- #define DW_DLE_DEBUG_MACRO_INCONSISTENT 186
- #define DW DLE DF NO CIE AUGMENTATION 187
- #define DW DLE DF REG NUM TOO HIGH 188
- #define DW DLE DF MAKE INSTR NO INIT 189
- #define DW_DLE_DF_NEW_LOC_LESS_OLD_LOC 190
- #define DW_DLE_DF_POP_EMPTY_STACK 191
- #define DW DLE DF ALLOC FAIL 192
- #define DW_DLE_DF_FRAME_DECODING_ERROR 193
- #define DW_DLE_DEBUG_LOC_SECTION_SHORT 194
- #define DW DLE FRAME AUGMENTATION UNKNOWN 195
- #define DW_DLE_PUBTYPE_CONTEXT 196 /* Unused. */

- #define DW DLE DEBUG PUBTYPES LENGTH BAD 197
- #define DW DLE DEBUG PUBTYPES VERSION ERROR 198
- #define DW_DLE_DEBUG_PUBTYPES_DUPLICATE 199
- #define DW DLE FRAME CIE DECODE ERROR 200
- #define DW DLE FRAME REGISTER UNREPRESENTABLE 201
- #define DW_DLE_FRAME_REGISTER_COUNT_MISMATCH 202
- #define DW DLE LINK LOOP 203
- #define DW_DLE_STRP_OFFSET_BAD 204
- #define DW DLE DEBUG RANGES DUPLICATE 205
- #define DW DLE DEBUG RANGES OFFSET BAD 206
- #define DW DLE DEBUG RANGES MISSING END 207
- #define DW DLE DEBUG RANGES OUT OF MEM 208
- #define DW DLE DEBUG SYMTAB ERR 209
- #define DW DLE DEBUG STRTAB ERR 210
- #define DW_DLE_RELOC_MISMATCH_INDEX 211
- #define DW DLE RELOC MISMATCH RELOC INDEX 212
- #define DW DLE RELOC MISMATCH STRTAB INDEX 213
- #define DW_DLE_RELOC_SECTION_MISMATCH 214
- #define DW DLE RELOC SECTION MISSING INDEX 215
- #define DW DLE RELOC SECTION LENGTH ODD 216
- #define DW_DLE_RELOC_SECTION_PTR_NULL 217
- #define DW DLE RELOC SECTION MALLOC FAIL 218
- #define DW DLE NO ELF64 SUPPORT 219
- #define DW_DLE_MISSING_ELF64_SUPPORT 220
- #define DW DLE ORPHAN FDE 221
- #define DW_DLE_DUPLICATE_INST_BLOCK 222
- #define DW_DLE_BAD_REF_SIG8_FORM 223
- #define DW DLE ATTR EXPRLOC FORM BAD 224
- #define DW DLE FORM SEC OFFSET LENGTH BAD 225
- #define DW_DLE_NOT_REF_FORM 226
- #define DW DLE DEBUG FRAME LENGTH NOT MULTIPLE 227
- #define DW DLE REF SIG8 NOT HANDLED 228
- #define DW_DLE_DEBUG_FRAME_POSSIBLE_ADDRESS_BOTCH 229
- #define DW_DLE_LOC_BAD_TERMINATION 230
- #define DW DLE SYMTAB SECTION LENGTH ODD 231
- #define DW_DLE_RELOC_SECTION_SYMBOL_INDEX_BAD 232
- #define DW DLE RELOC SECTION RELOC TARGET SIZE UNKNOWN 233
- #define DW DLE SYMTAB SECTION ENTRYSIZE ZERO 234
- #define DW DLE LINE NUMBER HEADER ERROR 235
- #define DW DLE DEBUG TYPES NULL 236
- #define DW DLE DEBUG TYPES DUPLICATE 237
- #define DW_DLE_DEBUG_TYPES_ONLY_DWARF4 238
- #define DW_DLE_DEBUG_TYPEOFFSET_BAD 239
- #define DW_DLE_GNU_OPCODE_ERROR 240
- #define DW_DLE_DEBUGPUBTYPES_ERROR 241
- #define DW DLE AT FIXUP NULL 242
- #define DW DLE AT FIXUP DUP 243
- #define DW DLE BAD ABINAME 244
- #define DW_DLE_TOO_MANY_DEBUG 245
- #define DW_DLE_DEBUG_STR_OFFSETS_DUPLICATE 246
- #define DW DLE SECTION DUPLICATION 247
- #define DW DLE SECTION ERROR 248
- #define DW DLE DEBUG ADDR DUPLICATE 249
- #define DW DLE DEBUG CU UNAVAILABLE FOR FORM 250
- #define DW_DLE_DEBUG_FORM_HANDLING_INCOMPLETE 251

- #define DW DLE NEXT DIE PAST END 252
- #define DW DLE NEXT DIE WRONG FORM 253
- #define DW_DLE_NEXT_DIE_NO_ABBREV_LIST 254
- #define DW DLE NESTED FORM INDIRECT ERROR 255
- #define DW DLE CU DIE NO ABBREV LIST 256
- #define DW DLE MISSING NEEDED DEBUG ADDR SECTION 257
- #define DW DLE ATTR FORM NOT ADDR INDEX 258
- #define DW_DLE_ATTR_FORM_NOT_STR_INDEX 259
- #define DW DLE DUPLICATE GDB INDEX 260
- #define DW DLE ERRONEOUS GDB INDEX SECTION 261
- #define DW DLE GDB INDEX COUNT ERROR 262
- #define DW DLE GDB INDEX COUNT ADDR ERROR 263
- #define DW DLE GDB INDEX INDEX ERROR 264
- #define DW DLE GDB INDEX CUVEC ERROR 265
- #define DW_DLE_DUPLICATE_CU_INDEX 266
- #define DW_DLE_DUPLICATE_TU_INDEX 267
- #define DW DLE XU TYPE ARG ERROR 268
- #define DW DLE XU IMPOSSIBLE ERROR 269
- #define DW DLE XU NAME COL ERROR 270
- #define DW DLE XU HASH ROW ERROR 271
- #define DW_DLE_XU_HASH_INDEX_ERROR 272
- #define DW DLE FAILSAFE ERRVAL 273
- #define DW DLE ARANGE ERROR 274
- #define DW_DLE_PUBNAMES_ERROR 275
- #define DW DLE FUNCNAMES ERROR 276
- #define DW_DLE_TYPENAMES_ERROR 277
- #define DW DLE VARNAMES ERROR 278
- #define DW_DLE_WEAKNAMES_ERROR 279
- #define DW_DLE_RELOCS_ERROR 280
- #define DW DLE ATTR OUTSIDE SECTION 281
- #define **DW_DLE_FISSION_INDEX_WRONG** 282
- #define DW DLE FISSION VERSION ERROR 283
- #define DW_DLE_NEXT_DIE_LOW_ERROR 284
- #define DW_DLE_CU_UT_TYPE_ERROR 285
- #define DW DLE NO SUCH SIGNATURE FOUND 286
- #define DW_DLE_SIGNATURE_SECTION_NUMBER_WRONG 287
- #define DW_DLE_ATTR_FORM_NOT_DATA8 288
- #define DW DLE SIG TYPE WRONG STRING 289
- #define DW DLE MISSING REQUIRED TU OFFSET HASH 290
- #define DW DLE MISSING REQUIRED CU OFFSET HASH 291
- #define DW DLE DWP MISSING DWO ID 292
- #define DW DLE DWP SIBLING ERROR 293
- #define DW_DLE_DEBUG_FISSION_INCOMPLETE 294
- #define DW_DLE_FISSION_SECNUM_ERR 295
- #define DW DLE DEBUG MACRO DUPLICATE 296
- #define **DW_DLE_DEBUG_NAMES_DUPLICATE** 297
- #define DW_DLE_DEBUG_LINE_STR_DUPLICATE 298
- #define DW DLE DEBUG SUP DUPLICATE 299
- #define DW_DLE_NO_SIGNATURE_TO_LOOKUP 300
- #define DW_DLE_NO_TIED_ADDR_AVAILABLE 301
- #define DW DLE NO TIED SIG AVAILABLE 302
- #define DW_DLE_STRING_NOT_TERMINATED 303
- #define DW_DLE_BAD_LINE_TABLE_OPERATION 304
- #define DW DLE LINE CONTEXT BOTCH 305
- #define DW_DLE_LINE_CONTEXT_INDEX_WRONG 306

- #define DW_DLE_NO_TIED_STRING_AVAILABLE 307
- #define DW_DLE_NO_TIED_FILE_AVAILABLE 308
- #define DW_DLE_CU_TYPE_MISSING 309
- #define DW DLE LLE CODE UNKNOWN 310
- #define DW DLE LOCLIST INTERFACE ERROR 311
- #define DW DLE LOCLIST INDEX ERROR 312
- #define DW DLE INTERFACE NOT SUPPORTED 313
- #define DW_DLE_ZDEBUG_REQUIRES_ZLIB 314
- #define DW_DLE_ZDEBUG_INPUT_FORMAT_ODD 315
- #define DW DLE ZLIB BUF ERROR 316
- #define DW DLE ZLIB DATA ERROR 317
- #define DW DLE MACRO OFFSET BAD 318
- #define DW_DLE_MACRO_OPCODE_BAD 319
- #define DW DLE MACRO OPCODE FORM BAD 320
- #define DW_DLE_UNKNOWN_FORM 321
- #define DW DLE BAD MACRO HEADER POINTER 322
- #define DW DLE BAD MACRO INDEX 323
- #define DW DLE MACRO OP UNHANDLED 324
- #define DW DLE MACRO PAST END 325
- #define DW DLE LINE STRP OFFSET BAD 326
- #define DW_DLE_STRING_FORM_IMPROPER 327
- #define DW DLE ELF FLAGS NOT AVAILABLE 328
- #define DW DLE LEB IMPROPER 329
- #define DW_DLE_DEBUG_LINE_RANGE_ZERO 330
- #define DW DLE READ LITTLEENDIAN ERROR 331
- #define DW_DLE_READ_BIGENDIAN_ERROR 332
- #define DW DLE RELOC INVALID 333
- #define DW DLE INFO HEADER ERROR 334
- #define DW DLE ARANGES HEADER ERROR 335
- #define DW_DLE_LINE_OFFSET_WRONG_FORM 336
- #define DW DLE FORM BLOCK LENGTH ERROR 337
- #define DW DLE ZLIB SECTION SHORT 338
- #define DW_DLE_CIE_INSTR_PTR_ERROR 339
- #define DW_DLE_FDE_INSTR_PTR_ERROR 340
- #define DW_DLE_FISSION_ADDITION_ERROR 341
- #define DW_DLE_HEADER_LEN_BIGGER_THAN_SECSIZE 342
- #define **DW_DLE_LOCEXPR_OFF_SECTION_END** 343
- #define DW_DLE_POINTER_SECTION_UNKNOWN 344
- #define DW_DLE_ERRONEOUS_XU_INDEX_SECTION 345
- #define DW DLE DIRECTORY FORMAT COUNT VS DIRECTORIES MISMATCH 346
- #define DW DLE COMPRESSED EMPTY SECTION 347
- #define DW_DLE_SIZE_WRAPAROUND 348
- #define DW_DLE_ILLOGICAL_TSEARCH 349
- #define DW_DLE_BAD_STRING_FORM 350
- #define DW DLE DEBUGSTR ERROR 351
- #define DW DLE DEBUGSTR UNEXPECTED REL 352
- #define DW DLE DISCR ARRAY ERROR 353
- #define DW DLE LEB OUT ERROR 354
- #define DW_DLE_SIBLING_LIST_IMPROPER 355
- #define DW_DLE_LOCLIST_OFFSET_BAD 356
- #define DW DLE LINE TABLE BAD 357
- #define DW_DLE_DEBUG_LOCIISTS_DUPLICATE 358
- #define DW_DLE_DEBUG_RNGLISTS_DUPLICATE 359
- #define DW DLE ABBREV OFF END 360
- #define DW_DLE_FORM_STRING_BAD_STRING 361

- #define DW DLE AUGMENTATION STRING OFF END 362
- #define DW_DLE_STRING_OFF_END_PUBNAMES_LIKE 363
- #define DW DLE LINE STRING BAD 364
- #define DW_DLE_DEFINE_FILE_STRING_BAD 365
- #define DW DLE MACRO STRING BAD 366
- #define **DW_DLE_MACINFO_STRING_BAD** 367
- #define DW DLE ZLIB UNCOMPRESS ERROR 368
- #define DW_DLE_IMPROPER_DWO_ID 369
- #define DW DLE GROUPNUMBER ERROR 370
- #define DW DLE ADDRESS SIZE ZERO 371
- #define DW DLE DEBUG NAMES HEADER ERROR 372
- #define DW DLE DEBUG NAMES AUG STRING ERROR 373
- #define DW DLE DEBUG NAMES PAD NON ZERO 374
- #define DW DLE DEBUG NAMES OFF END 375
- #define DW_DLE_DEBUG_NAMES_ABBREV_OVERFLOW 376
- #define DW DLE DEBUG NAMES ABBREV CORRUPTION 377
- #define DW DLE DEBUG NAMES NULL POINTER 378
- #define DW DLE DEBUG NAMES BAD INDEX ARG 379
- #define DW DLE DEBUG NAMES ENTRYPOOL OFFSET 380
- #define DW DLE DEBUG NAMES UNHANDLED FORM 381
- #define DW_DLE_LNCT_CODE_UNKNOWN 382
- #define DW DLE LNCT FORM CODE NOT HANDLED 383
- #define DW DLE LINE HEADER LENGTH BOTCH 384
- #define DW_DLE_STRING_HASHTAB_IDENTITY_ERROR 385
- #define DW DLE UNIT TYPE NOT HANDLED 386
- #define DW_DLE_GROUP_MAP_ALLOC 387
- #define DW_DLE_GROUP_MAP_DUPLICATE 388
- #define DW DLE GROUP COUNT ERROR 389
- #define DW DLE GROUP INTERNAL ERROR 390
- #define DW_DLE_GROUP_LOAD_ERROR 391
- #define DW DLE GROUP LOAD READ ERROR 392
- #define DW DLE AUG DATA LENGTH BAD 393
- #define DW_DLE_ABBREV_MISSING 394
- #define DW_DLE_NO_TAG_FOR_DIE 395
- #define DW_DLE_LOWPC_WRONG_CLASS 396
- #define DW_DLE_HIGHPC_WRONG_FORM 397
- #define DW_DLE_STR_OFFSETS_BASE_WRONG_FORM 398
- #define DW DLE DATA16 OUTSIDE SECTION 399
- #define DW_DLE_LNCT_MD5_WRONG_FORM 400
- #define DW DLE LINE HEADER CORRUPT 401
- #define DW DLE STR OFFSETS NULLARGUMENT 402
- #define DW_DLE_STR_OFFSETS_NULL_DBG 403
- #define DW_DLE_STR_OFFSETS_NO_MAGIC 404
- #define **DW_DLE_STR_OFFSETS_ARRAY_SIZE** 405
- #define DW_DLE_STR_OFFSETS_VERSION_WRONG 406
- #define DW_DLE_STR_OFFSETS_ARRAY_INDEX_WRONG 407
- #define DW_DLE_STR_OFFSETS_EXTRA_BYTES 408
- #define DW_DLE_DUP_ATTR_ON_DIE 409
- #define DW_DLE_SECTION_NAME_BIG 410
- #define DW_DLE_FILE_UNAVAILABLE 411
- #define DW DLE FILE WRONG TYPE 412
- #define DW_DLE_SIBLING_OFFSET_WRONG 413
- #define DW DLE OPEN FAIL 414
- #define DW_DLE_OFFSET_SIZE 415
- #define DW_DLE_MACH_O_SEGOFFSET_BAD 416

- #define DW DLE FILE OFFSET BAD 417
- #define DW_DLE_SEEK_ERROR 418
- #define DW_DLE_READ_ERROR 419
- #define DW DLE ELF CLASS BAD 420
- #define DW DLE ELF ENDIAN BAD 421
- #define DW_DLE_ELF_VERSION_BAD 422
- #define DW DLE FILE TOO SMALL 423
- #define DW_DLE_PATH_SIZE_TOO_SMALL 424
- #define DW_DLE_BAD_TYPE_SIZE 425
- #define DW DLE PE SIZE SMALL 426
- #define DW DLE PE OFFSET BAD 427
- #define DW DLE PE STRING TOO LONG 428
- #define DW DLE IMAGE FILE UNKNOWN TYPE 429
- #define **DW DLE LINE TABLE LINENO ERROR** 430
- #define DW_DLE_PRODUCER_CODE_NOT_AVAILABLE 431
- #define DW DLE NO ELF SUPPORT 432
- #define DW DLE NO STREAM RELOC SUPPORT 433
- #define DW DLE RETURN EMPTY PUBNAMES ERROR 434
- #define DW DLE SECTION SIZE ERROR 435
- #define DW DLE INTERNAL NULL POINTER 436
- #define DW_DLE_SECTION_STRING_OFFSET_BAD 437
- #define DW DLE SECTION INDEX BAD 438
- #define DW DLE INTEGER TOO SMALL 439
- #define DW_DLE_ELF_SECTION_LINK_ERROR 440
- #define DW DLE ELF SECTION GROUP ERROR 441
- #define DW_DLE_ELF_SECTION_COUNT_MISMATCH 442
- #define DW_DLE_ELF_STRING_SECTION_MISSING 443
- #define DW DLE SEEK OFF END 444
- #define DW DLE READ OFF END 445
- #define DW_DLE_ELF_SECTION_ERROR 446
- #define DW_DLE_ELF_STRING_SECTION_ERROR 447
- #define DW DLE MIXING SPLIT DWARF VERSIONS 448
- #define DW_DLE_TAG_CORRUPT 449
- #define DW_DLE_FORM_CORRUPT 450
- #define DW_DLE_ATTR_CORRUPT 451
- #define DW_DLE_ABBREV_ATTR_DUPLICATION 452
- #define **DW_DLE_DWP_SIGNATURE_MISMATCH** 453
- #define DW DLE CU UT TYPE VALUE 454
- #define DW DLE DUPLICATE GNU DEBUGLINK 455
- #define DW DLE CORRUPT GNU DEBUGLINK 456
- #define DW DLE CORRUPT NOTE GNU DEBUGID 457
- #define DW_DLE_CORRUPT_GNU_DEBUGID_SIZE 458
- #define DW_DLE_CORRUPT_GNU_DEBUGID_STRING 459
- #define DW_DLE_HEX_STRING_ERROR 460
- #define DW_DLE_DECIMAL_STRING_ERROR 461
- #define DW DLE PRO INIT EXTRAS UNKNOWN 462
- #define DW DLE PRO INIT EXTRAS ERR 463
- #define DW DLE NULL ARGS DWARF ADD PATH 464
- #define DW_DLE_DWARF_INIT_DBG_NULL 465
- #define DW_DLE_ELF_RELOC_SECTION_ERROR 466
- #define DW DLE USER DECLARED ERROR 467
- #define DW_DLE_RNGLISTS_ERROR 468
- #define DW DLE LOCLISTS ERROR 469
- #define DW DLE SECTION SIZE OR OFFSET LARGE 470
- #define DW_DLE_GDBINDEX_STRING_ERROR 471

- #define DW DLE GNU PUBNAMES ERROR 472
- #define DW DLE GNU PUBTYPES ERROR 473
- #define DW DLE DUPLICATE GNU DEBUG PUBNAMES 474
- #define DW DLE DUPLICATE GNU DEBUG PUBTYPES 475
- #define DW DLE DEBUG SUP STRING ERROR 476
- #define DW DLE DEBUG SUP ERROR 477
- #define DW DLE LOCATION ERROR 478
- #define DW DLE DEBUGLINK PATH SHORT 479
- #define DW DLE SIGNATURE MISMATCH 480
- #define DW_DLE_MACRO_VERSION_ERROR 481
- #define DW DLE NEGATIVE SIZE 482
- #define DW DLE UDATA VALUE NEGATIVE 483
- #define DW DLE DEBUG NAMES ERROR 484
- #define DW_DLE_CFA_INSTRUCTION_ERROR 485
- #define DW_DLE_MACHO_CORRUPT_HEADER 486
- #define DW_DLE_MACHO_CORRUPT_COMMAND 487
- #define DW DLE MACHO CORRUPT SECTIONDETAILS 488
- #define DW DLE RELOCATION SECTION SIZE ERROR 489
- #define DW DLE SYMBOL SECTION SIZE ERROR 490
- #define DW_DLE_PE_SECTION_SIZE_ERROR 491
- #define DW_DLE_DEBUG_ADDR_ERROR 492
- #define DW_DLE_NO_SECT_STRINGS 493
- #define DW_DLE_TOO_FEW_SECTIONS 494
- #define DW DLE BUILD ID DESCRIPTION SIZE 495
- #define DW DLE BAD SECTION FLAGS 496
- #define DW DLE IMPROPER SECTION ZERO 497
- #define DW DLE INVALID NULL ARGUMENT 498
- #define DW_DLE_LINE_INDEX_WRONG 499
- #define DW_DLE_LINE_COUNT_WRONG 500
- #define DW DLE ARITHMETIC OVERFLOW 501
- #define DW_DLE_UNIVERSAL_BINARY_ERROR 502
- #define DW_DLE_UNIV_BIN_OFFSET_SIZE_ERROR 503
- #define DW DLE PE SECTION SIZE HEURISTIC FAIL 504
- #define DW_DLE_LLE_ERROR 505
- #define DW_DLE_RLE_ERROR 506
- #define DW_DLE_MACHO_SEGMENT_COUNT_HEURISTIC_FAIL 507
- #define DW_DLE_LAST 507
- #define DW_DLE_LO_USER 0x10000

9.6.1 Detailed Description

These identify the various error codes that have been used. Not all of them are still use. We do not recycle obsolete codes into new uses. The codes 1 through 22 are historic and it is unlikely they are used anywhere in the library.

9.6.2 Macro Definition Documentation

9.6.2.1 DW_DLE_LAST

#define DW_DLE_LAST 507

Note

DW_DLE_LAST MUST EQUAL LAST ERROR NUMBER

9.7 Libdwarf Initialization Functions

Functions

int dwarf_init_path (const char *dw_path, char *dw_true_path_out_buffer, unsigned int dw_true_path_
 bufferlen, unsigned int dw_groupnumber, Dwarf_Handler dw_errhand, Dwarf_Ptr dw_errarg, Dwarf_Debug
 *dw dbg, Dwarf Error *dw error)

Initialization based on path, the most common initialization.

int dwarf_init_path_a (const char *dw_path, char *dw_true_path_out_buffer, unsigned int dw_true_path
 — bufferlen, unsigned int dw_groupnumber, unsigned int dw_universalnumber, Dwarf_Handler dw_errhand,
 Dwarf_Ptr dw_errarg, Dwarf_Debug *dw_dbg, Dwarf_Error *dw_error)

Initialization based on path.

int dwarf_init_path_dl (const char *dw_path, char *dw_true_path_out_buffer, unsigned int dw_true_path
 — bufferlen, unsigned int dw_groupnumber, Dwarf_Handler dw_errhand, Dwarf_Ptr dw_errarg, Dwarf_Debug
 *dw_dbg, char **dw_dl_path_array, unsigned int dw_dl_path_array_size, unsigned char *dw_dl_path_
 source, Dwarf_Error *dw_error)

Initialization following GNU debuglink section data.

int dwarf_init_path_dl_a (const char *dw_path, char *dw_true_path_out_buffer, unsigned int dw_true_path
 _ bufferlen, unsigned int dw_groupnumber, unsigned int dw_universalnumber, Dwarf_Handler dw_errhand,
 Dwarf_Ptr dw_errarg, Dwarf_Debug *dw_dbg, char **dw_dl_path_array, unsigned int dw_dl_path_array_
 size, unsigned char *dw_dl_path_source, Dwarf_Error *dw_error)

Initialization based on path with debuglink.

 int dwarf_init_b (int dw_fd, unsigned int dw_groupnumber, Dwarf_Handler dw_errhand, Dwarf_Ptr dw_errarg, Dwarf Debug *dw dbg, Dwarf Error *dw error)

Initialization based on Unix/Linux (etc) fd.

int dwarf_finish (Dwarf_Debug dw_dbg)

Close the initialized dw_dbg and free all data libdwarf has for this dw_dbg.

• int dwarf_object_init_b (Dwarf_Obj_Access_Interface_a *dw_obj, Dwarf_Handler dw_errhand, Dwarf_Ptr dw_errarg, unsigned int dw_groupnumber, Dwarf_Debug *dw_dbg, Dwarf_Error *dw_error)

Used to access DWARF information in memory or in an object format unknown to libdwarf.

· int dwarf object finish (Dwarf Debug dw dbg)

Used to close the object_init dw_dbg.

- int dwarf_set_tied_dbg (Dwarf_Debug dw_split_dbg, Dwarf_Debug dw_tied_dbg, Dwarf_Error *dw_error)
 Use with split dwarf.
- int dwarf_get_tied_dbg (Dwarf_Debug dw_dbg, Dwarf_Debug *dw_tieddbg_out, Dwarf_Error *dw_error)
 Use with split dwarf.

9.7.1 Detailed Description

9.7.2 Initialization And Finish Operations

Opening and closing libdwarf on object files.

9.7.3 Function Documentation

9.7.3.1 dwarf_init_path()

On a Mach-O universal binary this function can only return information about the first (zero index) object in the universal binary.

Parameters

dw_path	Pass in the path to the object file to open.
dw_true_path_out_buffer	Pass in NULL or the name of a string buffer (The buffer should be initialized with an initial NUL byte) The returned string will be null-terminated. The path actually used is copied to true_path_out. If true_path_buffer len is zero or true_path_out_buffer is zero then the Special MacOS processing will not occur, nor will the GNU_debuglink processing occur. In case GNU debuglink data was followed or MacOS dSYM applies the true_path_out will not match path and the initial byte will be non-null. The value put in true_path_out is the actual file name.
dw_true_path_bufferlen	Pass in the length in bytes of the buffer.
dw_groupnumber	The value passed in should be DW_GROUPNUMBER_ANY unless one wishes to other than a standard group.
dw_errhand	Pass in NULL unless one wishes libdwarf to call this error handling function (which you must write) instead of passing meaningful values to the dw_error argument.
dw_errarg	If dw_errorhand is non-null, then this value (a pointer or integer that means something to you) is passed to the dw_errhand function in case that is helpful to you.
dw_dbg	On success, *dw_dbg is set to a pointer to a new Dwarf_Debug structure to be used in calls to libdwarf functions.
dw_error	In case return is DW_DLV_ERROR dw_error is set to point to the error details.

Returns

DW_DLV_OK etc.

Details on separate DWARF object access

See also

```
dwarf_init_path_dl dwarf_init_b
Using dwarf_init_path()
```

9.7.3.2 dwarf_init_path_a()

This identical to dwarf_init_path() except that it adds a new argument, dw_universalnumber, with which you can specify which object in a Mach-O universal binary you wish to open.

It is always safe and appropriate to pass zero as the dw_universalnumber. Elf and PE and (non-universal) Mach-O object files ignore the value of dw_universalnumber.

9.7.3.3 dwarf init path dl()

Sets the true-path with DWARF if there is appropriate debuglink data available.

In case DW_DLV_ERROR returned be sure to call dwarf_dealloc_error even though the returned Dwarf_Debug is NULL.

Parameters

dw_path	Pass in the path to the object file to open.
dw_true_path_out_buffer	Pass in NULL or the name of a string buffer.
dw_true_path_bufferlen	Pass in the length in bytes of the buffer.
dw_groupnumber	The value passed in should be DW_GROUPNUMBER_ANY unless one wishes to other than a standard group.
dw_errhand	Pass in NULL, normally. If non-null one wishes libdwarf to call this error handling function (which you must write) instead of passing meaningful values to the dw_error argument.
dw_errarg	Pass in NULL, normally. If dw_errorhand is non-null, then this value (a pointer or integer that means something to you) is passed to the dw_errhand function in case that is helpful to you.
dw_dbg	On success, *dw_dbg is set to a pointer to a new Dwarf_Debug structure to be used in calls to libdwarf functions.

Parameters

dw_dl_path_array	debuglink processing allows a user-specified set of file paths and this argument allows one to specify these. Pass in a pointer to array of pointers to strings which you, the caller, have filled in. The strings should be alternate paths (see the GNU debuglink documentation.)
dw_dl_path_array_size	Specify the size of the dw_dl_path_array.
dw_dl_path_source	returns DW_PATHSOURCE_basic or other such value so the caller can know how the true-path was resolved.
dw_error	In case return is DW_DLV_ERROR dw_error is set to point to the error details.

Returns

DW_DLV_OK etc.

Details on separate DWARF object access

See also

Using dwarf_init_path_dl()

9.7.3.4 dwarf_init_path_dl_a()

This identical to dwarf_init_path_dl() except that it adds a new argument, dw_universalnumber, with which you can specify which object in a Mach-O universal binary you wish to open.

It is always safe and appropriate to pass zero as the dw_universalnumber. Elf and PE and (non-universal) Mach-O object files ignore the value of dw_universalnumber.

Mach-O objects do not contain or use debuglink data.

9.7.3.5 dwarf_init_b()

In case DW_DLV_ERROR returned be sure to call dwarf_dealloc_error even though the returned Dwarf_Debug is NULL.

Parameters

dw_fd	An open Unix/Linux/etc fd on the object file.
dw_groupnumber	The value passed in should be DW_GROUPNUMBER_ANY unless one wishes to other than a standard group.
dw_errhand	Pass in NULL unless one wishes libdwarf to call this error handling function (which you must write) instead of passing meaningful values to the dw_error argument.
dw_errarg	If dw_errorhand is non-null, then this value (a pointer or integer that means something to you) is passed to the dw_errhand function in case that is helpful to you.
dw_dbg	On success, *dw_dbg is set to a pointer to a new Dwarf_Debug structure to be used in calls to libdwarf functions.
dw_error	In case return is DW_DLV_ERROR dw_error is set to point to the error details.

Returns

DW_DLV_OK etc.

9.7.3.6 dwarf_finish()

```
int dwarf_finish ( {\tt Dwarf\_Debug}\ dw\_dbg\ )
```

Parameters

dw_dbg	Close the dbg.
--------	----------------

Returns

May return DW_DLV_ERROR if something is very wrong: no further information is available. May return DW_DLV_NO_ENTRY but no further information is available. Normally returns DW_DLV_OK.

There is nothing the caller can do with the return value except report it somehow. Most callers ignore the return value.

9.7.3.7 dwarf_object_init_b()

In case DW_DLV_ERROR returned be sure to call dwarf_dealloc_error even though the returned Dwarf_Debug is NULL.

See also

Demonstrating reading DWARF without a file.

and

See also

dw_noobject Reading DWARF not in object file

Parameters

dw_obj	A data structure filled out by the caller so libdwarf can access DWARF data not in a supported object file format.
dw_errhand	Pass in NULL normally.
dw_errarg	Pass in NULL normally.
dw_groupnumber	The value passed in should be DW_GROUPNUMBER_ANY unless one wishes to other than a standard group (quite unlikely for this interface).
dw_dbg	On success, *dw_dbg is set to a pointer to a new Dwarf_Debug structure to be used in calls to libdwarf functions.
dw_error	In case return is DW_DLV_ERROR dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.7.3.8 dwarf_object_finish()

Close the dw_dbg opened by dwarf_object_init_b().

Parameters

dw_dbg	Must be an open Dwarf_Debug opened by dwarf_object_init_b(). The init call dw_obj data is not
	freed by the call to dwarf_object_finish.

Returns

The return value DW_DLV_OK etc is useless, one could possibly report it somehow. Callers usually ignore the return value.

9.7.3.9 dwarf_set_tied_dbg()

In libdwarf usage the object file being reported on [a] is opened with dwarf_init_path() or the like. If that object file [a] is a split-dwarf object then important data needed to report all of what is in the object file [a] needs an open Dwarf_Debug on the base object file [b] (usually the base executable object). Here we call that executable object file [b] the *tied* object.

See DWARF5 Appendix F.

Parameters

dw_split_dbg	Pass in an open dbg, on a split-dwarf object file with (normally) lots of DWARF but no executable code.
dw_tied_dbg	Pass in an open dbg on an executable (we call it a <i>tied</i> dbg here) which has minimal DWARF (to save space in the executable).
dw_error	In case return is DW_DLV_ERROR dw_error is set to point to the error details.

Returns

DW_DLV_OK etc.

See also

Attaching a tied dbg

Detaching a tied dbg

9.7.3.10 dwarf_get_tied_dbg()

Given a main Dwarf_Debug this returns the tied Dwarf_Debug if there is one or else returns null(0).

Before v0.11.0 it was not defined what this returned if the tied-Dwarf_Debug was passed in, but it would have returned null(0) in that case. Unlikely anyone uses this call as callers had the tied and base dbg when calling dwarf_set_tied_dbg().

Parameters

dw_dbg	Pass in a non-null Dwarf_Debug which is either a main-Dwarf_Debug or a tied-Dwarf_Debug.
dw_tieddbg_out	On success returns the applicable tied-Dwarf_Debug through the pointer. If dw_dbg is a tied-Dwarf_Debug the function returns null(0) through the poiner. If there is no tied-Dwarf_Debug (meaning there is just a main-Dwarf_Debug) the function returns null (0) through the pointer.
dw_error	If the dw_dbg is invalid or damaged then the function returns DW_DLV_ERROR and dw_error is set to point to the error details.

Returns

DW_DLV_OK or DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY.

9.8 Compilation Unit (CU) Access

Functions

int dwarf_next_cu_header_e (Dwarf_Debug dw_dbg, Dwarf_Bool dw_is_info, Dwarf_Die *dw_cu_die, Dwarf_Unsigned *dw_cu_header_length, Dwarf_Half *dw_version_stamp, Dwarf_Off *dw_abbrev_offset, Dwarf_Half *dw_address_size, Dwarf_Half *dw_length_size, Dwarf_Half *dw_extension_size, Dwarf_Sig8 *dw_type_signature, Dwarf_Unsigned *dw_typeoffset, Dwarf_Unsigned *dw_next_cu_header_offset, Dwarf_Half *dw_header_cu_type, Dwarf_Error *dw_error)

Return information on the next CU header(e).

int dwarf_next_cu_header_d (Dwarf_Debug dw_dbg, Dwarf_Bool dw_is_info, Dwarf_Unsigned *dw_cu_
header_length, Dwarf_Half *dw_version_stamp, Dwarf_Off *dw_abbrev_offset, Dwarf_Half *dw_address
_size, Dwarf_Half *dw_length_size, Dwarf_Half *dw_extension_size, Dwarf_Sig8 *dw_type_signature,
Dwarf_Unsigned *dw_typeoffset, Dwarf_Unsigned *dw_next_cu_header_offset, Dwarf_Half *dw_header
_cu_type, Dwarf_Error *dw_error)

Return information on the next CU header(d)

- int dwarf_siblingof_c (Dwarf_Die dw_die, Dwarf_Die *dw_return_siblingdie, Dwarf_Error *dw_error)

 Return the next sibling DIE.
- int dwarf_siblingof_b (Dwarf_Debug dw_dbg, Dwarf_Die dw_die, Dwarf_Bool dw_is_info, Dwarf_Die *dw_←
 return siblingdie, Dwarf Error *dw error)

Return the first DIE or the next sibling DIE.

int dwarf_cu_header_basics (Dwarf_Die dw_die, Dwarf_Half *dw_version, Dwarf_Bool *dw_is_info, Dwarf_Bool *dw_is_dwo, Dwarf_Half *dw_offset_size, Dwarf_Half *dw_address_size, Dwarf_Half *dw_county extension_size, Dwarf_Sig8 **dw_signature, Dwarf_Off *dw_offset_of_length, Dwarf_Unsigned *dw_totalcounty byte_length, Dwarf_Error *dw_error)

Return some CU-relative facts.

• int dwarf_child (Dwarf_Die dw_die, Dwarf_Die *dw_return_childdie, Dwarf_Error *dw_error)

Return the child DIE, if any. The child may be the first of a list of sibling DIEs.

void dwarf_dealloc_die (Dwarf_Die dw_die)

Deallocate (free) a DIE.

int dwarf_die_from_hash_signature (Dwarf_Debug dw_dbg, Dwarf_Sig8 *dw_hash_sig, const char *dw_

 sig_type, Dwarf_Die *dw_returned_CU_die, Dwarf_Error *dw_error)

Return a CU DIE given a has signature.

int dwarf_offdie_b (Dwarf_Debug dw_dbg, Dwarf_Off dw_offset, Dwarf_Bool dw_is_info, Dwarf_Die *dw_
 return_die, Dwarf_Error *dw_error)

Return DIE given global (not CU-relative) offset.

• int dwarf_find_die_given_sig8 (Dwarf_Debug dw_dbg, Dwarf_Sig8 *dw_ref, Dwarf_Die *dw_die_out, Dwarf_Bool *dw_is_info, Dwarf_Error *dw_error)

Return a DIE given a Dwarf_Sig8 hash.

• Dwarf_Bool dwarf_get_die_infotypes_flag (Dwarf_Die dw_die)

Return the is_info flag.

9.8.1 Detailed Description

9.8.2 Function Documentation

9.8.2.1 dwarf_next_cu_header_e()

```
Dwarf_Die * dw_cu_die,
Dwarf_Unsigned * dw_cu_header_length,
Dwarf_Half * dw_version_stamp,
Dwarf_Off * dw_abbrev_offset,
Dwarf_Half * dw_address_size,
Dwarf_Half * dw_length_size,
Dwarf_Half * dw_extension_size,
Dwarf_Sig8 * dw_type_signature,
Dwarf_Unsigned * dw_typeoffset,
Dwarf_Unsigned * dw_next_cu_header_offset,
Dwarf_Half * dw_header_cu_type,
Dwarf_Error * dw_error )
```

New in v0.9.0 November 2023.

The library keeps track of where it is in the object file and it knows where to find 'next'.

It returns the CU_DIE pointer through dw_cu_die;

dwarf_next_cu_header_e() is preferred over dwarf_next_cu_header_d() as the latter requires a second (immediate) step to access the CU-DIE of the CU.

With the CU-DIE returned by dwarf_next_cu_header_e() one calls dwarf_child() first (the CU-DIE has no siblings) and then one calls dwarf_siblingof_c() and dwarf_child() appropriately to descend the tree of DIEs.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_is_info	Pass in TRUE if reading through .debug_info Pass in FALSE if reading through DWARF4 .debug_types.
dw_cu_die	Pass in a pointer to a Dwarf_Die. the call sets the passed-in pointer to be a Compilation Unit Die for use with dwarf_child() or any other call requiring a Dwarf_Die argument.
dw_cu_header_length	Returns the length of the just-read CU header.
dw_version_stamp	Returns the version number (2 to 5) of the CU header just read.
dw_abbrev_offset	Returns the .debug_abbrev offset from the the CU header just read.
dw_address_size	Returns the address size specified for this CU, usually either 4 or 8.
dw_length_size	Returns the offset size (the length of the size field from the header) specified for this CU, either 4 or 4.
dw_extension_size	If the section is standard 64bit DWARF then this value is 4. Else the value is zero.
dw_type_signature	If the CU is DW_UT_skeleton DW_UT_split_compile, DW_UT_split_type or DW_UT_type this is the type signature from the CU_header compiled into this field.
dw_typeoffset	For DW_UT_split_type or DW_UT_type this is the type offset from the CU header.
dw_next_cu_header_offset	The offset in the section of the next CU (unless there is a compiler bug this is rarely of interest).
dw_header_cu_type	Returns DW_UT_compile, or other DW_UT value.
dw_error	In case return is DW_DLV_ERROR dw_error is set to point to the error details.

Returns

Returns DW_DLV_OK on success. Returns DW_DLV_NO_ENTRY if all CUs have been read.

See also

Example walking CUs(e)

9.8.2.2 dwarf_next_cu_header_d()

This is the version to use for linking against libdwarf v0.8.0 and earlier (and it also works for later versions).

This version will eventually be deprecated.

The library keeps track of where it is in the object file and it knows where to find 'next'.

In order to read the DIE tree of the CU this records information in the dw_dbg data and after a successful call to dwarf_next_cu_header_d() only an immediate call to dwarf_siblingof_b(dw_dbg,NULL,dw_is_info, &cu_die,...) is guaranteed to return the correct DIE (a Compilation Unit DIE).

Avoid any call to libdwarf between a successful call to dwarf_next_cu_header_d() and dwarf_siblingof_b(dw_dbg, ← NULL,dw_is_info, &cu_die,...) to ensure the intended and correct Dwarf_Die is returned.

See also

Example walking CUs(d)

All arguments are the same as dwarf_next_cu_header_e() except that there is no dw_cu_die argument here.

9.8.2.3 dwarf_siblingof_c()

Parameters

dw_die	Pass in a known DIE and this will retrieve the next sibling in the chain.
dw_return_siblingdie	The DIE returned through the pointer.
dw_error	The usual error information, if any.

Returns

```
Returns DW_DLV_OK etc.
```

See also

```
example4
dwarf_get_die_infotypes
```

9.8.2.4 dwarf_siblingof_b()

This function follows dwarf_next_cu_header_d() to return the CU-DIE that dwarf_next_cu_header_d() implies but does not reveal.

Aside from the special case required use of dwarf_siblingof_b() immediately following dwarf_next_cu_header_d(), dwarf_siblingof_c() is the faster function.

This function will eventually be deprecated.

Parameters

dw_dbg	The Dwarf_Debug one is operating on.
dw_die	Immediately after calling dwarf_next_cu_header_d pass in NULL to retrieve the CU DIE. Or pass in a known DIE and this will retrieve the next sibling in the chain.
dw_is_info	Pass TRUE or FALSE to match the applicable dwarf_next_cu_header_d call.
dw_return_siblingdie	The DIE returned through the pointer.
dw_error	The usual error information, if any.

Returns

```
Returns DW_DLV_OK etc.
```

See also

```
example4
dwarf_get_die_infotypes
```

9.8.2.5 dwarf_cu_header_basics()

```
Dwarf_Bool * dw_is_info,
Dwarf_Bool * dw_is_dwo,
Dwarf_Half * dw_offset_size,
Dwarf_Half * dw_address_size,
Dwarf_Half * dw_extension_size,
Dwarf_Sig8 ** dw_signature,
Dwarf_Off * dw_offset_of_length,
Dwarf_Unsigned * dw_total_byte_length,
Dwarf_Error * dw_error )
```

Any Dwarf_Die will work. The values returned through the pointers are about the CU for a DIE

Parameters

dw_die	Some open Dwarf_Die.
dw_version	Returns the DWARF version: 2,3,4, or 5
dw_is_info	Returns non-zero if the CU is .debug_info. Returns zero if the CU is .debug_types (DWARF4).
dw_is_dwo	Returns ton-zero if the CU is a dwo/dwp object and zero if it is a standard object.
dw_offset_size	Returns offset size, 4 and 8 are possible.
dw_address_size	Almost always returns 4 or 8. Could be 2 in unusual circumstances.
dw_extension_size	The sum of dw_offset_size and dw_extension_size are the count of the initial bytes of the CU. Standard lengths are 4 and 12. For 1990's SGI objects the length could be 8.
dw_signature	Returns a pointer to an 8 byte signature.
dw_offset_of_length	Returns the section offset of the initial byte of the CU.
dw_total_byte_length	Returns the total length of the CU including the length field and the content of the CU.
dw_error	The usual Dwarf_Error*.

Returns

Returns DW_DLV_OK etc.

9.8.2.6 dwarf_child()

Parameters

dw_die	We will return the first child of this DIE.	
dw_return_childdie	Returns the first child through the pointer. For subsequent dies siblings of the first, use	
	dwarf_siblingof_c().	
dw_error	The usual Dwarf_Error*.	

Returns

Returns DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if dw_{die} has no children.

See also

Using dwarf_child()

9.8.2.7 dwarf_dealloc_die()

Parameters

dw_die	Frees (deallocs) memory associated with this Dwarf_Die.
--------	---

DIEs not freed explicitly will be freed by dwarf_finish().

9.8.2.8 dwarf die from hash signature()

```
int dwarf_die_from_hash_signature (
    Dwarf_Debug dw_dbg,
    Dwarf_Sig8 * dw_hash_sig,
    const char * dw_sig_type,
    Dwarf_Die * dw_returned_CU_die,
    Dwarf_Error * dw_error )
```

Parameters

dw_dbg	
dw_hash_sig	A pointer to an 8 byte signature to be looked up. in .debug_names.
dw_sig_type	Valid type requests are "cu" and "tu"
dw_returned_CU_die	Returns the found CU DIE if one is found.
dw_error	The usual Dwarf_Error*.

Returns

DW_DLV_OK means dw_returned_CU_die was set. DW_DLV_NO_ENTRY means the signature could not be found.

9.8.2.9 dwarf_offdie_b()

This works whether or not the target section has had dwarf_next_cu_header_d() applied, the CU the offset exists in has been seen at all, or the target offset is one libdwarf has seen before.

Parameters

dw_dbg	The applicable Dwarf_Debug	
dw_offset	The global offset of the DIE in the appropriate section.	
dw_is_info	Pass TRUE if the target is .debug_info. Pass FALSE if the target is .debug_types.	
dw_return_die	dw_return_die On success this returns a DIE pointer to the found DIE.	
dw_error	The usual Dwarf_Error*.	

Returns

DW_DLV_OK means dw_returned_die was found DW_DLV_NO_ENTRY is only possible if the offset is to a null DIE, and that is very unusual. Otherwise expect DW_DLV_ERROR.

See also

Using dwarf_offdie_b()

9.8.2.10 dwarf_find_die_given_sig8()

Returns DIE and is_info flag if it finds the hash signature of a DIE. Often will be the CU DIE of DW_UT_split_type or DW_UT_type CU.

Parameters

dw_dbg	The applicable Dwarf_Debug	
dw_ref	A pointer to a Dwarf_Sig8 struct whose content defines what is being searched for.	
dw_die_out	If found, this returns the found DIE itself.	
dw_is_info	dw_is_info If found, this returns section (.debug_is_info or .debug_is_types).	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc.

9.8.2.11 dwarf_get_die_infotypes_flag()

So client software knows if a DIE is in debug_info or (DWARF4-only) debug_types.

Parameters

dw_die	The DIE being queried.
--------	------------------------

Returns

If non-zero the flag means the DIE is in .debug info. Otherwise it means the DIE is in .debug types.

9.9 Debugging Information Entry (DIE) content

Functions

• int dwarf_die_abbrev_global_offset (Dwarf_Die dw_die, Dwarf_Off *dw_abbrev_offset, Dwarf_Unsigned *dw abbrev count, Dwarf Error *dw error)

Return the abbrev section offset of a DIE's abbrevs.

• int dwarf_tag (Dwarf_Die dw_die, Dwarf_Half *dw_return_tag, Dwarf_Error *dw_error)

Get TAG value of DIE.

int dwarf_dieoffset (Dwarf_Die dw_die, Dwarf_Off *dw_return_offset, Dwarf_Error *dw_error)

Return the global section offset of the DIE.

int dwarf_debug_addr_index_to_addr (Dwarf_Die dw_die, Dwarf_Unsigned dw_index, Dwarf_Addr *dw_←
return addr, Dwarf Error *dw error)

Extract address given address index. DWARF5.

· Dwarf Bool dwarf addr form is indexed (int dw form)

Informs if a DW_FORM is an indexed form.

- int dwarf_CU_dieoffset_given_die (Dwarf_Die dw_die, Dwarf_Off *dw_return_offset, Dwarf_Error *dw_error)

 Return the CU DIE offset given any DIE.
- int dwarf_get_cu_die_offset_given_cu_header_offset_b (Dwarf_Debug dw_dbg, Dwarf_Off dw_in_cu_
 header_offset, Dwarf_Bool dw_is_info, Dwarf_Off *dw_out_cu_die_offset, Dwarf_Error *dw_error)

Return the CU DIE section offset given CU header offset.

- int dwarf_die_CU_offset (Dwarf_Die dw_die, Dwarf_Off *dw_return_offset, Dwarf_Error *dw_error)
 returns the CU relative offset of the DIE.
- int dwarf_die_CU_offset_range (Dwarf_Die dw_die, Dwarf_Off *dw_return_CU_header_offset, Dwarf_Off *dw_return_CU_length_bytes, Dwarf_Error *dw_error)

Return the offset length of the entire CU of a DIE.

int dwarf_attr (Dwarf_Die dw_die, Dwarf_Half dw_attrnum, Dwarf_Attribute *dw_returned_attr, Dwarf_Error
 *dw error)

Given DIE and attribute number return a Dwarf_attribute.

int dwarf_die_text (Dwarf_Die dw_die, Dwarf_Half dw_attrnum, char **dw_ret_name, Dwarf_Error *dw_←
error)

Given DIE and attribute number return a string.

• int dwarf diename (Dwarf Die dw die, char **dw diename, Dwarf Error *dw error)

Return the string from a DW_AT_name attribute.

Dwarf_Unsigned dwarf_die_abbrev_code (Dwarf_Die dw_die)

Return the DIE abbrev code.

int dwarf_die_abbrev_children_flag (Dwarf_Die dw_die, Dwarf_Half *dw_ab_has_child)

Return TRUE if the DIE has children.

• int dwarf validate die sibling (Dwarf Die dw sibling, Dwarf Off *dw offset)

Validate a sibling DIE.

 int dwarf_hasattr (Dwarf_Die dw_die, Dwarf_Half dw_attrnum, Dwarf_Bool *dw_returned_bool, Dwarf_Error *dw_error) Tells whether a DIE has a particular attribute.

int dwarf_offset_list (Dwarf_Debug dw_dbg, Dwarf_Off dw_offset, Dwarf_Bool dw_is_info, Dwarf_Off **dw
 —offbuf, Dwarf_Unsigned *dw_offcount, Dwarf_Error *dw_error)

Return an array of DIE children offsets.

- int dwarf_get_die_address_size (Dwarf_Die dw_die, Dwarf_Half *dw_addr_size, Dwarf_Error *dw_error)

 Get the address size applying to a DIE.
- int dwarf_die_offsets (Dwarf_Die dw_die, Dwarf_Off *dw_global_offset, Dwarf_Off *dw_local_offset, Dwarf Error *dw error)

Return section and CU-local offsets of a DIE.

- int dwarf_get_version_of_die (Dwarf_Die dw_die, Dwarf_Half *dw_version, Dwarf_Half *dw_offset_size)

 Get the version and offset size.
- int dwarf_lowpc (Dwarf_Die dw_die, Dwarf_Addr *dw_returned_addr, Dwarf_Error *dw_error)

 Return the DW AT low pc value.
- int dwarf_highpc_b (Dwarf_Die dw_die, Dwarf_Addr *dw_return_addr, Dwarf_Half *dw_return_form, enum Dwarf_Form_Class *dw_return_class, Dwarf_Error *dw_error)

Return the DW_AT_hipc address value.

 int dwarf_dietype_offset (Dwarf_Die dw_die, Dwarf_Off *dw_return_offset, Dwarf_Bool *dw_is_info, Dwarf Error *dw error)

Return the offset from the DW AT type attribute.

- int dwarf_bytesize (Dwarf_Die dw_die, Dwarf_Unsigned *dw_returned_size, Dwarf_Error *dw_error)

 Return the value of the attribute DW_AT_byte_size.
- int dwarf_bitsize (Dwarf_Die dw_die, Dwarf_Unsigned *dw_returned_size, Dwarf_Error *dw_error)

 Return the value of the attribute DW AT bitsize.
- int dwarf_bitoffset (Dwarf_Die dw_die, Dwarf_Half *dw_attrnum, Dwarf_Unsigned *dw_returned_offset, Dwarf_Error *dw_error)

Return the bit offset attribute of a DIE.

- int dwarf_srclang (Dwarf_Die dw_die, Dwarf_Unsigned *dw_returned_lang, Dwarf_Error *dw_error)

 Return the value of the DW AT language attribute.
- int dwarf_language_version_string (Dwarf_Unsigned dw_lang_name, int *dw_default_lower_bound, const char **dw_version_string)

Return the value of the DW_AT_language_version attribute.

• int dwarf_arrayorder (Dwarf_Die dw_die, Dwarf_Unsigned *dw_returned_order, Dwarf_Error *dw_error)

Return the value of the DW AT ordering attribute.

9.9.1 Detailed Description

This is the main interface to attributes of a DIE.

9.9.2 Function Documentation

9.9.2.1 dwarf_die_abbrev_global_offset()

So we can associate a DIE's abbreviations with the contents the abbreviations section. Useful for detailed printing and analysis of abbreviations.

Parameters

dw_die	The DIE of interest	
dw_abbrev_offset	On success is set to the global offset in the .debug_abbrev section of the abbreviations for	
	the DIE.	
dw_abbrev_count	On success is set to the count of abbreviations in the .debug_abbrev section of the	
	abbreviations for the DIE.	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc.

9.9.2.2 dwarf_tag()

Parameters

dw_die	The DIE of interest
dw_return_tag	On success, set to the DW_TAG value of the DIE.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.3 dwarf_dieoffset()

Parameters

dw_die	The DIE of interest
dw_return_offset	On success the offset refers to the section of the DIE itself, which may be .debug_offset or .debug_types.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.4 dwarf_debug_addr_index_to_addr()

Useful for checking for compiler/linker errors in the creation of DWARF5.

Parameters

dw_die	The DIE of interest	
dw_index	An index into .debug_addr. This will look first for .debug_addr in the dbg object DIE and if not there will look in the tied object if that is available.	
dw_return_addr	On success the address is returned through the pointer.	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc.

9.9.2.5 dwarf_addr_form_is_indexed()

Reading a CU DIE with DW_AT_low_pc an indexed value can be problematic as several different FORMs are indexed. Some in DWARF5 others being extensions to DWARF4 and DWARF5. Indexed forms interact with DW — _AT_addr_base in a DIE making this a very relevant distinction.

9.9.2.6 dwarf_CU_dieoffset_given_die()

Returns the global debug_info section offset of the CU DIE in the CU containing the given_die (the passed in DIE can be any DIE).

This does not identify whether the section is .debug_info or .debug_types, use dwarf_get_die_infotypes_flag() to determine the section.

See also

```
dwarf_get_cu_die_offset_given_cu_header_offset_b
Using dwarf_offset_given_die()
```

Parameters

dw_die	The DIE being queried.
dw_return_offset	Returns the section offset of the CU DIE for dw_die.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.7 dwarf_get_cu_die_offset_given_cu_header_offset_b()

Returns the CU DIE global offset if one knows the CU header global offset.

See also

```
dwarf_CU_dieoffset_given_die
```

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_in_cu_header_offset	The CU header offset.
dw_is_info	If TRUE the CU header offset is in .debug_info. Otherwise the CU header offset is in .debug_types.
dw_out_cu_die_offset	The CU DIE offset returned through this pointer.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.8 dwarf_die_CU_offset()

See also

```
dwarf_CU_dieoffset_given_die
```

This does not identify whether the section is .debug_info or .debug_types, use dwarf_get_die_infotypes_flag() to determine the section.

Parameters

dw_die	The DIE being queried.
dw_return_offset	Returns the CU relative offset of this DIE.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.9 dwarf_die_CU_offset_range()

This does not identify whether the section is .debug_info or .debug_types, use dwarf_get_die_infotypes_flag() to determine the section.

Parameters

dw_die	The DIE being queried.
dw_return_CU_header_offset	On success returns the section offset of the CU this DIE is in.
dw_return_CU_length_bytes	On success returns the CU length of the CU this DIE is in, including the CU length, header, and all DIEs.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.10 dwarf_attr()

Returns DW_DLV_NO_ENTRY if the DIE has no attribute dw_attrnum.

Parameters

dw_die	The DIE of interest.
dw_attrnum	An attribute number, for example DW_AT_name.
dw_returned_attr	On success a Dwarf_Attribute pointer is returned and it should eventually be deallocated.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.11 dwarf_die_text()

Returns DW_DLV_NO_ENTRY if the DIE has no attribute dw_attrnum.

Parameters

dw_die	The DIE of interest.
dw_attrnum	An attribute number, for example DW_AT_name.
dw_ret_name	On success a pointer to the string is returned. Do not free the string. Many attributes allow various forms that directly or indirectly contain strings and this returns the string.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.12 dwarf_diename()

Returns DW_DLV_NO_ENTRY if the DIE has no attribute DW_AT_name

Parameters

dw_die	The DIE of interest.
dw_diename	On success a pointer to the string is returned. Do not free the string. Various forms direct indirectly contain strings and this follows all of them to their string.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.13 dwarf_die_abbrev_code()

The Abbrev code for a DIE is a positive integer assigned by the compiler within a particular CU. For .debug_names abbreviations the situation is conceptually similar. The code values are arbitrary but compilers are motivated to make them small so the object size is as small as possible.

Returns the abbrev code of the die. Cannot fail.

Parameters

dw die	The DIE of interest.

Returns

The abbrev code. of the DIE.

9.9.2.14 dwarf_die_abbrev_children_flag()

Parameters

dw_die	A valid DIE pointer (not NULL).
dw_ab_has_child	Sets TRUE though the pointer if the DIE has children. Otherwise sets FALSE.

Returns

Returns TRUE if the DIE has a child DIE. Else returns FALSE.

9.9.2.15 dwarf_validate_die_sibling()

This is used by dwarfdump (when dwarfdump is checking for valid DWARF) to try to catch a corrupt DIE tree.

This does not identify whether the section is .debug_info or .debug_types, use dwarf_get_die_infotypes_flag() to determine the section.

See also

```
using dwarf validate die sibling
```

Parameters

dw_sibling	Pass in a DIE returned by dwarf_siblingof_b().
dw_offset	Set to zero through the pointer.

Returns

Returns DW_DLV_OK if the sibling is at an appropriate place in the section. Otherwise it returns DW_DLV_\circ} ERROR indicating the DIE tree is corrupt.

9.9.2.16 dwarf_hasattr()

Parameters

dw_die	The DIE of interest.
dw_attrnum	The attribute number we are asking about, DW_AT_name for example.
dw_returned_bool	On success is set TRUE if dw_die has dw_attrnum and FALSE otherwise.
dw_error	The usual error detail return pointer.

Returns

Never returns DW_DLV_NO_ENTRY. Returns DW_DLV_OK unless there is an error, in which case it returns DW_DLV_ERROR and sets dw_error to the error details.

9.9.2.17 dwarf_offset_list()

Given a DIE section offset and dw_is_info, returns an array of DIE global [section] offsets of the children of DIE.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_offset	A DIE offset.
dw_is_info	If TRUE says to use the offset in .debug_info. Else use the offset in .debug_types.
dw_offbuf	A pointer to an array of children DIE global [section] offsets is returned through the pointer.
dw_offcount	The number of elements in dw_offbuf. If the DIE has no children it could be zero, in which case dw_offbuf and dw_offcount are not touched.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. DW_DLV_NO_ENTRY means there are no children of the DIE, hence no list of child offsets.

On successful return, use dwarf_dealloc(dbg, dw_offbuf, DW_DLA_UARRAY); to dealloc the allocated space.

See also

Using dwarf_offset_list()

9.9.2.18 dwarf_get_die_address_size()

Parameters

dw_die	The DIE of interest.
dw_addr_size	On success, returns the address size that applies to dw_die. Normally 4 or 8.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.19 dwarf_die_offsets()

This does not identify whether the section is .debug_info or .debug_types, use dwarf_get_die_infotypes_flag() to determine the section.

Parameters

dw_die	The DIE of interest.
dw_global_offset	On success returns the offset of the DIE in its section.
dw_local_offset	On success returns the offset of the DIE within its CU.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.20 dwarf_get_version_of_die()

The values returned apply to the CU this DIE belongs to. This is useful as preparation for calling dwarf_get_form class

Parameters

dw_die	The DIE of interest.
dw_version	Returns the version of the CU this DIE is contained in. Standard version numbers are 2 through 5.
dw_offset_size	Returns the offset_size (4 or 8) of the CU this DIE is contained in.

9.9.2.21 dwarf_lowpc()

Parameters

dw_die	The DIE of interest.
dw_returned_addr	On success returns, through the pointer, the address DW_AT_low_pc defines.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.22 dwarf_highpc_b()

This is accessing the DW_AT_high_pc attribute. Calculating the high pc involves elements which we don't describe here, but which are shown in the example. See the DWARF5 standard.

See also

Reading high pc from a DIE.

Parameters

dw_die	The DIE of interest.
dw_return_addr	On success returns the high-pc address for this DIE. If the high-pc is a not DW_FORM_addr and is a non-indexed constant form one must add the value of the DW_AT_low_pc to this to get the true high-pc value as the value returned is an unsigned offset of the associated low-pc value.
dw_return_form	On success returns the actual FORM for this attribute. Needed for certain cases to calculate the true dw_return_addr;
dw_return_class	On success returns the FORM CLASS for this attribute. Needed for certain cases to calculate the true dw_return_addr;
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.23 dwarf_dietype_offset()

The offset returned is is a global offset from the DW_AT_type of the DIE passed in. If this CU is DWARF4 the offset could be in .debug_types, otherwise it is in .debug_info Check the section of the DIE to know which it is, dwarf_cu_header_basics() will return that.

Added pointer argument to return the section the offset applies to. December 2022.

Parameters

dw_die	The DIE of interest.
dw_return_offset	If successful, returns the offset through the pointer.
dw_is_info	If successful, set to TRUE if the dw_return_offset is in .debug_info and FALSE if the dw_return_offset is in .debug_types.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.24 dwarf_bytesize()

Parameters

dw_die	The DIE of interest.
dw_returned_size	If successful, returns the size through the pointer.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.25 dwarf_bitsize()

Parameters

dw_die	The DIE of interest.
dw_returned_size	If successful, returns the size through the pointer.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.26 dwarf_bitoffset()

If the attribute is DW_AT_data_bit_offset (DWARF4, DWARF5) the returned bit offset has one meaning. If the attribute is DW_AT_bit_offset (DWARF2, DWARF3) the meaning is quite different.

Parameters

dw_die	The DIE of interest.
dw_attrnum	If successful, returns the number of the attribute (DW_AT_data_bit_offset or DW_AT_bit_offset)
dw_returned_offset	If successful, returns the bit offset value.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.27 dwarf_srclang()

The DIE should be a CU DIE.

Parameters

dw_die	The DIE of interest.
dw_returned_lang	On success returns the language code (normally only found on a CU DIE). For example DW_LANG_C
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.9.2.28 dwarf_language_version_string()

Parameters

dw_lang_name	Pass in a DW_LNAME value, for example DW_LNAME_C.
dw_default_lower_bound.	On success returns the language code (normally only found on a CU DIE). For example DW_LANG_C has a default lower bound of zero (0) that will be returned through the pointer.
dw_version_scheme	On success, return the version scheme, For DW_LNAME_C the string returned would by "YYYYMM". If there is no version scheme defined, return a NULL through the pointer. Never dealloc or free() any returned value as it is a static constant string.

Returns

Returns DW_DLV_OK or the dw_lang_name is unknown, returns DW_DLV_NO_ENTRY. Never returns DW ← DLV_ERROR;

9.9.2.29 dwarf_arrayorder()

```
int dwarf\_arrayorder (
```

```
Dwarf_Die dw_die,
Dwarf_Unsigned * dw_returned_order,
Dwarf_Error * dw_error )
```

Parameters

dw_die	The DIE of interest.
dw_returned_order	On success returns the ordering value. For example DW_ORD_row_major
dw_error	The usual error detail return pointer.

Returns

Returns DW DLV OK etc.

9.10 DIE Attribute and Attribute-Form Details

Functions

 int dwarf_attrlist (Dwarf_Die dw_die, Dwarf_Attribute **dw_attrbuf, Dwarf_Signed *dw_attrcount, Dwarf_Error *dw_error)

Gets the full list of attributes.

 int dwarf_hasform (Dwarf_Attribute dw_attr, Dwarf_Half dw_form, Dwarf_Bool *dw_returned_bool, Dwarf_Error *dw_error)

Sets TRUE if a Dwarf_Attribute has the indicated FORM.

- int dwarf_whatform (Dwarf_Attribute dw_attr, Dwarf_Half *dw_returned_final_form, Dwarf_Error *dw_error)

 Return the form of the Dwarf_Attribute.
- int dwarf_whatform_direct (Dwarf_Attribute dw_attr, Dwarf_Half *dw_returned_initial_form, Dwarf_Error *dw_error)

Return the initial form of the Dwarf_Attribute.

- int dwarf_whatattr (Dwarf_Attribute dw_attr, Dwarf_Half *dw_returned_attrnum, Dwarf_Error *dw_error)

 **Return the attribute number of the Dwarf_Attribute.
- int dwarf_formref (Dwarf_Attribute dw_attr, Dwarf_Off *dw_return_offset, Dwarf_Bool *dw_is_info, Dwarf Error *dw error)

Retrieve the CU-relative offset of a reference.

int dwarf_global_formref_b (Dwarf_Attribute dw_attr, Dwarf_Off *dw_return_offset, Dwarf_Bool *dw_offset
 _is_info, Dwarf_Error *dw_error)

Return the section-relative offset of a Dwarf_Attribute.

- int dwarf_global_formref (Dwarf_Attribute dw_attr, Dwarf_Off *dw_return_offset, Dwarf_Error *dw_error)

 Same as dwarf_global_formref_b except...
- int dwarf_formsig8 (Dwarf_Attribute dw_attr, Dwarf_Sig8 *dw_returned_sig_bytes, Dwarf_Error *dw_error)

 Return an 8 byte reference form for DW_FORM_ref_sig8.
- int dwarf_formsig8_const (Dwarf_Attribute dw_attr, Dwarf_Sig8 *dw_returned_sig_bytes, Dwarf_Error *dw
 —error)

Return an 8 byte reference form for DW_FORM_data8.

- int dwarf_formaddr (Dwarf_Attribute dw_attr, Dwarf_Addr *dw_returned_addr, Dwarf_Error *dw_error)

 Return the address when the attribute has form address.
- int dwarf_get_debug_addr_index (Dwarf_Attribute dw_attr, Dwarf_Unsigned *dw_return_index, Dwarf_Error *dw error)

Get the addr index of a Dwarf_Attribute.

• int dwarf_formflag (Dwarf_Attribute dw_attr, Dwarf_Bool *dw_returned_bool, Dwarf_Error *dw_error)

Return the flag value of a flag form.

- int dwarf_formudata (Dwarf_Attribute dw_attr, Dwarf_Unsigned *dw_returned_val, Dwarf_Error *dw_error)

 Return an unsigned value.
- int dwarf_formsdata (Dwarf_Attribute dw_attr, Dwarf_Signed *dw_returned_val, Dwarf_Error *dw_error)

 Return a signed value.
- int dwarf_formdata16 (Dwarf_Attribute dw_attr, Dwarf_Form_Data16 *dw_returned_val, Dwarf_Error *dw
 —error)

Return a 16 byte Dwarf_Form_Data16 value.

- int dwarf_formblock (Dwarf_Attribute dw_attr, Dwarf_Block **dw_returned_block, Dwarf_Error *dw_error)

 *Return an allocated filled-in Form_Block.
- int dwarf_formstring (Dwarf_Attribute dw_attr, char **dw_returned_string, Dwarf_Error *dw_error)

 Return a pointer to a string.
- int dwarf_get_debug_str_index (Dwarf_Attribute dw_attr, Dwarf_Unsigned *dw_return_index, Dwarf_Error *dw_error)

Return a string index.

int dwarf_formexprloc (Dwarf_Attribute dw_attr, Dwarf_Unsigned *dw_return_exprlen, Dwarf_Ptr *dw_
 block_ptr, Dwarf_Error *dw_error)

Return a pointer-to and length-of a block of data.

 enum Dwarf_Form_Class dwarf_get_form_class (Dwarf_Half dw_version, Dwarf_Half dw_attrnum, Dwarf Half dw offset size, Dwarf Half dw form)

Return the FORM_CLASS applicable. Four pieces of information are necessary to get the correct FORM_CLASS.

int dwarf_attr_offset (Dwarf_Die dw_die, Dwarf_Attribute dw_attr, Dwarf_Off *dw_return_offset, Dwarf_Error
 *dw error)

Return the offset of an attribute in its section.

 int dwarf_uncompress_integer_block_a (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_input_length_in_bytes, void *dw_input_block, Dwarf_Unsigned *dw_value_count, Dwarf_Signed **dw_value_array, Dwarf_Error *dw error)

Uncompress a block of sleb numbers It's not much of a compression so not much of an uncompression. Developed by Sun Microsystems and it is unclear if it was ever used.

void dwarf_dealloc_uncompressed_block (Dwarf_Debug dw_dbg, void *dw_value_array)

Dealloc what dwarf_uncompress_integer_block_a allocated.

int dwarf_convert_to_global_offset (Dwarf_Attribute dw_attr, Dwarf_Off dw_offset, Dwarf_Off *dw_return_←
 offset, Dwarf Error *dw error)

Convert local offset to global offset.

void dwarf_dealloc_attribute (Dwarf_Attribute dw_attr)

Dealloc a Dwarf_Attribute When this call returns the dw_attr is a stale pointer.

- int dwarf_discr_list (Dwarf_Debug dw_dbg, Dwarf_Small *dw_blockpointer, Dwarf_Unsigned dw_blocklen, Dwarf_Dsc_Head *dw_dsc_head_out, Dwarf_Unsigned *dw_dsc_array_length_out, Dwarf_Error *dw_error)
 Return an array of discriminant values.
- int dwarf_discr_entry_u (Dwarf_Dsc_Head dw_dsc, Dwarf_Unsigned dw_entrynum, Dwarf_Half *dw_out_
 type, Dwarf_Unsigned *dw_out_discr_low, Dwarf_Unsigned *dw_out_discr_high, Dwarf_Error *dw_error)
 Access a single unsigned discriminant list entry.
- int dwarf_discr_entry_s (Dwarf_Dsc_Head dw_dsc, Dwarf_Unsigned dw_entrynum, Dwarf_Half *dw_out_
 type, Dwarf_Signed *dw_out_discr_low, Dwarf_Signed *dw_out_discr_high, Dwarf_Error *dw_error)

Access to a single signed discriminant list entry.

9.10.1 Detailed Description

Access to the details of DIEs

9.10.2 Function Documentation

9.10.2.1 dwarf_attrlist()

Parameters

dw_die	The DIE from which to pull attributes.	
dw_attrbuf	The pointer is set to point to an array of Dwarf_Attribute (pointers to attribute data). This array must eventually be deallocated.	
dw_attrcount	The number of entries in the array of pointers. There is no null-pointer to terminate the list, use	
	this count.	
dw_error	A place to return error details.	

Returns

If it returns DW_DLV_ERROR and dw_error is non-null it creates an Dwarf_Error and places it in this argument. Usually returns DW_DLV_OK.

See also

```
Using dwarf_attrlist()
Using dwarf_attrlist()
```

9.10.2.2 dwarf_hasform()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_form	The DW_FORM you are asking about, DW_FORM_strp for example.
dw_returned_bool	The pointer passed in must be a valid non-null pointer to a Dwarf_Bool. On success, sets
	the value to TRUE or FALSE.
dw_error	A place to return error details.

Returns

Returns DW_DLV_OK and sets dw_returned_bool. If attribute is passed in NULL or the attribute is badly broken the call returns DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY;

9.10.2.3 dwarf_whatform()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_final_form	The form of the item is returned through the pointer. If the base form is
	DW_FORM_indirect the function resolves the final form and returns that final form.
dw_error	A place to return error details.

Returns

Returns DW_DLV_OK and sets dw_returned_final_form If attribute is passed in NULL or the attribute is badly broken the call returns DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY;

9.10.2.4 dwarf_whatform_direct()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_initial_form	The form of the item is returned through the pointer. If the base form is
	DW_FORM_indirect the value set is DW_FORM_indirect.
dw_error	A place to return error details.

Returns

Returns DW_DLV_OK and sets dw_returned_initial_form. If attribute is passed in NULL or the attribute is badly broken the call returns DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY;

9.10.2.5 dwarf_whatattr()

dw_attr	The Dwarf_Attribute of interest.
dw_returned_attrnum	The attribute number of the attribute is returned through the pointer. For example, DW_AT_name
dw_error Generated by Doxygen	A place to return error details.

Returns

Returns DW_DLV_OK and sets dw_returned_attrnum If attribute is passed in NULL or the attribute is badly broken the call returns DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY;

9.10.2.6 dwarf_formref()

The DW_FORM of the attribute must be one of a small set of local reference forms: DW_FORM_ref<n> or DW \leftarrow _FORM_udata.

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_return_offset	Returns the CU-relative offset through the pointer.
dw_is_info	Returns a flag through the pointer. TRUE if the offset is in .debug_info, FALSE if it is in .debug_types
dw_error	A place to return error details.

Returns

Returns DW_DLV_OK and sets dw_returned_attrnum If attribute is passed in NULL or the attribute is badly broken or the FORM of this attribute is not one of the small set of local references the call returns DW_DLV \leftarrow _ERROR. Never returns DW_DLV_NO_ENTRY;

9.10.2.7 dwarf global formref b()

The target section of the returned offset can be in various sections depending on the FORM. Only a DW_FORM
__ref_sig8 can change the returned offset of a .debug_info DIE via a lookup into .debug_types by changing dw_←
offset_is_info to FALSE (DWARF4).

The caller must determine the target section from the FORM.

dw_attr	The Dwarf_Attribute of interest.
dw_return_offset	Returns the CU-relative offset through the pointer.
dw_offset_is_info	For references to DIEs this informs whether the target DIE (the target the offset refers to) is in .debug_info or .debug_types. For non-DIE targets this field is not meaningful. Refer to the attribute FORM to determine the target section of the offset.
dw_error	A place to return error details.

Returns

Returns DW_DLV_OK and sets dw_return_offset and dw_offset_is_info. If attribute is passed in NULL or the attribute is badly broken or the FORM of this attribute is not one of the many reference types the call returns DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY;

9.10.2.8 dwarf_global_formref()

See also

```
dwarf_global_formref_b
```

This is the same, except there is no dw_offset_is_info pointer so in the case of DWARF4 and DW_FORM_ref_sig8 it is not possible to determine which section the offset applies to!

9.10.2.9 dwarf_formsig8()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_sig_bytes	On success returns DW_DLV_OK and copies the 8 bytes into dw_returned_sig_bytes.
dw_error	A place to return error details.

Returns

On success returns DW_DLV_OK and copies the 8 bytes into dw_returned_sig_bytes. If attribute is passed in NULL or the attribute is badly broken the call returns DW_DLV_ERROR. If the dw_attr has a form other than DW_FORM_ref_sig8 the function returns DW_DLV_NO_ENTRY

9.10.2.10 dwarf_formsig8_const()

dw_attr	The Dwarf_Attribute of interest.
dw_returned_sig_bytes	On success Returns DW_DLV_OK and copies the 8 bytes into dw_returned_sig_bytes.
dw error Generated by Doxygen	A place to return error details.

Returns

On success returns DW_DLV_OK and copies the 8 bytes into dw_returned_sig_bytes. If attribute is passed in NULL or the attribute is badly broken the call returns DW_DLV_ERROR. If the dw_attr has a form other than DW_FORM_data8 the function returns DW_DLV_NO_ENTRY

9.10.2.11 dwarf_formaddr()

There are several address forms, some of them indexed.

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_addr	On success this set through the pointer to the address in the attribute.
dw_error	A place to return error details.

Returns

On success returns DW_DLV_OK sets dw_returned_addr . If attribute is passed in NULL or the attribute is badly broken or the address cannot be retrieved the call returns DW_DLV_ERROR. Never returns DW_DLV \leftarrow _NO_ENTRY.

9.10.2.12 dwarf_get_debug_addr_index()

So a consumer can get the index when the object with the actual .debug_addr section is elsewhere (Debug Fission). Or if the caller just wants the index. Only call it when you know it should does have an index address FORM such as DW_FORM_addrx1 or one of the GNU address index forms.

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_return_index	If successful it returns the index through the pointer.
dw_error	The usual error pointer.

Returns

DW DLV OK if it succeeds. Never returns DW DLV NO ENTRY.

9.10.2.13 dwarf_formflag()

It is an error if the FORM is not a flag form.

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_bool	Returns either TRUE or FALSE through the pointer.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. Never returns DW_DLV_NO_ENTRY.

9.10.2.14 dwarf_formudata()

The form can be an unsigned or signed integral type but if it is a signed type the value must be non-negative. It is an error otherwise.

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_val	On success returns the unsigned value through the pointer.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. Never returns DW_DLV_NO_ENTRY.

9.10.2.15 dwarf_formsdata()

The form must be a signed integral type. It is an error otherwise.

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_val	On success returns the signed value through the pointer.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. Never returns DW_DLV_NO_ENTRY.

9.10.2.16 dwarf_formdata16()

We just store the bytes in a struct, we have no 16 byte integer type. It is an error if the FORM is not DW_FORM $_{\leftarrow}$ data16

See also

```
Dwarf_Form_Data16
```

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_val	Copies the 16 byte value into the pointed to area.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. Never returns DW_DLV_NO_ENTRY.

9.10.2.17 dwarf_formblock()

It is an error if the DW_FORM in the attribute is not a block form. DW_FORM_block2 is an example of a block form.

See also

```
Dwarf_Block
Using dwarf_discr_list()
```

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_block	Allocates a Dwarf_Block and returns a pointer to the filled-in block.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. Never returns DW_DLV_NO_ENTRY.

9.10.2.18 dwarf_formstring()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_returned_string	On success puts a pointer to a string existing in an appropriate DWARF section into
	dw_returned_string. Never free() or dealloc the returned string.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.10.2.19 dwarf_get_debug_str_index()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_return_index	If the form is a string index form (for example DW_FORM_strx) the string index value is returned via the pointer.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. If the attribute form is not one of the string index forms it returns DW_DLV $_{\leftarrow}$ ERROR and sets dw_error to point to the error details.

9.10.2.20 dwarf_formexprloc()

Parameters

dw_attr	The Dwarf_Attribute of interest.
dw_return_exprlen	Returns the length in bytes of the block if it succeeds.
dw_block_ptr	Returns a pointer to the first byte of the block of data if it succeeds.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. If the attribute form is not DW_FORM_exprloc it returns DW_DLV_ERROR and sets dw_error to point to the error details.

9.10.2.21 dwarf_get_form_class()

Parameters

dw_version	The CU's DWARF version. Standard numbers are 2,3,4, or 5.
dw_attrnum	For example DW_AT_name
dw_offset_size	The offset size applicable to the compilation unit relevant to the attribute and form.
dw_form	The FORM number, for example DW_FORM_data4

Returns

Returns a form class, for example DW_FORM_CLASS_CONSTANT. The FORM_CLASS names are mentioned (for example as 'address' in Table 2.3 of DWARF5) but are not assigned formal names & numbers in the standard.

9.10.2.22 dwarf_attr_offset()

Parameters

dw_die	The DIE of interest.
dw_attr	A Dwarf_Attribute of interest in this DIE
dw_return_offset	The offset is in .debug_info if the DIE is there. The offset is in .debug_types if the DIE is there.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. DW_DLV_NO_ENTRY is impossible.

9.10.2.23 dwarf uncompress integer block a()

See also

dwarf_dealloc_uncompressed_block

9.10.2.24 dwarf_dealloc_uncompressed_block()

Parameters

dw_dbg	The Dwarf_Debug of interest
dw_value_array	The array was called an array of Dwarf_Signed. We dealloc all of it without needing
	dw_value_count.

9.10.2.25 dwarf_convert_to_global_offset()

Uses the DW_FORM of the attribute to determine if the dw_offset is local, and if so, adds the CU base offset to adjust dw_offset.

Parameters

dw_attr	The attribute the local offset was extracted from.
dw_offset	The global offset of the attribute.
dw_return_offset	The returned section (global) offset.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds. Returns DW_DLV_ERROR if the dw_attr form is not an offset form (for example, DW_FORM_ref_udata).

9.10.2.26 dwarf_dealloc_attribute()

Parameters

9.10.2.27 dwarf_discr_list()

This applies if a DW_TAG_variant has one of the DW_FORM_block forms.

See also

dwarf_formblock

For an example of use and dealloc:

See also

Using dwarf_discr_list()

dw_dbg	The applicable Dwarf_Debug
dw_blockpointer	The bl_data value from a Dwarf_Block.
dw_blocklen	The bl_len value from a Dwarf_Block.
dw_dsc_head_out	On success returns a pointer to an array of discriminant values in an opaque struct.
dw_dsc_array_length_out	On success returns the number of entries in the dw_dsc_head_out_array Doxygen
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.10.2.28 dwarf_discr_entry_u()

It is up to the caller to know whether the discriminant values are signed or unsigned (therefore to know whether this or dwarf_discr_entry_s. should be called)

Parameters

dw_dsc	The Dwarf_Dsc_Head applicable.
dw_entrynum	Valid values are zero to dw_dsc_array_length_out-1
dw_out_type	On success is set to either DW_DSC_label or DW_DSC_range through the pointer.
dw_out_discr_low	On success set to the lowest in this discriminant range
dw_out_discr_high	On success set to the highest in this discriminant range
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.10.2.29 dwarf_discr_entry_s()

The same as dwarf_discr_entry_u except here the values are signed.

9.11 Line Table For a CU

Functions

 int dwarf_srcfiles (Dwarf_Die dw_cu_die, char ***dw_srcfiles, Dwarf_Signed *dw_filecount, Dwarf_Error *dw error)

The list of source files from the line table header.

int dwarf_srclines_b (Dwarf_Die dw_cudie, Dwarf_Unsigned *dw_version_out, Dwarf_Small *dw_table_
 count, Dwarf Line Context *dw linecontext, Dwarf Error *dw error)

Initialize Dwarf_Line_Context for line table access.

int dwarf_srclines_from_linecontext (Dwarf_Line_Context dw_linecontext, Dwarf_Line **dw_linebuf,
 Dwarf Signed *dw linecount, Dwarf Error *dw error)

Access source lines from line context.

• int dwarf_srclines_two_level_from_linecontext (Dwarf_Line_Context dw_context, Dwarf_Line **dw_linebuf, Dwarf_Signed *dw_linecount, Dwarf_Line **dw_linebuf_actuals, Dwarf_Signed *dw_linecount_actuals, Dwarf_Error *dw error)

Returns line table counts and data.

void dwarf_srclines_dealloc_b (Dwarf_Line_Context dw_context)

Dealloc the memory allocated by dwarf_srclines_b.

 int dwarf_srclines_table_offset (Dwarf_Line_Context dw_context, Dwarf_Unsigned *dw_offset, Dwarf_Error *dw_error)

Return the srclines table offset.

• int dwarf_srclines_comp_dir (Dwarf_Line_Context dw_context, const char **dw_compilation_directory, Dwarf_Error *dw_error)

Compilation Directory name for the CU.

 int dwarf_srclines_subprog_count (Dwarf_Line_Context dw_context, Dwarf_Signed *dw_count, Dwarf_Error *dw error)

Subprog count: Part of the two-level line table extension.

• int dwarf_srclines_subprog_data (Dwarf_Line_Context dw_context, Dwarf_Signed dw_index, const char **dw_name, Dwarf_Unsigned *dw_decl_file, Dwarf_Unsigned *dw_decl_line, Dwarf_Error *dw_error)

Retrieve data from the line table subprog array.

• int dwarf_srclines_files_indexes (Dwarf_Line_Context dw_context, Dwarf_Signed *dw_baseindex, Dwarf_Signed *dw_count, Dwarf_Signed *dw_endindex, Dwarf_Error *dw_error)

Return values easing indexing line table file numbers. Count is the real count of files array entries. Since DWARF 2,3,4 are zero origin indexes and DWARF5 and later are one origin, this function replaces dwarf_srclines_files_count().

• int dwarf_srclines_files_data_b (Dwarf_Line_Context dw_context, Dwarf_Signed dw_index_in, const char **dw_name, Dwarf_Unsigned *dw_directory_index, Dwarf_Unsigned *dw_last_mod_time, Dwarf_Unsigned *dw_file_length, Dwarf_Form_Data16 **dw_md5ptr, Dwarf_Error *dw_error)

Access data for each line table file.

• int dwarf_srclines_include_dir_count (Dwarf_Line_Context dw_line_context, Dwarf_Signed *dw_count, Dwarf Error *dw error)

Return the number of include directories in the Line Table.

• int dwarf_srclines_include_dir_data (Dwarf_Line_Context dw_line_context, Dwarf_Signed dw_index, const char **dw name, Dwarf Error *dw error)

Return the include directories in the Line Table.

• int dwarf_srclines_version (Dwarf_Line_Context dw_line_context, Dwarf_Unsigned *dw_version, Dwarf_Small *dw table count, Dwarf Error *dw error)

The DWARF version number of this compile-unit.

- int dwarf_linebeginstatement (Dwarf_Line dw_line, Dwarf_Bool *dw_returned_bool, Dwarf_Error *dw_error)

 Read Line beginstatement register.
- int dwarf_lineendsequence (Dwarf_Line dw_line, Dwarf_Bool *dw_returned_bool, Dwarf_Error *dw_error)

 Read Line endsequence register flag.
- int dwarf_lineno (Dwarf_Line dw_line, Dwarf_Unsigned *dw_returned_linenum, Dwarf_Error *dw_error)

 Read Line line register.
- int dwarf_line_srcfileno (Dwarf_Line dw_line, Dwarf_Unsigned *dw_returned_filenum, Dwarf_Error *dw_←
 error)

Read Line file register.

• int dwarf line is addr set (Dwarf Line dw line, Dwarf Bool *dw is addr set, Dwarf Error *dw error)

Is the Dwarf_Line address from DW_LNS_set_address? This is not a line register, but it is a flag set by the library in each Dwarf_Line, and it is derived from reading the line table.

- int dwarf_lineaddr (Dwarf_Line dw_line, Dwarf_Addr *dw_returned_addr, Dwarf_Error *dw_error)

 Return the address of the Dwarf_Line.
- int dwarf_lineoff_b (Dwarf_Line dw_line, Dwarf_Unsigned *dw_returned_lineoffset, Dwarf_Error *dw_error)

 Return a column number through the pointer.
- int dwarf_linesrc (Dwarf_Line dw_line, char **dw_returned_name, Dwarf_Error *dw_error)

 Return the file name applicable to the Dwarf_Line.
- int dwarf_lineblock (Dwarf_Line dw_line, Dwarf_Bool *dw_returned_bool, Dwarf_Error *dw_error)
 Return the basic_block line register.
- int dwarf_prologue_end_etc (Dwarf_Line dw_line, Dwarf_Bool *dw_prologue_end, Dwarf_Bool *dw_
 epilogue_begin, Dwarf_Unsigned *dw_isa, Dwarf_Unsigned *dw_discriminator, Dwarf_Error *dw_error)
 Return various line table registers in one call.
- int dwarf_linelogical (Dwarf_Line dw_line, Dwarf_Unsigned *dw_returned_logical, Dwarf_Error *dw_error)

 Experimental Two-level logical Row Number Experimental two level line tables. Not explained here. When reading from an actuals table, dwarf_line_logical() returns the logical row number for the line.
- int dwarf_linecontext (Dwarf_Line dw_line, Dwarf_Unsigned *dw_returned_context, Dwarf_Error *dw_←
 error)

Experimental Two-level line tables call contexts Experimental two level line tables. Not explained here. When reading from a logicals table, dwarf_linecontext() returns the logical row number corresponding the the calling context for an inlined call

• int dwarf_line_subprogno (Dwarf_Line, Dwarf_Unsigned *, Dwarf_Error *)

Two-level line tables get subprogram number Experimental two level line tables. Not explained here. When reading from a logicals table, dwarf_line_subprogno() returns the index in the subprograms table of the inlined subprogram. Currently this always returns zero through the pointer as the relevant field is never updated from the default of zero.

• int dwarf_line_subprog (Dwarf_Line, char **, char **, Dwarf_Unsigned *, Dwarf_Error *)

Two-level line tables get subprog, file, line Experimental two level line tables. Not explained here. When reading from a logicals table, dwarf_line_subprog() returns the name of the inlined subprogram, its declaration filename, and its declaration line number, if available.

- int dwarf_check_lineheader_b (Dwarf_Die dw_cu_die, int *dw_errcount_out, Dwarf_Error *dw_error)

 Access to detailed line table header issues.
- int dwarf_print_lines (Dwarf_Die dw_cu_die, Dwarf_Error *dw_error, int *dw_errorcount_out)

 Print line information in great detail.
- struct Dwarf_Printf_Callback_Info_s dwarf_register_printf_callback (Dwarf_Debug dw_dbg, struct Dwarf_Printf_Callback_Info_s *dw_callbackinfo)

For line details this records callback details.

9.11.1 Detailed Description

Access to all the line table details.

9.11.2 Function Documentation

9.11.2.1 dwarf_srcfiles()

The array returned by this function applies to a single compilation unit (CU).

The returned array is indexed from 0 (zero) to dw_filecount-1 when the function returns DW_DLV_OK.

In referencing the array via a file-number from a **DW_AT_decl_file** or **DW_AT_call_file** attribute one needs to know if the CU is DWARF5 or not.

Line Table Version numbers match compilation unit version numbers except that an experimental line table with line table version 0xfe06 has sometimes been used with DWARF4.

For DWARF5:

The file-number from a **DW_AT_decl_file** or **DW_AT_call_file** is the proper index into the array of string pointers.

For DWARF2,3,4, including experimental line table version 0xfe06 and a file-number from a **DW_AT_decl_file** or **DW_AT_call_file**:

- 1. If the file-number is zero there is no file name to find.
- 2. Otherwise subtract one(1) from the file-number and use the new value as the index into the array of string pointers.

The name strings returned are each assembled in the following way by dwarf srcfiles():

- 1. The file number denotes a name in the line table header.
- 2. If the name is not a full path (i.e. not starting with / in posix/linux/MacOS) then prepend the appropriate directory string from the line table header.
- 3. If the name is still not a full path then prepend the content of the DW_AT_comp_dir attribute of the CU DIE.

To retrieve the line table version call dwarf srclines b() and dwarf srclines version().

See also

Using dwarf srclines b()

Parameters

dw_cu_die	The CU DIE in this CU.
dw_srcfiles	On success allocates an array of pointers to strings and for each such, computes the fullest path possible given the CU DIE data for each file name listed in the line table header.
dw_filecount	On success returns the number of entries in the array of pointers to strings. The number returned is non-negative.
dw_error	The usual error pointer.

Returns

DW DLV OK if it succeeds. If there is no .debug line[.dwo] returns DW DLV NO ENTRY.

See also

Using dwarf_srcfiles()

9.11.2.2 dwarf_srclines_b()

Returns Dwarf_Line_Context pointer, needed for access to line table data. Returns the line table version number (needed to use dwarf_srcfiles() properly).

See also

```
Using dwarf_srclines_b()
Using dwarf_srclines_b() and linecontext
```

Parameters

dw_cudie	The Compilation Unit (CU) DIE of interest.
dw_version_out	The DWARF Line Table version number (Standard: 2,3,4, or 5) Version 0xf006 is an experimental (two-level) line table.
dw_table_count	Zero or one means this is a normal DWARF line table. Two means this is an experimental two-level line table.
dw_linecontext	On success sets the pointer to point to an opaque structure usable for further queries.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.3 dwarf_srclines_from_linecontext()

Provides access to Dwarf_Line data from a Dwarf_Line_Context on a standard line table.

dw_linecontext	The line context of interest.
dw_linebuf	On success returns an array of pointers to Dwarf_Line.
dw_linecount	On success returns the count of entries in dw_linebuf. If dw_linecount is returned as zero this
	is a line table with no lines.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.4 dwarf_srclines_two_level_from_linecontext()

Works for DWARF2,3,4,5 and for experimental two-level line tables. A single level table will have *linebuf_actuals and *linecount actuals set to 0.

Two-level line tables are non-standard and not documented further. For standard (one-level) tables, it will return the single table through dw_linebuf, and the value returned through dw_linecount_actuals will be 0.

People not using these two-level tables should dwarf_srclines_from_linecontext instead.

9.11.2.5 dwarf srclines dealloc b()

The way to deallocate (free) a Dwarf_Line_Context

Parameters

dw_context	The context to be dealloced (freed). On return the pointer passed in is stale and calling
	applications should zero the pointer.

9.11.2.6 dwarf_srclines_table_offset()

The offset is in the relevant .debug_line or .debug_line.dwo section (and in a split dwarf package file includes the base line table offset).

dw_context	
dw_offset	On success returns the section offset of the dw_context.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.7 dwarf_srclines_comp_dir()

Do not free() or dealloc the string, it is in a dwarf section.

Parameters

dw_context	The Line Context of interest.
dw_compilation_directory	On success returns a pointer to a string identifying the compilation directory of the
	CU.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.8 dwarf_srclines_subprog_count()

A non-standard table. The actual meaning of subprog count left undefined here.

Parameters

dw_context	The Dwarf_Line_Context of interest.
dw_count	On success returns the two-level line table subprogram array size in this line context.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.9 dwarf_srclines_subprog_data()

```
const char ** dw_name,
Dwarf_Unsigned * dw_decl_file,
Dwarf_Unsigned * dw_decl_line,
Dwarf_Error * dw_error )
```

A non-standard table. Not defined here.

Parameters

dw_context	The Dwarf_Line_Context of interest.
dw_index	The item to retrieve. Valid indexes are 1 through dw_count.
dw_name	On success returns a pointer to the subprog name.
dw_decl_file	On success returns a file number through the pointer.
dw_decl_line	On success returns a line number through the pointer.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.10 dwarf_srclines_files_indexes()

Parameters

dw_context	The line context of interest.
dw_baseindex	On success returns the base index of valid file indexes. With DWARF2,3,4 the value is 1. With
	DWARF5 the value is 0.
dw_count	On success returns the real count of entries.
dw_endindex	On success returns value such that callers should index as dw_baseindex through
	dw_endindex-1.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

See also

Using dwarf_srclines_b()

9.11.2.11 dwarf_srclines_files_data_b()

Has the md5ptr field so cases where DW_LNCT_MD5 is present can return pointer to the MD5 value. With DWARF 5 index starts with 0. dwarf_srclines_files_indexes() makes indexing through the files easy.

See also

```
dwarf_srclines_files_indexes
Using dwarf_srclines_b()
```

Parameters

dw_context	The line context of interest.
dw_index_in	The entry of interest. Callers should index as dw_baseindex through dw_endindex-1.
dw_name	If dw_name non-null on success returns The file name in the line table header through the pointer.
dw_directory_index	If dw_directory_index non-null on success returns the directory number in the line table header through the pointer.
dw_last_mod_time	If dw_last_mod_time non-null on success returns the directory last modification date/time through the pointer.
dw_file_length	If dw_file_length non-null on success returns the file length recorded in the line table through the pointer.
dw_md5ptr	If dw_md5ptr non-null on success returns a pointer to the 16byte MD5 hash of the file through the pointer. If there is no md5 value present it returns 0 through the pointer.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.12 dwarf_srclines_include_dir_count()

dw_line_context	The line context of interest.
dw_count	On success returns the count of directories. How to use this depends on the line table
	version number.
dw error Generated by Doxygen	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

See also

```
dwarf_srclines_include_dir_data
```

9.11.2.13 dwarf_srclines_include_dir_data()

Parameters

dw_line_context	The line context of interest.
dw_index	Pass in an index to the line context list of include directories. If the line table is version 2,3, or 4, the valid indexes are 1 through dw_count. If the line table is version 5 the valid indexes are 0 through dw_count-1.
dw_name	On success it returns a pointer to a directory name. Do not free/deallocate the string.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

See also

dwarf srclines include dir count

9.11.2.14 dwarf_srclines_version()

The .debug_lines[.dwo] table count informs about the line table version and the type of line table involved.

Meaning of the value returned via dw_table_count:

- 0 The table is a header with no lines.
- 1 The table is a standard line table.
- 2 The table is an experimental line table.

Parameters

dw_line_context	The Line Context of interest.
dw_version	On success, returns the line table version through the pointer.
dw_table_count	On success, returns the tablecount through the pointer. If the table count is zero the line table is a header with no lines. If the table count is 1 this is a standard line table. If the table count is this is an experimental two-level line table.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.15 dwarf_linebeginstatement()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.	
dw_returned_bool	On success it sets the value TRUE (if the dw_line has the is_stmt register set) and FALSE	
	if is_stmt is not set.	
dw_error	The usual error pointer.	

Returns

DW_DLV_OK if it succeeds.

9.11.2.16 dwarf_lineendsequence()

Line Table Registers

dw_line	The Dwarf_Line of interest.
dw_returned_bool	On success it sets the value TRUE (if the dw_line has the end_sequence register set) and FALSE if end_sequence is not set.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.17 dwarf_lineno()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_returned_linenum	On success it sets the value to the line number from the Dwarf_Line line register
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.18 dwarf_line_srcfileno()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_returned_filenum	On success it sets the value to the file number from the Dwarf_Line file register
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.19 dwarf_line_is_addr_set()

Parameters

dw_line	The Dwarf_Line of interest.
dw_is_addr_set	On success it sets the flag to TRUE or FALSE.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.20 dwarf_lineaddr()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_returned_addr	On success it sets the value to the value of the address register in the Dwarf_Line.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.21 dwarf_lineoff_b()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_returned_lineoffset	On success it sets the value to the column register from the Dwarf_Line.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.22 dwarf_linesrc()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_returned_name	On success it reads the file register and finds constructs a file name from a directory and filename there and and returns a pointer to that string through the pointer. It is necessary to deallocthe returned string with dwarf_dealloc(dbg, lsrc_filename, DW_DLA_STRING); (Older versions of this function incorrectly said not to free() or dwarf dealloc().)
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

See also

Using dwarf_srclines_b() and linecontext

9.11.2.23 dwarf_lineblock()

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_returned_bool	On success it sets the flag to TRUE or FALSE from the basic_block register in the line table.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.24 dwarf_prologue_end_etc()

```
Dwarf_Bool * dw_prologue_end,
Dwarf_Bool * dw_epilogue_begin,
Dwarf_Unsigned * dw_isa,
Dwarf_Unsigned * dw_discriminator,
Dwarf_Error * dw_error )
```

Line Table Registers

Parameters

dw_line	The Dwarf_Line of interest.
dw_prologue_end	On success it sets the flag to TRUE or FALSE from the prologue_end register in the line
	table.
dw_epilogue_begin	On success it sets the flag to TRUE or FALSE from the epilogue_begin register in the
	line table.
dw_isa	On success it sets the value to the value of from the isa register in the line table.
dw_discriminator	On success it sets the value to the value of from the discriminator register in the line
	table.
dw_error	The usual error pointer.

Returns

DW_DLV_OK if it succeeds.

9.11.2.25 dwarf_check_lineheader_b()

Lets the caller get detailed messages about some compiler errors we detect. Calls back, the caller should do something with the messages (likely just print them). The lines passed back already have newlines.

See also

```
dwarf_check_lineheader(b)
Dwarf_Printf_Callback_Info_s
```

Parameters

dw_cu_die	The CU DIE of interest
dw_error	If DW_DLV_ERROR this shows one error encountered.
dw_errcount_out	Returns the count of detected errors through the pointer.

Returns

DW_DLV_OK etc.

9.11.2.26 dwarf_print_lines()

dwarf_print_lines lets the caller prints line information for a CU in great detail. Does not use printf. Instead it calls back to the application using a function pointer once per line-to-print. The lines passed back already have any needed newlines.

dwarfdump uses this function for verbose printing of line table data.

Failing to call the dwarf_register_printf_callback() function will prevent the lines from being passed back but such omission is not an error. The same function, but focused on checking for errors is dwarf_check_lineheader_b().

See also

```
Dwarf_Printf_Callback_Info_s
```

Parameters

dw_cu_die	The CU DIE of interest
dw_error	
dw_errorcount_out	

Returns

DW_DLV_OK etc.

9.11.2.27 dwarf_register_printf_callback()

Not usually needed. It is a way to check (while using the library) what callback data is in use or to update that callback data.

See also

```
Dwarf Printf Callback Info s
```

dw_dbg	The Dwarf_Debug of interest.
dw_callbackinfo	h h
	the fields filled in.

Returns

If dw_callbackinfo NULL it returns a copy of the current Dwarf_Printf_Callback_Info_s for dw_dbg. Otherwise it returns the previous contents of the struct.

9.12 Ranges: code addresses in DWARF3-4

Functions

 int dwarf_get_ranges_b (Dwarf_Debug dw_dbg, Dwarf_Off dw_rangesoffset, Dwarf_Die dw_die, Dwarf_Off *dw_return_realoffset, Dwarf_Ranges **dw_rangesbuf, Dwarf_Signed *dw_rangecount, Dwarf_Unsigned *dw_bytecount, Dwarf_Error *dw_error)

Access to code ranges from a CU or just reading through the raw .debug_ranges section.

void dwarf_dealloc_ranges (Dwarf_Debug dw_dbg, Dwarf_Ranges *dw_rangesbuf, Dwarf_Signed dw_
 rangecount)

Dealloc the array dw_rangesbuf.

int dwarf_get_ranges_baseaddress (Dwarf_Debug dw_dbg, Dwarf_Die dw_die, Dwarf_Bool *dw_known
 _base, Dwarf_Unsigned *dw_baseaddress, Dwarf_Bool *dw_at_ranges_offset_present, Dwarf_Unsigned
 *dw_at_ranges_offset, Dwarf_Error *dw_error)

Find ranges base address.

9.12.1 Detailed Description

In DWARF3 and DWARF4 the DW_AT_ranges attribute provides an offset into the .debug_ranges section, which contains code address ranges.

See also

Dwarf_Ranges

DWARF3 and DWARF4. DW_AT_ranges with an unsigned constant FORM (DWARF3) or DW_FORM_sec_offset(DWARF4).

9.12.2 Function Documentation

9.12.2.1 dwarf_get_ranges_b()

Adds return of the dw_realoffset to accommodate DWARF4 GNU split-dwarf, where the ranges could be in the tieddbg (meaning the real executable, a.out, not in a dwp). DWARF4 split-dwarf is an extension, not standard DWARF4.

If printing all entries in the section pass in an initial dw_rangesoffset of zero and dw_die of NULL. Then increment dw_rangesoffset by dw_bytecount and call again to get the next batch of ranges. With a specific option dwarfdump can do this. This not a normal thing to do!

See also

Example getting .debug_ranges data

Parameters

dw_dbg	The Dwarf_Debug of interest
dw_rangesoffset	The offset to read from in the section.
dw_die	Pass in the DIE whose DW_AT_ranges brought us to ranges.
dw_return_realoffset	The actual offset in the section actually read. In a tieddbg dwp DWARF4 extension object the base offset is added to dw_rangesoffset and returned here.
dw_rangesbuf	A pointer to an array of structs is returned here. The struct contents are the raw values in the section.
dw_rangecount	The count of structs in the array is returned here.
dw_bytecount	The number of bytes in the .debug_ranges section applying to the returned array. This makes possible just marching through the section by offset.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.12.2.2 dwarf_dealloc_ranges()

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_rangesbuf	The dw_rangesbuf pointer returned by dwarf_get_ranges_b
dw_rangecount	The dw_rangecount returned by dwarf_get_ranges_b

9.12.2.3 dwarf_get_ranges_baseaddress()

The function allows callers to calculate actual address from .debug_ranges data in a simple and efficient way.

dw_dbg	The Dwarf_Debug of interest.
dw_die	Pass in any non-null valid Dwarf_Die to find the applicable .debug_ranges
	base address. The dw_die need not be a CU-DIE. A null dw_die is allowed.

Parameters

dw_known_base	if dw_die is non-null and there is a known base address for the CU DIE that (a DW_at_low_pc in the CU DIE) dw_known_base will be set TRUE, Otherwise the value FALSE will be returned through dw_known_base.
dw_baseaddress	if dw_known_base is retured as TRUE then dw_baseaddress will be set with the correct pc value. Otherwise zero will be set through dw_baseaddress.
dw_at_ranges_offset_present	Set to 1 (TRUE) if the dw_die has the attribute DW_AT_ranges, otherwise set to zero (FALSE).
dw_at_ranges_offset	Set to the value of dw_die DW_AT_ranges attribute of dw_die if and only iff dw_at_ranges_offset_present was set to 1.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK or DW_DLV_ERROR. Never returns DW_DLV_NO_ENTRY.

9.13 Rnglists: code addresses in DWARF5

Functions

int dwarf_rnglists_get_rle_head (Dwarf_Attribute dw_attr, Dwarf_Half dw_theform, Dwarf_Unsigned dw_
index_or_offset_value, Dwarf_Rnglists_Head *dw_head_out, Dwarf_Unsigned *dw_count_of_entries_in_
head, Dwarf_Unsigned *dw_global_offset_of_rle_set, Dwarf_Error *dw_error)

Get Access to DWARF5 rnglists.

• int dwarf_get_rnglists_entry_fields_a (Dwarf_Rnglists_Head dw_head, Dwarf_Unsigned dw_entrynum, unsigned int *dw_entrylen, unsigned int *dw_rle_value_out, Dwarf_Unsigned *dw_raw1, Dwarf_Unsigned *dw_raw2, Dwarf_Bool *dw_debug_addr_unavailable, Dwarf_Unsigned *dw_cooked1, Dwarf_Unsigned *dw cooked2, Dwarf_Error *dw error)

Access rnglist entry details.

void dwarf_dealloc_rnglists_head (Dwarf_Rnglists_Head dw_head)

Dealloc a Dwarf_Rnglists_Head.

int dwarf_load_rnglists (Dwarf_Debug dw_dbg, Dwarf_Unsigned *dw_rnglists_count, Dwarf_Error *dw_←
error)

Loads all .debug_rnglists headers.

 int dwarf_get_rnglist_offset_index_value (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_context_index, Dwarf_Unsigned dw_offsetentry_index, Dwarf_Unsigned *dw_offset_value_out, Dwarf_Unsigned *dw← _global_offset_value_out, Dwarf_Error *dw_error)

Retrieve the section offset of a rnglist.

int dwarf_get_rnglist_head_basics (Dwarf_Rnglists_Head dw_head, Dwarf_Unsigned *dw_rle_count, Dwarf_Unsigned *dw_rnglists_version, Dwarf_Unsigned *dw_rnglists_index_returned, Dwarf_Unsigned *dw_bytes_total_in_rle, Dwarf_Half *dw_offset_size, Dwarf_Half *dw_address_size, Dwarf_Half *dw_compart_versions
 segment_selector_size, Dwarf_Unsigned *dw_overall_offset_of_this_context, Dwarf_Unsigned *dw_totalcompart_versions
 length_of_this_context, Dwarf_Unsigned *dw_offset_table_offset, Dwarf_Unsigned *dw_offset_table_ometrycount, Dwarf_Bool *dw_rnglists_base_present, Dwarf_Unsigned *dw_rnglists_base_address, Dwarf_Bool *dw_compart_versions
 *dw_rnglists_base_address_present, Dwarf_Unsigned *dw_rnglists_base_address, Dwarf_Bool *dw_compart_versions
 *dw_rnglists_base_address, Dwarf_Bool *dw_compart_versions
 *dw_rnglists_base_address, Dwarf_Bool *dw_compart_versions
 *dw_rnglists_base_address, Dwarf_Bool *dw_compart_versions
 *dw_rnglists_debug_addr_base_present, Dwarf_Unsigned *dw_rnglists_debug_addr_base, Dwarf_Error *dw_compart_versions

Access to internal data on rangelists.

int dwarf_get_rnglist_context_basics (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_index, Dwarf_Unsigned *dw_header_offset, Dwarf_Small *dw_offset_size, Dwarf_Small *dw_extension_size, unsigned int *dw_\iff version, Dwarf_Small *dw_address_size, Dwarf_Small *dw_segment_selector_size, Dwarf_Unsigned *dw\iff offset_entry_count, Dwarf_Unsigned *dw_offset_of_offset_array, Dwarf_Unsigned *dw_offset_of_first_\iff rangeentry, Dwarf_Unsigned *dw_offset_past_last_rangeentry, Dwarf_Error *dw_error)

Access to rnglists header data.

int dwarf_get_rnglist_rle (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_contextnumber, Dwarf_Unsigned dw—
 entry_offset, Dwarf_Unsigned dw_endoffset, unsigned int *dw_entrylen, unsigned int *dw_entry_kind,
 Dwarf_Unsigned *dw_entry_operand1, Dwarf_Unsigned *dw_entry_operand2, Dwarf_Error *dw_error)

Access to raw rnglists range data.

9.13.1 Detailed Description

Used in DWARF5 to define valid address ranges for code.

DW FORM rnglistx or DW AT ranges with DW FORM sec offset

9.13.2 Function Documentation

9.13.2.1 dwarf_rnglists_get_rle_head()

Opens a Dwarf_Rnglists_Head to access a set of DWARF5 rangelists .debug_rnglists DW_FORM_sec_offset DW ← _FORM_rnglistx (DW_AT_ranges in DWARF5).

See also

Accessing rnglists section

dw_attr	The attribute referring to .debug_rnglists
dw_theform	The form number, DW_FORM_sec_offset or DW_FORM_rnglistx.
dw_index_or_offset_value	If the form is an index, pass it here. If the form is an offset, pass that here.
dw_head_out	On success creates a record owning the rnglists data for this attribute.
dw_count_of_entries_in_head	On success this is set to the number of entry in the rnglists for this attribute.
dw_global_offset_of_rle_set	On success set to the global offset of the rnglists in the rnglists section.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.13.2.2 dwarf_get_rnglists_entry_fields_a()

See also

Accessing rnglists section

Parameters

dw_head	The Dwarf_Rnglists_Head of interest.
dw_entrynum	Valid values are 0 through dw_count_of_entries_in_head-1.
dw_entrylen	On success returns the length in bytes of this individual entry.
dw_rle_value_out	On success returns the RLE value of the entry, such as DW_RLE_startx_endx. This determines which of dw_raw1 and dw_raw2 contain meaningful data.
dw_raw1	On success returns a value directly recorded in the rangelist entry if that applies to this rle.
dw_raw2	On success returns a value directly recorded in the rangelist entry if that applies to this rle.
dw_debug_addr_unavailable	On success returns a flag. If the .debug_addr section is required but absent or unavailable the flag is set to TRUE. Otherwise sets the flag FALSE.
dw_cooked1	On success returns (if appropriate) the dw_raw1 value turned into a valid address.
dw_cooked2	On success returns (if appropriate) the dw_raw2 value turned into a valid address. Ignore the value if dw_debug_addr_unavailable is set.
dw_error	The usual error detail return pointer. Ignore the value if dw_debug_addr_unavailable is set.

Returns

Returns DW_DLV_OK etc.

9.13.2.3 dwarf_dealloc_rnglists_head()

```
void dwarf_dealloc_rnglists_head ( {\tt Dwarf\_Rnglists\_Head}\ dw\_head\ )
```

Parameters

dw_head	dealloc all the memory associated with dw_head. The caller should then immediately set the	
	pointer to zero/NULL as it is stale.	

9.13.2.4 dwarf_load_rnglists()

Loads all the rnglists headers and returns DW_DLV_NO_ENTRY if the section is missing or empty. Intended to be done quite early. It is automatically done if anything needing CU or DIE information is called, so it is not necessary for you to call this in any normal situation.

See also

Accessing accessing raw rnglist

Doing it more than once is never necessary or harmful. There is no deallocation call made visible, deallocation happens when dwarf_finish() is called.

Parameters

dw_dbg		
dw_rnglists_count	On success it returns the number of rnglists headers in the section through	
	dw_rnglists_count.	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc. If the section does not exist the function returns DW_DLV_OK.

9.13.2.5 dwarf get rnglist offset index value()

Can be used to access raw rnglist data. Not used by most callers. See DWARF5 Section 7.28 Range List Table Page 242

dw_dbg The Dwarf_Debug of interest.	
-------------------------------------	--

Parameters

dw_context_index	Begin this at zero.
dw_offsetentry_index	Begin this at zero.
dw_offset_value_out	On success returns the rangelist entry offset within the rangelist set.
dw_global_offset_value_out	On success returns the rangelist entry offset within rnglist section.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If there are no rnglists at all, or if one of the above index values is too high to be valid it returns DW_DLV_NO_ENTRY.

9.13.2.6 dwarf get rnglist head basics()

```
int dwarf_get_rnglist_head_basics (
             Dwarf_Rnglists_Head dw_head,
             Dwarf_Unsigned * dw_rle_count,
             Dwarf_Unsigned * dw_rnglists_version,
             Dwarf_Unsigned * dw_rnglists_index_returned,
             Dwarf_Unsigned * dw_bytes_total_in_rle,
             Dwarf_Half * dw_offset_size,
             Dwarf_Half * dw_address_size,
             Dwarf_Half * dw_segment_selector_size,
             Dwarf_Unsigned * dw_overall_offset_of_this_context,
             Dwarf_Unsigned * dw_total_length_of_this_context,
             Dwarf_Unsigned * dw_offset_table_offset,
             Dwarf_Unsigned * dw_offset_table_entrycount,
             Dwarf_Bool * dw_rnglists_base_present,
             Dwarf_Unsigned * dw_rnglists_base,
             Dwarf_Bool * dw_rnglists_base_address_present,
             Dwarf_Unsigned * dw_rnglists_base_address,
             Dwarf_Bool * dw_rnglists_debug_addr_base_present,
             Dwarf_Unsigned * dw_rnglists_debug_addr_base,
             Dwarf_Error * dw_error )
```

Returns detailed data from a Dwarf_Rnglists_Head Since this is primarily internal data we don't describe the details of the returned fields here.

9.13.2.7 dwarf_get_rnglist_context_basics()

```
Dwarf_Unsigned * dw_offset_of_first_rangeentry,
Dwarf_Unsigned * dw_offset_past_last_rangeentry,
Dwarf_Error * dw_error )
```

This returns, independent of any DIEs or CUs information on the .debug_rnglists headers present in the section.

We do not document the details here. See the DWARF5 standard.

Enables printing of details about the Range List Table Headers, one header per call. Index starting at 0. Returns DW_DLV_NO_ENTRY if index is too high for the table. A .debug_rnglists section may contain any number of Range List Table Headers with their details.

9.13.2.8 dwarf get rnglist rle()

Describes the actual raw data recorded in a particular range entry.

We do not describe all these fields for now, the raw values are mostly useful for people debugging compilergenerated DWARF.

9.14 Locations of data: DWARF2-DWARF5

Macros

- #define DW_LKIND_expression 0 /* DWARF2,3,4,5 */
- #define DW_LKIND_loclist 1 /* DWARF 2,3,4 */
- #define DW_LKIND_GNU_exp_list 2 /* GNU DWARF4 .dwo extension */
- #define DW_LKIND_loclists 5 /* DWARF5 loclists */
- #define DW LKIND unknown 99

Functions

• int dwarf_get_loclist_c (Dwarf_Attribute dw_attr, Dwarf_Loc_Head_c *dw_loclist_head, Dwarf_Unsigned *dw_locentry_count, Dwarf_Error *dw_error)

Location Lists and Expressions.

int dwarf_get_loclist_head_kind (Dwarf_Loc_Head_c dw_loclist_head, unsigned int *dw_lkind, Dwarf_Error
 *dw error)

Know what kind of location data it is.

int dwarf_get_locdesc_entry_d (Dwarf_Loc_Head_c dw_loclist_head, Dwarf_Unsigned dw_index, Dwarf_Small *dw_lle_value_out, Dwarf_Unsigned *dw_rawlowpc, Dwarf_Unsigned *dw_rawhipc, Dwarf_Bool *dw_debug_addr_unavailable, Dwarf_Addr *dw_lowpc_cooked, Dwarf_Addr *dw_hipc_cooked, Dwarf_Unsigned *dw_locexpr_op_count_out, Dwarf_Locdesc_c *dw_locentry_out, Dwarf_Small *dw_cooked, Dwarf_Unsigned *dw_locdesc_offset_out, Dwarf_Unsigned *dw_locdesc_offset_out, Dwarf_Error *dw_error)

Retrieve the details(_d) of a location expression.

int dwarf_get_locdesc_entry_e (Dwarf_Loc_Head_c dw_loclist_head, Dwarf_Unsigned dw_index, Dwarf_Small *dw_lle_value_out, Dwarf_Unsigned *dw_rawlowpc, Dwarf_Unsigned *dw_rawhipc, Dwarf_Bool *dw_debug_addr_unavailable, Dwarf_Addr *dw_lowpc_cooked, Dwarf_Addr *dw_hipc_cooked, Dwarf_Unsigned *dw_locexpr_op_count_out, Dwarf_Unsigned *dw_lle_bytecount, Dwarf_Locdesc_c *dw_locentry_out, Dwarf_Small *dw_loclist_source_out, Dwarf_Unsigned *dw_expression_offset_out, Dwarf_Unsigned *dw_locdesc_offset_out, Dwarf_Unsigned *dw_locdesc_offset_out, Dwarf_Unsigned *dw_expression_offset_out, Dwarf_Unsigned *dw_locdesc_offset_out, Dwarf_Unsigned *dw_expression_offset_out, Dwarf_Unsigned *dw_expressi

Retrieve the details(_e) of a location expression.

• int dwarf_get_location_op_value_c (Dwarf_Locdesc_c dw_locdesc, Dwarf_Unsigned dw_index, Dwarf_Small *dw_operator_out, Dwarf_Unsigned *dw_operand1, Dwarf_Unsigned *dw_operand2, Dwarf_Unsigned *dw_operand3, Dwarf_Unsigned *dw_offset_for_branch, Dwarf_Error *dw_error)

Get the raw values from a single location operation.

int dwarf_loclist_from_expr_c (Dwarf_Debug dw_dbg, Dwarf_Ptr dw_expression_in, Dwarf_Unsigned dw_
 expression_length, Dwarf_Half dw_address_size, Dwarf_Half dw_offset_size, Dwarf_Half dw_dwarf_version,
 Dwarf_Loc_Head_c *dw_loc_head, Dwarf_Unsigned *dw_listlen, Dwarf_Error *dw_error)

Generate a Dwarf_Loc_Head_c from an expression block.

void dwarf dealloc loc head c (Dwarf Loc Head c dw head)

Dealloc (free) all memory allocated for Dwarf_Loc_Head_c.

- int dwarf_load_loclists (Dwarf_Debug dw_dbg, Dwarf_Unsigned *dw_loclists_count, Dwarf_Error *dw_error)

 Load Loclists.
- int dwarf_get_loclist_offset_index_value (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_context_index, Dwarf_Unsigned dw_offsetentry_index, Dwarf_Unsigned *dw_offset_value_out, Dwarf_Unsigned *dw_offset_value_out, Dwarf_Error *dw_error)

Return certain loclists offsets.

int dwarf_get_loclist_head_basics (Dwarf_Loc_Head_c dw_head, Dwarf_Small *dw_lkind, Dwarf_Unsigned *dw_lle_count, Dwarf_Unsigned *dw_loclists_version, Dwarf_Unsigned *dw_loclists_index_returned, Dwarf_Unsigned *dw_bytes_total_in_rle, Dwarf_Half *dw_offset_size, Dwarf_Half *dw_address_
 size, Dwarf_Half *dw_segment_selector_size, Dwarf_Unsigned *dw_overall_offset_of_this_context, Dwarf_Unsigned *dw_total_length_of_this_context, Dwarf_Unsigned *dw_offset_table_offset, Dwarf_Unsigned *dw_offset_table_entrycount, Dwarf_Bool *dw_loclists_base_present, Dwarf_Unsigned *dw_loclists_base_address, Dwarf_Bool *dw_loclists_base_address_present, Dwarf_Unsigned *dw_loclists_base_address, Dwarf_Bool *dw_loclists_debug_addr_base_present, Dwarf_Unsigned *dw_loclists_debug_addr_base, Dwarf_Unsigned *dw_loclists_debug_addr_base, Dwarf_Unsigned *dw_offset_this_lle_area, Dwarf_Error *dw_error)

Return basic data about a loclists head.

int dwarf_get_loclist_context_basics (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_index, Dwarf_Unsigned *dw_header_offset, Dwarf_Small *dw_offset_size, Dwarf_Small *dw_extension_size, unsigned int *dw_ ⇔ version, Dwarf_Small *dw_address_size, Dwarf_Small *dw_segment_selector_size, Dwarf_Unsigned *dw → offset_entry_count, Dwarf_Unsigned *dw_offset_of_offset_array, Dwarf_Unsigned *dw_offset_of_first_⇔ locentry, Dwarf_Unsigned *dw_offset_past_last_locentry, Dwarf_Error *dw_error)

Return basic data about a loclists context.

int dwarf_get_loclist_lle (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_contextnumber, Dwarf_Unsigned dw—
 entry_offset, Dwarf_Unsigned dw_endoffset, unsigned int *dw_entrylen, unsigned int *dw_entry_kind,
 Dwarf_Unsigned *dw_entry_operand1, Dwarf_Unsigned *dw_entry_operand2, Dwarf_Unsigned *dw_context = context =

Return basic data about a loclists context entry.

9.14.1 Detailed Description

9.14.2 Function Documentation

9.14.2.1 dwarf_get_loclist_c()

This works on DWARF2 through DWARF5.

See also

Location/expression access

Parameters

dw_attr	The attribute must refer to a location expression or a location list, so must be DW_FORM_block, DW_FORM_exprloc, or a loclist reference form
dw_loclist_head	On success returns a pointer to the created loclist head record.
dw_locentry_count	On success returns the count of records. For an expression it will be one.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.14.2.2 dwarf_get_loclist_head_kind()

Parameters

dw_loclist_head	Pass in a loclist head pointer.
dw_lkind	On success returns the loclist kind through the pointer. For example DW_LKIND_expression.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.14.2.3 dwarf_get_locdesc_entry_d()

Cooked value means the addresses from the location description after base values applied, so they are actual addresses. debug_addr_unavailable non-zero means the record from a Split Dwarf skeleton unit could not be accessed from the .dwo section or dwp object so the cooked values could not be calculated.

Parameters

dw_loclist_head	A loclist head pointer.
dw_index	Pass in an index value less than dw_locentry_count .
dw_lle_value_out	On success returns the DW_LLE value applicable, such as DW_LLE_start_end .
dw_rawlowpc	On success returns the first operand in the expression (if the expression has an operand).
dw_rawhipc	On success returns the second operand in the expression. (if the expression has a second operand).
dw_debug_addr_unavailable	On success returns FALSE if the data required to calculate dw_lowpc_cooked or dw_hipc_cooked was present or TRUE if some required data was missing (for example in split dwarf).
dw_lowpc_cooked	On success and if dw_debug_addr_unavailable FALSE returns the true low address.
dw_hipc_cooked	On success and if dw_debug_addr_unavailable FALSE returns the true high address.
dw_locexpr_op_count_out	On success returns the count of operations in the expression.
dw_locentry_out	On success returns a pointer to a specific location description.
dw_loclist_source_out	On success returns the applicable DW_LKIND value.
dw_expression_offset_out	On success returns the offset of the expression in the applicable section.
dw_locdesc_offset_out	On return sets the offset to the location description offset (if that is meaningful) or zero for simple location expressions.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.14.2.4 dwarf_get_locdesc_entry_e()

```
int dwarf_get_locdesc_entry_e (
```

```
Dwarf_Loc_Head_c dw_loclist_head,
Dwarf_Unsigned dw_index,
Dwarf_Small * dw_lle_value_out,
Dwarf_Unsigned * dw_rawlowpc,
Dwarf_Unsigned * dw_rawhipc,
Dwarf_Bool * dw_debug_addr_unavailable,
Dwarf_Addr * dw_lowpc_cooked,
Dwarf_Addr * dw_hipc_cooked,
Dwarf_Unsigned * dw_locexpr_op_count_out,
Dwarf_Unsigned * dw_lle_bytecount,
Dwarf_Locdesc_c * dw_locentry_out,
Dwarf_Small * dw_loclist_source_out,
Dwarf_Unsigned * dw_expression_offset_out,
Dwarf_Unsigned * dw_locdesc_offset_out,
Dwarf_Unsigned * dw_locdesc_offset_out,
Dwarf_Unsigned * dw_locdesc_offset_out,
Dwarf_Error * dw_error )
```

Cooked value means the addresses from the location description after base values applied, so they are actual addresses. debug_addr_unavailable non-zero means the record from a Split Dwarf skeleton unit could not be accessed from the .dwo section or dwp object so the cooked values could not be calculated.

This is identical to dwarf_get_locdesc_entry_d except that it adds a pointer argument so the caller can know the size, in bytes, of the loclist DW_LLE operation itself.

It's used by dwarfdump but it is unlikely to be of interest to most callers..

9.14.2.5 dwarf get location op value c()

Parameters

dw_locdesc	Pass in a valid Dwarf_Locdesc_c.
dw_index	Pass in the operator index. zero through dw_locexpr_op_count_out-1.
dw_operator_out	On success returns the DW_OP operator, such as DW_OP_plus .
dw_operand1	On success returns the value of the operand or zero.
dw_operand2	On success returns the value of the operand or zero.
dw_operand3	On success returns the value of the operand or zero.
dw_offset_for_branch	On success returns The byte offset of the operator within the entire expression. Useful for checking the correctness of operators that branch
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.14.2.6 dwarf_loclist_from_expr_c()

```
int dwarf_loclist_from_expr_c (
    Dwarf_Debug dw_dbg,
    Dwarf_Ptr dw_expression_in,
    Dwarf_Unsigned dw_expression_length,
    Dwarf_Half dw_address_size,
    Dwarf_Half dw_offset_size,
    Dwarf_Half dw_dwarf_version,
    Dwarf_Loc_Head_c * dw_loc_head,
    Dwarf_Unsigned * dw_listlen,
    Dwarf_Error * dw_error )
```

Useful if you have an expression block (from somewhere), do not have a Dwarf_Attribute available, and wish to deal with the expression.

See also

Reading a location expression

Parameters

dw_dbg	The applicable Dwarf_Debug
dw_expression_in	Pass in a pointer to the expression bytes.
dw_expression_length	Pass in the length, in bytes, of the expression.
dw_address_size	Pass in the applicable address_size.
dw_offset_size	Pass in the applicable offset size.
dw_dwarf_version	Pass in the applicable dwarf version.
dw_loc_head	On success returns a pointer to a dwarf location head record for use in getting to the details of the expression.
dw_listlen	On success, sets the listlen to one.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.14.2.7 dwarf_dealloc_loc_head_c()

Parameters

dw_head	A head pointer.
an_noaa	71 Hodd pointon

The caller should zero the passed-in pointer on return as it is stale at that point.

9.14.2.8 dwarf_load_loclists()

This loads raw .debug_loclists (DWARF5). It is unlikely you have a reason to use this function. If CUs or DIES have been referenced in any way loading is already done. A duplicate loading attempt returns DW_DLV_OK immediately, returning dw loclists count filled in and does nothing else.

Doing it more than once is never necessary or harmful. There is no deallocation call made visible, deallocation happens when dwarf_finish() is called.

Parameters

dw_dbg	The applicable Dwarf_Debug.
dw_loclists_count	On success, returns the number of DWARF5 loclists contexts in the section, whether this is the first or a duplicate load.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK if it loaded successfully or if it is a duplicate load. If no .debug_loclists present returns DW_DLV_NO_ENTRY.

9.14.2.9 dwarf_get_loclist_offset_index_value()

Useful with the DWARF5 .debug_loclists section.

dw_dbg	The Dwarf_Debug of interest.
dw_context_index	Pass in the loclists context index.
dw_offsetentry_index	Pass in the offset array index.
dw_offset_value_out	On success returns the offset value at offset table[dw_offsetentry_index], an offset local to this context.
dw_global_offset_value_out	On success returns the same offset value but with the offset of the table added in to form a section offset.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If one of the indexes passed in is out of range it returns DW_DLV_NO_ENTRY.

9.14.2.10 dwarf_get_loclist_head_basics()

```
int dwarf_get_loclist_head_basics (
            Dwarf_Loc_Head_c dw_head,
             Dwarf_Small * dw_lkind,
             Dwarf_Unsigned * dw_lle_count,
             Dwarf_Unsigned * dw_loclists_version,
             Dwarf_Unsigned * dw_loclists_index_returned,
             Dwarf_Unsigned * dw_bytes_total_in_rle,
             Dwarf_Half * dw_offset_size,
             Dwarf_Half * dw_address_size,
             Dwarf_Half * dw_segment_selector_size,
             Dwarf_Unsigned * dw_overall_offset_of_this_context,
             Dwarf_Unsigned * dw_total_length_of_this_context,
             Dwarf_Unsigned * dw_offset_table_offset,
             Dwarf_Unsigned * dw_offset_table_entrycount,
             Dwarf_Bool * dw_loclists_base_present,
             Dwarf_Unsigned * dw_loclists_base,
            Dwarf_Bool * dw_loclists_base_address_present,
             Dwarf_Unsigned * dw_loclists_base_address,
             Dwarf_Bool * dw_loclists_debug_addr_base_present,
             Dwarf_Unsigned * dw_loclists_debug_addr_base,
             Dwarf_Unsigned * dw_offset_this_lle_area,
             Dwarf_Error * dw_error )
```

Used by dwarfdump to print basic data from the data generated to look at a specific loclist context as returned by dwarf_loclists_index_get_lle_head() or dwarf_loclists_offset_get_lle_head. Here we know there was a Dwarf← _Attribute so additional things are known as compared to calling dwarf_get_loclist_context_basics See DWARF5 Section 7.20 Location List Table page 243.

9.14.2.11 dwarf_get_loclist_context_basics()

Some of the same values as from dwarf_get_loclist_head_basics but here without any dependence on data derived from a CU context. Useful to print raw loclist data.

9.14.2.12 dwarf_get_loclist_lle()

Useful to print raw loclist data.

9.15 .debug_addr access: DWARF5

Functions

 int dwarf_debug_addr_table (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_section_offset, Dwarf_Debug_Addr_Table *dw_table_header, Dwarf_Unsigned *dw_length, Dwarf_Half *dw_version, Dwarf_Small *dw_address_size, Dwarf_Unsigned *dw_at_addr_base, Dwarf_Unsigned *dw_entry_count, Dwarf_Unsigned *dw_next_← table_offset, Dwarf_Error *dw_error)

Return a .debug_addr table.

• int dwarf_debug_addr_by_index (Dwarf_Debug_Addr_Table dw_dat, Dwarf_Unsigned dw_entry_index, Dwarf_Unsigned *dw_address, Dwarf_Error *dw_error)

Return .debug_addr address given table index.

void dwarf_dealloc_debug_addr_table (Dwarf_Debug_Addr_Table dw_dat)
 dealloc (free) a Dwarf_Attr_Table record.

9.15.1 Detailed Description

Reading just the .debug_addr section.

These functions solely useful for reading that section. It seems unlikely you would have a reason to call these. The functions getting attribute values use the section when appropriate without using these functions.

9.15.2 Function Documentation

9.15.2.1 dwarf_debug_addr_table()

```
Dwarf_Small * dw_address_size,
Dwarf_Unsigned * dw_at_addr_base,
Dwarf_Unsigned * dw_entry_count,
Dwarf_Unsigned * dw_next_table_offset,
Dwarf_Error * dw_error )
```

Allocates and returns a pointer to a Dwarf_Debug_Addr_Table as well as the contents of the record.

Other than dw_debug and dw_error and dw_table_header a NULL passed in as a pointer argument means the return value will not be set through the pointer, so a caller can pass NULL for return values of no immediate interest.

It is only intended to enable printing of the simple DWARF5 .debug_addr section (by dwarfdump).

When emitting DWARF4, gcc may emit a GNU-specified .debug_addr format. If some CU has been opened then this call will work, but the single table will have all the entries for all CUs.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_section_offset	Pass in the section offset of a table header. Start with zero. If the passed-in offset is past the last byte of the table the function returns DW_DLV_NO_ENTRY.
dw_table_header	On success Returns a pointer to a Dwarf_Debug_Addr_Table for use with dwarf_get_attr_by_index().
dw_length	On success Returns the length in bytes of this contribution to .debug_addr from the table header, including the table length field and the array of addresses.
dw_version	On success returns the version number, which should be 5.
dw_address_size	On success returns the address size of the address entries in this table.
dw_at_addr_base	On success returns the value that will appear in some DW_AT_addr_base attribute.
dw_entry_count	On success returns the number of table entries in this table instance.
dw_next_table_offset	On success returns the offset of the next table in the section. Use the offset returned in the next call to this function.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If the dw_section_offset passed in is out of range it returns DW_DLV_NO_ENTRY. If it returns DW_DLV_ERROR only dw_error is set, none of the other return values are set through the pointers.

9.15.2.2 dwarf_debug_addr_by_index()

dw_dat	Pass in a Dwarf_Debug_Addr_Table pointer.
dw_entry_index	Pass in a Dwarf_Debug_Addr_Table index to an address. If out of the valid range 0 through dw_entry_count-1 the function returns DW_DLV_NO_ENTRY.
dw_address	Returns an address in the program through the pointer.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If the dw_section_offset passed in is out of range it returns DW_DLV_NO_ENTRY. If it returns DW_DLV_ERROR only dw_error is set, dw_address is not set.

9.15.2.3 dwarf dealloc debug addr table()

Parameters

dw dat

Pass in a valid Dwarf_Debug_Addr_Table pointer. Does nothing if the dw_dat field is NULL.

9.16 Macro Access: DWARF5

Functions

 int dwarf_get_macro_context (Dwarf_Die dw_die, Dwarf_Unsigned *dw_version_out, Dwarf_Macro_Context *dw_macro_context, Dwarf_Unsigned *dw_macro_unit_offset_out, Dwarf_Unsigned *dw_macro_ops_← count_out, Dwarf_Unsigned *dw_macro_ops_data_length_out, Dwarf_Error *dw_error)

DWARF5 .debug_macro access via Dwarf_Die.

int dwarf_get_macro_context_by_offset (Dwarf_Die dw_die, Dwarf_Unsigned dw_offset, Dwarf_Unsigned *dw_version_out, Dwarf_Macro_Context *dw_macro_context, Dwarf_Unsigned *dw_macro_ops_count_
 out, Dwarf_Unsigned *dw_macro_ops_data_length, Dwarf_Error *dw_error)

DWARF5 .debug_macro access via Dwarf_Die and an offset.

int dwarf_macro_context_total_length (Dwarf_Macro_Context dw_context, Dwarf_Unsigned *dw_mac_
 total_len, Dwarf_Error *dw_error)

Return a macro context total length.

void dwarf_dealloc_macro_context (Dwarf_Macro_Context dw_mc)

Dealloc a macro context.

• int dwarf_macro_context_head (Dwarf_Macro_Context dw_mc, Dwarf_Half *dw_version, Dwarf_Unsigned *dw_mac_offset, Dwarf_Unsigned *dw_mac_len, Dwarf_Unsigned *dw_mac_header_len, unsigned int *dw_flags, Dwarf_Bool *dw_has_line_offset, Dwarf_Unsigned *dw_line_offset, Dwarf_Bool *dw_has_cooperands_table, Dwarf_Half *dw_opcode_count, Dwarf_Error *dw_cooperands_table, Dwarf_Error *dw_cooper

Access the internal details of a Dwarf_Macro_Context.

int dwarf_macro_operands_table (Dwarf_Macro_Context dw_mc, Dwarf_Half dw_index, Dwarf_Half *dw
 _opcode_number, Dwarf_Half *dw_operand_count, const Dwarf_Small **dw_operand_array, Dwarf_Error
 *dw error)

Access to the details of the opcode operands table.

 int dwarf_get_macro_op (Dwarf_Macro_Context dw_macro_context, Dwarf_Unsigned dw_op_number, Dwarf_Unsigned *dw_op_start_section_offset, Dwarf_Half *dw_macro_operator, Dwarf_Half *dw_forms_← count, const Dwarf_Small **dw_formcode_array, Dwarf_Error *dw_error)

Access macro operation details of a single operation.

 int dwarf_get_macro_defundef (Dwarf_Macro_Context dw_macro_context, Dwarf_Unsigned dw_op_number, Dwarf_Unsigned *dw_line_number, Dwarf_Unsigned *dw_index, Dwarf_Unsigned *dw_offset, Dwarf_Half *dw forms count, const char **dw macro string, Dwarf Error *dw error)

Get Macro defundef.

int dwarf_get_macro_startend_file (Dwarf_Macro_Context dw_macro_context, Dwarf_Unsigned dw_op_
 number, Dwarf_Unsigned *dw_line_number, Dwarf_Unsigned *dw_name_index_to_line_tab, const char
 **dw_src_file_name, Dwarf_Error *dw_error)

Get Macro start end.

• int dwarf_get_macro_import (Dwarf_Macro_Context dw_macro_context, Dwarf_Unsigned dw_op_number, Dwarf_Unsigned *dw_target_offset, Dwarf_Error *dw_error)

Get Macro import.

9.16.1 Detailed Description

Reading the .debug macro section.

See also

Reading .debug macro data (DWARF5) An example reading .debug macro

9.16.2 Function Documentation

9.16.2.1 dwarf_get_macro_context()

See also

Reading .debug_macro data (DWARF5)

Parameters

dw_die	The CU DIE of interest.
dw_version_out	On success returns the macro context version (5)
dw_macro_context	On success returns a pointer to a macro context which allows access to the context content.
dw_macro_unit_offset_out	On success returns the offset of the macro context.
dw_macro_ops_count_out	On success returns the number of macro operations in the context.
dw_macro_ops_data_length_out	On success returns the length in bytes of the operations in the context.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If no .debug_macro section exists for the CU it returns DW_DLV_NO_ENTRY.

9.16.2.2 dwarf_get_macro_context_by_offset()

Parameters

dw_die	The CU DIE of interest.
dw_offset	The offset in the section to begin reading.
dw_version_out	On success returns the macro context version (5)
dw_macro_context	On success returns a pointer to a macro context which allows access to the context content.
dw_macro_ops_count_out	On success returns the number of macro operations in the context.
dw_macro_ops_data_length	On success returns the length in bytes of the macro context, starting at the offset of the first byte of the context.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If no .debug_macro section exists for the CU it returns DW_DLV_NO_ENTRY. If the dw_offset is outside the section it returns DW_DLV_ERROR.

9.16.2.3 dwarf_macro_context_total_length()

Parameters

dw_context	A pointer to the macro context of interest.
dw_mac_total_len	On success returns the length in bytes of the macro context.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.16.2.4 dwarf_dealloc_macro_context()

Parameters

dw_mc	A pointer to the macro context of interest. On return the caller should zero the pointer as the pointer
	is then stale.

9.16.2.5 dwarf_macro_context_head()

Not described in detail here. See DWARF5 Standard Section 6.3.1 Macro Information Header page 166.

9.16.2.6 dwarf_macro_operands_table()

Not of much interest to most libdwarf users.

Parameters

dw_mc	The macro context of interest.
dw_index	The opcode operands table index. 0 through dw_opcode_count-1.
dw_opcode_number	On success returns the opcode number in the table.
dw_operand_count	On success returns the number of forms for that dw_index.
dw_operand_array	On success returns the array of op operand forms
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.16.2.7 dwarf_get_macro_op()

```
int dwarf_get_macro_op (
```

```
Dwarf_Macro_Context dw_macro_context,
Dwarf_Unsigned dw_op_number,
Dwarf_Unsigned * dw_op_start_section_offset,
Dwarf_Half * dw_macro_operator,
Dwarf_Half * dw_forms_count,
const Dwarf_Small ** dw_formcode_array,
Dwarf_Error * dw_error )
```

Useful for printing basic data about the operation.

Parameters

dw_macro_context	The macro context of interest.
dw_op_number	valid values are 0 through dw_macro_ops_count_out-1.
dw_op_start_section_offset	On success returns the section offset of this operator.
dw_macro_operator	On success returns the the macro operator itself, for example DW_MACRO_define.
dw_forms_count	On success returns the number of forms in the formcode array.
dw_formcode_array	On success returns a pointer to the formcode array of operand forms.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.16.2.8 dwarf_get_macro_defundef()

To extract the value portion of a macro define:

See also

dwarf_find_macro_value_start

dw_macro_context	The macro context of interest.
dw_op_number	valid values are 0 through dw_macro_ops_count_out-1. The op number must be for a def/undef.
dw_line_number	The line number in the user source for this define/undef
dw_index	On success if the macro is an strx form the value returned is the string index in the record, otherwise zero is returned.
dw_offset	On success if the macro is an strp or sup form the value returned is the string offset in the appropriate section, otherwise zero is returned.
dw_forms_count	On success the value 2 is returned.
dw_macro_string	On success a pointer to a null-terminated string is returned. Do not deallow on the string.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. It is an error if operator dw_op_number is not a DW_MACRO_define, DW — MACRO_undef, DW_MACRO_define_strp DW_MACRO_undef_strp, DW_MACRO_undef_sup, DW_— MACRO_undef_sup, DW_MACRO_define_strx, or DW_MACRO_undef_strx,

9.16.2.9 dwarf_get_macro_startend_file()

Parameters

dw_macro_context	The macro context of interest.
dw_op_number	Valid values are 0 through dw_macro_ops_count_out-1. The op number must
	be for a start/end.
dw_line_number	If end_file nothing is returned here. If start_file on success returns the line
	number of the source line of the include directive.
dw_name_index_to_line_tab	If end_file nothing is returned here. If start_file on success returns the file name
	index in the line table file names table.
dw_src_file_name	If end_file nothing is returned here. If start_file on success returns a pointer to
	the null-terminated source file name. Do not free or dealloc this string.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. It is an error if the operator is not DW_MACRO_start_file or DW_MACRO_end_file.

9.16.2.10 dwarf_get_macro_import()

dw_macro_context	The macro context of interest.	
dw_op_number	Valid values are 0 through dw_macro_ops_count_out-1.	
dw_target_offset	et Returns the offset in the imported section.	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc. It is an error if the operator is not DW_MACRO_import or DW_MACRO_import_

sup.

9.17 Macro Access: DWARF2-4

Functions

• char * dwarf_find_macro_value_start (char *dw_macro_string)

int dwarf_get_macro_details (Dwarf_Debug dw_dbg, Dwarf_Off dw_macro_offset, Dwarf_Unsigned dw_
 maximum_count, Dwarf_Signed *dw_entry_count, Dwarf_Macro_Details **dw_details, Dwarf_Error *dw_
 error)

Getting .debug_macinfo macro details.

Return a pointer to the value part of a macro.

9.17.1 Detailed Description

Reading the .debug_macinfo section.

The section is rarely used since it takes a lot of disk space. DWARF5 has much more compact macro data (in section .debug macro).

For an example see

See also

Reading .debug_macinfo (DWARF2-4) An example reading .debug_macinfo

9.17.2 Function Documentation

9.17.2.1 dwarf_find_macro_value_start()

This function Works for all versions, DWARF2-DWARF5

Parameters

dw_macro_string	The macro string passed in should be properly formatted with a name, a space, and then
	the value portion (whether a function-like macro or not function-like).

Returns

On success it returns a pointer to the value portion of the macro. On failure it returns a pointer to a NUL byte (so a zero-length string).

9.17.2.2 dwarf_get_macro_details()

An example calling this function

See also

Reading .debug_macinfo (DWARF2-4)

Parameters

dw_dbg	The Dwarf_Debug of interest.	
dw_macro_offset	The offset in the section you wish to start from.	
dw_maximum_count	Pass in a count to ensure we will not allocate an excessive amount (guarding against a	
dw_entry_count	On success returns a count of the macro operations in a CU macro set.	
dw_details	On success returns a pointer to an array of struct DW_Macro_Details_s .	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc.

9.18 Stack Frame Access

Functions

- int dwarf_get_fde_list (Dwarf_Debug dw_dbg, Dwarf_Cie **dw_cie_data, Dwarf_Signed *dw_cie_element ← count, Dwarf_Fde **dw_fde_data, Dwarf_Signed *dw_fde_element_count, Dwarf_Error *dw_error)
 Get lists of .debug_frame FDEs and CIEs.
- int dwarf_get_fde_list_eh (Dwarf_Debug dw_dbg, Dwarf_Cie **dw_cie_data, Dwarf_Signed *dw_cie_
 element_count, Dwarf_Fde **dw_fde_data, Dwarf_Signed *dw_fde_element_count, Dwarf_Error *dw_error)

 Get lists of .eh_frame FDEs and CIEs.
- void dwarf_dealloc_fde_cie_list (Dwarf_Debug dw_dbg, Dwarf_Cie *dw_cie_data, Dwarf_Signed dw_cie_
 element_count, Dwarf_Fde *dw_fde_data, Dwarf_Signed dw_fde_element_count)

Release storage associated with FDE and CIE arrays.

int dwarf_get_fde_range (Dwarf_Fde dw_fde, Dwarf_Addr *dw_low_pc, Dwarf_Unsigned *dw_func_
 length, Dwarf_Small **dw_fde_bytes, Dwarf_Unsigned *dw_fde_byte_length, Dwarf_Off *dw_cie_offset,
 Dwarf_Signed *dw_cie_index, Dwarf_Off *dw_fde_offset, Dwarf_Error *dw_error)

Return the FDE data for a single FDE.

 int dwarf_get_fde_exception_info (Dwarf_Fde dw_fde, Dwarf_Signed *dw_offset_into_exception_tables, Dwarf Error *dw error)

IRIX only access to C++ destructor tables.

int dwarf_get_cie_of_fde (Dwarf_Fde dw_fde, Dwarf_Cie *dw_cie_returned, Dwarf_Error *dw_error)

Given FDE get CIE.

int dwarf_get_cie_info_b (Dwarf_Cie dw_cie, Dwarf_Unsigned *dw_bytes_in_cie, Dwarf_Small *dw_
 version, char **dw_augmenter, Dwarf_Unsigned *dw_code_alignment_factor, Dwarf_Signed *dw_data
 alignment_factor, Dwarf_Half *dw_return_address_register_rule, Dwarf_Small **dw_initial_instructions,
 Dwarf_Unsigned *dw_initial_instructions_length, Dwarf_Half *dw_offset_size, Dwarf_Error *dw_error)

Given a CIE get access to its content.

• int dwarf_get_cie_index (Dwarf_Cie dw_cie, Dwarf_Signed *dw_index, Dwarf_Error *dw_error)

Return CIE index given CIE.

int dwarf_get_fde_instr_bytes (Dwarf_Fde dw_fde, Dwarf_Small **dw_outinstrs, Dwarf_Unsigned *dw_← outlen, Dwarf Error *dw error)

Return length and pointer to access frame instructions.

int dwarf_get_fde_info_for_all_regs3_b (Dwarf_Fde dw_fde, Dwarf_Addr dw_pc_requested, Dwarf_Regtable3
 *dw_reg_table, Dwarf_Addr *dw_row_pc, Dwarf_Bool *dw_has_more_rows, Dwarf_Addr *dw_←
 subsequent_pc, Dwarf_Error *dw_error)

Return information on frame registers at a given pc value.

• int dwarf_get_fde_info_for_all_regs3 (Dwarf_Fde dw_fde, Dwarf_Addr dw_pc_requested, Dwarf_Regtable3 *dw reg table, Dwarf Addr *dw row pc, Dwarf Error *dw error)

Return information on frame registers at a given pc value.

int dwarf_get_fde_info_for_reg3_c (Dwarf_Fde dw_fde, Dwarf_Half dw_table_column, Dwarf_Addr dw
 __pc_requested, Dwarf_Small *dw_value_type, Dwarf_Unsigned *dw_offset_relevant, Dwarf_Unsigned
 *dw_register, Dwarf_Signed *dw_offset, Dwarf_Block *dw_block_content, Dwarf_Addr *dw_row_pc_out,
 Dwarf_Bool *dw_has_more_rows, Dwarf_Addr *dw_subsequent_pc, Dwarf_Error *dw_error)

Return details about a particular pc and register.

int dwarf_get_fde_info_for_reg3_b (Dwarf_Fde dw_fde, Dwarf_Half dw_table_column, Dwarf_Addr dw_pc←
 _requested, Dwarf_Small *dw_value_type, Dwarf_Unsigned *dw_offset_relevant, Dwarf_Unsigned *dw←
 _register, Dwarf_Unsigned *dw_offset, Dwarf_Block *dw_block_content, Dwarf_Addr *dw_row_pc_out,
 Dwarf_Bool *dw_has_more_rows, Dwarf_Addr *dw_subsequent_pc, Dwarf_Error *dw_error)

Return details about a particular pc and register.

• int dwarf_get_fde_info_for_cfa_reg3_c (Dwarf_Fde dw_fde, Dwarf_Addr dw_pc_requested, Dwarf_Small *dw_value_type, Dwarf_Unsigned *dw_offset_relevant, Dwarf_Unsigned *dw_register, Dwarf_Signed *dw_offset, Dwarf_Block *dw_block, Dwarf_Addr *dw_row_pc_out, Dwarf_Bool *dw_has_more_rows, Dwarf_Addr *dw_subsequent_pc, Dwarf_Error *dw_error)

Get the value of the CFA for a particular pc value.

int dwarf_get_fde_info_for_cfa_reg3_b (Dwarf_Fde dw_fde, Dwarf_Addr dw_pc_requested, Dwarf_Small *dw_value_type, Dwarf_Unsigned *dw_offset_relevant, Dwarf_Unsigned *dw_register, Dwarf_Unsigned *dw_offset, Dwarf_Block *dw_block, Dwarf_Addr *dw_row_pc_out, Dwarf_Bool *dw_has_more_rows, Dwarf_Addr *dw_subsequent_pc, Dwarf_Error *dw_error)

Get the value of the CFA for a particular pc value.

 int dwarf_get_fde_for_die (Dwarf_Debug dw_dbg, Dwarf_Die dw_subr_die, Dwarf_Fde *dw_returned_fde, Dwarf_Error *dw_error)

Get the fde given DW_AT_MIPS_fde in a DIE.

int dwarf_get_fde_n (Dwarf_Fde *dw_fde_data, Dwarf_Unsigned dw_fde_index, Dwarf_Fde *dw_returned
 _fde, Dwarf_Error *dw_error)

Retrieve an FDE from an FDE table.

• int dwarf_get_fde_at_pc (Dwarf_Fde *dw_fde_data, Dwarf_Addr dw_pc_of_interest, Dwarf_Fde *dw_← returned_fde, Dwarf_Addr *dw_lopc, Dwarf_Addr *dw_hipc, Dwarf_Error *dw_error)

Retrieve an FDE given a pc.

• int dwarf_get_cie_augmentation_data (Dwarf_Cie dw_cie, Dwarf_Small **dw_augdata, Dwarf_Unsigned *dw augdata len, Dwarf Error *dw error)

Return .eh_frame CIE augmentation data.

• int dwarf_get_fde_augmentation_data (Dwarf_Fde dw_fde, Dwarf_Small **dw_augdata, Dwarf_Unsigned *dw augdata len, Dwarf Error *dw error)

Return .eh_frame FDE augmentation data.

int dwarf_expand_frame_instructions (Dwarf_Cie dw_cie, Dwarf_Small *dw_instructionspointer, Dwarf_Unsigned dw_length_in_bytes, Dwarf_Frame_Instr_Head *dw_head, Dwarf_Unsigned *dw_instr_count, Dwarf_Error *dw error)

Expands CIE or FDE instructions for detailed examination. Called for CIE initial instructions and FDE instructions. Call dwarf_get_fde_instr_bytes() or dwarf_get_cie_info_b() to get the initial instruction bytes and instructions byte count you wish to expand.

int dwarf_get_frame_instruction (Dwarf_Frame_Instr_Head dw_head, Dwarf_Unsigned dw_instr_index, Dwarf_Unsigned *dw_instr_offset_in_instrs, Dwarf_Small *dw_cfa_operation, const char **dw_fields_
 description, Dwarf_Unsigned *dw_u0, Dwarf_Unsigned *dw_u1, Dwarf_Signed *dw_s0, Dwarf_Signed *dw_s1, Dwarf_Unsigned *dw_code_alignment_factor, Dwarf_Signed *dw_data_alignment_factor, Dwarf_Block *dw expression block, Dwarf_Error *dw error)

Return information about a single instruction Fields_description means a sequence of up to three letters including u,s,r,c,d,b, terminated by NUL byte. It is a string but we test individual bytes instead of using string compares. Do not free any of the returned values.

int dwarf_get_frame_instruction_a (Dwarf_Frame_Instr_Head dw_, Dwarf_Unsigned dw_instr_index, Dwarf_Unsigned *dw_instr_offset_in_instrs, Dwarf_Small *dw_cfa_operation, const char **dw_fields_
 description, Dwarf_Unsigned *dw_u0, Dwarf_Unsigned *dw_u1, Dwarf_Unsigned *dw_u2, Dwarf_Signed *dw_s0, Dwarf_Signed *dw_s1, Dwarf_Unsigned *dw_code_alignment_factor, Dwarf_Signed *dw_data_
 alignment_factor, Dwarf_Block *dw_expression_block, Dwarf_Error *dw_error)

Expands CIE or FDE instructions for detailed examination. Called for CIE initial instructions and FDE instructions. This is the same as dwarf_get_frame_instruction() except that it adds a dw_u2 field which contains an address-space identifier if the letter a appears in dw_fields_description. The dw_u2 field is non-standard and only applies to Heterogeneous Debugging frame instructions defined by LLVM (DW_CFA_LLVM_def_aspace_cfa and DW_CFA_LLVM_def_aspace_cfa_sf)

void dwarf_dealloc_frame_instr_head (Dwarf_Frame_Instr_Head dw_head)

Deallocates the frame instruction data in dw_head.

int dwarf_fde_section_offset (Dwarf_Debug dw_dbg, Dwarf_Fde dw_in_fde, Dwarf_Off *dw_fde_off, Dwarf_Off *dw_cie_off, Dwarf_Error *dw_error)

Return FDE and CIE offsets from debugging info.

 int dwarf_cie_section_offset (Dwarf_Debug dw_dbg, Dwarf_Cie dw_in_cie, Dwarf_Off *dw_cie_off, Dwarf_Error *dw_error)

Use to print CIE offsets from debugging info.

Dwarf_Half dwarf_set_frame_rule_table_size (Dwarf_Debug dw_dbg, Dwarf_Half dw_value)

Frame Rule Table Size Invariants for setting frame registers .

Dwarf_Half dwarf_set_frame_rule_initial_value (Dwarf_Debug dw_dbg, Dwarf_Half dw_value)

Frame Rule Initial Value.

• Dwarf_Half dwarf_set_frame_cfa_value (Dwarf_Debug dw_dbg, Dwarf_Half dw_value)

Frame CFA Column Invariants for setting frame registers .

• Dwarf_Half dwarf_set_frame_same_value (Dwarf_Debug dw_dbg, Dwarf_Half dw_value)

Frame Same Value Default Invariants for setting frame registers .

Dwarf_Half dwarf_set_frame_undefined_value (Dwarf_Debug dw_dbg, Dwarf_Half dw_value)

Frame Undefined Value Default Invariants for setting frame registers .

9.18.1 Detailed Description

Use to access DWARF2-5 .debug_frame and GNU .eh_frame sections. Does not evaluate frame instructions, but provides detailed data so it is possible do that yourself.

9.18.2 Function Documentation

9.18.2.1 dwarf_get_fde_list()

See DWARF5 Section 6.4 Call Frame Information, page 171.

See also

Extracting fde, cie lists.

The FDE array returned through dw_fde_data is sorted low-to-high by the lowest-pc in each FDE.

Parameters

dw_dbg	The Dwarf_Debug of interest.	
dw_cie_data	On success returns a pointer to an array of pointers to CIE data.	
dw_cie_element_count	On success returns a count of the number of elements in the dw_cie_data array.	
dw_fde_data	On success returns a pointer to an array of pointers to FDE data.	
dw_fde_element_count	On success returns a count of the number of elements in the dw_fde_data array. On	
	success	
dw_error	The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc.

9.18.2.2 dwarf_get_fde_list_eh()

The arguments are identical to the previous function, the difference is the section read. The GNU-defined .eh_frame section is very similar to .debug_frame but has unique features that matter when following a stack trace.

See also

```
dwarf_get_fde_list
```

9.18.2.3 dwarf_dealloc_fde_cie_list()

Applies to .eh_frame and .debug_frame lists.

Parameters

dw_dbg	The Dwarf_Debug used in the list setup.
dw_cie_data	As returned from the list setup call.
dw_cie_element_count	
dw_fde_data	As returned from the list setup call.
dw_fde_element_count	As returned from the list setup call.

On return the pointers passed in dw_cie_data and dw_fde_data should be zeroed by the caller as they are then stale pointers.

9.18.2.4 dwarf_get_fde_range()

Parameters

dw_fde	The FDE of interest.
dw_low_pc	On success returns the low pc value for the function involved.
dw_func_length	On success returns the length of the function code in bytes.
dw_fde_bytes	On success returns a pointer to the bytes of the FDE.
dw_fde_byte_length	On success returns the length of the dw_fde_bytes area.
dw_cie_offset	On success returns the section offset of the associated CIE.
dw_cie_index	On success returns the CIE index of the associated CIE.
dw_fde_offset	On success returns the section offset of this FDE.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.18.2.5 dwarf_get_fde_exception_info()

This applies only to IRIX C++ destructor information which was never documented and is unlikely to be of interest.

9.18.2.6 dwarf_get_cie_of_fde()

Parameters

dw_fde	The FDE of interest.
dw_cie_returned	On success returns a pointer to the applicable CIE.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.18.2.7 dwarf_get_cie_info_b()

dw_cie	Pass in the CIE of interest.
dw_bytes_in_cie	On success, returns the length of the CIE in bytes.
dw_version	On success, returns the CIE version number.
dw_augmenter	On success, returns a pointer to the augmentation string (which could be the empty string).
dw_code_alignment_factor	On success, returns a the code_alignment_factor used to interpret CIE/FDE operations.

Parameters

dw_data_alignment_factor	On success, returns a the data_alignment_factor used to interpret CIE/FDE operations.
dw_return_address_register_rule	On success, returns a register number of the return address register.
dw_initial_instructions	On success, returns a pointer to the bytes of initial_instructions in the CIE.
dw_initial_instructions_length	On success, returns the length in bytes of the initial_instructions.
dw_offset_size	On success, returns the offset_size within this CIE.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.18.2.8 dwarf_get_cie_index()

Parameters

dw_cie	Pass in the CIE of interest.
dw_index	On success, returns the index (the position of the CIE in the CIE pointer array).
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc.

9.18.2.9 dwarf_get_fde_instr_bytes()

See also

```
dwarf_expand_frame_instructions
Using dwarf_expand_frame_instructions
```

dw_fde	Pass in the FDE of interest.
dw_outinstrs	On success returns a pointer to the FDE instruction byte stream.
dw_outlen	On success returns the length of the dw_outinstrs byte stream.
Geografe Por Poxygen The usual error detail return pointer.	

Returns

Returns DW_DLV_OK etc.

9.18.2.10 dwarf_get_fde_info_for_all_regs3_b()

An FDE at a given pc (code address) This function is new in October 2023 version 0.9.0.

Parameters

dw_fde	Pass in the FDE of interest.
dw_pc_requested	Pass in a pc (code) address inside that FDE.
dw_reg_table	On success, returns a pointer to a struct given the frame state.
dw_row_pc	On success returns the address of the row of frame data which may be a few counts off of the pc requested.
dw_has_more_rows	On success returns FALSE if there are no more rows, otherwise returns TRUE.
dw_subsequent_pc	On success this returns the address of the next pc for which there is a register row, making access to all the rows in sequence much more efficient than just adding 1 to a pc value.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK if the dw_pc_requested is in the FDE passed in and there is some applicable row in the table.

9.18.2.11 dwarf_get_fde_info_for_all_regs3()

Identical to $dwarf_get_fde_info_for_all_regs3_b()$ except that this doesn't output $dw_has_more_rows$ and $dw_info_for_all_regs3_b()$ except $dw_info_for_all_regs3_b()$ except that this doesn't output $dw_has_more_rows$ and $dw_info_for_all_regs3_b()$ except $dw_info_for_all_regs3_b()$

If you need to iterate through all rows of the FDE, consider switching to dwarf_get_fde_info_for_all_regs3_b() as it is more efficient.

9.18.2.12 dwarf_get_fde_info_for_reg3_c()

It is efficient to iterate across all table_columns (registers) using this function (dwarf_get_fde_info_for_reg3_c()). Or one could instead call dwarf_get_fde_info_for_all_regs3() and index into the table it fills in.

If dw_value_type == DW_EXPR_EXPRESSION or DW_EXPR_VALUE_EXPRESSION dw_offset is not set and the caller must evaluate the expression, which usually depends on runtime frame data which cannot be calculated without a stack frame including registers (etc).

dwarf_get_fde_info_for_reg3_c() is new in libdwarf 0.8.0. It corrects the incorrect type of the dw_offset argument in dwarf_get_fde_info_for_reg3_b(). Both versions operate correctly.

Parameters

dw_fde	Pass in the FDE of interest.
dw_table_column	Pass in the table_column, column numbers in the table are 0 through the
	number_of_registers-1.
dw_pc_requested	Pass in the pc of interest within dw_fde.
dw_value_type	On success returns the value type, a DW_EXPR value. For example
	DW_EXPR_EXPRESSION
dw_offset_relevant	On success returns FALSE if the offset value is irrelevant, otherwise TRUE.
dw_register	On success returns a register number.
dw_offset	On success returns a signed register offset value when dw_value_type is
	DW_EXPR_OFFSET or DW_EXPER_VAL_OFFSET.
dw_block_content	On success returns a pointer to a block. For example, for DW_EXPR_EXPRESSION
	the block gives access to the expression bytes.
dw_row_pc_out	On success returns the address of the actual pc for this register at this pc.
dw_has_more_rows	On success returns FALSE if there are no more rows, otherwise returns TRUE.
dw_subsequent_pc	On success this returns the address of the next pc for which there is a register row,
	making access to all the rows in sequence much more efficient than just adding 1 to a
	pc value.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK if the dw_pc_requested is in the FDE passed in and there is a row for the pc in the table.

9.18.2.13 dwarf_get_fde_info_for_reg3_b()

Identical to dwarf_get_fde_info_for_reg3_c() except that this returns dw_offset as a Dwarf_Unsigned, which was never appropriate, and required you to cast that value to Dwarf_Signed to use it properly.

Please switch to using dwarf_get_fde_info_for_reg3_c()

9.18.2.14 dwarf_get_fde_info_for_cfa_reg3_c()

See also

dwarf_get_fde_info_for_reg3_c() has essentially the same return values as dwarf_get_fde_info_for_reg3_c but it refers to the CFA (which is not part of the register table) so this function has no table column argument.

New in September 2023, release 0.8.0. dwarf_get_fde_info_for_cfa_reg3_c() returns dw_offset as a signed type. dwarf_get_fde_info_for_cfa_reg3_b() returns dw_offset as an unsigned type, requiring the caller to cast to Dwarf

_Signed before using the value. Both versions exist and operate properly.

If dw_value_type == DW_EXPR_EXPRESSION or DW_EXPR_VALUE_EXPRESSION dw_offset is not set and the caller must evaluate the expression, which usually depends on runtime frame data which cannot be calculated without a stack frame including register values (etc).

9.18.2.15 dwarf_get_fde_info_for_cfa_reg3_b()

See also

```
dwarf_get_fde_info_for_cfa_reg3_c
```

This is the earlier version that returns a dw_offset of type Dwarf_Unsigned, requiring you to cast to Dwarf_Signed to work with the value.

9.18.2.16 dwarf_get_fde_for_die()

This is essentially useless as only SGI/MIPS compilers from the 1990's had DW_AT_MIPS_fde in DW_TAG_ \leftarrow subprogram DIEs and this relies on that attribute to work.

9.18.2.17 dwarf_get_fde_n()

This is just like indexing into the FDE array but with extra checking of the pointer and index.

See also

```
dwarf_get_fde_list
```

9.18.2.18 dwarf_get_fde_at_pc()

Using binary search this finds the FDE that contains this dw_pc_of_interest That works because libdwarf ensures the array of FDEs is sorted by the low-pc

See also

```
dwarf_get_fde_list
```

Parameters

dw_fde_data	Pass in a pointer an array of fde pointers.
dw_pc_of_interest	The pc value of interest.
dw_returned_fde	On success a pointer to the applicable FDE is set through the pointer.
dw_lopc	On success a pointer to the low pc in dw_returned_fde is set through the pointer.
dw_hipc	On success a pointer to the high pc (one past the actual last byte address) in
	dw_returned_fde is set through the pointer.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK if the dw_pc_of_interest found in some FDE in the array. If no FDE is found containing dw pc of interest DW DLV NO ENTRY is returned.

9.18.2.19 dwarf_get_cie_augmentation_data()

GNU .eh frame CIE augmentation information. See Linux Standard Base Core Specification version 3.0 .

See also

```
https://gcc.gnu.org/legacy-ml/gcc/2003-12/msg01168.html
```

dw_cie	The CIE of interest.
dw_augdata	On success returns a pointer to the augmentation data.
dw_augdata_len	On success returns the length in bytes of the augmentation data.
_dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If the augmentation data length is zero it returns DW_DLV_NO_ENTRY.

9.18.2.20 dwarf_get_fde_augmentation_data()

GNU .eh_frame FDE augmentation information. See Linux Standard Base Core Specification version 3.0 .

See also

```
https://gcc.gnu.org/legacy-ml/gcc/2003-12/msg01168.html
```

Parameters

dw_fde	The FDE of interest.
dw_augdata	On success returns a pointer to the augmentation data.
dw_augdata_len	On success returns the length in bytes of the augmentation data.
dw_error	The usual error detail return pointer.

Returns

Returns DW_DLV_OK etc. If the augmentation data length is zero it returns DW_DLV_NO_ENTRY.

9.18.2.21 dwarf_expand_frame_instructions()

Combined with dwarf_get_frame_instruction() or dwarf_get_frame_instruction_a() (the second is like the first but adds an argument for LLVM address space numbers) it enables detailed access to frame instruction fields for evaluation or printing.

Free allocated memory with dwarf_dealloc_frame_instr_head().

See also

Using dwarf_expand_frame_instructions

Parameters

dw_cie	The cie relevant to the instructions.
dw_instructionspointer	points to the instructions
dw_length_in_bytes	byte length of the instruction sequence.
dw_head	The address of an allocated dw_head
dw_instr_count	Returns the number of instructions in the byte stream
dw_error	Error return details

Returns

On success returns DW_DLV_OK

9.18.2.22 dwarf_get_frame_instruction()

```
int dwarf_get_frame_instruction (
    Dwarf_Frame_Instr_Head dw_head,
    Dwarf_Unsigned dw_instr_index,
    Dwarf_Unsigned * dw_instr_offset_in_instrs,
    Dwarf_Small * dw_cfa_operation,
    const char ** dw_fields_description,
    Dwarf_Unsigned * dw_u0,
    Dwarf_Unsigned * dw_u1,
    Dwarf_Signed * dw_s0,
    Dwarf_Signed * dw_s1,
    Dwarf_Unsigned * dw_code_alignment_factor,
    Dwarf_Signed * dw_data_alignment_factor,
    Dwarf_Block * dw_expression_block,
    Dwarf_Error * dw_error )
```

See also

Using dwarf_expand_frame_instructions

dw_head	A head record
dw_instr_index	index 0 < i < instr_count
dw_instr_offset_in_instrs	Returns the byte offset of this instruction within instructions.
dw_cfa_operation	Returns a DW_CFA opcode.
dw_fields_description	Returns a string. Do not free.
dw_u0	May be set to an unsigned value
dw_u1	May be set to an unsigned value
dw_s0	May be set to a signed value
dw_s1	May be set to a signed value
dw_code_alignment_factor	May be set by the call
dw_data_alignment_factor	May be set by the call
dw_expression_block	Pass in a pointer to a block
dw_error	If DW_DLV_ERROR and the argument is non-NULL, returns details about the error.

Returns

On success returns DW_DLV_OK If there is no such instruction with that index it returns DW_DLV_NO_ENTRY On error it returns DW_DLV_ERROR and if dw_error is NULL it pushes back a pointer to a Dwarf_Error to the caller.

Frame expressions have a variety of formats and content. The dw_fields parameter is set to a pointer to a short string with some set of the letters s,u,r,d,c,b,a which enables determining exactly which values the call sets. Some examples: A s in fields[0] means s0 is a signed number.

A b somewhere in fields means the expression block passed in has been filled in.

A r in fields[1] means u1 is set to a register number.

A d in fields means data alignment factor is set

A c in fields means code alignment factor is set

An a in fields means an LLVM address space value and only exists if calling dwarf_get_frame_instruction_a().

```
The possible frame instruction formats are:
"" "b" "r" "rb" "rr" "rsd" "rsda" "ru" "rua" "rud"
"sd" "u" "uc"
```

are the possible frame instruction formats.

9.18.2.23 dwarf get frame instruction a()

Where multiplication is called for (via dw_code_alignment_factor or dw_data_alignment_factor) to produce an offset there is no need to check for overflow as libdwarf has already verified there is no overflow.

The return values are the same except here we have: an a in fields[2] or fields[3] means dw_u2 is an address-space identifier for the LLVM CFA instruction.

9.18.2.24 dwarf_dealloc_frame_instr_head()

```
void dwarf_dealloc_frame_instr_head ( {\tt Dwarf\_Frame\_Instr\_Head} \ dw\_head \ )
```

Parameters

dw_head	A head pointer. Frees all data created by dwarf_expand_frame_instructions() and makes the head
	pointer stale. The caller should set to NULL.

9.18.2.25 dwarf_fde_section_offset()

Parameters

dw_dbg	The Dwarf_Debug of interest
dw_in_fde	Pass in the FDE of interest.
dw_fde_off	On success returns the section offset of the FDE.
dw_cie_off	On success returns the section offset of the CIE.
dw_error	Error return details

Returns

Returns DW_DLV_OK etc.

9.18.2.26 dwarf_cie_section_offset()

Parameters

dw_dbg	The Dwarf_Debug of interest
dw_in_cie	Pass in the CIE of interest.
dw_cie_off	On success returns the section offset of the CIE.
dw_error	Error return details

Returns

Returns DW_DLV_OK etc.

9.18.2.27 dwarf_set_frame_rule_table_size()

```
Dwarf_Half dwarf_set_frame_rule_table_size (
```

```
Dwarf_Debug dw_dbg,
Dwarf_Half dw_value )
```

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_value	Pass in the value to record for the library to use.

Returns

Returns the previous value.

9.18.2.28 dwarf_set_frame_rule_initial_value()

Invariants for setting frame registers

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_value	Pass in the value to record for the library to use.

Returns

Returns the previous value.

9.18.2.29 dwarf_set_frame_cfa_value()

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_value	Pass in the value to record for the library to use.

Returns

Returns the previous value.

9.18.2.30 dwarf_set_frame_same_value()

```
Dwarf_Half dwarf_set_frame_same_value (
```

```
Dwarf_Debug dw_dbg,
Dwarf_Half dw_value )
```

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_value	Pass in the value to record for the library to use.

Returns

Returns the previous value.

9.18.2.31 dwarf_set_frame_undefined_value()

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_value	Pass in the value to record for the library to use.

Returns

Returns the previous value.

9.19 Abbreviations Section Details

Functions

- int dwarf_get_abbrev (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_offset, Dwarf_Abbrev *dw_returned_

 abbrev, Dwarf_Unsigned *dw_length, Dwarf_Unsigned *dw_attr_count, Dwarf_Error *dw_error)
 - Reading Abbreviation Data.
- int dwarf_get_abbrev_tag (Dwarf_Abbrev dw_abbrev, Dwarf_Half *dw_return_tag_number, Dwarf_Error *dw_error)

Get abbreviation tag.

 int dwarf_get_abbrev_code (Dwarf_Abbrev dw_abbrev, Dwarf_Unsigned *dw_return_code_number, Dwarf_Error *dw_error)

Get Abbreviation Code.

 int dwarf_get_abbrev_children_flag (Dwarf_Abbrev dw_abbrev, Dwarf_Signed *dw_return_flag, Dwarf_Error *dw error)

Get Abbrev Children Flag.

int dwarf_get_abbrev_entry_b (Dwarf_Abbrev dw_abbrev, Dwarf_Unsigned dw_indx, Dwarf_Bool dw_filter
 _outliers, Dwarf_Unsigned *dw_returned_attr_num, Dwarf_Unsigned *dw_returned_form, Dwarf_Signed
 *dw_returned_implicit_const, Dwarf_Off *dw_offset, Dwarf_Error *dw_error)

Get Abbrev Entry Details.

9.19.1 Detailed Description

Allows reading section .debug_abbrev independently of CUs or DIEs. Normally not done (libdwarf uses it as necessary to access DWARF DIEs and DWARF attributes) unless one is interested in the content of the section.

About Reading Independently.

9.19.2 Function Documentation

9.19.2.1 dwarf_get_abbrev()

Normally you never need to call these functions. Calls that involve DIEs do all this for you behind the scenes in the library.

This reads the data for a single abbrev code starting at dw_offset. Essentially, opening access to an abbreviation entry.

When libdwarf itself reads abbreviations to access DIEs the offset comes from the Compilation Unit Header debug abbrev offset field.

See also

```
dwarf_next_cu_header_d
```

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_offset	Pass in the offset where a Debug_Abbrev starts.
dw_returned_abbrev	On success, sets a pointer to a Dwarf_Abbrev through the pointer to allow further
	access.
dw_length	On success, returns the length of the entire abbreviation block (bytes), useful to
	calculate the next offset if reading the section independently of any compilation unit.
dw_attr_count	On success, returns the number of attributes in this abbreviation entry.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. If the abbreviation is a single zero byte it is a null abbreviation. DW_← DLV_OK is returned.

Close the abbrev by calling dwarf_dealloc(dbg,*dw_returned_abbrev, DW_DLA_ABBREV)

9.19.2.2 dwarf_get_abbrev_tag()

Parameters

dw_abbrev	The Dwarf_Abbrev of interest.
dw_return_tag_number	Returns the tag value, for example DW_TAG_compile_unit.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.19.2.3 dwarf_get_abbrev_code()

Parameters

dw_abbrev	The Dwarf_Abbrev of interest.
dw_return_code_number	Returns the code for this abbreviation, a number assigned to the abbreviation and unique within the applicable CU.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.19.2.4 dwarf_get_abbrev_children_flag()

dw_abbrev	The Dwarf_Abbrev of interest.
dw_return_flag	On success returns the flag TRUE (greater than zero) if the DIE referencing the abbreviation has children, else returns FALSE (zero).
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.19.2.5 dwarf_get_abbrev_entry_b()

Most will will call with filter_outliers non-zero.

Parameters

dw_abbrev	The Dwarf_Abbrev of interest.
dw_indx	Valid dw_index values are 0 through dw_attr_count-1
dw_filter_outliers	Pass non-zero (TRUE) so the function will check for unreasonable abbreviation content and return DW_DLV_ERROR if such found. If zero (FALSE) passed in even a nonsensical attribute number and/or unknown DW_FORM are allowed (used by dwarfdump to report the issue(s)).
dw_returned_attr_num	On success returns the attribute number, such as DW_AT_name
dw_returned_form	On success returns the attribute FORM, such as DW_FORM_udata
dw_returned_implicit_const	On success, if the dw_returned_form is DW_FORM_implicit_const then dw_returned_implicit_const is the implicit const value, but if not implicit const the return value is zero
dw_offset	On success returns the offset of the start of this attr/form pair in the abbreviation section.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. If the abbreviation code for this Dwarf_Abbrev is 0 it is a null abbreviation, the dw_indx is ignored, and the function returns DW_DLV_NO_ENTRY.

9.20 String Section .debug_str Details

Functions

int dwarf_get_str (Dwarf_Debug dw_dbg, Dwarf_Off dw_offset, char **dw_string, Dwarf_Signed *dw_←
 strlen of string, Dwarf Error *dw error)

Reading From a String Section.

9.20.1 Detailed Description

Shows just the section content in detail

9.20.2 Function Documentation

9.20.2.1 dwarf get str()

Reading The String Section

Parameters

dw_dbg	The Dwarf_Debug whose .debug_str section we want to access.
dw_offset	Pass in a string offset. Start at 0, and for the next call pass in dw_offset plus dw_strlen_of_string plus 1.
dw_string	The caller must pass in a valid pointer to a char *. On success returns a pointer to a string from offset dw_offset. Never dealloc or free this string.
dw_strlen_of_string	The caller must pass in a valid pointer to a Dwarf_Signed.

On success returns the strlen() of the string.

Parameters

dw_error	On error dw_error is set to point to the error details.
----------	---

Returns

The usual value: DW_DLV_OK etc. If there is no such section it returns DW_DLV_NO_ENTRY. If the dw coffset is greater than the section size, or dw_string passed in is NULL or dw_strlen_of_string is NULL the function returns DW_DLV_ERROR.

9.21 Str Offsets section details

Functions

int dwarf_open_str_offsets_table_access (Dwarf_Debug dw_dbg, Dwarf_Str_Offsets_Table *dw_table_data,
 Dwarf_Error *dw_error)

Creates access to a .debug_str_offsets table.

- int dwarf_close_str_offsets_table_access (Dwarf_Str_Offsets_Table dw_table_data, Dwarf_Error *dw_error)

 Close str_offsets access, free table_data.

Iterate through the offsets tables.

int dwarf_str_offsets_value_by_index (Dwarf_Str_Offsets_Table dw_table_data, Dwarf_Unsigned dw_
index_to_entry, Dwarf_Unsigned *dw_entry_value, Dwarf_Error *dw_error)

Access to an individual str offsets table entry.

int dwarf_str_offsets_statistics (Dwarf_Str_Offsets_Table dw_table_data, Dwarf_Unsigned *dw_wasted_
 byte_count, Dwarf_Unsigned *dw_table_count, Dwarf_Error *dw_error)

Reports final wasted-bytes count.

9.21.1 Detailed Description

Shows just the section content in detail. Most library users will never call these, as references to this is handled by the code accessing some Dwarf Attribute. Reading The Str Offsets

9.21.2 Function Documentation

9.21.2.1 dwarf_open_str_offsets_table_access()

See also

Reading string offsets section data

Parameters

dw_dbg	Pass in the Dwarf_Debug of interest.
dw_table_data	On success returns a pointer to an opaque structure for use in further calls.
dw_error	On error dw_error is set to point to the error details.

Returns

DW_DLV_OK etc. If there is no .debug_str_offsets section it returns DW_DLV_NO_ENTRY

9.21.2.2 dwarf_close_str_offsets_table_access()

See also

Reading string offsets section data

dw_table_data	
dw_error	On error dw_error is set to point to the error details.

Returns

DW_DLV_OK etc. If there is no .debug_str_offsets section it returns DW_DLV_NO_ENTRY If it returns DW __DLV_ERROR there is nothing you can do except report the error and, optionally, call dwarf_dealloc_error to dealloc the error content (and then set the dw_error to NULL as after the dealloc the pointer is stale)..

9.21.2.3 dwarf_next_str_offsets_table()

See also

Reading string offsets section data

Access to the tables starts at offset zero. The library progresses through the next table automatically, keeping track internally to know where it is.

Parameters

dw_table_data	Pass in an open Dwarf_Str_Offsets_Table.
dw_unit_length	On success returns a table unit_length field
dw_unit_length_offset	On success returns the section offset of the unit_length field.
dw_table_start_offset	On success returns the section offset of the array of table entries.
dw_entry_size	On success returns the entry size (4 or 8)
dw_version	On success returns the value in the version field 5.
dw_padding	On success returns the zero value in the padding field.
dw_table_value_count	On success returns the number of table entries, each of size dw_entry_size, in the table.
dw_error	On error dw_error is set to point to the error details.

Returns

DW_DLV_OK Returns DW_DLV_NO_ENTRY if there are no more entries.

9.21.2.4 dwarf_str_offsets_value_by_index()

See also

Reading string offsets section data

Parameters

dw_table_data	Pass in the open table pointer.
dw_index_to_entry	Pass in the entry number, 0 through dw_table_value_count-1 for the active table
dw_entry_value	On success returns the value in that table entry, an offset into a string table.
dw_error	On error dw_error is set to point to the error details.

Returns

DW_DLV_OK Returns DW_DLV_ERROR if dw_index_to_entry is out of the correct range.

9.21.2.5 dwarf_str_offsets_statistics()

Reports the number of tables seen so far. Not very interesting.

Parameters

dw_table_data	Pass in the open table pointer.
dw_wasted_byte_count	Always returns 0 at present.
dw_table_count	On success returns the total number of tables seen so far in the section.
dw_error	On error dw_error is set to point to the error details.

Returns

DW_DLV_OK etc.

9.22 Dwarf_Error Functions

Functions

• Dwarf Unsigned dwarf errno (Dwarf Error dw error)

What DW_DLE code does the error have?

char * dwarf_errmsg (Dwarf_Error dw_error)

What message string is in the error?

• char * dwarf_errmsg_by_number (Dwarf_Unsigned dw_errornum)

What message string is associated with the error number.

• void dwarf_error_creation (Dwarf_Debug dw_dbg, Dwarf_Error *dw_error, char *dw_errmsg)

Creating an error. This is very rarely helpful. It lets the library user create a Dwarf_Error and associate any string with that error. Your code could then return DW_DLV_ERROR to your caller when your intent is to let your caller clean up whatever seems wrong.

• void dwarf_dealloc_error (Dwarf_Debug dw_dbg, Dwarf_Error dw_error)

Free (dealloc) an Dwarf_Error something created.

9.22.1 Detailed Description

These functions aid in understanding handling.

9.22.2 Function Documentation

9.22.2.1 dwarf_errno()

Parameters

dw_eri	<i>or</i> │ The dv	_error should be non-null and a valid Dwarf_Erro	or.
--------	--------------------	--	-----

Returns

A DW_DLE value of some kind. For example: DW_DLE_DIE_NULL.

9.22.2.2 dwarf errmsg()

Parameters

dw error	The dw error should be non-null and a valid Dwarf Error.
av	The aw_choi enedia be non hall and a valid bwan_birelien.

Returns

A string with a message related to the error.

9.22.2.3 dwarf_errmsg_by_number()

dw_errornum	The dw_error should be an integer from the DW_DLE set. For example, DW_DLE_DIE_NULL.
-------------	--

Returns

The generic string describing that error number.

9.22.2.4 dwarf_error_creation()

Parameters

dw_dbg	The relevant Dwarf_Debug.
dw_error	a Dwarf_Error is returned through this pointer.
dw_errmsg	The message string you provide.

9.22.2.5 dwarf_dealloc_error()

Parameters

dw_dbg	The relevant Dwarf_Debug pointer.
dw_error	A pointer to a Dwarf_Error. The pointer is then stale so you should immediately zero that pointer
	passed in.

9.23 Generic dwarf_dealloc Function

Functions

• void dwarf_dealloc (Dwarf_Debug dw_dbg, void *dw_space, Dwarf_Unsigned dw_type)

The generic dealloc (free) function. It requires you know the correct DW_DLA value to pass in, and in a few cases such is not provided. The functions doing allocations tell you which dealloc to use.

9.23.1 Detailed Description

Works for most dealloc needed.

For easier to use versions see the following

See also

```
dwarf_dealloc_attribute
dwarf_dealloc_die
dwarf_dealloc_dnames
dwarf_dealloc_error
dwarf_dealloc_fde_cie_list
dwarf_dealloc_frame_instr_head
dwarf_dealloc_macro_context
dwarf_dealloc_ranges
dwarf_dealloc_ranglists_head
dwarf_dealloc_uncompressed_block
dwarf_globals_dealloc
dwarf_gnu_index_dealloc
dwarf_srclines_dealloc_b
```

9.23.2 Function Documentation

9.23.2.1 dwarf dealloc()

Parameters

dw_dbg	Must be a valid open Dwarf_Debug. and must be the dw_dbg that the error was created on. If it is not the dealloc will do nothing.	
dw_space	Must be an address returned directly by a libdwarf call that the call specifies as requiring	
	dealloc/free. If it is not a segfault or address fault is possible.	
dw_type	Must be a correct naming of the DW_DLA type. If it is not the dealloc will do nothing.	

9.24 Access to Section .debug_sup

Functions

int dwarf_get_debug_sup (Dwarf_Debug dw_dbg, Dwarf_Half *dw_version, Dwarf_Small *dw_is_
 supplementary, char **dw_filename, Dwarf_Unsigned *dw_checksum_len, Dwarf_Small **dw_checksum,
 Dwarf_Error *dw_error)

Return basic .debug_sup section header data.

9.24.1 Detailed Description

9.24.2 Function Documentation

9.24.2.1 dwarf get debug sup()

This returns basic data from the header of a .debug_sup section. See DWARF5 Section 7.3.6, "DWARF Supplementary Object Files"

Other sections present should be normal DWARF5, so normal libdwarf calls should work. We have no existing examples on hand, so it is hard to know what really works.

If there is no such section it returns DW_DLV_NO_ENTRY.

9.25 Fast Access to .debug_names DWARF5

Functions

 int dwarf_dnames_header (Dwarf_Debug dw_dbg, Dwarf_Off dw_starting_offset, Dwarf_Dnames_Head *dw_dn, Dwarf_Off *dw_offset_of_next_table, Dwarf_Error *dw_error)

Open access to a .debug_names table.

· void dwarf dealloc dnames (Dwarf Dnames Head dw dn)

Frees all the malloc data associated with dw_dn.

int dwarf_dnames_abbrevtable (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned dw_index, Dwarf_Unsigned *dw_abbrev_offset, Dwarf_Unsigned *dw_abbrev_code, Dwarf_Unsigned *dw_abbrev_tag, Dwarf_Unsigned dw_array_size, Dwarf_Half *dw_idxattr_array, Dwarf_Half *dw_form_array, Dwarf_Unsigned *dw_idxattr_count)

Access to the abbrevs table content.

int dwarf_dnames_sizes (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned *dw_comp_unit_count, Dwarf_Unsigned *dw_local_type_unit_count, Dwarf_Unsigned *dw_foreign_type_unit_count, Dwarf_Unsigned *dw_bucket_count, Dwarf_Unsigned *dw_name_count, Dwarf_Unsigned *dw_abbrev_table_size, Dwarf_Unsigned *dw_entry_pool_size, Dwarf_Unsigned *dw_augmentation_string_size, char **dw_⇔ augmentation_string, Dwarf_Unsigned *dw_section_size, Dwarf_Half *dw_table_version, Dwarf_Half *dw→ offset size, Dwarf_Error *dw error)

Sizes and counts from the debug names table.

int dwarf_dnames_offsets (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned *dw_header_offset, Dwarf_Unsigned *dw_cu_table_offset, Dwarf_Unsigned *dw_tu_local_offset, Dwarf_Unsigned *dw_foreign_tu_offset, Dwarf_Unsigned *dw_bucket_offset, Dwarf_Unsigned *dw_hashes_offset, Dwarf_Unsigned *dw_totale_offset, Dwarf_Unsigned *dw_entryoffsets_offset, Dwarf_Unsigned *dw_abbrev_table_offset, Dwarf_Unsigned *dw_entry_pool_offset, Dwarf_Error *dw_error)

Offsets from the debug names table.

• int dwarf_dnames_cu_table (Dwarf_Dnames_Head dw_dn, const char *dw_type, Dwarf_Unsigned dw_\circ index_number, Dwarf_Unsigned *dw_offset, Dwarf_Sig8 *dw_sig, Dwarf_Error *dw_error)

Each debug names cu list entry one at a time.

 int dwarf_dnames_bucket (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned dw_bucket_number, Dwarf_Unsigned *dw_index, Dwarf_Unsigned *dw_indexcount, Dwarf_Error *dw_error)

Access to bucket contents.

int dwarf_dnames_name (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned dw_name_index, Dwarf_Unsigned *dw_bucket_number, Dwarf_Unsigned *dw_hash_value, Dwarf_Unsigned *dw_offset_to_debug_str, char **dw_ptrtostr, Dwarf_Unsigned *dw_offset_in_entrypool, Dwarf_Unsigned *dw_abbrev_number, Dwarf_Half *dw_abbrev_tag, Dwarf_Unsigned dw_array_size, Dwarf_Half *dw_idxattr_array, Dwarf_Half *dw_form_array, Dwarf_Unsigned *dw_idxattr_count, Dwarf_Error *dw_error)

Retrieve a name table entry.

 int dwarf_dnames_entrypool (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned dw_offset_in_entrypool, Dwarf_Unsigned *dw_abbrev_code, Dwarf_Half *dw_tag, Dwarf_Unsigned *dw_value_count, Dwarf_Unsigned *dw index of abbrev, Dwarf Unsigned *dw offset of initial value, Dwarf Error *dw error)

Return a the set of values from an entrypool entry.

int dwarf_dnames_entrypool_values (Dwarf_Dnames_Head dw_dn, Dwarf_Unsigned dw_index_of_abbrev, Dwarf_Unsigned dw_offset_in_entrypool_of_values, Dwarf_Unsigned dw_arrays_length, Dwarf_Half *dw
 array_idx_number, Dwarf_Half *dw_array_form, Dwarf_Unsigned *dw_array_of_offsets, Dwarf_Sig8 *dw
 array_of_signatures, Dwarf_Bool *dw_single_cu, Dwarf_Unsigned *dw_cu_offset, Dwarf_Unsigned *dw
 offset of next entrypool, Dwarf_Error *dw error)

Return the value set defined by this entry.

9.25.1 Detailed Description

The section is new in DWARF5 and supersedes .debug_pubnames and .debug_pubtypes in DWARF2, DWARF3, and DWARF4.

The functions provide a detailed reporting of the content and structure of the table (so one can build one's own search table) but they are not particularly helpful for searching.

A new function (more than one?) would be needed for convenient searching.

9.25.2 Function Documentation

9.25.2.1 dwarf_dnames_header()

dw_dbg	The Dwarf_Debug of interest.
dw_starting_offset	Read this section starting at offset zero.
dw_dn	On success returns a pointer to a set of data allowing access to the table.
dw_offset_of_next_table	On success returns Offset just past the end of the the opened table.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. If there is no such table or if dw_starting_offset is past the end of the section it returns DW_DLV_NO_ENTRY.

9.25.2.2 dwarf_dealloc_dnames()

```
void dwarf_dealloc_dnames ( {\tt Dwarf\_Dnames\_Head} \ dw\_dn \ )
```

Parameters

dw_dn

A Dwarf_Dnames_Head pointer. Callers should zero the pointer passed in as soon as possible after this returns as the pointer is then stale.

9.25.2.3 dwarf_dnames_abbrevtable()

Of interest mainly to debugging issues with compilers or debuggers.

dw_dn	A Dwarf_Dnames_Head pointer.
dw_index	An index (starting at zero) into a table constructed of abbrev data. These indexes are derived from abbrev data and are not in the abbrev data itself.
dw_abbrev_offset	Returns the offset of the abbrev table entry for this names table entry.
dw_abbrev_code	Returns the abbrev code for the abbrev at offset dw_abbrev_offset.
dw_abbrev_tag	Returns the tag for the abbrev at offset dw_abbrev_offset.
dw_array_size	The size you allocated in each of the following two arrays.
dw_idxattr_array	Pass in an array you allocated where the function returns and array of index attributes (DW_IDX) for this dw_abbrev_code. The last attribute code in the array is zero.
dw_form_array	Pass in an array you allocated where the function returns and array of forms for this dw_abbrev_code (paralled to dw_idxattr_array). The last form code in the array is zero.
dw_idxattr_count	Returns the actual idxattribute/form count (including the terminating 0,0 pair. If the array_size passed in is less than this value the array returned is incomplete. Array entries needed. Might be larger than dw_array_size, meaning not all entries could be returned in your arrays.

Returns

Returns DW_DLV_OK on success. If the offset does not refer to a known part of the abbrev table it returns DW_DLV_NO_ENTRY. Never returns DW_DLV_ERROR.

9.25.2.4 dwarf dnames sizes()

We do not describe these returned values. Other than for dw_dn and dw_error passing pointers you do not care about as NULL is fine. Of course no value can be returned through those passed as NULL.

Any program referencing a names table will need at least a few of these values.

See DWARF5 section 6.1.1 "Lookup By Name" particularly the graph page 139. dw_comp_unit_count is K(k), dw_local_type_unit_count is T(t), and dw_foreign_type_unit_count is F(f).

9.25.2.5 dwarf_dnames_offsets()

We do not describe these returned values, which refer to the .debug_names section.

The header offset is a section offset. The rest are offsets from the header.

See DWARF5 section 6.1.1 "Lookup By Name"

9.25.2.6 dwarf_dnames_cu_table()

Indexes to the cu/tu/ tables start at 0.

Some values in dw_offset are actually offsets, such as for DW_IDX_die_offset. DW_IDX_compile_unit and DW_\circ
IDX_type_unit are indexes into the table specified by dw_type and are returned through dw_offset field;

Parameters

dw_dn	The table of interest.
dw_type	Pass in the type, "cu" or "tu"
dw_index_number	For "cu" index range is 0 through K-1 For "tu" index range is 0 through T+F-1
dw_offset	Zero if it cannot be determined. (check the return value!).
dw_sig	the Dwarf_Sig8 is filled in with a signature if the TU index is T through T+F-1
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.25.2.7 dwarf dnames bucket()

Parameters

dw_dn	The Dwarf_Dnames_Head of interest.	
dw_bucket_number	Pass in a bucket number Bucket numbers start at 0.	
dw_index	On success returns the index of the appropriate name entry. Name entry indexes start at one, a zero index means the bucket is unused.	
dw_indexcount	On success returns the number of name entries in the bucket.	
dw_error	On error dw_error is set to point to the error details.	

Returns

The usual value: DW_DLV_OK etc. An out of range dw_index_number gets a return if DW_DLV_NO_ENTRY

9.25.2.8 dwarf_dnames_name()

Retrieve the name and other data from a single name table entry.

Parameters

dw_dn	The table of interest.
dw_name_index	Pass in the desired index, start at one.
dw_bucket_number	On success returns a bucket number, zero if no buckets present.
dw_hash_value	The hash value, all zeros if no hashes present
dw_offset_to_debug_str	The offset to the .debug_str section string.
dw_ptrtostr	if dw_ptrtostr non-null returns a pointer to the applicable string here.
dw_offset_in_entrypool	Returns the offset in the entrypool
dw_abbrev_number	Returned from entrypool.
dw_abbrev_tag	Returned from entrypool abbrev data.
dw_array_size	Size of array you provide to hold DW_IDX index attribute and form numbers.
	Possibly 10 suffices for practical purposes.
dw_idxattr_array	Array space you provide, for idx attribute numbers (function will initialize it). The final entry in the array will be 0.
dw_form_array	Array you provide, for form numbers (function will initialize it). The final entry in the array will be 0.
dw_idxattr_count	Array entries needed. Might be larger than dw_array_size, meaning not all entries could be returned in your array.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. If the index passed in is outside the valid range returns DW_DLV_NO $_{\leftarrow}$ ENTRY.

9.25.2.9 dwarf_dnames_entrypool()

```
Dwarf_Unsigned * dw_abbrev_code,
Dwarf_Half * dw_tag,
Dwarf_Unsigned * dw_value_count,
Dwarf_Unsigned * dw_index_of_abbrev,
Dwarf_Unsigned * dw_offset_of_initial_value,
Dwarf_Error * dw_error )
```

Returns the basic data about an entrypool record and enables correct calling of dwarf_dnames_entrypool_values (see below). The two-stage approach makes it simple for callers to prepare for the number of values that will be returned by dwarf_dnames_entrypool_values()

Parameters

dw_dn	Pass in the debug names table of interest.
dw_offset_in_entrypool	The record offset (in the entry pool table) of the first record of IDX attributes.
	Starts at zero.
dw_abbrev_code	On success returns the abbrev code of the idx attributes for the pool entry.
dw_tag	On success returns the TAG of the DIE referred to by this entrypool entry.
dw_value_count	On success returns the number of distinct values imply by this entry.
dw_index_of_abbrev	On success returns the index of the abbrev index/form pairs in the abbreviation
	table.
dw_offset_of_initial_value	On success returns the entry pool offset of the sequence of bytes containing
	values, such as a CU index or a DIE offset.
dw_error	The usual error detail record

Returns

DW_DLV_OK is returned if the specified name entry exists. DW_DLV_NO_ENTRY is returned if the specified offset is outside the size of the table. DW_DLV_ERROR is returned in case of an internal error or corrupt section content.

9.25.2.10 dwarf_dnames_entrypool_values()

Call here after calling dwarf_dnames_entrypool to provide data to call this function correctly.

This retrieves the index attribute values that identify a names table name.

The caller allocates a set of arrays and the function fills them in. If dw_array_idx_number[n] is DW_IDX_type_hash then dw_array_of_signatures[n] contains the hash. For other IDX values dw_array_of_offsets[n] contains the value being returned.

Parameters

dw_dn	Pass in the debug names table of interest.
dw_index_of_abbrev	Pass in the abbreviation index.
dw_offset_in_entrypool_of_values	Pass in the offset of the values returned by dw_offset_of_initial_value above.
dw_arrays_length	Pass in the array length of each of the following four fields. The dw_value_count returned above is what you need to use.
dw_array_idx_number	Create an array of Dwarf_Half values, dw_arrays_length long, and pass a pointer to the first entry here.
dw_array_form	Create an array of Dwarf_Half values, dw_arrays_length long, and pass a pointer to the first entry here.
dw_array_of_offsets	Create an array of Dwarf_Unsigned values, dw_arrays_length long, and pass a pointer to the first entry here.
dw_array_of_signatures	Create an array of Dwarf_Sig8 structs, dw_arrays_length long, and pass a pointer to the first entry here.
dw_offset_of_next_entrypool	On success returns the offset of the next entrypool. A value here is usable in the next call to dwarf_dnames_entrypool.
dw_single_cu	On success, if it is a single-cu name table there is likely no DW_IDX_compile_unit. So we return TRUE via this flag in such a case.
dw_cu_offset	On success, for a single-cu name table with no DW_IDX_compile_unit this is set to the CU offset from that single CU-table entry.
dw_error	The usual error detail record

Returns

DW_DLV_OK is returned if the specified name entry exists. DW_DLV_NO_ENTRY is returned if the specified offset is outside the size of the table. DW_DLV_ERROR is returned in case of an internal error or corrupt section content.

9.26 Fast Access to a CU given a code address

Functions

int dwarf_get_aranges (Dwarf_Debug dw_dbg, Dwarf_Arange **dw_aranges, Dwarf_Signed *dw_arange
 — count, Dwarf_Error *dw_error)

Get access to CUs given code addresses.

Find a range given a code address.

int dwarf_get_cu_die_offset (Dwarf_Arange dw_arange, Dwarf_Off *dw_return_offset, Dwarf_Error *dw_←
error)

Given an arange return its CU DIE offset.

Given an arange return its CU header offset.

int dwarf_get_arange_info_b (Dwarf_Arange dw_arange, Dwarf_Unsigned *dw_segment, Dwarf_Unsigned *dw_segment_entry_size, Dwarf_Addr *dw_start, Dwarf_Unsigned *dw_length, Dwarf_Off *dw_cu_die_← offset, Dwarf_Error *dw_error)

Get the data in an arange entry.

9.26.1 Detailed Description

9.26.2 Function Documentation

9.26.2.1 dwarf_get_aranges()

This intended as a fast-access to tie code addresses to CU dies. The data is in the .debug_aranges section. which may appear in DWARF2,3,4, or DWARF5.

See also

Reading an aranges section

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_aranges	On success returns a pointer to an array of Dwarf_Arange pointers.
dw_arange_count	On success returns a count of the length of the array.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if there is no such section.

9.26.2.2 dwarf_get_arange()

dw_aranges	Pass in a pointer to the first entry in the aranges array of pointers.
dw_arange_count	Pass in the dw_arange_count, the count for the array.
dw_address	Pass in the code address of interest.
dw_returned_arange	On success, returns the particular arange that holds that address.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if there is no such code address present in the section.

9.26.2.3 dwarf_get_cu_die_offset()

Parameters

dw_arange	The specific arange of interest.
dw_return_offset	The CU DIE offset (in .debug_info) applicable to this arange
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.26.2.4 dwarf_get_arange_cu_header_offset()

Parameters

dw_arange	The specific arange of interest.
dw_return_cu_header_offset	The CU header offset (in .debug_info) applicable to this arange.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.26.2.5 dwarf_get_arange_info_b()

Parameters

dw_arange	The specific arange of interest.
dw_segment	On success and if segment_entry_size is non-zero this returns the segment number
	from the arange.
dw_segment_entry_size	On success returns the segment entry size from the arange.
dw_start	On success returns the low address this arange refers to.
dw_length	On success returns the length, in bytes of the code area this arange refers to.
dw_cu_die_offset	On success returns the .debug_info section offset the arange refers to.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.27 Fast Access to .debug pubnames and more.

Macros

- #define DW_GL_GLOBALS 0 /* .debug_pubnames and .debug_names */
- #define DW_GL_PUBTYPES 1 /* .debug_pubtypes */
- #define DW_GL_FUNCS 2 /* .debug_funcnames */
- #define DW_GL_TYPES 3 /* .debug_typenames */
- #define DW_GL_VARS 4 /* .debug_varnames */
- #define DW_GL_WEAKS 5 /* .debug_weaknames */

Functions

int dwarf_get_globals (Dwarf_Debug dw_dbg, Dwarf_Global **dw_globals, Dwarf_Signed *dw_number_
 of globals, Dwarf Error *dw error)

Global name space operations, .debug_pubnames access.

int dwarf_get_pubtypes (Dwarf_Debug dw_dbg, Dwarf_Global **dw_pubtypes, Dwarf_Signed *dw_←
number_of_pubtypes, Dwarf_Error *dw_error)

Global debug_types access.

int dwarf_globals_by_type (Dwarf_Debug dw_dbg, int dw_requested_section, Dwarf_Global **dw_contents,
 Dwarf Signed *dw count, Dwarf Error *dw error)

Allocate Any Fast Access DWARF2-DWARF4.

- void dwarf_globals_dealloc (Dwarf_Debug dw_dbg, Dwarf_Global *dw_global_like, Dwarf_Signed dw_count)

 Dealloc the Dwarf_Global data.
- int dwarf_globname (Dwarf_Global dw_global, char **dw_returned_name, Dwarf_Error *dw_error)

 Return the name of a global-like data item.
- int dwarf_global_die_offset (Dwarf_Global dw_global, Dwarf_Off *dw_die_offset, Dwarf_Error *dw_error)

 Return the DIE offset of a global data item.
- int dwarf_global_cu_offset (Dwarf_Global dw_global, Dwarf_Off *dw_cu_header_offset, Dwarf_Error *dw← error)

Return the CU header data of a global data item.

int dwarf_global_name_offsets (Dwarf_Global dw_global, char **dw_returned_name, Dwarf_Off *dw_die
 _offset, Dwarf_Off *dw_cu_die_offset, Dwarf_Error *dw_error)

Return the name and offsets of a global entry.

• Dwarf_Half dwarf_global_tag_number (Dwarf_Global dw_global)

Return the DW_TAG number of a global entry.

int dwarf_get_globals_header (Dwarf_Global dw_global, int *dw_category, Dwarf_Off *dw_offset_pub
 —header, Dwarf_Unsigned *dw_length_size, Dwarf_Unsigned *dw_length_pub, Dwarf_Unsigned *dw_
 version, Dwarf_Unsigned *dw_header_info_offset, Dwarf_Unsigned *dw_info_length, Dwarf_Error *dw_
 error)

For more complete globals printing.

• int dwarf_return_empty_pubnames (Dwarf_Debug dw_dbg, int dw_flag)

A flag for dwarfdump on pubnames, pubtypes etc.

9.27.1 Detailed Description

Pubnames and Pubtypes overview

These functions each read one of a set of sections designed for fast access by name, but they are not always emitted as they each have somewhat limited and inflexible capabilities. So you may not see many of these.

All have the same set of functions with a name reflecting the specific object section involved. Only the first, of type Dwarf_Global, is documented here in full detail as the others do the same jobs just each for their applicable object section..

9.27.2 Function Documentation

9.27.2.1 dwarf_get_globals()

This accesses .debug_pubnames and .debug_names sections. Section .debug_pubnames is defined in DWARF2, DWARF3, and DWARF4. Section .debug_names is defined in DWARF5 and contains lots of information, but only the part of the wealth of information that this interface allows can be retrieved here. See dwarf_dnames_header() for access to all. debug_names data.

The code here, as of 0.4.3, September 3 2022, returns data from either section.

See also

Using dwarf_get_globals()

dw_dbg	The Dwarf_Debug of interest.
dw_globals	On success returns an array of pointers to opaque structs
dw_number_of_globals	On success returns the number of entries in the array.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if the section is not present.

9.27.2.2 dwarf_get_pubtypes()

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_pubtypes	On success returns an array of pointers to opaque structs
dw_number_of_pubtypes	On success returns the number of entries in the array.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if the section is not present.

Same function name as 0.5.0 and earlier, but the data type changes to Dwarf Global

dwarf_get_pubtypes() is an alternate name for dwarf_globals_by_type(...,DW_GL_PUBTYPES,..).

9.27.2.3 dwarf_globals_by_type()

This interface new in 0.6.0. Simplfies access by replace dwarf_get_pubtypes, dwarf_get_funcs, dwarf_get_types, dwarf_get_vars, and dwarf_get_weaks with a single set of types.

dw_dbg	The Dwarf_Debug of interest.
dw_requested_section	Pass in one of the values DW_GL_GLOBALS through DW_GL_WEAKS to select the
	section to extract data from.
dw_contents	On success returns an array of pointers to opaque structs.
dw_count	On success returns the number of entries in the array.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if the section is not present.

9.27.2.4 dwarf_globals_dealloc()

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_global_like	The array of globals/types/etc data to dealloc (free).
dw_count	The number of entries in the array.

9.27.2.5 dwarf_globname()

Parameters

dw_global	The Dwarf_Global of interest.
dw_returned_name	On success a pointer to the name (a null-terminated string) is returned.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.27.2.6 dwarf_global_die_offset()

dw_global	The Dwarf_Global of interest.
dw_die_offset	On success a the section-global DIE offset of a data item is returned.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.27.2.7 dwarf_global_cu_offset()

A CU header offset is rarely useful.

Parameters

dw_global	The Dwarf_Global of interest.
dw_cu_header_offset	On success a the section-global offset of a CU header is returned.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.27.2.8 dwarf_global_name_offsets()

Parameters

dw_global	The Dwarf_Global of interest.
dw_returned_name	On success a pointer to the name (a null-terminated string) is returned.
dw_die_offset	On success a the section-global DIE offset of the global with the name.
dw_cu_die_offset	On success a the section-global offset of the relevant CU DIE is returned.
dw_error	On error dw_error is set to point to the error details.

Returns

The usual value: DW_DLV_OK etc.

9.27.2.9 dwarf_global_tag_number()

Parameters

dw_global The Dwan_Global of Interest.	dw_global	The Dwarf_Global of interest.
--	-----------	-------------------------------

Returns

If the Dwarf_Global refers to a global from the .debug_names section the return value is the DW_TAG for the DIE in the global entry, for example DW_TAG_subprogram. In case of error or if the section for this global was not .debug_names zero is returned.

9.27.2.10 dwarf_get_globals_header()

```
int dwarf_get_globals_header (
    Dwarf_Global dw_global,
    int * dw_category,
    Dwarf_Off * dw_offset_pub_header,
    Dwarf_Unsigned * dw_length_size,
    Dwarf_Unsigned * dw_length_pub,
    Dwarf_Unsigned * dw_version,
    Dwarf_Unsigned * dw_header_info_offset,
    Dwarf_Unsigned * dw_info_length,
    Dwarf_Error * dw_error )
```

For each CU represented in .debug_pubnames, etc, there is a .debug_pubnames header. For any given Dwarf _ Global this returns the content of the applicable header. This does not include header information from any .debug_names headers.

The function declaration changed at version 0.6.0.

9.27.2.11 dwarf return empty pubnames()

Sets a flag in the dbg. Always returns DW_DLV_OK. Applies to all the sections of this kind: pubnames, pubtypes, funcs, typenames,vars, weaks. Ensures empty content (meaning no offset/name tuples, but with a header) for a CU shows up rather than being suppressed.

Primarily useful if one wants to note any pointless header data in the section.

Pubnames and Pubtypes overview

dw_dbg	The Dwarf_Debug of interest.
dw_flag	Must be the value one.

Returns

Returns DW_DLV_OK. Always.

9.28 Fast Access to GNU .debug_gnu_pubnames

Functions

• int dwarf_get_gnu_index_head (Dwarf_Debug dw_dbg, Dwarf_Bool dw_which_section, Dwarf_Gnu_Index_Head *dw_head, Dwarf_Unsigned *dw_index_block_count_out, Dwarf_Error *dw_error)

Access to .debug_gnu_pubnames or .debug_gnu_pubtypes.

void dwarf_gnu_index_dealloc (Dwarf_Gnu_Index_Head dw_head)

Free resources of .debug_gnu_pubnames .debug_gnu_pubtypes.

 int dwarf_get_gnu_index_block (Dwarf_Gnu_Index_Head dw_head, Dwarf_Unsigned dw_number, Dwarf_Unsigned *dw_block_length, Dwarf_Half *dw_version, Dwarf_Unsigned *dw_offset_into_debug← _info, Dwarf_Unsigned *dw_size_of_debug_info_area, Dwarf_Unsigned *dw_count_of_index_entries, Dwarf_Error *dw_error)

Access a particular block.

int dwarf_get_gnu_index_block_entry (Dwarf_Gnu_Index_Head dw_head, Dwarf_Unsigned dw_
 blocknumber, Dwarf_Unsigned dw_entrynumber, Dwarf_Unsigned *dw_offset_in_debug_info, const char
 **dw_name_string, unsigned char *dw_flagbyte, unsigned char *dw_staticorglobal, unsigned char *dw_
 typeofentry, Dwarf_Error *dw_error)

Access a particular entry of a block.

9.28.1 Detailed Description

Section .debug_gnu_pubnames or .debug_gnu_pubtypes.

This is a section created for and used by the GNU gdb debugger to access DWARF information.

Not part of standard DWARF.

9.28.2 Function Documentation

9.28.2.1 dwarf_get_gnu_index_head()

Call this to get access.

dw_dbg	Pass in the Dwarf_Debug of interest.
dw_which_section	Pass in TRUE to access .debug_gnu_pubnames. Pass in FALSE to access .debug_gnu_typenames.
dw_head	On success, set to a pointer to a head record allowing access to all the content of
Generated by Doxygen	the section.
dw_index_block_count_out	On success, set to a count of the number of blocks of data available.
dw_error	

Returns

Returns DW_DLV_OK, DW_DLV_NO_ENTRY (if the section does not exist or is empty), or, in case of an error reading the section, DW_DLV_ERROR.

9.28.2.2 dwarf_gnu_index_dealloc()

Call this to deallocate all memory used by dw_head.

Parameters

dw_head	Pass in the Dwarf_Gnu_Index_head whose data is to be deallocated.	l

9.28.2.3 dwarf_get_gnu_index_block()

Parameters

dw_head	Pass in the Dwarf_Gnu_Index_head interest.
dw_number	Pass in the block number of the block of interest. 0 through
	dw_index_block_count_out-1.
dw_block_length	On success set to the length of the data in this block, in bytes.
dw_version	On success set to the version number of the block.
dw_offset_into_debug_info	On success set to the offset, in .debug_info, of the data for this block. The returned offset may be outside the bounds of the actual .debug_info section, such a possibility does not cause the function to return DW_DLV_ERROR.
dw_size_of_debug_info_area	On success set to the size in bytes, in .debug_info, of the area this block refers to. The returned dw_dw_size_of_debug_info_are plus dw_offset_into_debug_info may be outside the bounds of the actual .debug_info section, such a possibility does not cause the function to return DW_DLV_ERROR. Use dwarf_get_section_max_offsets_d() to learn the size of .debug_info and optionally other sections as well.
dw_count_of_index_entries	On success set to the count of index entries in this particular block number.
dw_error	On error dw_error is set to point to the error details.

Returns

Returns DW_DLV_OK, DW_DLV_NO_ENTRY (if the section does not exist or is empty), or, in case of an error reading the section, DW_DLV_ERROR.

9.28.2.4 dwarf_get_gnu_index_block_entry()

Access to a single entry in a block.

Parameters

dw_head	Pass in the Dwarf_Gnu_Index_head interest.
dw_blocknumber	Pass in the block number of the block of interest. 0 through dw_index_block_count_out-1.
dw_entrynumber	Pass in the entry number of the entry of interest. 0 through dw_count_of_index_entries-1.
dw_offset_in_debug_info	On success set to the offset in .debug_info relevant to this entry.
dw_name_string	On success set to the size in bytes, in .debug_info, of the area this block refersto.
dw_flagbyte	On success set to the entry flag byte content.
dw_staticorglobal	On success set to the entry static/global letter.
dw_typeofentry	On success set to the type of entry.
dw_error	On error dw_error is set to point to the error details.

Returns

Returns DW_DLV_OK, DW_DLV_NO_ENTRY (if the section does not exist or is empty), or, in case of an error reading the section, DW_DLV_ERROR.

9.29 Fast Access to Gdb Index

Functions

int dwarf_gdbindex_header (Dwarf_Debug dw_dbg, Dwarf_Gdbindex *dw_gdbindexptr, Dwarf_Unsigned *dw_version, Dwarf_Unsigned *dw_cu_list_offset, Dwarf_Unsigned *dw_types_cu_list_offset, Dwarf_Unsigned *dw_address_area_offset, Dwarf_Unsigned *dw_symbol_table_offset, Dwarf_Unsigned *dw_constant_
 pool_offset, Dwarf_Unsigned *dw_section_size, const char **dw_section_name, Dwarf_Error *dw_error)

Open access to the .gdb_index section.

void dwarf_dealloc_gdbindex (Dwarf_Gdbindex dw_gdbindexptr)

Free (dealloc) all allocated Dwarf_Gdbindex memory It should named dwarf_dealloc_gdbindex.

• int dwarf_gdbindex_culist_array (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned *dw_list_length, Dwarf_Error *dw_error)

Return the culist array length.

 int dwarf_gdbindex_culist_entry (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_entryindex, Dwarf_Unsigned *dw_cu_offset, Dwarf_Unsigned *dw_cu_length, Dwarf_Error *dw_error)

For a CU entry in the list return the offset and length.

int dwarf_gdbindex_types_culist_array (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned *dw_types_list
 — length, Dwarf_Error *dw_error)

Return the types culist array length.

int dwarf_gdbindex_types_culist_entry (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_types_
 entryindex, Dwarf_Unsigned *dw_cu_offset, Dwarf_Unsigned *dw_tu_offset, Dwarf_Unsigned *dw_type
 _signature, Dwarf_Error *dw_error)

For a types CU entry in the list returns the offset and length.

Get access to adbindex address area.

 int dwarf_gdbindex_addressarea_entry (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_entryindex, Dwarf_Unsigned *dw_low_address, Dwarf_Unsigned *dw_high_address, Dwarf_Unsigned *dw_cu_index, Dwarf_Error *dw_error)

Get an address area value.

int dwarf_gdbindex_symboltable_array (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned *dw_symtab_
 —
 list_length, Dwarf_Error *dw_error)

Get access to the symboltable array.

• int dwarf_gdbindex_symboltable_entry (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_entryindex, Dwarf_Unsigned *dw_string_offset, Dwarf_Unsigned *dw_cu_vector_offset, Dwarf_Error *dw_error)

Access individual symtab entry.

int dwarf_gdbindex_cuvector_length (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_cuvector_

 offset, Dwarf_Unsigned *dw_innercount, Dwarf_Error *dw_error)

Get access to a cuvector.

int dwarf_gdbindex_cuvector_inner_attributes (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_
 cuvector_offset_in, Dwarf_Unsigned dw_innerindex, Dwarf_Unsigned *dw_field_value, Dwarf_Error *dw
 error)

Get access to a cuvector.

• int dwarf_gdbindex_cuvector_instance_expand_value (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_field_value, Dwarf_Unsigned *dw_cu_index, Dwarf_Unsigned *dw_symbol_kind, Dwarf_Unsigned *dw_is_static, Dwarf_Error *dw_error)

Expand the bit fields in a cuvector entry.

• int dwarf_gdbindex_string_by_offset (Dwarf_Gdbindex dw_gdbindexptr, Dwarf_Unsigned dw_stringoffset, const char **dw string ptr, Dwarf Error *dw error)

Retrieve a symbol name from the index data.

9.29.1 Detailed Description

Section .gdb index

This is a section created for and used by the GNU gdb debugger to access DWARF information.

Not part of standard DWARF.

See also

```
\label{local-section-format}  \mbox{https://sourceware.org/gdb/onlinedocs/gdb/Index-Section-Format.html} \\  \mbox{Holdex-Section-Format.html}
```

Version 8 built by gdb, so type entries are ok as is. Version 7 built by the 'gold' linker and type index entries for a CU must be derived otherwise, the type index is not correct... Earlier versions cannot be read correctly by the functions here.

The functions here make it possible to print the section content in detail, there is no search function here.

9.29.2 Function Documentation

9.29.2.1 dwarf_gdbindex_header()

The section is a single table one thinks.

See also

Reading gdbindex data

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_gdbindexptr	On success returns a pointer to make access to table details possible.
dw_version	On success returns the table version.
dw_cu_list_offset	On success returns the offset of the cu_list in the section.
dw_types_cu_list_offset	On success returns the offset of the types cu_list in the section.
dw_address_area_offset	On success returns the area pool offset.
dw_symbol_table_offset	On success returns the symbol table offset.
dw_constant_pool_offset	On success returns the constant pool offset.
dw_section_size	On success returns section size.
dw_section_name	On success returns section name.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if the section is absent.

9.29.2.2 dwarf_dealloc_gdbindex()

dw_gdbindexptr	Pass in a valid dw_gdbindexptr and on return assign zero to dw_gdbindexptr as it is stale.
----------------	--

9.29.2.3 dwarf_gdbindex_culist_array()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_list_length	On success returns the array length of the cu list.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.4 dwarf_gdbindex_culist_entry()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_entryindex	Pass in a number from 0 through dw_list_length-1. If dw_entryindex is too large for the array the function returns DW_DLV_NO_ENTRY.
dw_cu_offset	On success returns the CU offset for this list entry.
dw_cu_length	On success returns the CU length(in bytes) for this list entry.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.5 dwarf_gdbindex_types_culist_array()

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_types_list_length	On success returns the array length of the types cu list.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.6 dwarf_gdbindex_types_culist_entry()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_types_entryindex	Pass in a number from 0 through dw_list_length-1. If the value is greater than dw_list_length-1 the function returns DW_DLV_NO_ENTRY.
dw_cu_offset	On success returns the types CU offset for this list entry.
dw_tu_offset	On success returns the tu offset for this list entry.
dw_type_signature	On success returns the type unit offset for this entry if the type has a signature.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.7 dwarf_gdbindex_addressarea()

See also

Reading gdbindex addressarea

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_addressarea_list_length	On success returns the number of entries in the addressarea.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.8 dwarf_gdbindex_addressarea_entry()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_entryindex	Pass in an index, 0 through dw_addressarea_list_length-1. addressarea.
dw_low_address	On success returns the low address for the entry.
dw_high_address	On success returns the high address for the entry.
dw_cu_index	On success returns the index to the cu for the entry.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.9 dwarf_gdbindex_symboltable_array()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_symtab_list_length	On success returns the number of entries in the symbol table
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.10 dwarf_gdbindex_symboltable_entry()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_entryindex	Pass in a valid index in the range 0 through dw_symtab_list_length-1 If the value is greater than dw_symtab_list_length-1 the function returns DW_DLV_NO_ENTRY;
dw_string_offset	On success returns the string offset in the appropriate string section.
dw_cu_vector_offset	On success returns the CU vector offset.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.11 dwarf_gdbindex_cuvector_length()

See also

Reading the gdbindex symbol table

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_cuvector_offset	Pass in the offset, dw_cu_vector_offset.
dw_innercount	On success returns the number of CUs in the cuvector instance array.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.12 dwarf_gdbindex_cuvector_inner_attributes()

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
----------------	---

Parameters

dw_cuvector_offset←	Pass in the value of dw_cuvector_offset
_in	
dw_innerindex	Pass in the index of the CU vector in, from 0 through dw_innercount-1.
dw_field_value	On success returns a field of bits. To expand the bits call
	dwarf_gdbindex_cuvector_instance_expand_value.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.13 dwarf_gdbindex_cuvector_instance_expand_value()

Parameters

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.
dw_field_value	Pass in the dw_field_value returned by dwarf_gdbindex_cuvector_inner_attributes.
dw_cu_index	On success returns the CU index from the dw_field_value
dw_symbol_kind	On success returns the symbol kind (see the sourceware page. Kinds are TYPE, VARIABLE, or FUNCTION.
dw_is_static	On success returns non-zero if the entry is a static symbol (file-local, as in C or C++), otherwise it returns non-zero and the symbol is global.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.29.2.14 dwarf_gdbindex_string_by_offset()

dw_gdbindexptr	Pass in the Dwarf_Gdbindex pointer of interest.

Parameters

	dw_stringoffset	Pass in the string offset returned by dwarf_gdbindex_symboltable_entry
dw_string_ptr On success returns a a pointer to the null-terminated string.		On success returns a a pointer to the null-terminated string.
	dw_error	The usual pointer to return error details.

Returns

Returns DW DLV OK etc.

9.30 Fast Access to Split Dwarf (Debug Fission)

Functions

int dwarf_get_xu_index_header (Dwarf_Debug dw_dbg, const char *dw_section_type, Dwarf_Xu_Index_Header *dw_xuhdr, Dwarf_Unsigned *dw_version_number, Dwarf_Unsigned *dw_section_count, Dwarf_Unsigned *dw_units_count, Dwarf_Unsigned *dw_hash_slots_count, const char **dw_sect_name, Dwarf_Error *dw error)

Access a .debug_cu_index or dw_tu_index section.

void dwarf dealloc xu header (Dwarf Xu Index Header dw xuhdr)

Dealloc (free) memory associated with dw_xuhdr.

int dwarf_get_xu_index_section_type (Dwarf_Xu_Index_Header dw_xuhdr, const char **dw_typename, const char **dw_sectionname, Dwarf_Error *dw_error)

Return basic information about a Dwarf Xu Index Header.

 int dwarf_get_xu_hash_entry (Dwarf_Xu_Index_Header dw_xuhdr, Dwarf_Unsigned dw_index, Dwarf_Sig8 *dw_hash_value, Dwarf_Unsigned *dw_index_to_sections, Dwarf_Error *dw_error)

Get a Hash Entry.

 int dwarf_get_xu_section_names (Dwarf_Xu_Index_Header dw_xuhdr, Dwarf_Unsigned dw_column_index, Dwarf_Unsigned *dw_SECT_number, const char **dw_SECT_name, Dwarf_Error *dw_error)

get DW_SECT value for a column.

 int dwarf_get_xu_section_offset (Dwarf_Xu_Index_Header dw_xuhdr, Dwarf_Unsigned dw_row_index, Dwarf_Unsigned dw_column_index, Dwarf_Unsigned *dw_sec_offset, Dwarf_Unsigned *dw_sec_size, Dwarf_Error *dw_error)

Get row data (section data) for a row and column.

 int dwarf_get_debugfission_for_die (Dwarf_Die dw_die, Dwarf_Debug_Fission_Per_CU *dw_percu_out, Dwarf_Error *dw_error)

Get debugfission data for a Dwarf_Die.

int dwarf_get_debugfission_for_key (Dwarf_Debug dw_dbg, Dwarf_Sig8 *dw_hash_sig, const char *dw_←
 cu_type, Dwarf_Debug_Fission_Per_CU *dw_percu_out, Dwarf_Error *dw_error)

Given a hash signature find per-cu Fission data.

9.30.1 Detailed Description

9.30.2 Function Documentation

9.30.2.1 dwarf_get_xu_index_header()

```
const char * dw_section_type,
Dwarf_Xu_Index_Header * dw_xuhdr,
Dwarf_Unsigned * dw_version_number,
Dwarf_Unsigned * dw_section_count,
Dwarf_Unsigned * dw_units_count,
Dwarf_Unsigned * dw_hash_slots_count,
const char ** dw_sect_name,
Dwarf_Error * dw_error )
```

These sections are in a DWARF5 package file, a file normally named with the .dwo or .dwp extension.. See DWARF5 section 7.3.5.3 Format of the CU and TU Index Sections.

Parameters

dw_dbg	Pass in the Dwarf_Debug of interest
dw_section_type	Pass in a pointer to either "cu" or "tu".
dw_xuhdr	On success, returns a pointer usable in further calls.
dw_version_number	On success returns five.
dw_section_count	On success returns the number of entries in the table of section counts. Referred to as
	N.
dw_units_count	On success returns the number of compilation units or type units in the index.
	Referred to as U .
dw_hash_slots_count	On success returns the number of slots in the hash table. Referred to as S .
dw_sect_name	On success returns a pointer to the name of the section. Do not free/dealloc the
	returned pointer.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc. Returns DW_DLV_NO_ENTRY if the section requested is not present.

9.30.2.2 dwarf_dealloc_xu_header()

Should be named dwarf_dealloc_xuhdr instead.

Parameters

dw_	xuhdr	Dealloc (free) all associated memory. The caller should zero the passed in value on return as it is
		then a stale value.

9.30.2.3 dwarf_get_xu_index_section_type()

Parameters

dw_xuhdr	Pass in an open header pointer.
dw_typename	On success returns a pointer to the immutable string "tu" or "cu". Do not free.
dw_sectionname	On success returns a pointer to the section name in the object file. Do not free.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.30.2.4 dwarf_get_xu_hash_entry()

See also

examplez/x

Parameters

dw_xuhdr	Pass in an open header pointer.
dw_index	Pass in the index of the entry you wish. Valid index values are 0 through S-1 . If the dw_index passed in is outside the valid range the functionj
dw_hash_value	Pass in a pointer to a Dwarf_Sig8. On success the hash struct is filled in with the 8 byte hash value.
dw_index_to_sections	On success returns the offset/size table index for this hash entry.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK on success. If the dw_index passed in is outside the valid range the function it returns DW_DLV_NO_ENTRY (before version 0.7.0 it returned DW_DLV_ERROR, though nothing mentioned that). In case of error it returns DW_DLV_ERROR. If dw_error is non-null returns error details through dw_error (the usual error behavior).

9.30.2.5 dwarf_get_xu_section_names()

See also

Reading Split Dwarf (Debug Fission) data

Parameters

dw_xuhdr	Pass in an open header pointer.
dw_column_index	The section names are in row zero of the table so we do not mention the row number at all. Pass in the column of the entry you wish. Valid dw_column_index values are 0 through N-1 .
dw_SECT_number	On success returns DW_SECT_INFO or other section id as appears in
	dw_column_index.
dw_SECT_name	On success returns a pointer to the string with the section name.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.30.2.6 dwarf_get_xu_section_offset()

The section offset represents a base offset for the section the row data refers to. DWARF6 Section 7.3.5.3 page 193.

Parameters

dw_xuhdr	Pass in an open header pointer.
dw_row_index	Pass in a row number , 1 through U
dw_column_index	Pass in a column number , 0 through N-1
dw_sec_offset	On success returns the section offset of the section whose name dwarf_get_xu_section_names returns.
dw_sec_size	On success returns the section size of the section whose name dwarf_get_xu_section_names returns. If the returned section size is zero then this column makes no contribution to the dwp object file and the dw_sec_size and dw_sec_offset shoul be ignored.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.30.2.7 dwarf_get_debugfission_for_die()

For any Dwarf_Die in a compilation unit, return the debug fission table data through dw_percu_out. Usually applications will pass in the CU die. Calling code should zero all of the struct Dwarf_Debug_Fission_Per_CU_s before calling this. If there is no debugfission data this returns DW_DLV_NO_ENTRY (only .dwp objects have debugfission data)

Parameters

dw_die	Pass in a Dwarf_Die pointer, Usually pass in a CU DIE pointer.
dw_percu_out	Pass in a pointer to a zeroed structure. On success the function fills in the structure.
dw_error	The usual pointer to return error details.

Returns

Returns DW DLV OK etc.

9.30.2.8 dwarf_get_debugfission_for_key()

Parameters

dw_dbg	Pass in the Dwarf_Debug of interest.
dw_hash_sig	Pass in a pointer to a Dwarf_Sig8 containing a hash value of interest.
dw_cu_type	Pass in the type, a string. Either "cu" or "tu".
dw_percu_out	Pass in a pointer to a zeroed structure. On success the function fills in the structure.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.31 Access GNU .gnu_debuglink, build-id.

Functions

• int dwarf_gnu_debuglink (Dwarf_Debug dw_dbg, char **dw_debuglink_path_returned, unsigned char **dw_crc_returned, char **dw_debuglink_fullpath_returned, unsigned int *dw_debuglink_path_length← __returned, unsigned int *dw_buildid_type_returned, char **dw_buildid_owner_name_returned, unsigned

char **dw_buildid_returned, unsigned int *dw_buildid_length_returned, char ***dw_paths_returned, unsigned int *dw_paths_length_returned, Dwarf_Error *dw_error)

Find a separated DWARF object file.

int dwarf suppress debuglink crc (int dw suppress)

Suppressing crc calculations.

int dwarf_add_debuglink_global_path (Dwarf_Debug dw_dbg, const char *dw_pathname, Dwarf_Error *dw
 _error)

Adding debuglink global paths.

- int dwarf_crc32 (Dwarf_Debug dw_dbg, unsigned char *dw_crcbuf, Dwarf_Error *dw_error)

 Crc32 used for debuglink crc calculation.
- unsigned int dwarf_basic_crc32 (const unsigned char *dw_buf, unsigned long dw_len, unsigned int dw_init)

 Public interface to the real crc calculation.

9.31.1 Detailed Description

When DWARF sections are in a differenct object than the executable or a normal shared object. The special GNU section provides a way to name the object file with DWARF.

libdwarf will attempt to use this data to find the object file with DWARF.

Has nothing to do with split-dwarf/debug-fission.

9.31.2 Function Documentation

9.31.2.1 dwarf gnu debuglink()

.gnu_debuglink and/or the section .note.gnu.build-id.

Unless something is odd and you want to know details of the two sections you will not need this function.

See also

https://sourceware.org/gdb/onlinedocs/gdb/Separate-Debug-Files.html Using GNU debuglink data

If no debuglink then name_returned,crc_returned and debuglink_path_returned will get set 0 through the pointers.

If no .note.gnu.build-id then buildid_length_returned, and buildid_returned will be set 0 through the pointers.

In most cases output arguments can be passed as zero and the function will simply not return data through such arguments. Useful if you only care about some of the data potentially returned.

If $dw_debuglink_fullpath$ returned is set by the call the space allocated must be freed by the caller with free($dw_debuglink_fullpath_returned$).

if $dw_debuglink_paths_returned$ is set by the call the space allocated must be free by the caller with free($dw_debuglink_paths_returned$).

dwarf finish() will not free strings dw debuglink fullpath returned or dw debuglink paths returned.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_debuglink_path_returned	On success returns a pointer to a path in the debuglink section. Do not free!
dw_crc_returned	On success returns a pointer to a 4 byte area through the pointer.
dw_debuglink_fullpath_returned	On success returns a pointer to a full path computed from debuglink data of a correct path to a file with DWARF sections. Free this string when no longer of interest.
dw_debuglink_path_length_returned	On success returns the strlen() of $dw_debuglink_fullpath_returned$.
dw_buildid_type_returned	On success returns a pointer to integer with a type code. See the buildid definition.
dw_buildid_owner_name_returned	On success returns a pointer to the owner name from the buildid section. Do not free this.
dw_buildid_returned	On success returns a pointer to a sequence of bytes containing the buildid.
dw_buildid_length_returned	On success this is set to the length of the set of bytes pointed to by dw_buildid_returned .
dw_paths_returned	On success sets a pointer to an array of pointers to strings, each with a global path. These strings must be freed by the caller, dwarf_finish() will not free these strings. Call free(dw_paths_returned).
dw_paths_length_returned	On success returns the length of the array of string pointers dw_paths_returned points at.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.31.2.2 dwarf suppress debuglink crc()

The .gnu_debuglink section contains a compilation-system created crc (4 byte) value. If dwarf_init_path[_dl]() is called such a section can result in the reader/consumer calculating the crc value of a different object file. Which on a large object file could seem slow. See https://en.wikipedia.org/wiki/Cyclic_redundancye_check

When one is confident that any debug_link file found is the appropriate one one can call dwarf_suppress_complete debuglink_crc with a non-zero argument and any dwarf_init_path[_dl] call will skip debuglink crc calculations and just assume the crc would match whenever it applies. This is a global flag, applies to all Dwarf_Debug opened after the call in the program execution.

Does not apply to the .note.gnu.buildid section as that section never implies the reader/consumer needs to do a crc calculation.

Parameters

dw_suppress	Pass in 1 to suppress future calculation of crc values to verify a debuglink target is correct. So
	use only when you know this is safe. Pass in 0 to ensure future dwarf_init_path_dl calls
	compute debuglink CRC values as required.

Returns

Returns the previous value of the global flag.

Details on separate DWARF object access

9.31.2.3 dwarf_add_debuglink_global_path()

Used inside src/bin/dwarfexample/dwdebuglink.c so we can show all that is going on. The following has the explanation for how debuglink and global paths interact:

See also

https://sourceware.org/gdb/onlinedocs/gdb/Separate-Debug-Files.html

Parameters

dw_dbg	Pass in the Dwarf_Debug of interest.
dw_pathname	Pass in a pathname to add to the list of global paths used by debuglink.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.31.2.4 dwarf_crc32()

Caller passes pointer to array of 4 unsigned char provided by the caller and if this returns DW_DLV_OK that array is filled in.

Callers must guarantee dw_crcbuf points to at least 4 bytes of writable memory. Passing in a null dw_crcbug results in an immediate return of DW DLV NO ENTRY and the pointer is not used.

Parameters

dw_dbg	Pass in an open dw_dbg. When you attempted to open it, and it succeeded then pass the it via the Dwarf_Debug The function reads the file into memory and performs a crc calculation.
dw_crcbuf	Pass in a pointer to a 4 byte area to hold the returned crc, on success the function puts the 4 bytes there.
dw_error	The usual pointer to return error details.

Returns

Returns DW_DLV_OK etc.

9.31.2.5 dwarf_basic_crc32()

It is unlikely this is useful. The calculation will not produce a return matching that of Linux/Macos if the compiler implements unsigned int or signed int as 16 bits long.

The caller must guarantee that dw_buf is non-null and pointing to dw_len bytes of readable memory. If dw_buf is NULL then 0 is immediately returned and there is no indication of error.

Parameters

	dw_buf	Pass in a pointer to some bytes on which the crc calculation as done in debuglink is to be done.
Ī	dw_len	Pass in the length in bytes of dw_buf.
	dw_init	Pass in the initial 32 bit value, zero is the right choice.

Returns

Returns an int (assumed 32 bits int!) with the calculated crc.

9.32 Harmless Error recording

Macros

• #define DW_HARMLESS_ERROR_CIRCULAR_LIST_DEFAULT_SIZE 4

Default size of the libdwarf-internal circular list.

Functions

int dwarf_get_harmless_error_list (Dwarf_Debug dw_dbg, unsigned int dw_count, const char **dw_errmsg
 —ptrs_array, unsigned int *dw_newerr_count)

Get the harmless error count and content.

· unsigned int dwarf set harmless error list size (Dwarf Debug dw dbg, unsigned int dw maxcount)

The size of the circular list of strings libdwarf holds internally may be set and reset as needed. If it is shortened excess messages are simply dropped. It returns the previous size. If zero passed in the size is unchanged and it simply returns the current size.

void dwarf_insert_harmless_error (Dwarf_Debug dw_dbg, char *dw_newerror)

Harmless Error Insertion is only for testing.

9.32.1 Detailed Description

The harmless error list is a fixed size circular buffer of errors we note but which do not stop us from processing the object. Created so dwarfdump or other tools can report such inconsequential errors without causing anything to stop early.

You can change the list size from the default of DW_HARMLESS_ERROR_CIRCULAR_LIST_DEFAULT_SIZE at any time for a Dwarf_Debug dbg.

Harmless error data is dealloc'd by dwarf finish().

9.32.2 Function Documentation

9.32.2.1 dwarf get harmless error list()

User code supplies size of array of pointers dw_errmsg_ptrs_array in count and the array of pointers (the pointers themselves need not be initialized). The pointers returned in the array of pointers are invalidated by ANY call to libdwarf. Use them before making another libdwarf call! The array of string pointers passed in always has a final null pointer, so if there are N pointers the and M actual strings, then MIN(M,N-1) pointers are set to point to error strings. The array of pointers to strings always terminates with a NULL pointer. Do not free the strings. Every string is null-terminated.

Each call empties the error list (discarding all current entries). and fills in your array

Parameters

dw_dbg	The applicable Dwarf_Debug.
dw_count	The number of string buffers. If count is passed as zero no elements of the array are touched.
dw_errmsg_ptrs_array	A pointer to a user-created array of pointer to const char.
dw_newerr_count	If non-NULL the count of harmless errors pointers since the last call is returned through the pointer. If dw_count is greater than zero the first dw_count of the pointers in the user-created array point to null-terminated strings. Do not free the strings. print or copy the strings before any other libdwarf call.

Returns

Returns DW_DLV_NO_ENTRY if no harmless errors were noted so far. Returns DW_DLV_OK if there are harmless errors. Never returns DW_DLV_ERROR.

If DW_DLV_NO_ENTRY is returned none of the arguments other than dw_dbg are touched or used.

9.32.2.2 dwarf_set_harmless_error_list_size()

Parameters

dw_dbg	The applicable Dwarf_Debug.
dw_maxcount	Set the new internal buffer count to a number greater than zero.

Returns

returns the current size of the internal circular buffer if dw_maxcount is zero. If dw_maxcount is greater than zero the internal array is adjusted to hold that many and the previous number of harmless errors possible in the circular buffer is returned.

9.32.2.3 dwarf insert harmless error()

Useful for testing the harmless error mechanism.

Parameters

dw_dbg	Pass in an open Dwarf_Debug	
dw_newerror	Pass in a string whose content the function inserts as a harmless error (which	
	dwarf_get_harmless_error_list will retrieve).	

9.33 Names DW_TAG_member etc as strings

Functions

- int dwarf_get_ACCESS_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_ACCESS_name
- int dwarf_get_ADDR_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_ADDR_name
- int dwarf_get_AT_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf get AT name
- int dwarf_get_ATCF_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_AT_name
- int dwarf_get_ATE_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_ATE_name
- int dwarf_get_CC_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_CC_name
- int dwarf_get_CFA_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_CFA_name
- int dwarf_get_children_name (unsigned int dw_val_in, const char **dw_s_out) dwarf_get_children_namea - historic misspelling.
- int dwarf_get_CHILDREN_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_CHILDREN_name

- int dwarf_get_DEFAULTED_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_DEFAULTED_name
- int dwarf_get_DS_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_DS_name
- int dwarf_get_DSC_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_DSC_name
- int dwarf_get_GNUIKIND_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_GNUIKIND_name libdwarf invention
- int dwarf_get_EH_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_EH_name
- int dwarf_get_END_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_END_name
- int dwarf_get_FORM_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_FORM_name
- int dwarf_get_FRAME_name (unsigned int dw_val_in, const char **dw_s_out)

 This is a set of register names.
- int dwarf_get_GNUIVIS_name (unsigned int dw_val_in, const char **dw_s_out)

 dwarf_get_GNUIVIS_name a libdwarf invention
- int dwarf_get_ID_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_ID_name
- int dwarf_get_IDX_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_IDX_name
- int dwarf_get_INL_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_INL_name
- int dwarf_get_ISA_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_ISA_name
- int dwarf_get_LANG_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LANG_name
- int dwarf_get_LLE_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LLE_name
- int dwarf_get_LLEX_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LLEX_name a GNU extension.
- int dwarf_get_LNAME_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LNAME
- int dwarf_get_LNCT_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LNCT_name
- int dwarf_get_LNE_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LNE_name
- int dwarf_get_LNS_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_LNS_name
- int dwarf_get_MACINFO_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_MACINFO_name
- int dwarf_get_MACRO_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_MACRO_name
- int dwarf_get_OP_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_OP_name
- int dwarf_get_ORD_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_ORD_name
- int dwarf_get_RLE_name (unsigned int dw_val_in, const char **dw_s_out)
 dwarf_get_RLE_name
- int dwarf_get_SECT_name (unsigned int dw_val_in, const char **dw_s_out)

```
dwarf_get_SECT_name
```

• int dwarf_get_TAG_name (unsigned int dw_val_in, const char **dw_s_out)

```
dwarf_get_TAG_name
```

• int dwarf_get_UT_name (unsigned int dw_val_in, const char **dw_s_out)

```
dwarf_get_UT_name
```

int dwarf_get_VIRTUALITY_name (unsigned int dw_val_in, const char **dw_s_out)

```
dwarf_get_VIRTUALITY_name
```

int dwarf_get_VIS_name (unsigned int dw_val_in, const char **dw_s_out)

```
dwarf get VIS name
```

int dwarf_get_FORM_CLASS_name (enum Dwarf_Form_Class dw_fc, const char **dw_s_out)

dwarf_get_FORM_CLASS_name is for a libdwarf extension. Not defined by the DWARF standard though the concept is defined in the standard. It seemed essential to invent it for libdwarf to report correctly.

9.33.1 Detailed Description

Given a value you know is one of a particular name category in DWARF2 or later, call the appropriate function and on finding the name it returns DW_DLV_OK and sets the identifier for the value through a pointer. On success these functions return the string corresponding to **dw_val_in** passed in through the pointer **dw_s_out** and the value returned is DW_DLV_OK.

The strings returned on sucess are in static storage and must not be freed.

These functions are generated from information in dwarf.h, not hand coded functions.

If DW DLV NO ENTRY is returned the dw val in is not known and *s out is not set. This is unusual.

DW_DLV_ERROR is never returned.

The example referred to offers the suggested way to use functions like these.

See also

Retrieving tag, attribute, etc names

9.33.2 Function Documentation

9.33.2.1 dwarf_get_GNUIKIND_name()

So we can report things GNU extensions sensibly.

9.33.2.2 dwarf_get_EH_name()

```
int dwarf_get_EH_name (
          unsigned int dw_val_in,
          const char ** dw_s_out )
```

So we can report this GNU extension sensibly.

9.33.2.3 dwarf_get_FRAME_name()

```
int dwarf_get_FRAME_name (
          unsigned int dw_val_in,
          const char ** dw_s_out )
```

The set of register names is unlikely to match your register set, but perhaps this is better than no name.

9.33.2.4 dwarf_get_GNUIVIS_name()

```
int dwarf_get_GNUIVIS_name (
          unsigned int dw_val_in,
          const char ** dw_s_out )
```

So we report a GNU extension sensibly.

9.33.2.5 dwarf_get_LLEX_name()

```
int dwarf_get_LLEX_name (
          unsigned int dw_val_in,
          const char ** dw_s_out )
```

The name is a libdwarf invention for the GNU extension. So we report a GNU extension sensibly.

9.33.2.6 dwarf_get_MACINFO_name()

```
int dwarf_get_MACINFO_name (
          unsigned int dw_val_in,
          const char ** dw_s_out )
```

Used in DWARF2-DWARF4

9.33.2.7 dwarf_get_MACRO_name()

```
int dwarf_get_MACRO_name (
          unsigned int dw_val_in,
          const char ** dw_s_out )
```

Used in DWARF5

9.33.2.8 dwarf_get_FORM_CLASS_name()

See DWARF5 Table 2.3, Classes of Attribute Value page 23. Earlier DWARF versions have a similar table.

9.34 Object Sections Data

Functions

int dwarf_get_die_section_name (Dwarf_Debug dw_dbg, Dwarf_Bool dw_is_info, const char **dw_sec_
 name, Dwarf_Error *dw_error)

Get the real name a DIE section.

- int dwarf_get_die_section_name_b (Dwarf_Die dw_die, const char **dw_sec_name, Dwarf_Error *dw_error)

 Get the real name of a DIE section.
- int dwarf_get_macro_section_name (Dwarf_Debug dw_dbg, const char **dw_sec_name_out, Dwarf_Error *dw err)

Get the real name of a .debug_macro section.

int dwarf_get_real_section_name (Dwarf_Debug dw_dbg, const char *dw_std_section_name, const char **dw_actual_sec_name_out, Dwarf_Small *dw_marked_zcompressed, Dwarf_Small *dw_marked_zlibcompressed, Dwarf_Small *dw_marked_shf_compressed, Dwarf_Unsigned *dw_compressed_length, Dwarf_Unsigned *dw_uncompressed_length, Dwarf_Error *dw_error)

Get the real name of a section.

 int dwarf_get_frame_section_name (Dwarf_Debug dw_dbg, const char **dw_section_name_out, Dwarf_Error *dw_error)

Get .debug_frame section name.

• int dwarf_get_frame_section_name_eh_gnu (Dwarf_Debug dw_dbg, const char **dw_section_name_out, Dwarf_Error *dw_error)

Get GNU .eh_frame section name.

 int dwarf_get_aranges_section_name (Dwarf_Debug dw_dbg, const char **dw_section_name_out, Dwarf_Error *dw_error)

Get .debug_aranges section name The usual arguments.

int dwarf_get_ranges_section_name (Dwarf_Debug dw_dbg, const char **dw_section_name_out,
 Dwarf Error *dw error)

Get .debug_ranges section name The usual arguments and return values.

- int dwarf_get_offset_size (Dwarf_Debug dw_dbg, Dwarf_Half *dw_offset_size, Dwarf_Error *dw_error)
 Get offset size as defined by the object.
- int dwarf_get_address_size (Dwarf_Debug dw_dbg, Dwarf_Half *dw_addr_size, Dwarf_Error *dw_error)

 Get the address size as defined by the object.
- int dwarf_get_string_section_name (Dwarf_Debug dw_dbg, const char **dw_section_name_out, Dwarf_Error *dw_error)

Get the string table section name The usual arguments and return values.

• int **dwarf_get_line_section_name** (Dwarf_Debug dw_dbg, const char **dw_section_name_out, Dwarf_Error *dw_error)

Get the line table section name The usual arguments and return values.

• int dwarf_get_line_section_name_from_die (Dwarf_Die dw_die, const char **dw_section_name_out, Dwarf_Error *dw_error)

Get the line table section name.

 int dwarf_get_section_info_by_name_a (Dwarf_Debug dw_dbg, const char *dw_section_name, Dwarf_Addr *dw_section_addr, Dwarf_Unsigned *dw_section_size, Dwarf_Unsigned *dw_section_flags, Dwarf_Unsigned *dw_section_offset, Dwarf_Error *dw_error)

Given a section name, get its size, address, etc.

• int dwarf_get_section_info_by_name (Dwarf_Debug dw_dbg, const char *dw_section_name, Dwarf_Addr *dw_section_addr, Dwarf_Unsigned *dw_section_size, Dwarf_Error *dw_error)

Given a section name, get its size and address.

int dwarf_get_section_info_by_index_a (Dwarf_Debug dw_dbg, int dw_section_index, const char **dw_
 section_name, Dwarf_Addr *dw_section_addr, Dwarf_Unsigned *dw_section_size, Dwarf_Unsigned *dw
 _section_flags, Dwarf_Unsigned *dw_section_offset, Dwarf_Error *dw_error)

Given a section index, get its size and address, etc.

- int dwarf_get_section_info_by_index (Dwarf_Debug dw_dbg, int dw_section_index, const char **dw_
 section_name, Dwarf_Addr *dw_section_addr, Dwarf_Unsigned *dw_section_size, Dwarf_Error *dw_error)
 Given a section index, get its size and address.
- int dwarf_machine_architecture_a (Dwarf_Debug dw_dbg, Dwarf_Small *dw_ftype, Dwarf_Small *dw_←
 obj_pointersize, Dwarf_Bool *dw_obj_is_big_endian, Dwarf_Unsigned *dw_obj_machine, Dwarf_Unsigned
 *dw_obj_type, Dwarf_Unsigned *dw_obj_flags, Dwarf_Small *dw_path_source, Dwarf_Unsigned *dw_ub←
 _offset, Dwarf_Unsigned *dw_ub_count, Dwarf_Unsigned *dw_ub_index, Dwarf_Unsigned *dw_comdat_←
 groupnumber)

Get basic object information from Dwarf_Debug.

int dwarf_machine_architecture (Dwarf_Debug dw_dbg, Dwarf_Small *dw_ftype, Dwarf_Small *dw_obj
 _pointersize, Dwarf_Bool *dw_obj_is_big_endian, Dwarf_Unsigned *dw_obj_machine, Dwarf_Unsigned
 *dw_obj_flags, Dwarf_Small *dw_path_source, Dwarf_Unsigned *dw_ub_offset, Dwarf_Unsigned *dw_
 ub_count, Dwarf_Unsigned *dw_ub_index, Dwarf_Unsigned *dw_comdat_groupnumber)

Get basic object information original version.

- Dwarf_Unsigned dwarf_get_section_count (Dwarf_Debug dw_dbg)
 Get section count (of object file sections).
- int dwarf_get_section_max_offsets_d (Dwarf_Debug dw_dbg, Dwarf_Unsigned *dw_debug_info_size, Dwarf_Unsigned *dw_debug_abbrev_size, Dwarf_Unsigned *dw_debug_line_size, Dwarf_Unsigned *dw-debug_line_size, Dwarf_Unsigned *dw_debug_macinfo_size, Dwarf_Unsigned *dw_debug_pubnames_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_compublypes_size, Dwarf_Unsigned *dw_debug_compublypes_size, Dwarf_Unsigned *dw_debug_compublypes_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_compublypes_size, Dwarf_Unsigned *dw_debug_compublypes_size, Dwarf_Unsigned *dw_debug_str_size, Dwarf_Unsigned *dw_debug_compublypes_size, D

Get section sizes for many sections.

9.34.1 Detailed Description

These functions are not often used. They give access to section- and objectfile-related information, and that sort of information is not generally needed to understand DWARF content.

Section name access. Because names sections such as .debug_info might end with .dwo or be .zdebug or might not.

String pointers returned via these functions must not be freed, the strings are statically declared.

For non-Elf the name reported will be as if it were Elf sections. For example, not the names MacOS puts in its object sections (which the MacOS reader translates).

These calls returning selected object header {machine architecture,flags) and section (offset, flags) data are not of interest to most library callers: dwarf_machine_architecture(), dwarf_get_section_info_by_index_a(), and dwarf_get_section_info_by_name_a().

The simple calls will not be documented in full detail here.

9.34.2 Function Documentation

9.34.2.1 dwarf get die section name()

dw is info

Parameters

dw_dbg	The Dwarf_Debug of interest
dw_is_info	We do not pass in a DIE, so we have to pass in TRUE for for .debug_info, or if DWARF4 .debug_types pass in FALSE.
dw_sec_name	On success returns a pointer to the actual section name in the object file. Do not free the string.
dw_error	The usual error argument to report error details.

Returns

DW_DLV_OK etc.

9.34.2.2 dwarf_get_die_section_name_b()

The same as <code>dwarf_get_die_section_name</code> except we have a DIE so do not need <code>dw_is_info</code> as a argument.

9.34.2.3 dwarf_get_real_section_name()

If the object has section groups only the sections in the group in dw_dbg will be found.

Whether .zdebug or ZLIB or SHF_COMPRESSED is the marker there is just one uncompress algorithm (zlib) for all three cases.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_std_section_name	Pass in a standard section name, such as .debug_info or .debug_info.dwo .
dw_actual_sec_name_out	On success returns the actual section name from the object file.
dw_marked_zcompressed	On success returns TRUE if the original section name ends in .zdebug
dw_marked_zlib_compressed	On success returns TRUE if the section has the ZLIB string at the front of the section.
dw_marked_shf_compressed	On success returns TRUE if the section flag (Elf SHF_COMPRESSED) is marked as compressed.
dw_compressed_length	On success if the section was compressed it returns the original section length in the object file.
dw_uncompressed_length	On success if the section was compressed this returns the uncompared section.
dw_error	On error returns the error usual details.

Returns

The usual DW_DLV_OK etc. If the section is not relevant to this Dwarf_Debug or is not in the object file at all, returns DW_DLV_NO_ENTRY

9.34.2.4 dwarf_get_frame_section_name()

Returns

returns DW_DLV_OK if the .debug_frame exists

9.34.2.5 dwarf_get_frame_section_name_eh_gnu()

Returns

Returns DW DLV OK if the .debug frame is present Returns DW DLV NO ENTRY if it is not present.

9.34.2.6 dwarf_get_offset_size()

This is not from DWARF information, it is from object file headers.

9.34.2.7 dwarf_get_address_size()

This is not from DWARF information, it is from object file headers.

9.34.2.8 dwarf_get_line_section_name_from_die()

Parameters

dw_die	Pass in a Dwarf_Die pointer.
dw_section_name_out	On success returns the section name, usually some .debug_info* name but in DWARF4 could be a .debug_types* name.
dw_error	On error returns the usual error pointer.

Returns

Returns DW_DLV_OK etc.

9.34.2.9 dwarf_get_section_info_by_name_a()

New in v0.9.0 November 2023.

This is not often used and is completely unnecessary for most to call.

See dwarf_get_section_info_by_name() for the older and still current version.

Any of the pointers dw_section_addr, dw_section_size, dw_section_flags, and dw_section_offset may be passed in as zero and those will be ignored by the function.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_section_name	Pass in a pointer to a section name. It must be an exact match to the real section name.
dw_section_addr	On success returns the section address as defined by an object header.
dw_section_size	On success returns the section size as defined by an object header.
dw_section_flags	On success returns the section flags as defined by an object header. The flag meaning depends on which object format is being read and the meaning is defined by the object format. We hope it is of some use. In PE object files this field is called Characteristics .
dw_section_offset	On success returns the section offset as defined by an object header. The offset meaning is supposedly an object file offset but the meaning depends on the object file type(!). We hope it is of some use.
dw_error	On error returns the usual error pointer.

Returns

Returns DW_DLV_OK etc.

9.34.2.10 dwarf_get_section_info_by_name()

See dwarf_get_section_info_by_name_a() for the newest version which returns additional values.

Fields and meanings in dwarf_get_section_info_by_name() are the same as in dwarf_get_section_info_by_name_a() except that the arguments dw_section_flags and dw_section_offset are missing here.

9.34.2.11 dwarf_get_section_info_by_index_a()

See dwarf_get_section_info_by_index() for the older and still current version.

Any of the pointers dw_section_addr, dw_section_size, dw_section_flags, and dw_section_offset may be passed in as zero and those will be ignored by the function.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_section_index	Pass in an index, 0 through N-1 where N is the count returned from
	dwarf_get_section_count . As an index type -int- works in practice, but should really be
	Dwarf_Unsigned.
dw_section_name	On success returns a pointer to the section name as it appears in the object file.
dw_section_addr	On success returns the section address as defined by an object header.
dw_section_size	On success returns the section size as defined by an object header.
dw_section_flags	On success returns the section flags as defined by an object header. The flag meaning depends on which object format is being read and the meaning is defined by the object format. In PE object files this field is called Characteristics . We hope it is of some use.
dw_section_offset	On success returns the section offset as defined by an object header. The offset meaning is supposedly an object file offset but the meaning depends on the object file type(!). We hope it is of some use.
dw_error	On error returns the usual error pointer.

Returns

Returns DW_DLV_OK etc.

9.34.2.12 dwarf_get_section_info_by_index()

See dwarf_get_section_info_by_index_a() for the newest version which returns additional values.

Fields and meanings in dwarf_get_section_info_by_index() are the same as in dwarf_get_section_info_by_index_a() except that the arguments dw_section_flags and dw_section_offset are missing here.

9.34.2.13 dwarf machine architecture a()

Not all the fields here are relevant for all object types, and the dw_obj_machine and dw_obj_flags have ABI-defined values which have nothing to do with DWARF.

This version added December 2024 with an additional argument: dw_obj_type.

dwarf_ub_offset, dw_ub_count, dw_ub_index only apply to DW_FTYPE_APPLEUNIVERSAL.

dw_comdat_groupnumber only applies to DW_FTYPE_ELF.

Other than dw_dbg one can pass in NULL for any pointer parameter whose value is not of interest.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_ftype	Pass in a pointer. On success the value pointed to will be set to the the applicable DW_FTYPE value (see libdwarf.h).
dw_obj_pointersize	Pass in a pointer. On success the value pointed to will be set to the the applicable pointer size, which is almost always either 4 or 8.
dw_obj_is_big_endian	Pass in a pointer. On success the value pointed to will be set to either 1 (the object being read is big-endia) or 0 (the object being read is little-endian.
dw_obj_machine	Pass in a pointer. On success the value pointed to will be set to a value that the specific ABI uses for the machine-architecture the object file says it is for.
dw_obj_type	Pass in a pointer. On success the value pointed to will be set to a value that the specific ABI uses for the machine-architecture the object file says it is for (for ELF is elf header e_type).

Parameters

dw_obj_flags	Pass in a pointer. On success the value pointed to will be set to a value that the specific ABI uses for a header record flags word (in a PE object the flags word is called Characteristics).
dw_path_source	Pass in a pointer. On success the value pointed to will be set to a value that libdwarf sets to a DW_PATHSOURCE value indicating what caused the file path.
dw_ub_offset	Pass in a pointer. On success if the value of dw_ftype is DW_FTYPE_APPLEUNIVERSAL the returned value will be set to the count (in all other cases, the value is set to 0)
dw_ub_count	Pass in a pointer. On success if the value of dw_ftype is DW_FTYPE_APPLEUNIVERSAL the returned value will be set to the number of object files in the binary (in all other cases, the value is set to 0)
dw_ub_index	Pass in a pointer. On success if the value of dw_ftype is DW_FTYPE_APPLEUNIVERSAL the returned value will be set to the number of the specific object from the universal-binary, usable values are 0 through dw_ub_count-1. (in all other cases, the value is set to 0)
dw_comdat_groupnumber	Pass in a pointer. On success if the value of dw_ftype is DW_FTYPE_ELF the returned value will be the comdat group being referenced. (in all other cases, the value is set to 0)

Returns

Returns DW_DLV_NO_ENTRY if the Dwarf_Debug passed in is null or stale. Otherwise returns DW_DLV_OK and non-null return-value pointers will have meaningful data.

9.34.2.14 dwarf_machine_architecture()

```
int dwarf_machine_architecture (
    Dwarf_Debug dw_dbg,

    Dwarf_Small * dw_ftype,

    Dwarf_Small * dw_obj_pointersize,

    Dwarf_Bool * dw_obj_is_big_endian,

    Dwarf_Unsigned * dw_obj_machine,

    Dwarf_Unsigned * dw_obj_flags,

    Dwarf_Small * dw_path_source,

    Dwarf_Unsigned * dw_ub_offset,

    Dwarf_Unsigned * dw_ub_count,

    Dwarf_Unsigned * dw_ub_index,

    Dwarf_Unsigned * dw_comdat_groupnumber )
```

Identical to dwarf_machine_architecture_a() except that this older version does not have the the dw_obj_type argument so it cannot return the Elf e_type value..

9.34.2.15 dwarf get section count()

```
\begin{tabular}{ll} $\tt Dwarf\_Unsigned \ dwarf\_get\_section\_count \ ( \\ &\tt Dwarf\_Debug \ dw\_dbg \ ) \end{tabular}
```

Return the section count. Returns 0 if the dw_dbg argument is improper in any way.

Parameters

dw_dbg	Pass in a valid Dwarf_Debug of interest.
--------	--

Returns

Returns the count of sections in the object file or zero.

9.34.2.16 dwarf_get_section_max_offsets_d()

```
int dwarf_get_section_max_offsets_d (
            Dwarf_Debug dw_dbg,
             Dwarf_Unsigned * dw_debug_info_size,
             Dwarf_Unsigned * dw_debug_abbrev_size,
             Dwarf_Unsigned * dw_debug_line_size,
             Dwarf_Unsigned * dw_debug_loc_size,
             Dwarf_Unsigned * dw_debug_aranges_size,
             Dwarf_Unsigned * dw_debug_macinfo_size,
             Dwarf_Unsigned * dw_debug_pubnames_size,
             Dwarf_Unsigned * dw_debug_str_size,
             Dwarf_Unsigned * dw_debug_frame_size,
             Dwarf_Unsigned * dw_debug_ranges_size,
             Dwarf_Unsigned * dw_debug_pubtypes_size,
             Dwarf_Unsigned * dw_debug_types_size,
             Dwarf_Unsigned * dw_debug_macro_size,
             Dwarf_Unsigned * dw_debug_str_offsets_size,
             Dwarf_Unsigned * dw_debug_sup_size,
             Dwarf_Unsigned * dw_debug_cu_index_size,
             Dwarf_Unsigned * dw_debug_tu_index_size,
             Dwarf_Unsigned * dw_debug_names_size,
             Dwarf_Unsigned * dw_debug_loclists_size,
             Dwarf_Unsigned * dw_debug_rnglists_size )
```

The list of sections is incomplete and the argument list is ... too long ... making this an unusual function

Originally a hack so clients could verify offsets. Added so that one can detect broken offsets (which happened in an IRIX executable larger than 2GB with MIPSpro 7.3.1.3 toolchain.).

Parameters

dw_dbg Pass in a valid Dwarf_Debug of interest.
--

Returns

If the dw_dbg is non-null it returns DW_DLV_OK. If dw_dbg is NULL it returns DW_DLV_NO_ENTRY.

9.35 Section Groups Objectfile Data

Functions

int dwarf_sec_group_sizes (Dwarf_Debug dw_dbg, Dwarf_Unsigned *dw_section_count_out, Dwarf_Unsigned *dw_group_count_out, Dwarf_Unsigned *dw_selected_group_out, Dwarf_Unsigned *dw_map_entry_count_out, Dwarf_Error *dw_error)

Get Section Groups data counts.

 int dwarf_sec_group_map (Dwarf_Debug dw_dbg, Dwarf_Unsigned dw_map_entry_count, Dwarf_Unsigned *dw_group_numbers_array, Dwarf_Unsigned *dw_sec_numbers_array, const char **dw_sec_names_array, Dwarf_Error *dw_error)

Return a map between group numbers and section numbers.

9.35.1 Detailed Description

Section Groups are defined in the extended Elf ABI and are seen in relocatable Elf object files, not executables or shared objects.

Section Groups Overview

9.35.2 Function Documentation

9.35.2.1 dwarf sec group sizes()

Allows callers to find out what groups (dwo or COMDAT) are in the object and how much to allocate so one can get the group-section map data.

This is relevant for Debug Fission. If an object file has both .dwo sections and non-dwo sections or it has Elf COMDAT GROUP sections this becomes important.

Section Groups Overview

Parameters

dw_dbg	Pass in the Dwarf_Debug of interest.
dw_section_count_out	On success returns the number of DWARF sections in the object file. Can sometimes be many more than are of interest.
dw_group_count_out	On success returns the number of groups. Though usually one, it can be much larger.
dw_selected_group_out	On success returns the groupnumber that applies to this specific open Dwarf_Debug.
dw_map_entry_count_out	On success returns the count of record allocations needed to call dwarf_sec_group_map successfully. dw_map_entry_count_out will be less than or equal to dw_section_count_out.
dw_error	The usual error details pointer.

Returns

On success returns DW_DLV_OK

9.35.2.2 dwarf_sec_group_map()

This map shows all the groups in the object file and shows which object sections go with which group.

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_map_entry_count	Pass in the dw_map_entry_count_out from dwarf_sec_group_sizes
dw_group_numbers_array	Pass in an array of Dwarf_Unsigned with dw_map_entry_count entries. Zero the data before the call here. On success returns a list of group numbers.
dw_sec_numbers_array	Pass in an array of Dwarf_Unsigned with dw_map_entry_count entries. Zero the data before the call here. On success returns a list of section numbers.
dw_sec_names_array	Pass in an array of const char * with dw_map_entry_count entries. Zero the data before the call here. On success returns a list of section names.
dw_error	The usual error details pointer.

Returns

On success returns DW_DLV_OK

9.36 LEB Encode and Decode

Functions

- int dwarf_encode_leb128 (Dwarf_Unsigned dw_val, int *dw_nbytes, char *dw_space, int dw_splen)
- int dwarf_encode_signed_leb128 (Dwarf_Signed dw_val, int *dw_nbytes, char *dw_space, int dw_splen)
- int dwarf_decode_leb128 (char *dw_leb, Dwarf_Unsigned *dw_leblen, Dwarf_Unsigned *dw_outval, char *dw endptr)
- int dwarf_decode_signed_leb128 (char *dw_leb, Dwarf_Unsigned *dw_leblen, Dwarf_Signed *dw_outval, char *dw_endptr)

9.36.1 Detailed Description

These are LEB/ULEB reading and writing functions heavily used inside libdwarf.

While the DWARF Standard does not mention allowing extra insignificant trailing bytes in a ULEB these functions allow a few such for compilers using extras for alignment in DWARF.

9.37 Miscellaneous Functions

Functions

const char * dwarf_package_version (void)

Return the version string in the library.

int dwarf_set_stringcheck (int dw_stringcheck)

Turn off libdwarf checks of strings.

int dwarf_set_reloc_application (int dw_apply)

Set libdwarf response to *.rela relocations.

void dwarf_record_cmdline_options (Dwarf_Cmdline_Options dw_dd_options)

Tell libdwarf to add verbosity to Line Header errors By default the flag in the struct argument is zero. dwarfdump uses this when -v used on dwarfdump.

int dwarf_set_de_alloc_flag (int dw_v)

Eliminate libdwarf tracking of allocations Independent of any Dwarf_Debug and applicable to all whenever the setting is changed. Defaults to non-zero.

• int dwarf library allow dup attr (int dw v)

Eliminate libdwarf checking attribute duplication.

Dwarf_Small dwarf_set_default_address_size (Dwarf_Debug dw_dbg, Dwarf_Small dw_value)

Set the address size on a Dwarf_Debug.

 int dwarf_get_universalbinary_count (Dwarf_Debug dw_dbg, Dwarf_Unsigned *dw_current_index, Dwarf_Unsigned *dw_available_count)

Retrieve universal binary index.

Variables

- void(*)(void *, const void *, unsigned long) dwarf_get_endian_copy_function (Dwarf_Debug dw_dbg)
 Get a pointer to the applicable swap/noswap function.
- Dwarf_Cmdline_Options dwarf_cmdline_options

9.37.1 Detailed Description

9.37.2 Function Documentation

9.37.2.1 dwarf package version()

An example: "0.3.0" which is a Semantic Version identifier. Before September 2021 the version string was a date, for example "20210528", which is in ISO date format. See DW_LIBDWARF_VERSION DW_LIBDWARF_VERSION → MAJOR DW LIBDWARF VERSION MINOR DW LIBDWARF VERSION MICRO

Returns

The Package Version built into libdwarf.so or libdwarf.a

9.37.2.2 dwarf_set_stringcheck()

Zero is the default and means do all string length validity checks. It applies to all Dwarf_Debug open and all opened later in this library instance.

Parameters

dw_stringcheck	Pass in a small non-zero value to turn off all libdwarf string validity checks. It speeds up
	libdwarf, butis dangerous and voids all promises the library will not segfault.

Returns

Returns the previous value of this flag.

9.37.2.3 dwarf_set_reloc_application()

```
int dwarf_set_reloc_application ( \label{eq:condition} \text{int } dw\_apply \ )
```

dw_apply defaults to 1 and means apply all '.rela' relocations on reading in a dwarf object section of such relocations. Best to just ignore this function It applies to all Dwarf_Debug open and all opened later in this library instance.

Parameters

dw_apply	Pass in a zero to turn off reading and applying of .rela relocations, which will likely break reading of
	.o object files but probably will not break reading executables or shared objects. Pass in non zero
	(it is really just an 8 bit value, so use a small value) to turn off inspecting .rela sections.

Returns

Returns the previous value of the apply flag.

9.37.2.4 dwarf_record_cmdline_options()

```
void dwarf_record_cmdline_options ( {\tt Dwarf\_Cmdline\_Options} \ dw\_dd\_options \ )
```

See also

dwarf_register_printf_callback

Parameters

dw_dd_options	The structure has one flag, and if the flag is nonzero and there is an error in reading a line
	table header the function passes back detail error messages via
	dwarf_register_printf_callback.

9.37.2.5 dwarf_set_de_alloc_flag()

```
int dwarf_set_de_alloc_flag ( \label{eq:condition} \mbox{int } d \mbox{$w$\_$} \mbox{$v$} \mbox{} \mbox{} \mbox{} )
```

Parameters



If zero passed in libdwarf will run somewhat faster and library memory allocations will not all be tracked and dwarf_finish() will be unable to free/dealloc some things. User code can do the necessary deallocs (as documented), but the normal guarantee that libdwarf will clean up is revoked. If non-zero passed in libdwarf will resume or continue tracking allocations

Returns

Returns the previous version of the flag.

9.37.2.6 dwarf library allow dup attr()

```
int dwarf_library_allow_dup_attr ( int \ dw\_v \ )
```

Independent of any Dwarf_Debug, this is sets a global flag in libdwarf and is applicable to all whenever the setting is changed. Defaults to zero so by default libdwarf does check every set of abbreviations for duplicate attributes.

DWARF5 Sec 2.2 Attribute Types Each attribute value is characterized by an attribute name. No more than one attribute with a given name may appear in any debugging information entry. Essentially the same wording is in Sec 2.2 of DWARF2, DWARF3 and DWARF4.

Do not call this with non-zero dw v unless you really want the library to avoid this basic DWARF-correctness check.

Since

 $\{0.12.0\}$

Parameters

dw⊷ v If non-zero passed in libdwarf will avoid the checks and will not return errors for an abbreviation list with duplicate attributes.

Returns

Returns the previous version of the flag.

9.37.2.7 dwarf_set_default_address_size()

DWARF information CUs and other section DWARF headers define a CU-specific address size, but this Dwarf_
Debug value is used when other address size information does not exist, for example in a DWARF2 CIE or FDE.

Parameters

dw_dbg	The Dwarf_Debug of interest.	
dw_value	Sets the address size for the Dwarf_Debug to a non-zero value. The default address size is	
	derived from headers in the object file. Values larger than the size of Dwarf_Addr are not set. If	
	zero passed the default is not changed.	

Returns

Returns the last set address size.

9.37.2.8 dwarf_get_universalbinary_count()

For Mach-O universal binaries this returns relevant information.

For non-universal binaries (Mach-O, Elf, or PE) the values are not meaningful, so the function returns DW_DLV_{\leftarrow} NO_ENTRY .

Parameters

dw_dbg	The Dwarf_Debug of interest.
dw_current_index	If dw_current_index is passed in non-null the function returns the universal-binary index of the current object (which came from a universal binary).
dw_available_count	If dw_current_index is passed in non-null the function returns the count of binaries in the universal binary.

Returns

Returns DW_DLV_NO_ENTRY if the object file is not from a Mach-O universal binary. Returns DW_DLV_← NO_ENTRY if dw_dbg is passed in NULL. Never returns DW_DLV_ERROR.

9.37.3 Variable Documentation

9.37.3.1 dwarf_get_endian_copy_function

the function pointer returned enables libdwarf users to use the same 64bit/32bit/16bit word copy as libdwarf does internally for the Dwarf_Debug passed in. The function makes it possible for libdwarf to read either endianness.

Parameters

dw_dbg	Pass in a pointer to the applicable Dwarf_Debug.
--------	--

Returns

a pointer to a copy function. If the object file referred to and the libdwarf reading that file are the same endianness the function returned will, when called, do a simple memcpy, effectively, while otherwise it would do a byte-swapping copy. It seems unlikely this will be useful to most library users. To call the copy function returned the first argument must be a pointer to the target word and the second must be a pointer to the input word. The third argument is the length to be copied and it must be 2,4,or 8.

9.38 Determine Object Type of a File

Functions

- int dwarf_object_detector_path_b (const char *dw_path, char *dw_outpath_buffer, unsigned long dw_← outpathlen, char **dw_gl_pathnames, unsigned int dw_gl_pathcount, unsigned int *dw_ftype, unsigned int *dw_endian, unsigned int *dw_offsetsize, Dwarf_Unsigned *dw_filesize, unsigned char *dw_pathsource, int *dw errcode)
- int dwarf_object_detector_path_dSYM (const char *dw_path, char *dw_outpath, unsigned long dw_← outpath_len, char **dw_gl_pathnames, unsigned int dw_gl_pathcount, unsigned int *dw_ftype, unsigned int *dw_endian, unsigned int *dw_offsetsize, Dwarf_Unsigned *dw_filesize, unsigned char *dw_pathsource, int *dw_errcode)
- int **dwarf_object_detector_fd** (int dw_fd, unsigned int *dw_ftype, unsigned int *dw_endian, unsigned int *dw_offsetsize, Dwarf_Unsigned *dw_filesize, int *dw_errcode)

9.38.1 Detailed Description

This group of functions are unlikely to be called by your code unless your code needs to know the basic data about an object file without actually opening a Dwarf_Debug.

These are crucial for libdwarf itself. The dw_ftype returned is one of DW_FTYPE_ELF, DW_FTYPE_PE, DW_← FTYPE MACH O, or DW FTYPE APPLEUNIVERSAL.

9.39 Section allocation: malloc or mmap

Functions

- enum Dwarf_Sec_Alloc_Pref dwarf_set_load_preference (enum Dwarf_Sec_Alloc_Pref dw_load_preference)

 Set/Retrieve section allocation preference.
- int dwarf_get_mmap_count (Dwarf_Debug dw_dbg, Dwarf_Unsigned *dw_mmap_count, Dwarf_Unsigned *dw_mmap_size, Dwarf_Unsigned *dw_malloc_count, Dwarf_Unsigned *dw_malloc_size)

Retrieve count of mmap/malloc sections.

9.39.1 Detailed Description

Functions related to the choice of malloc/read or mmap for object section memory allocation.

The default allocation preference is malloc().

The shell environment variable DWARF_WHICH_ALLOC is also involved at runtime but it only applies to reading Elf object files.. If the value is 'malloc' then use of read/malloc is preferred. If the value is 'mmap' then use of mmap is preferred (Example: 'export DWARF_WHICH_ALLOC=mmap'). Otherwise, the environment value is checked and ignored.

If present and valid this environment variable takes precedence over dwarf_set_load_preference().

9.39.2 Function Documentation

9.39.2.1 dwarf set load preference()

By default object file sections are loaded using malloc and read (Dwarf_Alloc_Malloc). This works everywhere and works well on all but gigantic object files.

The preference of Dwarf_Alloc_Mmap does not guarantee mmap will be used for object section data, but does cause mmap() to be used when possible.

In 0.12.0 mmap() is only usable on Elf object files.

dw_load_preference is one of Dwarf_Alloc_Malloc (1) Dwarf_Alloc_Mmap (2)

Must be called before calling a dwarf_init*() to be effective in a dwarf_init*(). The value is remembered for subsequent dwarf_init*() in the library runtime being executed.

Parameters

dw_load_preference	If passed in Dwarf_Alloc_Mmap then future calls to any dwarf_init*() function will use
	mmap to load object sections if possible. If passed in Dwarf_Alloc_Malloc then future
	calls to any dwarf_init*() function will use mmap to load sections. Any other value
	passed in dw_load_preference is ignored.

Returns

Always returns the value before dw_load_preference applied, of this runtime global preference.

9.39.2.2 dwarf_get_mmap_count()

 $\{0.12.0\}$

Since

Note that compressed section contents will be expanded into a malloc/read section in all cases.

Parameters

dw_dbg	A valid open Dwarf_Debug.
dw_mmap_count	On success the number of sections allocated with mmap is returned. If null passed in the argument is ignored.
dw_mmap_size	On success the size total in bytes of sections allocated with mmap is returned. If null passed in the argument is ignored.
dw_malloc_count	On success the number of sections read/allocated with read/malloc is returned. If null passed in the argument is ignored. On success the number of sections allocated with malloc/read is returned.
dw_malloc_size	On success the total size in bytes of sections with malloc/read is returned. If null passed in the argument is ignored. On success the number of sections read/allocated with read/malloc is returned.

Returns

On success returns DW_DLV_OK and sets the counts and total size through the respective non-null pointer arguments. If dw_dbg is invalid or NULL the function returns DW_DLV_ERROR. Never returns DW_DLV_ \leftarrow NO ENTRY.

9.40 Using dwarf_init_path()

Example of a libdwarf initialization call.

An example calling dwarf_init_path() and dwarf_finish()

Parameters

path	Path to an object we wish to open.	
groupnumber	er Desired groupnumber. Use DW_DW_GROUPNUMBER_ANY unless you have reason to do	
	otherwise.	

Returns

Returns the applicable result. DW_DLV_OK etc.

```
int exampleinit(const char *path, unsigned groupnumber)
    static char true_pathbuf[FILENAME_MAX];
    unsigned tpathlen = FILENAME_MAX;
    Dwarf_Handler errhand = 0;
    Dwarf_Ptr errarg = 0;
    Dwarf_Error error = 0;
    Dwarf_Debug dbg = 0;
    int res = 0;
    res = dwarf_init_path(path,true_pathbuf,
        tpathlen, groupnumber, errhand,
    errarg, &dbg, &error);
if (res == DW_DLV_ERROR) {
        /* Necessary call even though dbg is null!
   This avoids a memory leak. */
        dwarf_dealloc_error(dbg,error);
        return res;
    if (res == DW_DLV_NO_ENTRY) {
         /* Nothing we can do */
        return res;
    printf("The file we actually opened is s\n",
```

```
true_pathbuf);
/* Call libdwarf functions here */
dwarf_finish(dbg);
return DW_DLV_OK;
```

9.41 Using dwarf_init_path_dl()

Example focused on GNU debuglink data.

In case GNU debuglink data is followed the true_pathbuf content will not match path. The path actually used is copied to true_path_out.

In the case of MacOS dSYM the true_path_out may not match path.

If debuglink data is missing from the Elf executable or shared-object (ie, it is a normal object!) or unusable by libdwarf or true_path_buffer len is zero or true_path_out_buffer is zero libdwarf accepts the path given as the object to report on, no debuglink or dSYM processing will be used.

See also

```
https://sourceware.org/gdb/onlinedocs/gdb/Separate-Debug-Files.html
```

An example calling dwarf_init_path_dl() and dwarf_finish()

Parameters

path	Path to an object we wish to open.	
groupnumber	Desired groupnumber. Use DW_DW_GROUPNUMBER_ANY unless you have reason to do	
	otherwise.	
error	A pointer we can use to record error details.	

Returns

Returns the applicable result. DW_DLV_OK etc.

```
int exampleinit_dl(const char *path, unsigned groupnumber,
    Dwarf_Error *error)
    static char true_pathbuf[FILENAME_MAX];
    static const char *glpath[3] = {
   "/usr/local/debug",
        "/usr/local/private/debug",
        "/usr/local/libdwarf/debug
                  tpathlen = FILENAME_MAX;
    unsigned
    Dwarf_Handler errhand = 0;
    Dwarf_Ptr errarg = 0;
                 dbg = 0;
res = 0;
    Dwarf_Debug
    unsigned char path_source = 0;
    res = dwarf_init_path_dl(path,true_pathbuf,
        tpathlen, groupnumber, errhand,
        errarg, &dbg,
        (char **)glpath,
        &path_source,
        error);
    if (res == DW_DLV_ERROR) {
        /* We are not returning dbg, so we must do:
            dwarf_dealloc_error(dbg,*error);
            here to free the error details. */
```

```
dwarf_dealloc_error(dbg,*error);
   *error = 0;
   return res;
}
if (res == DW_DLV_NO_ENTRY) {
   return res;
}
printf("The file we actually opened is %s\n",
   true_pathbuf);
/* Call libdwarf functions here */
dwarf_finish(dbg);
return res;
```

9.42 Using dwarf_attrlist()

Example showing dwarf_attrlist()

Parameters

somedie	Pass in any valid relevant DIE pointer.
error	An error pointer we can use.

Returns

Return DW DLV OK (etc).

```
int example1(Dwarf_Die somedie, Dwarf_Error *error)
    Dwarf_Debug dbg = 0;
    Dwarf_Signed atcount;
   Dwarf_Attribute *atlist;
Dwarf_Signed i = 0;
    int errv;
    errv = dwarf_attrlist(somedie, &atlist,&atcount, error);
    if (errv != DW_DLV_OK) {
        return errv;
    for (i = 0; i < atcount; ++i) {</pre>
        Dwarf_Half attrnum = 0;
        const char *attrname = 0;
        /* use atlist[i], likely calling
    libdwarf functions and likely
            returning DW_DLV_ERROR if
            what you call gets DW_DLV_ERROR */
        errv = dwarf_whatattr(atlist[i], &attrnum, error);
        if (errv != DW_DLV_OK) {
             /\star Something really bad happened. \star/
             return errv;
        dwarf_get_AT_name(attrnum, &attrname);
        printf("Attribute[%ld], value %u name %s\n",
            (long int)i,attrnum,attrname);
        dwarf_dealloc_attribute(atlist[i]);
        atlist[i] = 0;
    dwarf_dealloc(dbg, atlist, DW_DLA_LIST);
    return DW_DLV_OK;
```

9.43 Attaching a tied dbg

Example attaching base dbg to a split-DWARF object.

See DWARF5 Appendix F on Split-DWARF.

By libdwarf convention, open the split Dwarf_Debug using a dwarf_init call. Then open the executable as the tied object. Then call dwarf_set_tied_dbg() so the library can look for relevant data in the tied-dbg (the executable).

With split dwarf your libdwarf calls after the the initial open are done against the split Dwarf_Dbg and libdwarf automatically looks in the tied dbg when and as appropriate. the tied_dbg can be detached too, see example3 link, though you must call dwarf_finish() on the detached dw_tied_dbg, the library will not do that for you.

Parameters

split_dbg	
tied_dbg	
error	

Returns

Returns DW_DLV_OK or DW_DLV_ERROR or DW_DLV_NO_ENTRY to the caller.

9.44 Detaching a tied dbg

Example detaching a tied (executable) dbg.

See DWARF5 Appendix F on Split-DWARF.

With split dwarf your libdwarf calls after than the initial open are done against the split Dwarf_Dbg and libdwarf automatically looks in the open tied dbg when and as appropriate. the tied-dbg can be detached too, see example3 link, though you must call dwarf_finish() on the detached dw_tied_dbg, the library will not do that for you.

```
*/
int example3(Dwarf_Debug split_dbg,Dwarf_Error *error)
{
   int res = 0;
   res = dwarf_set_tied_dbg(split_dbg,NULL,error);
   if (res != DW_DLV_OK) {
        /* Something went wrong*/
        return res;
   }
   return res;
```

9.45 Examining Section Group data

Example accessing Section Group data.

With split dwarf your libdwarf calls after than the initial open are done against the base Dwarf_Dbg and libdwarf automatically looks in the open tied dbg when and as appropriate. the tied-dbg can be detached too, see example3 link, though you must call dwarf_finish() on the detached dw_tied_dbg, the library will not do that for you.

Section groups apply to Elf COMDAT groups too.

```
void examplesecgroup(Dwarf_Debug dbg)
    int res = 0;
    Dwarf_Unsigned section_count = 0;
    Dwarf_Unsigned group_count;
    Dwarf_Unsigned selected_group = 0;
    Dwarf_Unsigned group_map_entry_count = 0;
    Dwarf_Unsigned *sec_nums = 0;
    Dwarf_Unsigned *group_nums = 0;
   const char ** sec_names = 0;
Dwarf_Error error = 0;
                    error = 0;
   Dwarf_Unsigned i = 0;
    res = dwarf_sec_group_sizes(dbg,&section_count,
        &group_count, &selected_group, &group_map_entry_count,
    if (res != DW_DLV_OK) {
        /\star Something is badly wrong \star/
        return;
    /* In an object without split-dwarf sections
        or COMDAT sections we now have
        selected_group == 1. */
    sec_nums = calloc(group_map_entry_count, sizeof(Dwarf_Unsigned));
    if (!sec_nums) {
        /* FAIL. out of memory */
        return;
    group_nums = calloc(group_map_entry_count, sizeof(Dwarf_Unsigned));
    if (!group_nums) {
        free (group_nums);
        /* FAIL. out of memory */
        return;
    sec_names = calloc(group_map_entry_count, sizeof(char*));
    if (!sec_names) {
        free (group_nums);
        free (sec_nums);
        /* FAIL. out of memory */
    }
    res = dwarf_sec_group_map(dbg,group_map_entry_count,
        group_nums, sec_nums, sec_names, &error);
    if (res != DW_DLV_OK) {
        /* FAIL. Something badly wrong. */
        free(sec_names);
        free(group_nums);
        free (sec_nums);
    for ( i = 0; i < group_map_entry_count; ++i) {</pre>
        /* Now do something with
            group_nums[i],sec_nums[i],sec_names[i] */
    /* The strings are in Elf data.
       Do not free() the strings themselves.*/
    free (sec names);
    free (group_nums);
    free (sec_nums);
```

9.46 Using dwarf_siblingof_c()

Example accessing a DIE sibling.

Access to each DIE on a sibling list. This is the preferred form as it is slightly more efficient than dwarf_siblingof_b().

```
*/
int example4c(Dwarf_Die in_die,
    Dwarf_Error *error)
{
    Dwarf_Die return_sib = 0;
```

```
int res = 0;

/* in_die must be a valid Dwarf_Die */
res = dwarf_siblingof_c(in_die,&return_sib, error);
if (res == DW_DLV_OK) {
    /* Use return_sib here. */
    dwarf_dealloc_die(return_sib);
    /* return_sib is no longer usable for anything, we
        ensure we do not use it accidentally with: */
    return_sib = 0;
    return res;
}
return res;
}
```

9.47 Using dwarf siblingof b()

Example accessing a DIE sibling.

Access to each DIE on a sibling list This is the older form, required after dwarf next cu header d().

Better to use dwarf_next_cu_header_e() and dwarf_siblingof_c().

9.48 Using dwarf_child()

Example accessing a DIE child.

If the DIE has children (for example inner scopes in a function or members of a struct) this retrieves the DIE which appears first. The child itself may have its own sibling chain.

9.49 using dwarf validate die sibling

Example of a DIE tree validation.

Here we show how one uses dwarf_validate_die_sibling(). Dwarfdump uses this function as a part of its validation of DIF trees.

It is not something you need to use. But one must use it in a specific pattern for it to work properly.

dwarf_validate_die_sibling() depends on data set by dwarf_child() preceeding dwarf_siblingof_b() . dwarf_child() records a little bit of information invisibly in the Dwarf Debug data.

```
int example_sibvalid(Dwarf_Debug dbg,
    Dwarf_Die in_die,
    Dwarf Error*error)
               cres = DW_DLV_OK;
              sibres = DW_DLV_OK;
    Dwarf_Die die = 0;
    Dwarf_Die sibdie = 0;
    Dwarf Die child = 0:
   Dwarf_Bool is_info = dwarf_get_die_infotypes_flag(die);
    die = in_die;
    for ( ; die ; die = sibdie) {
        int vres = 0;
       Dwarf_Unsigned offset = 0;
        /* Maybe print something you extract from the DIE */
              dwarf_child(die,&child,error);
        if (cres == DW_DLV_ERROR) {
            if (die != in_die) {
               dwarf_dealloc_die(die);
           printf("dwarf_child ERROR\n");
           return DW_DLV_ERROR;
        if (cres == DW_DLV_OK) {
            int lres = 0;
           child = 0;
            lres = example_sibvalid(dbg,child,error);
            if (lres == DW_DLV_ERROR) {
                if (die != in_die) {
                    dwarf_dealloc_die(die);
                dwarf_dealloc_die(child);
                printf("example_sibvalid ERROR\n");
        sibdie = 0;
       sibres = dwarf_siblingof_b(dbg,die,is_info,
            &sibdie,error);
        if (sibres == DW_DLV_ERROR) {
            if (die != in_die) {
                dwarf_dealloc_die(die);
            if (child) {
               dwarf_dealloc_die(child);
           printf("dwarf_siblingof_b ERROR\n");
            return DW_DLV_ERROR;
        if (sibres == DW DLV NO ENTRY) {
            if (die != in_die) {
               dwarf_dealloc_die(die);
            if (child) {
                dwarf_dealloc_die(child);
            return DW DLV OK;
        vres = dwarf_validate_die_sibling(sibdie,&offset);
        if (vres == DW_DLV_ERROR) {
            if (die != in_die) {
                dwarf_dealloc_die(die);
            if (child) {
                dwarf_dealloc_die(child);
```

```
dwarf_dealloc_die(sibdie);
    printf("Invalid sibling DIE\n");
    return DW_DLV_ERROR;
}
/* loop again */
    if (die != in_die) {
        dwarf_dealloc_die(die);
    }
    die = 0;
}
return DW_DLV_OK;
```

9.50 Example walking CUs(e)

Example examining CUs looking for specific items(e).

Loops through as many CUs as needed, stops and returns once a CU provides the desired data.

Assumes certain functions you write to remember the aspect of CUs that matter to you so once found in a cumy_needed_data_exists() or some other function of yours can identify the correct record.

Depending on your goals in examining the DIE tree it may be helpful to maintain a DIE stack of active DIEs, pushing and popping as you make your way throught the DIE levels.

We assume that on a serious error we will give up (for simplicity here).

We assume the caller to examplecuhdre() will know what to retrieve (when we return DW_DLV_OK from example-cuhdree() and that myrecords points to a record with all the data needed by my_needed_data_exists() and recorded by myrecord_data_for_die().

```
struct myrecords struct *myrecords;
void myrecord_data_for_die(struct myrecords_struct *myrecords_data,
    Dwarf_Die d)
    /\star do somthing \star/
    /* avoid compiler warnings */
    (void) myrecords_data;
    (void)d;
int my_needed_data_exists(struct myrecords_struct *myrecords_data)
    /\star do something \star/
    /\star avoid compiler warnings \star/
    (void) myrecords data;
    return DW_DLV_OK;
/\star Loop on DIE tree. \star/
static void
record_die_and_siblings_e(Dwarf_Debug dbg, Dwarf_Die in_die,
    int is_info, int in_level,
    struct myrecords_struct *myrec,
    Dwarf_Error *error)
              res = DW_DLV_OK;
    Dwarf_Die cur_die=in_die;
    Dwarf_Die child = 0;
    myrecord_data_for_die (myrec,in_die);
    /\star~ Loop on a list of siblings \star/
    for (;;) {
        Dwarf Die sib die = 0;
        /* Depending on your goals, the in_level,
            and the DW_TAG of cur_die, you may want
            to skip the dwarf_child call. We descend
            the DWARF-standard way of depth-first.
        res = dwarf_child(cur_die,&child,error);
        if (res == DW_DLV_ERROR) {
            printf("Error in dwarf_child , level %d \n",in_level);
```

```
exit(EXIT_FAILURE);
         if (res == DW_DLV_OK) {
             record_die_and_siblings_e(dbg,child,is_info,
             in_level+1, myrec, error);
/* No longer need 'child' die. */
             dwarf_dealloc(dbg,child,DW_DLA_DIE);
             child = 0;
         /* res == DW_DLV_NO_ENTRY or DW_DLV_OK */
        res = dwarf_siblingof_c(cur_die,&sib_die,error);
if (res == DW_DLV_ERROR) {
             exit(EXIT_FAILURE);
         if (res == DW_DLV_NO_ENTRY) {
             /* Done at this level. */
             break:
         /* res == DW_DLV_OK */
         if (cur_die != in_die) {
             dwarf_dealloc(dbg,cur_die,DW_DLA_DIE);
             cur_die = 0;
        cur die = sib die;
        myrecord_data_for_die(myrec,sib_die);
    return;
}
/\star Assuming records properly initialized for your use. \star/ int examplecuhdre(Dwarf_Debug dbg,
    struct myrecords_struct *myrec,
    Dwarf_Error *error)
    Dwarf_Unsigned abbrev_offset = 0;
                  address_size = 0;
    Dwarf_Half
    Dwarf_Half
                     version_stamp = 0;
    Dwarf_Half
                    offset_size = 0;
    Dwarf_Half
                     extension_size = 0;
    Dwarf_Sig8
                     signature;
    Dwarf_Unsigned typeoffset = 0;
    Dwarf_Unsigned next_cu_header = 0;
                  header_cu_type = 0;
is_info = TRUE;
    Dwarf Half
    Dwarf_Bool
                    res = 0;
    while(!my_needed_data_exists(myrec)) {
        Dwarf_Die cu_die = 0;
        Dwarf_Unsigned cu_header_length = 0;
        memset(&signature,0, sizeof(signature));
        res = dwarf_next_cu_header_e(dbg,is_info,
             &cu_die,
             &cu_header_length,
             &version_stamp, &abbrev_offset,
&address_size, &offset_size,
&extension_size,&signature,
             &typeoffset, &next_cu_header,
             &header_cu_type,error);
         if (res == DW_DLV_ERROR) {
             return res;
         if (res == DW_DLV_NO_ENTRY) {
             if (is_info == TRUE) {
                 /\star Done with .debug_info, now check for
                      .debug_types. */
                 is_info = FALSE;
                 continue:
             /* No more CUs to read! Never found
                 what we were looking for in either
                  .debug_info or .debug_types. \star/
             return res;
         /* We have the cu_die .
             New in v0.9.0 because the connection of
             the CU_DIE to the CU header is clear
             in the argument list.
         record_die_and_siblings_e(dbg,cu_die,is_info,
        0, myrec,error);
dwarf_dealloc_die(cu_die);
    /* Found what we looked for */
    return DW_DLV_OK;
}
```

9.51 Example walking CUs(d)

Example accessing all CUs looking for specific items(d).

Loops through as many CUs as needed, stops and returns once a CU provides the desired data.

Assumes certain functions you write to remember the aspect of CUs that matter to you so once found in a cu my_
needed_data_exists() or some other function of yours can identify the correct record. (Possibly a DIE global offset.
Remember to note if each DIE has is_info TRUE or FALSE so libdwarf can find the DIE properly.)

Depending on your goals in examining the DIE tree it may be helpful to maintain a DIE stack of active DIEs, pushing and popping as you make your way throught the DIE levels.

We assume that on a serious error we will give up (for simplicity here).

We assume the caller to examplecuhdrd() will know what to retrieve (when we return DW_DLV_OK from example-cuhdrd() and that myrecords points to a record with all the data needed by my_needed_data_exists() and recorded by myrecord_data_for_die().

```
struct myrecords struct *myrecords;
void myrecord_data_for_die(struct myrecords_struct *myrecords,
int my_needed_data_exists(struct myrecords_struct *myrecords);
/* Loop on DIE tree. */
static void
record_die_and_siblingsd(Dwarf_Debug dbg, Dwarf_Die in_die,
    int is_info, int in_level,
    struct myrecords_struct *myrec,
    Dwarf_Error *error)
              res = DW DLV OK:
    Dwarf_Die cur_die=in_die;
    Dwarf_Die child = 0;
    myrecord_data_for_die(myrec,in_die);
        Loop on a list of siblings */
    for (::) {
        Dwarf_Die sib_die = 0;
        /* Depending on your goals, the in_level,
            and the DW_TAG of cur_die, you may want to skip the dwarf_child call. */
        res = dwarf_child(cur_die, &child, error);
        if (res == DW_DLV_ERROR) {
            printf("Error in dwarf_child , level %d \n",in_level);
            exit(EXIT_FAILURE);
        if (res == DW DLV OK) {
            record_die_and_siblingsd(dbg,child,is_info,
                in_level+1, myrec, error);
            /* No longer need 'child' die. */
            dwarf_dealloc(dbg,child,DW_DLA_DIE);
            child = 0;
        /* res == DW_DLV_NO_ENTRY or DW_DLV_OK */
        res = dwarf_siblingof_b (dbg, cur_die, is_info, &sib_die, error);
        if (res == DW_DLV_ERROR) {
            exit(EXIT_FAILURE);
        if (res == DW_DLV_NO_ENTRY) {
            /* Done at this level. */
            break;
        /* res == DW_DLV_OK */
        if (cur_die != in_die) {
   dwarf_dealloc(dbg,cur_die,DW_DLA_DIE);
            cur_die = 0;
        cur_die = sib_die;
        myrecord_data_for_die(myrec, sib_die);
    return;
/* Assuming records properly initialized for your use. */
int examplecuhdrd (Dwarf_Debug dbg,
```

```
struct myrecords_struct *myrec,
Dwarf_Error *error)
Dwarf_Unsigned abbrev_offset = 0;
              address_size = 0;
Dwarf_Half
Dwarf_Half
                version_stamp = 0;
               offset_size = 0;
Dwarf_Half
               extension_size = 0;
Dwarf_Half
Dwarf_Sig8
                signature;
Dwarf_Unsigned typeoffset = 0;
Dwarf_Unsigned next_cu_header = 0;
              header_cu_type = 0;
is_info = TRUE;
Dwarf Half
Dwarf Bool
               res = 0;
while(!my_needed_data_exists(myrec)) {
    Dwarf_Die no_die = 0;
    Dwarf_Die cu_die = 0;
    Dwarf_Unsigned cu_header_length = 0;
    memset(&signature,0, sizeof(signature));
    res = dwarf_next_cu_header_d(dbg,is_info,&cu_header_length,
         &version_stamp, &abbrev_offset,
         &address size, &offset size,
         &extension_size, & signature,
         &typeoffset, &next_cu_header,
         &header_cu_type,error);
    if (res == DW_DLV_ERROR) {
         return res;
    if (res == DW_DLV_NO_ENTRY) {
   if (is_info == TRUE) {
             /* Done with .debug_info, now check for
                  .debug_types. */
             is_info = FALSE;
             continue;
         /* No more CUs to read! Never found
             what we were looking for in either
             .debug_info or .debug_types. */
         return res;
    /* The CU will have a single sibling, a cu_die. It is essential to call this right after
         a call to dwarf_next_cu_header_d() because
         there is no explicit connection provided to
         dwarf_siblingof_b(), which returns a DIE
         from whatever CU was last accessed by
        dwarf_next_cu_header_d()!
The lack of explicit connection was a
        design mistake in the API (made in 1992). */
    res = dwarf_siblingof_b(dbg,no_die,is_info,
    &cu_die,error);
if (res == DW_DLV_ERROR) {
        return res;
    if (res == DW_DLV_NO_ENTRY) {
         /* Impossible */
         exit(EXIT_FAILURE);
    record_die_and_siblingsd(dbg,cu_die,is_info,
        0, myrec, error);
    dwarf_dealloc_die(cu_die);
/\star Found what we looked for \star/
return DW_DLV_OK;
```

9.52 Using dwarf_offdie_b()

```
Example accessing a DIE by its offset.
```

```
*/
int example6(Dwarf_Debug dbg,Dwarf_Off die_offset,
    Dwarf_Bool is_info,
    Dwarf_Error *error)
{
    Dwarf_Die return_die = 0;
    int res = 0;
    res = dwarf_offdie_b(dbg,die_offset,is_info,&return_die, error);
```

9.53 Using dwarf_offset_given_die()

Example finding the section offset of a DIE.

Here finding the offset of a CU-DIE.

```
int example7(Dwarf_Debug dbg, Dwarf_Die in_die,
                is_info,
    Dwarf Bool
    Dwarf_Error * error)
    int res = 0;
   Dwarf_Off cudieoff = 0;
   Dwarf_Die cudie = 0;
    res = dwarf_CU_dieoffset_given_die(in_die,&cudieoff,error);
    if (res != DW_DLV_OK) {
       /* FAIL */
       return res;
    res = dwarf_offdie_b(dbg,cudieoff,is_info,&cudie,error);
    if (res != DW_DLV_OK) {
       /* FAIL */
       return res;
    /* do something with cu_die */
    dwarf_dealloc_die(cudie);
    return res;
```

9.54 Using dwarf_attrlist()

Example Calling dwarf_attrlist()

```
*/
int example8(Dwarf_Debug dbg, Dwarf_Die somedie, Dwarf_Error *error)
{
    Dwarf_Signed atcount = 0;
    Dwarf_Attribute *atlist = 0;
    int errv = 0;
    Dwarf_Signed i = 0;

    errv = dwarf_attrlist(somedie, &atlist,&atcount, error);
    if (errv != DW_DLV_OK) {
        return errv;
    }
    for (i = 0; i < atcount; ++i) {
        /* use atlist[i] */
        dwarf_dealloc_attribute(atlist[i]);
        atlist[i] = 0;
    }
    dwarf_dealloc(dbg, atlist, DW_DLA_LIST);
    return DW_DLV_OK;
}</pre>
```

9.55 Using dwarf_offset_list()

Example using dwarf offset list.

An example calling dwarf offset list

Parameters

dbg	the Dwarf_Debug of interest
dieoffset	The section offset of a Dwarf_Die
is_info	Pass in TRUE if the dieoffset is for the .debug_info section, else pass in FALSE meaning the dieoffset is for the DWARF4 .debug_types section.
error	The usual error detail return.

Returns

9.56 Documenting Form_Block

Example documents Form_Block content.

Used with certain location information functions, a frame expression function, expanded frame instructions, and $DW_FORM_block <> functions$ and more.

See also

```
dwarf_formblock
    Dwarf_Block_s

struct Dwarf_Block_s fields {

Dwarf_Unsigned bl_len;
    Length of block bl_data points at

Dwarf_Ptr bl_data;
    Uninterpreted data bytes

Dwarf_Small bl_from_loclist;
    See libdwarf.h DW_LKIND, defaults to
    DW_LKIND_expression and except in certain location expressions the field is ignored.

Dwarf_Unsigned bl_section_offset;
    Section offset of what bl_data points to
```

9.57 Using dwarf_discr_list()

Example using dwarf_discr_list, dwarf_formblock.

An example calling dwarf_get_form_class, dwarf_discr_list, and dwarf_formblock. and the dwarf_deallocs applicable.

See also

```
dwarf_discr_list
dwarf_get_form_class
dwarf_formblock
```

Parameters

dw_dbg	The applicable Dwarf_Debug
dw_die	The applicable Dwarf_Die
dw_attr	The applicable Dwarf_Attribute
dw_attrnum,The	attribute number passed in to shorten this example a bit.
dw_isunsigned,The	attribute number passed in to shorten this example a bit.
dw_theform,The	form number passed in to shorten this example a bit.
dw_error	The usual error pointer.

Returns

Returns DW_DLV_OK etc

```
int example_discr_list(Dwarf_Debug dbg,
    Dwarf_Die die,
    Dwarf_Attribute attr,
    Dwarf_Half attrnum,
    Dwarf_Bool isunsigned,
    Dwarf_Half theform,
    Dwarf_Error *error)
    /\star The example here assumes that
         attribute attr is a DW_AT_discr_list.
         isunsigned should be set from the signedness
         of the parent of 'die' per DWARF rules for
    DW_AT_discr_list. */
enum Dwarf_Form_Class fc = DW_FORM_CLASS_UNKNOWN;
    Dwarf_Half version = 0;
    Dwarf_Half offset_size = 0;
int wres = 0;
    wres = dwarf_get_version_of_die(die,&version,&offset_size);
if (wres != DW_DLV_OK) {
         /* FAIL */
         return wres;
    fc = dwarf_get_form_class(version, attrnum, offset_size, theform);
    if (fc == DW_FORM_CLASS_BLOCK) {
  int fres = 0;
         Dwarf_Block *tempb = 0;
fres = dwarf_formblock(attr, &tempb, error);
         if (fres == DW_DLV_OK) {
              Dwarf_Dsc_Head h = 0;
Dwarf_Unsigned u = 0;
              Dwarf_Unsigned arraycount = 0;
              int sres = 0;
              sres = dwarf_discr_list(dbg,
                   (Dwarf_Small *)tempb->bl_data,
                  tempb->bl_len,
                   &h, &arraycount, error);
              if (sres == DW_DLV_NO_ENTRY) {
    /* Nothing here. */
```

```
dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
            return sres;
        if (sres == DW_DLV_ERROR) {
            /* FAIL . */
dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
            return sres ;
        for (u = 0; u < arraycount; u++) {
            int u2res = 0;
            Dwarf_Half dtype = 0;
            Dwarf_Signed dlow = 0;
            Dwarf_Signed dhigh = 0;
            Dwarf_Unsigned ulow = 0;
            Dwarf_Unsigned uhigh = 0;
            if (isunsigned) {
    u2res = dwarf_discr_entry_u(h,u,
                    &dtype, &ulow, &uhigh, error);
                u2res = dwarf_discr_entry_s(h,u,
                    &dtype, &dlow, &dhigh, error);
            if (u2res == DW_DLV_ERROR) {
                 /* Something wrong */
                dwarf_dealloc(dbg,h,DW_DLA_DSC_HEAD);
                dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
                return u2res ;
            if (u2res == DW_DLV_NO_ENTRY) {
                /* Impossible. u < arraycount. */</pre>
                dwarf_dealloc(dbg,h,DW_DLA_DSC_HEAD);
                dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
                return u2res;
            /* Do something with dtype, and whichever
                of ulow, uhigh, dlow, dhigh got set.
                Probably save the values somewhere.
                Simple casting of dlow to ulow (or vice versa)
                will not get the right value due to the nature
                of LEB values. Similarly for uhigh, dhigh.
                One must use the right call. */
        dwarf_dealloc(dbg,h,DW_DLA_DSC_HEAD);
        dwarf_dealloc(dbg, tempb, DW_DLA_BLOCK);
return DW_DLV_OK;
```

9.58 Location/expression access

Example using DWARF2-5 loclists and loc-expressions.

Valid for DWARF2 and later DWARF.

This example simply assumes the attribute has a form which relates to location lists or location expressions. Use dwarf_get_form_class() to determine if this attribute fits. Use dwarf_get_version_of_die() to help get the data you need.

See also

```
dwarf_get_form_class
    dwarf_get_version_of_die
    Reading a location expression

*/
int example_loclistcv5(Dwarf_Attribute someattr,
    Dwarf_Error *error)
{
    Dwarf_Unsigned lcount = 0;
    Dwarf_Loc_Head_c loclist_head = 0;
    int lres = 0;
    lres = dwarf_get_loclist_c(someattr,&loclist_head,
```

```
&lcount, error);
if (lres == DW_DLV_OK)
    Dwarf_Unsigned i = 0;
    /\star Before any return remember to call
    dwarf_loc_head_c_dealloc(loclist_head); */
for (i = 0; i < lcount; ++i) {</pre>
         Dwarf_Small loclist_lkind = 0;
         Dwarf_Small lle_value = 0;
         Dwarf_Unsigned rawval1 = 0;
Dwarf_Unsigned rawval2 = 0;
         Dwarf_Bool debug_addr_unavailable = FALSE;
         Dwarf_Addr lopc = 0;
Dwarf_Addr hipc = 0;
         Dwarf_Unsigned loclist_expr_op_count = 0;
         Dwarf_Locdesc_c locdesc_entry = 0;
Dwarf_Unsigned expression_offset = 0;
Dwarf_Unsigned locdesc_offset = 0;
         lres = dwarf_get_locdesc_entry_d(loclist_head,
              &lle_value,
              &rawval1,&rawval2,
              &debug_addr_unavailable,
              &lopc, &hipc,
              &loclist_expr_op_count,
              &locdesc_entry,
              &loclist_lkind,
              &expression_offset,
              &locdesc_offset,
         error);
if (lres == DW_DLV_OK) {
    Dwarf_Unsigned j = 0;
              int opres = 0;
              Dwarf_Small op = 0;
              for (j = 0; j < loclist_expr_op_count; ++j) {</pre>
                   Dwarf_Unsigned opd1 = 0;
                   Dwarf_Unsigned opd2 = 0;
                   Dwarf_Unsigned opd3 = 0;
                  Dwarf_Unsigned offsetforbranch = 0;
                   opres = dwarf_get_location_op_value_c(
                       locdesc_entry, j,&op, &opd1,&opd2,&opd3,
                       &offsetforbranch,
                       error);
                   if (opres == DW_DLV_OK) {
                        /* Do something with the operators.
                            Usually you want to use opd1,2,3 as appropriate. Calculations
                            involving base addresses etc
                            have already been incorporated
                            in opd1,2,3.
                   } else {
                       dwarf_dealloc_loc_head_c(loclist_head);
                       /*Something is wrong. */
                       return opres;
             }
         } else {
             /* Something is wrong. Do something. */
              dwarf_dealloc_loc_head_c(loclist_head);
              return lres;
         }
    }
    Always call dwarf_loc_head_c_dealloc()
    to free all the memory associated with loclist_head. */
dwarf_dealloc_loc_head_c(loclist_head);
loclist_head = 0;
return lres;
```

9.59 Reading a location expression

Example getting details of a location expression.

See also

Location/expression access

```
int example_locexprc(Dwarf_Debug dbg,Dwarf_Ptr expr_bytes,
    Dwarf_Unsigned expr_len,
    Dwarf_Half addr_size,
    Dwarf_Half offset_size,
    Dwarf_Half version,
    Dwarf_Error*error)
    Dwarf_Loc_Head_c head = 0;
    Dwarf_Locdesc_c locentry = 0;
                    res2 = 0;
    Dwarf_Unsigned rawlopc = 0;
    Dwarf_Unsigned rawhipc = 0;
    Dwarf_Bool debug_addr_unavail = FALSE;
Dwarf_Unsigned lopc = 0;
Dwarf_Unsigned hipc = 0;
    Dwarf_Unsigned ulistlen = 0;
    Dwarf_Unsigned ulocentry_count = 0;
    Dwarf_Unsigned section_offset = 0;
    Dwarf_Unsigned locdesc_offset = 0;
    Dwarf_Small lle_value = 0;
Dwarf_Small loclist_source = 0;
    Dwarf_Unsigned i = 0;
    res2 = dwarf_loclist_from_expr_c(dbg,
        expr_bytes,expr_len,
        addr size,
        offset size.
        version,
        &head,
        &ulistlen,
        error);
    if (res2 != DW_DLV_OK) {
        return res2;
    /\star These are a location expression, not loclist.
        So we just need the Oth entry. *
    res2 = dwarf_get_locdesc_entry_d(head,
        0, /\star Data from 0th because it is a loc expr,
            there is no list \star/
        &lle_value,
        &rawlopc, &rawhipc, &debug_addr_unavail, &lopc, &hipc,
        &ulocentry_count, &locentry,
        &loclist_source, &section_offset, &locdesc_offset,
    error);
if (res2 == DW_DLV_ERROR) {
        dwarf_dealloc_loc_head_c(head);
        return res2;
    } else if (res2 == DW_DLV_NO_ENTRY) {
        dwarf_dealloc_loc_head_c(head);
        return res2;
    /* ASSERT: ulistlen == 1 */
    for (i = 0; i < ulocentry_count;++i) {</pre>
        Dwarf_Small op = 0;
        Dwarf_Unsigned opd1 = 0;
        Dwarf_Unsigned opd2 = 0;
Dwarf_Unsigned opd3 = 0;
        Dwarf_Unsigned offsetforbranch = 0;
        res2 = dwarf_get_location_op_value_c(locentry,
             i, &op, &opd1, &opd2, &opd3,
             &offsetforbranch,
             error);
         /\star Do something with the expression operator and operands \star/
        if (res2 != DW_DLV_OK) {
   dwarf_dealloc_loc_head_c(head);
             return res2;
    dwarf_dealloc_loc_head_c(head);
return DW_DLV_OK;
```

9.60 Using dwarf_srclines_b()

Example using dwarf_srclines_b()

An example calling dwarf_srclines_b

dwarf_srclines_dealloc_b dwarf_srclines_from_linecontext dwarf_srclines_files_indexes dwarf_srclines_files_data_b dwarf_srclines_two_level_from_linecontext

Parameters

path	Path to an object we wish to open.
error	Allows passing back error details to the caller.

Returns

Return DW_DLV_OK etc.

```
int examplec(Dwarf_Die cu_die,Dwarf_Error *error)
    /* EXAMPLE: DWARF2-DWARF5 access. */
    Dwarf_Line    *linebuf = 0;
Dwarf_Signed    linecount = 0;
    Dwarf_Line_Context line_context = 0;
    Dwarf_Small table_count = 0;
    Dwarf_Unsigned lineversion = 0;
    int sres = 0;
    /* ... */  
/* we use 'return' here to signify we can do nothing more
        at this point in the code. */
    sres = dwarf_srclines_b(cu_die, &lineversion,
        &table_count,&line_context,error);
    if (sres != DW_DLV_OK) {
   /* Handle the DW_DLV_NO_ENTRY or DW_DLV_ERROR
            No memory was allocated so there nothing
            to dealloc here. */
        return sres;
    if (table_count == 0) {
        /\star A line table with no actual lines. \star/
        /*...do something, see dwarf_srclines_files_count()
            etc below. */
        dwarf_srclines_dealloc_b(line_context);
        /* All the memory is released, the line_context
    and linebuf zeroed now
            as a reminder they are stale. \star/
        linebuf = 0;
        line_context = 0;
    } else if (table_count == 1) {
        Dwarf_Signed i = 0;
        Dwarf_Signed baseindex = 0;
        Dwarf_Signed file_count = 0;
        Dwarf_Signed endindex = 0;
        /* Standard dwarf 2,3,4, or 5 line table */
        /* Do something. */
        /\star First let us index through all the files listed
        in the line table header. */
sres = dwarf_srclines_files_indexes(line_context,
            &baseindex, &file_count, &endindex, error);
        if (sres != DW_DLV_OK) {
            /* Something badly wrong! */
            return sres;
        /* Works for DWARF2,3,4 (one-based index)
            and DWARF5 (zero-based index) */
        for (i = baseindex; i < endindex; i++)</pre>
            Dwarf_Unsigned dirindex = 0;
            Dwarf_Unsigned modtime = 0;
            Dwarf_Unsigned flength = 0;
            Dwarf_Form_Data16 *md5data = 0;
            int vres = 0;
            const char *name = 0;
            vres = dwarf_srclines_files_data_b(line_context,i,
                &name,&dirindex, &modtime,&flength,
                &md5data.error);
            if (vres != DW_DLV_OK) {
                 /* something very wrong. */
```

```
return vres;
         /* do something */
    /* For this case where we have a line table we will likely
        wish to get the line details: */
    sres = dwarf_srclines_from_linecontext(line_context,
        &linebuf, &linecount,
        error);
    if (sres != DW_DLV_OK) {
        /* Error. Clean up the context information. */
dwarf_srclines_dealloc_b(line_context);
        return sres;
    /\star The lines are normal line table lines. \star/
    for (i = 0; i < linecount; ++i) {
    /* use linebuf[i] */</pre>
    dwarf_srclines_dealloc_b(line_context);
    /* All the memory is released, the line_context
        and linebuf zeroed now as a reminder they are stale \star/
    linebuf = 0;
    line_context = 0;
    linecount = 0;
} else {
    Dwarf_Signed i = 0;
    /* ASSERT: table_count == 2,
         Experimental two-level line table. Version 0xf006
        We do not define the meaning of this non-standard
        set of tables here. */
    /* For 'something C' (two-level line tables)
         one codes something like this
        Note that we do not define the meaning or
        use of two-level line
    tables as these are experimental, not standard DWARF. */
sres = dwarf_srclines_two_level_from_linecontext(line_context,
        &linebuf, &linecount,
         &linebuf_actuals, &linecount_actuals,
         error);
    if (sres == DW DLV OK) {
        for (i = 0; i < linecount; ++i) {
    /* use linebuf[i], these are the 'logicals'
                 entries. */
         for (i = 0; i < linecount_actuals; ++i) {</pre>
             /\star\  use linebuf_actuals[i], these are the
                 actuals entries */
        dwarf_srclines_dealloc_b(line_context);
         line_context = 0;
         linebuf = 0;
         linecount = 0;
         linebuf_actuals = 0;
         linecount_actuals = 0;
    } else if (sres == DW_DLV_NO_ENTRY) {
         /* This should be impossible, but do something.
         /* Then Free the line_context */
         dwarf_srclines_dealloc_b(line_context);
         line context = 0;
         \lim_{t\to 0} \frac{1}{t}
         linecount = 0;
         linebuf_actuals = 0;
         linecount_actuals = 0;
        /\star~\mbox{ERROR,} show the error or something.
            Free the line_context. */
         dwarf_srclines_dealloc_b(line_context);
         line_context = 0;
         linebuf = 0;
         linecount = 0;
         linebuf_actuals = 0;
         linecount_actuals = 0;
return DW_DLV_OK;
```

9.61 Using dwarf_srclines_b() and linecontext

Example two using dwarf_srclines_b(), dwarf_linesrc().

See also

```
dwarf srclines b
      dwarf_srclines_from_linecontext
      dwarf srclines dealloc b
int exampled(Dwarf_Debug dbg,Dwarf_Die somedie,Dwarf_Error *error)
    Dwarf_Signed
                        count = 0;
    Dwarf_Line_Context context = 0;
                      *linebuf = 0;
    Dwarf_Line
    Dwarf Signed
                        i = 0;
                       *line;
    Dwarf Line
                      table_count =0;
version = 0;
sres = 0;
    Dwarf_Small
    Dwarf_Unsigned
    sres = dwarf_srclines_b(somedie,
        &version, &table_count, &context, error);
    if (sres != DW_DLV_OK) {
        return sres;
    sres = dwarf_srclines_from_linecontext(context,
        &linebuf, &count, error);
    if (sres != DW_DLV_OK) {
        dwarf_srclines_dealloc_b(context);
        return sres;
    line = linebuf;
    for (i = 0; i < count; ++line,++i) {
    char * filename = 0;</pre>
         int lres = 0;
        Dwarf_Line dline = linebuf[i];
        lres = dwarf_linesrc(dline,&filename,error);
if (lres != DW_DLV_OK) {
             dwarf_srclines_dealloc_b(context);
             return lres;
         /* use filename */
        dwarf_dealloc(dbg, filename, DW_DLA_STRING);
    dwarf_srclines_dealloc_b(context);
return DW_DLV_OK;
```

9.62 Using dwarf srcfiles()

Example getting source file names given a DIE.

```
int examplee(Dwarf_Debug dbg,Dwarf_Die somedie,Dwarf_Error *error)
    /* It is an annoying historical mistake in libdwarf
       that the count is a signed value. */
                      count = 0;
**srcfiles = 0;
    Dwarf_Signed
    char
    Dwarf_Signed
                      i = 0;
                        res = 0;
    int
    Dwarf_Line_Context line_context = 0;
    Dwarf_Small
                      table_count = 0;
    Dwarf_Unsigned
                       lineversion = 0;
    res = dwarf_srclines_b(somedie,&lineversion,
     &table_count,&line_context,error);
    if (res != DW_DLV_OK) {
        /* dwarf_finish() will dealloc srcfiles, not doing
        return res;
    res = dwarf_srcfiles(somedie, &srcfiles,&count,error);
    if (res != DW_DLV_OK) {
        dwarf_srclines_dealloc_b(line_context);
        return res;
    for (i = 0; i < count; ++i) {</pre>
        Dwarf_Signed propernumber = 0;
        /* Use srcfiles[i] If you wish to print 'i'
```

```
mostusefully
       you should reflect the numbering that
        a DW_AT_decl_file attribute would report in
        this CU. */
    if (lineversion == 5) {
       propernumber = i;
    } else {
       propernumber = i+1;
   printf("File %4ld %s\n", (unsigned long)propernumber,
       srcfiles[i]);
   dwarf_dealloc(dbg, srcfiles[i], DW_DLA_STRING);
   srcfiles[i] = 0;
/\star We could leave all dealloc to dwarf_finish() to
   handle, but this tidies up sooner. \star/
dwarf_dealloc(dbg, srcfiles, DW_DLA_LIST);
dwarf_srclines_dealloc_b(line_context);
return DW_DLV_OK;
```

9.63 Using dwarf_get_globals()

Example using global symbol names.

For 0.4.2 and earlier this returned .debug_pubnames content. As of version 0.5.0 (October 2022) this returns .debug_pubnames (if it exists) and the relevant portion of .debug_names (if .debug_names exists) data.

```
*/
int examplef(Dwarf_Debug dbg,Dwarf_Error *error)
{
    Dwarf_Signed count = 0;
    Dwarf_Global *globs = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    res = dwarf_get_globals(dbg, &globs,&count, error);
    if (res != DW_DLV_OK) {
        return res;
    }
    for (i = 0; i < count; ++i) {
            /* use globs[i] */
            char *name = 0;
            res = dwarf_globname(globs[i],&name,error);
            if (res != DW_DLV_OK) {
                 dwarf_globals_dealloc(dbg,globs,count);
                 return res;
            }
        }
        dwarf_globals_dealloc(dbg, globs, count);
        return DW_DLV_OK;
}</pre>
```

9.64 Using dwarf_globals_by_type()

Example reading .debug pubtypes.

The .debug_pubtypes section was in DWARF4, it could appear as an extension in other DWARF versions.. In libdwarf 0.5.0 and earlier the function dwarf get pubtypes() was used instead.

```
*/
int exampleg(Dwarf_Debug dbg, Dwarf_Error *error)
{
    Dwarf_Signed count = 0;
    Dwarf_Global *types = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    res = dwarf_globals_by_type(dbg,DW_GL_PUBTYPES,
        &types,&count,error);
    /* Alternatively the 0.5.0 and earlier call:
        res=dwarf_get_pubtypes(dbg, &types,&count, error); */
    if (res != DW_DLV_OK) {
        return res;
```

```
for (i = 0; i < count; ++i) {
    /* use types[i] */
}
dwarf_globals_dealloc(dbg, types, count);
return DW_DLV_OK;</pre>
```

9.65 Reading .debug_weaknames (nonstandard)

Example. weaknames was IRIX/MIPS only.

This section is an SGI/MIPS extension, not created by modern compilers.

```
*/
int exampleh(Dwarf_Debug dbg, Dwarf_Error *error)
{
    Dwarf_Signed count = 0;
    Dwarf_Global *weaks = 0;
    Dwarf_Signed i = 0;
    int res = 0;

    res = dwarf_globals_by_type(dbg, DW_GL_WEAKS, &weaks, &count, error);
    if (res != DW_DLV_OK) {
        return res;
    }
    for (i = 0; i < count; ++i) {
            /* use weaks[i] */
    }
    dwarf_globals_dealloc(dbg, weaks, count);
    return DW_DLV_OK;
}</pre>
```

9.66 Reading .debug_funcnames (nonstandard)

Example. funcnames was IRIX/MIPS only.

This section is an SGI/MIPS extension, not created by modern compilers.

```
*/
int examplej(Dwarf_Debug dbg, Dwarf_Error*error)
{
    Dwarf_Signed count = 0;
    Dwarf_Global *funcs = 0;
    Dwarf_Signed i = 0;
    int fres = 0;

    fres = dwarf_globals_by_type(dbg,DW_GL_FUNCS,
        &funcs,&count,error);
    if (fres != DW_DLV_OK) {
        return fres;
    }
    for (i = 0; i < count; ++i) {
        /* use funcs[i] */
    }
    dwarf_globals_dealloc(dbg, funcs, count);
    return DW_DLV_OK;
}</pre>
```

9.67 Reading .debug_types (nonstandard)

Example .debug_types was IRIX/MIPS only.

This section is an SGI/MIPS extension, not created by modern compilers.

```
*/
int example1(Dwarf_Debug dbg, Dwarf_Error *error)
```

```
Dwarf_Signed count = 0;
Dwarf_Global *types = 0;
Dwarf_Signed i = 0;
int res = 0;
res = dwarf_globals_by_type(dbg,DW_GL_TYPES,
    &types,&count,error);
if (res != DW_DLV_OK) {
    return res;
}
for (i = 0; i < count; ++i) {
    /* use types[i] */
}
dwarf_globals_dealloc(dbg, types, count);
return DW_DLV_OK;
```

9.68 Reading .debug_varnames data (nonstandard)

Example .debug_varnames was IRIX/MIPS only.

This section is an SGI/MIPS extension, not created by modern compilers.

9.69 Reading .debug_names data

Example access to .debug_names.

This is accessing DWARF5 .debug_names, a section intended to provide fast access to DIEs.

It bears a strong resemblance to what libdwarf does in dwarf_global.c.

Making this a single (long) function here, though that is not how libdwarf or dwarfdump are written.

That is just one possible sort of access. There are many, and we would love to hear suggestions for specific new API functions in the library.

There is a wealth of information in .debug_names and the following is all taken care of for you by dwarf_get_globals().

```
Dwarf_Unsigned comp_unit_count = 0;
Dwarf_Unsigned local_type_unit_count = 0;
Dwarf_Unsigned foreign_type_unit_count = 0;
Dwarf_Unsigned bucket_count = 0;
Dwarf_Unsigned name_count = 0;
Dwarf_Unsigned abbrev_table_size = 0;
Dwarf_Unsigned entry_pool_size = 0;
Dwarf_Unsigned augmentation_string_size = 0;
         *aug_string = 0;
Dwarf_Unsigned section_size = 0;
Dwarf_Half table_version = 0;
Dwarf_Half
                 offset_size = 0;
Dwarf_Unsigned i = 0;
res = dwarf_dnames_header(dbg,offset,&dn,
     &new_offset,error);
if (res == DW_DLV_ERROR) {
   /* Something wrong. */
     return res;
if (res == DW_DLV_NO_ENTRY) {
     /\star Done. Normal end of the .debug_names section. \star/
     break;
*dnentrycount += 1;
res = dwarf_dnames_sizes(dn,&comp_unit_count,
     &local_type_unit_count,
     &foreign_type_unit_count,
     &bucket_count,
     &name count, &abbrev table size,
     &entry_pool_size, &augmentation_string_size,
     &aug_string,
     &section_size, &table_version,
     &offset_size,
     error);
if (res != DW_DLV_OK) {
     /* Something wrong. */
     return res:
/* name indexes start with one */
for (i = 1; i <= name_count; ++i) {
   Dwarf_Unsigned j = 0;
   /* dnames_name data */</pre>
     Dwarf_Unsigned bucketnum = 0;
     Dwarf_Unsigned hashvalunsign = 0;
     Dwarf_Unsigned offset_to_debug_str = 0;
    Dwarf_Unsigned offset_in_entrypool = 0;
Dwarf_Unsigned abbrev_code = 0;
Dwarf_Half abbrev_tag = 0;
Dwarf_Half nt_idxattr_array[MAXPAIRS];
     Dwarf Half
                      nt_form_array[MAXPAIRS];
     Dwarf_Unsigned attr_count = 0;
     /* dnames_entrypool data */
     Dwarf_Half tag = 0;
Dwarf_Bool single_cu_case = 0;
     Dwarf_Unsigned single_cu_offset = 0;
     Dwarf_Unsigned value_count = 0;
     Dwarf_Unsigned index_of_abbrev = 0;
Dwarf_Unsigned offset_of_initial_value = 0;
     Dwarf_Unsigned offset_next_entry_pool = 0;
     Dwarf_Half idx_array[MAXPAIRS];
Dwarf_Half form_array[MAXPAIRS];
     Dwarf_Unsigned offsets_array[MAXPAIRS];
     Dwarf_Sig8
                      signatures_array[MAXPAIRS];
     Dwarf_Unsigned cu_table_index = 0;
     Dwarf_Unsigned tu_table_index = 0;
     Dwarf_Unsigned local_die_offset = 0;
     Dwarf_Unsigned parent_index = 0;
     Dwarf_Sig8
                      parenthash;
     (void)parent_index;
                                 /* avoids warning */
     (void)local_die_offset; /* avoids warning */
(void)tu_table_index; /* avoids warning */
(void)cu_table_index; /* avoids warning */
     memset (&parenthash, 0, sizeof (parenthash));
     /* This gets us the entry pool offset we need.
we provide idxattr and nt_form arrays (need
         not be initialized) and on return
          attr_count of those arrays are filled in.
          if attr_count < array_size then array_size
         is too small and things will not go well!
See the count of DW_IDX entries in dwarf.h
```

```
and make the arrays (say) 2 or more larger
    ensuring against future new DW_IDX index
    attributes..
    ptrtostring is the name in the Names Table. \star/
res = dwarf dnames name(dn.i.
    &bucketnum, &hashvalunsign,
    &offset_to_debug_str,&ptrtostr,
    &offset_in_entrypool, &abbrev_code,
    &abbrev_tag,
    MAXPAIRS.
    nt_idxattr_array, nt_form_array,
&attr_count,error);
if (res == DW_DLV_NO_ENTRY) {
    /* past end. Normal. */
    break;
if (res == DW_DLV_ERROR) {
    dwarf_dealloc_dnames(dn);
    return res;
/\star Check attr_count < MAXPAIRS ! \star/
/* Now check the value of TAG to ensure it
    is something of interest as data or function.
    Plausible choices: */
switch (abbrev_tag) {
case DW_TAG_subprogram:
case DW_TAG_variable:
case DW_TAG_label:
case DW_TAG_member:
case DW_TAG_common_block:
case DW_TAG_enumerator:
case DW_TAG_namelist:
case DW_TAG_module:
    break;
default:
    /* Not data or variable DIE involved.
        Loop on the next i */
/* We need the number of values for this name
  from this call. tag will match abbrev_tag.
res = dwarf_dnames_entrypool(dn,
    offset_in_entrypool,
    &abbrev_code, &tag, &value_count, &index_of_abbrev,
    &offset_of_initial_value,
    error);
if (res != DW_DLV_OK) {
    dwarf_dealloc_dnames(dn);
    return res;
/* This gets us an actual array of values
    as the library combines abbreviations, IDX attributes and values. We use
    the idx_array and form_array data
    created above. */
res = dwarf_dnames_entrypool_values(dn,
    index of abbrev,
    offset_of_initial_value,
    value_count,
    idx_array,
    form_array,
    offsets_array,
    signatures_array,
&single_cu_case,&single_cu_offset,
    &offset_next_entry_pool,
    error);
if (res != DW_DLV_OK) {
    dwarf_dealloc_dnames(dn);
    return res:
for (j = 0; j < value_count; ++j) {</pre>
    Dwarf_Half idx = idx_array[j];
    switch(idx) {
    case DW_IDX_compile_unit:
    cu_table_index = offsets_array[j];
    case DW_IDX_die_offset:
        local_die_offset = offsets_array[j];
        break;
    /\star The following are not meaninful when
         reading globals. */
```

9.70 Reading .debug_macro data (DWARF5)

Example reading DWARF5 macro data.

This builds an list or some other data structure (not defined) to give an import somewhere to list the import offset and then later to enquire if the list has unexamined offsets. The code compiles but is not yet tested.

This example does not actually do the import at the correct time as this is just checking import offsets, not creating a proper full list (in the proper order) of the macros with the imports inserted. Here we find the macro context for a DIE, report those macro entries, noting any macro_import in a list loop extracting unchecked macro offsets from the list note any import in a list Of course some functions are not implemented here...

```
int
     has_unchecked_import_in_list(void)
    /* Do something */
    return DW_DLV_OK;
Dwarf_Unsigned get_next_import_from_list(void)
    /* Do something */
    return 22;
void mark_this_offset_as_examined(
    Dwarf_Unsigned macro_unit_offset)
    /\star do something \star/
    /\star avoid compiler warnings. \star/
    (void) macro unit offset;
void add_offset_to_list(Dwarf_Unsigned offset)
    /* do something */
    /* avoid compiler warnings. */
    (void) offset;;
int examplep5(Dwarf_Die cu_die,Dwarf_Error *error)
    int lres = 0;
    Dwarf_Unsigned
                       k = 0;
                        version = 0;
    Dwarf_Unsigned
    Dwarf_Macro_Context macro_context = 0;
    Dwarf_Unsigned macro_unit_offset = 0;
    Dwarf_Unsigned
                       number_of_ops = 0;
    Dwarf_Unsigned
                       ops_total_byte_len = 0;
    Dwarf Bool
                       is_primary = TRUE;
    /* Just call once each way to test both.
       Really the second is just for imported units.*/
    for (;; ) {
        if (is_primary) {
            lres = dwarf_get_macro_context(cu_die,
                &version, &macro context,
                &macro unit offset,
                &number_of_ops,
                &ops_total_byte_len,
```

```
error);
     is_primary = FALSE;
} else
     if (has_unchecked_import_in_list()) {
         macro_unit_offset = get_next_import_from_list();
     } else {
         /* We are done */
    lres = dwarf_get_macro_context_by_offset(cu_die,
    macro_unit_offset,
         &version.
         &macro context,
         &number_of_ops,
         &ops_total_byte_len,
         error);
    mark_this_offset_as_examined(macro_unit_offset);
if (lres == DW_DLV_ERROR) {
     /* Something is wrong. */
     return lres;
if (lres == DW_DLV_NO_ENTRY) {
     /* We are done. */
     break;
/* lres == DW_DLV_OK) */
for (k = 0; k < number_of_ops; ++k) {
    Dwarf_Unsigned section_offset = 0;
    Dwarf_Half macro_operator = 0;
    Dwarf_Half forms_count = 0:</pre>
     Dwarf_Half
                       forms_count = 0;
     const Dwarf_Small *formcode_array = 0;
    Dwarf_Unsigned line_number = 0;
Dwarf_Unsigned index = 0;
Dwarf_Unsigned offset =0;
                    * macro_string =0;
     const char
     int lres2 = 0;
     lres2 = dwarf_get_macro_op(macro_context,
         k, &section_offset,&macro_operator,
     &forms_count, &formcode_array,error);
if (lres2 != DW_DLV_OK) {
          /* Some error. Deal with it */
         dwarf_dealloc_macro_context (macro_context);
         return lres2;
     switch(macro_operator) {
     case 0:
         /* Nothing to do. */
         break;
     case DW_MACRO_end_file:
         /* Do something */
         break:
    case DW_MACRO_define:
case DW_MACRO_undef:
case DW_MACRO_define_strp:
     case DW_MACRO_undef_strp:
     case DW_MACRO_define_strx:
     case DW_MACRO_undef_strx:
     case DW_MACRO_define_sup:
     case DW_MACRO_undef_sup: {
         lres2 = dwarf_get_macro_defundef(macro_context,
              &line_number,
              &index,
              &offset,
              &forms_count,
              &macro_string,
              error);
         if (lres2 != DW_DLV_OK) {
              /\star Some error. Deal with it \star/
              dwarf_dealloc_macro_context(macro_context);
              return lres2:
          /* do something */
         break;
     case DW_MACRO_start_file: {
         lres2 = dwarf_get_macro_startend_file(macro_context,
              k,&line_number,
              &index,
              &macro_string,error);
         if (lres2 != DW_DLV_OK) {
              /\star Some error. Deal with it \star/
              dwarf_dealloc_macro_context(macro_context);
              return lres2;
```

```
/* do something */
            break:
        case DW_MACRO_import: {
            lres2 = dwarf get macro import (macro context,
                k,&offset,error);
             if (lres2 != DW_DLV_OK) {
                 /\star Some error. Deal with it \star/
                dwarf_dealloc_macro_context(macro_context);
                return lres2;
            add_offset_to_list(offset);
            break;
        case DW_MACRO_import_sup: {
            lres2 = dwarf_get_macro_import(macro_context,
                k, & offset, error);
               (lres2 != DW_DLV_OK) {
                 /* Some error. Deal with it */
                 dwarf_dealloc_macro_context (macro_context);
                 return lres2;
            /* do something */
            break;
        default:
            /* This is an error or an omission
                in the code here. We do not
                know what to do.
                Do something appropriate, print something?. \star/
            break;
    dwarf_dealloc_macro_context(macro_context);
macro_context = 0;
return DW_DLV_OK;
```

9.71 Reading .debug_macinfo (DWARF2-4)

```
Example reading .debug_macinfo, DWARF2-4.
```

```
void functionusingsigned(Dwarf_Signed s) {
    /* Do something */
/* Avoid compiler warnings. */
    (void)s;
int examplep2 (Dwarf_Debug dbg, Dwarf_Off cur_off,
    Dwarf_Error*error)
   Dwarf_Signed count = 0;
Dwarf_Macro_Details *maclist = 0;
    Dwarf_Signed
                      i = 0;
    Dwarf_Unsigned
                         max = 500000; /* sanity limit */
    int errv = 0;
    /\star This is for DWARF2, DWARF3, and DWARF4
       .debug_macinfo section only.*/
Given an offset from a compilation unit,
        start at that offset (from DW_AT_macroinfo)
        and get its macro details. \star/
    if (errv == DW_DLV_OK) {
        for (i = 0; i < count; ++i) {</pre>
            Dwarf_Macro_Details * mentry = maclist +i;
            /* example of use */
            Dwarf_Signed lineno = mentry->dmd_lineno;
            functionusingsigned(lineno);
        dwarf_dealloc(dbg, maclist, DW_DLA_STRING);
    /\star Loop through all the compilation units macro info from zero.
        This is not guaranteed to work because DWARF does not
        guarantee every byte in the section is meaningful:
        there can be garbage between the macro info
```

9.72 Extracting fde, cie lists.

Example Opening FDE and CIE lists.

9.73 Reading the .eh_frame section

Example access to .eh frame.

```
int exampler(Dwarf_Debug dbg,Dwarf_Addr mypcval,Dwarf_Error *error)
       Given a pc value
        for a function find the FDE and CIE data for \,
        the function.
        Example shows basic access to FDE/CIE plus
        one way to access details given a PC value
        dwarf_get_fde_n() allows accessing all FDE/CIE
        data so one could build up an application-specific table of information if that is more useful. \ \star/
    Dwarf_Cie  *cie_data = 0;
    Dwarf_Signed cie_count = 0;
    Dwarf_Fde *fde_data = 0;
    Dwarf_Signed fde_count = 0;
                 fres = 0;
    fres = dwarf_get_fde_list_eh(dbg,&cie_data,&cie_count,
        &fde_data, &fde_count, error);
    if (fres == DW_DLV_OK)
        Dwarf_Fde myfde = 0;
        Dwarf_Addr low_pc = 0;
        Dwarf_Addr high_pc = 0;
        fres = dwarf_get_fde_at_pc(fde_data,mypcval,
             &myfde, &low_pc, &high_pc,
             error);
        if (fres == DW_DLV_OK) {
            Dwarf_Cie mycie = 0;
fres = dwarf_get_cie_of_fde(myfde,&mycie,error);
             if (fres == DW_DLV_ERROR) {
                 return fres;
```

```
}
    if (fres == DW_DLV_OK) {
        /* Now we can access a range of information
            about the fde and cie applicable. */
    }
    dwarf_dealloc_fde_cie_list(dbg, cie_data, cie_count,
            fde_data,fde_count);
    return fres;
}
return fres;
}
```

9.74 Using dwarf_expand_frame_instructions

Example using dwarf expand frame instructions.

```
int examples(Dwarf_Cie cie,
    Dwarf_Ptr instruction, Dwarf_Unsigned len,
    Dwarf_Error *error)
    Dwarf_Frame_Instr_Head head = 0;
    Dwarf_Unsigned count = 0;
                            res = 0;
    Dwarf_Unsigned
    res = dwarf_expand_frame_instructions(cie,instruction,len,
    %head, &count, error);
if (res != DW_DLV_OK) {
        return res;
    for (i = 0; i < count; ++i) {</pre>
        Dwarf_Unsigned instr_offset_in_instrs = 0;
        Dwarf_Small cfa_operation const char *fields_description
        Dwarf_Unsigned u0 = 0;
        Dwarf_Unsigned u1 = 0;
        Dwarf_Signed s0 = 0;
Dwarf_Signed s1 = 0;
        Dwarf_Signed
        Dwarf_Unsigned code_alignment_factor = 0;
Dwarf_Signed data_alignment_factor = 0;
Dwarf_Block expression_block;
        Dwarf_Block
                        expression_block;
        const char * op_name = 0;
        {\tt memset (\&expression\_block, 0, sizeof (expression\_block));}
        &fields_description, &u0, &u1,
            &code_alignment_factor,
            &data_alignment_factor,
            &expression block, error);
        if (res == DW_DLV_ERROR) {
    dwarf_dealloc_frame_instr_head(head);
        if (res == DW_DLV_OK) {
            if (res != DW_DLV_OK) {
                op_name = "unknown op";
            op name.
                fields_description);
            /\star\,\, Do something with the various data
                as guided by the fields_description. \star/
    dwarf_dealloc_frame_instr_head(head);
    return DW_DLV_OK;
```

9.75 Reading string offsets section data

Example accessing the string offsets section.

An example accessing the string offsets section

Parameters

dbg	The Dwarf_Debug of interest.
dw_error	On error dw_error is set to point to the error details.

Returns

DW DLV OK etc.

```
int examplestrngoffsets(Dwarf_Debug dbg,Dwarf_Error *error)
    wasted_byte_count = 0;
    Dwarf_Unsigned
    Dwarf_Unsigned
                             table_count = 0;
    Dwarf_Error
                             closeerror = 0;
    res = dwarf_open_str_offsets_table_access(dbg, &sot,error);
    if (res == DW_DLV_NO_ENTRY) {
        /* No such table */
        return res;
    if (res == DW_DLV_ERROR) {
        /* Something is very wrong. Print the error? */
        return res;
    for (;;) {
        Dwarf_Unsigned unit_length =0;
        Dwarf_Unsigned unit_length_offset =0;
        Dwarf_Unsigned table_start_offset =0;
                      entry_size = 0;
version =0;
        Dwarf Half
        Dwarf_Half
        Dwarf_Half
                        padding =0;
        Dwarf_Unsigned table_value_count =0;
        Dwarf_Unsigned i = 0;
        Dwarf_Unsigned table_entry_value = 0;
        res = dwarf_next_str_offsets_table(sot,
             &unit_length, &unit_length_offset,
             &table_start_offset,
             &entry_size, &version, &padding,
            &table_value_count,error);
        if (res == DW_DLV_NO_ENTRY) {
            /* We have dealt with all tables */
            break;
        if (res == DW_DLV_ERROR) {
            /* Something badly wrong. Do something. */
dwarf_close_str_offsets_table_access(sot,&closeerror);
            dwarf_dealloc_error(dbg,closeerror);
            return res;
        /\star One could call dwarf_str_offsets_statistics to
            get the wasted bytes so far, but we do not do that in this example. \star/
        /* Possibly print the various table-related values
        returned just above. */
for (i=0; i < table_value_count; ++i) {
            res = dwarf_str_offsets_value_by_index(sot,i,
                &table_entry_value,error);
             if (res != DW_DLV_OK) {
                 /* Something is badly wrong. Do something. */
                 dwarf_close_str_offsets_table_access(sot,&closeerror);
                 dwarf_dealloc_error(dbg,closeerror);
                 return res;
             /* Do something with the table_entry_value at this index. Maybe just print it.
                 It is an offset in .debug_str. */
    res = dwarf_str_offsets_statistics(sot, &wasted_byte_count,
    &table_count,error);
if (res != DW_DLV_OK) {
        dwarf_close_str_offsets_table_access(sot,&closeerror);
        dwarf_dealloc_error(dbg,closeerror);
```

```
return res;
}
res = dwarf_close_str_offsets_table_access(sot,error);
/* little can be done about any error. */
sot = 0;
return res;
}
/*.
```

9.76 Reading an aranges section

Example reading .debug aranges.

An example accessing the .debug_aranges section. Looking all the aranges entries. This example is not searching for anything.

Parameters

dbg	The Dwarf_Debug of interest.
dw_error	On error dw_error is set to point to the error details.

Returns

DW_DLV_OK etc.

```
static void cleanupbadarange(Dwarf_Debug dbg,
    Dwarf_Arange *arange, Dwarf_Signed i, Dwarf_Signed count)
    Dwarf_Signed k = i;
    for ( ; k < count; ++k) {
    dwarf_dealloc(dbg,arange[k] , DW_DLA_ARANGE);</pre>
        arange[k] = 0;
int exampleu(Dwarf_Debug dbg,Dwarf_Error *error)
    /\star It is a historical accident that the count is signed.
        No negative count is possible. \star/
    Dwarf_Signed count = 0;
    Dwarf_Arange *arange = 0;
    res = dwarf_get_aranges(dbg, &arange,&count, error);
if (res == DW_DLV_OK) {
        Dwarf_Signed i = 0;
         for (i = 0; i < count; ++i) {</pre>
             Dwarf_Arange ara = arange[i];
             Dwarf_Unsigned segment = 0;
             Dwarf_Unsigned segment = 0;
Dwarf_Addr start = 0;
             Dwarf_Unsigned length = 0;
             Dwarf_Off cu_die_offset = 0;
             res = dwarf_get_arange_info_b(ara,
                 &segment, &segment_entry_size,
                 &start, &length,
                 &cu_die_offset,error);
             if (res != DW_DLV_OK) {
                 cleanupbadarange(dbg, arange, i, count);
                 dwarf_dealloc(dbg, arange, DW_DLA_LIST);
                 return res:
             ^{\prime} /* Do something with ara */
             dwarf_dealloc(dbg, ara, DW_DLA_ARANGE);
             arange[i] = 0;
        dwarf_dealloc(dbg, arange, DW_DLA_LIST);
    return res;
```

9.77 Example getting .debug ranges data

Example accessing ranges data.

If have_base_addr is false there is no die (as in reading the raw .debug_ranges section) or there is some serious data corruption somewhere.

```
static
void functionusingrange(Dwarf_Signed i, Dwarf_Ranges *r,
    Dwarf_Bool *have_base_addr,
    Dwarf_Unsigned *baseaddr)
    Dwarf_Unsigned base = *baseaddr;
    printf("[%41d] ", (signed long)i);
    switch(r->dwr_type) {
    case DW_RANGES_ENTRY:
        printf(
             "DW_RANGES_ENTRY: raw
                                       addr1 " PRX
             " addr2 " PRX,
         r->dwr_addr1,r->dwr_addr2);
if (r->dwr_addr1 == r->dwr_addr2) {
            printf(" (empty range)");
        printf("\n");
         if (*have_base_addr) {
             printf(" "
"DW_RANGES_ENTRY: cooked addr1 0x%0811x"
             " addr2 " PRX "\n" ,
             r->dwr_addr1+base, r->dwr_addr2+base);
        break:
    case DW_RANGES_ADDRESS_SELECTION:
        printf(
            "Base Address : " PRX "\n",
             r->dwr_addr2);
        *have_base_addr = TRUE;
        *baseaddr = r->dwr_addr2;
        break:
    case DW_RANGES_END:
        printf(
            "DW_RANGES_END : 0,0\n");
         *have_base_addr = FALSE;
        *baseaddr = 0;
        break;
    default:
        printf(
                               : incorrect dwr_type is 0x%lx\n",
             (unsigned long)r->dwr_type);
}
/* On call the rangesoffset is a default zero. */
int examplev(Dwarf_Debug dbg, Dwarf_Off rangesoffset_in,
    Dwarf_Die die, Dwarf_Error*error)
    Dwarf_Signed count = 0;
    Dwarf_Off realoffset = 0;
Dwarf_Ranges *rangesbuf = 0;
    Dwarf_Unsigned bytecount = 0;
                    res = 0;
    Dwarf_Unsigned base_address = 0;
    Dwarf_Bool have_base_addr = FALSE;
Dwarf_Bool have_rangesoffset = FALSE;
    Dwarf_Unsigned rangesoffset = (Dwarf_Unsigned) rangesoffset_in;
    (void) have_rangesoffset;
    if (die) {
         /\star~ Find the ranges for a specific DIE \star/
        res = dwarf_get_ranges_baseaddress(dbg,die,&have_base_addr,
&base_address,&have_rangesoffset,&rangesoffset,error);
         if (res == DW_DLV_ERROR) {
             /* Just pretend not an error. */
             dwarf_dealloc_error(dbg,*error);
             *error = 0;
        }
    } else {
        /\star To test getting all ranges and no knowledge
            of the base address (so cooked values
             cannot be definitely known unless
             the base is in the .\ensuremath{\mbox{debug\_ranges}} entries
```

```
themselves */
res = dwarf_get_ranges_b(dbg,rangesoffset,die,
    &realoffset,
&rangesbuf,&count,&bytecount,error);
if (res != DW_DLV_OK) {
     if (res == DW_DLV_ERROR) {
        printf("ERROR dwarf_get_ranges_b %s\n",
              dwarf_errmsg(*error));
     } else {
         printf("NO_ENTRY dwarf_get_ranges_b\n");
    Dwarf Signed i = 0:
    pwint_Signature of,
printf("Range group base address: " PRX
    ", offset in .debug_ranges:"
    " 0x%081lx\n",
         base_address, rangesoffset);
     for ( i = 0; i < count; ++i )</pre>
         Dwarf_Ranges *cur = rangesbuf+i;
/* Use cur. */
         functionusingrange(i, cur, &have_base_addr, &base_address);
     dwarf_dealloc_ranges(dbg, rangesbuf, count);
return DW_DLV_OK;
```

9.78 Reading gdbindex data

Example accessing gdbindex section data.

```
int examplew(Dwarf_Debug dbg,Dwarf_Error *error)
                Dwarf_Gdbindex gindexptr = 0;
                Dwarf_Unsigned version = 0;
                Dwarf_Unsigned cu_list_offset = 0;
                Dwarf_Unsigned types_cu_list_offset = 0;
                Dwarf_Unsigned address_area_offset = 0;
                Dwarf_Unsigned symbol_table_offset = 0;
               Dwarf_Unsigned constant_pool_offset = 0;
Dwarf_Unsigned section_size = 0;
                const char * section_name = 0;
                                                                           res = 0;
                res = dwarf_gdbindex_header(dbg,&gindexptr,
                                &version, &cu_list_offset, &types_cu_list_offset,
                                &address_area_offset,&symbol_table_offset,
                                &constant_pool_offset, &section_size,
                                &section_name,error);
                 \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm} \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm}  \hspace{0.1cm} \hspace{0.1cm}  \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm}  \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0.1cm} \hspace{0
                                return res;
                                /\star do something with the data \star/
                                Dwarf_Unsigned length = 0;
                               Dwarf_Unsigned typeslength = 0;
                               Dwarf_Unsigned i = 0;
                                res = dwarf_gdbindex_culist_array(gindexptr,
                                               &length,error);
                                 /* Example actions. */
                                 if (res != DW_DLV_OK) {
                                                dwarf_dealloc_gdbindex(gindexptr);
                                                return res;
                                for (i = 0; i < length; ++i) {</pre>
                                               Dwarf_Unsigned cuoffset = 0;
Dwarf_Unsigned culength = 0;
                                                res = dwarf_gdbindex_culist_entry(gindexptr,
                                                              i,&cuoffset,&culength,error);
                                                if (res != DW_DLV_OK) {
                                                                return res;
                                                /\star Do something with cuoffset, culength \star/
                                res = dwarf_gdbindex_types_culist_array(gindexptr,
                                                & typeslength, error);
                                if (res != DW_DLV_OK) {
```

9.79 Reading gdbindex addressarea

Example accessing gdbindex addressarea data.

```
int examplewgdbindex(Dwarf_Gdbindex gdbindex,
    Dwarf_Error *error)
    Dwarf_Unsigned list_len = 0;
    Dwarf_Unsigned i = 0;
                   res = 0;
    res = dwarf_gdbindex_addressarea(gdbindex, &list_len,error);
    if (res != DW_DLV_OK) {
        /\star Something wrong, ignore the addressarea \star/
        return res;
    /* Iterate through the address area. */
    for (i = 0; i < list_len; i++) {</pre>
        Dwarf_Unsigned lowpc = 0;
        Dwarf_Unsigned highpc = 0;
        Dwarf_Unsigned cu_index = 0;
        res = dwarf_gdbindex_addressarea_entry(gdbindex,i,
            &lowpc, &highpc,
            &cu_index,
            error);
        if (res != DW_DLV_OK) {
            /\star Something wrong, ignore the addressarea \star/
            return res:
           We have a valid address area entry, do something
    return DW_DLV_OK;
```

9.80 Reading the gdbindex symbol table

```
Example accessing gdbindex symbol table data.
```

```
Dwarf_Unsigned ii = 0;
    const char *name = 0;
    int resl = 0;
    resl = dwarf_gdbindex_symboltable_entry(gdbindex,i,
        &symnameoffset, &cuvecoffset,
    if (resl != DW_DLV_OK) {
        return resl;
    resl = dwarf_gdbindex_string_by_offset(gdbindex,
        symnameoffset,&name,error);
    if (resl != DW_DLV_OK) {
        return resl;
    resl = dwarf_gdbindex_cuvector_length(gdbindex,
        cuvecoffset,&cuvec_len,error);
    if (resl != DW_DLV_OK) {
    return resl;
    for (ii = 0; ii < cuvec_len; ++ii ) {</pre>
        Dwarf_Unsigned attributes = 0;
        Dwarf_Unsigned cu_index = 0;
        Dwarf_Unsigned symbol_kind = 0;
        Dwarf_Unsigned is_static = 0;
        int res2 = 0;
        res2 = dwarf_gdbindex_cuvector_inner_attributes(
            gdbindex, cuvecoffset, ii,
             &attributes, error);
        if (res2 != DW_DLV_OK) {
            return res2;
        /\star 'attributes' is a value with various internal
            fields so we expand the fields. \star/
        res2 = dwarf_gdbindex_cuvector_instance_expand_value(
            gdbindex, attributes, &cu_index, &symbol_kind, &is_static,
             error);
        if (res2 != DW_DLV_OK) {
             return res2;
        /\star Do something with the attributes. \star/
return DW_DLV_OK;
```

9.81 Reading cu and tu Debug Fission data

Example using dwarf_get_xu_index_header.

Debug Fission is an older name for Split Dwarf.

```
int exampley(Dwarf_Debug dbg, const char *type,
    Dwarf_Error *error)
    /* type is "tu" or "cu" */
                             res = 0;
    Dwarf_Xu_Index_Header xuhdr = 0;
    Dwarf_Unsigned version_number = 0;

Dwarf_Unsigned version_number = 0;

/*L */
                            units_count = 0; /* M */
hash_slots_count = 0; /* N */
    Dwarf_Unsigned
    Dwarf_Unsigned
    const char
                            *section_name = 0;
    res = dwarf_get_xu_index_header(dbg,
        type,
         &xuhdr,
         &version_number,
         &offsets_count,
         &units_count,
         &hash_slots_count,
         &section_name,
         error);
    if (res != DW_DLV_OK) {
         return res;
    /* Do something with the xuhdr here . */
dwarf_dealloc_xu_header(xuhdr);
    return DW_DLV_OK;
```

9.82 Reading Split Dwarf (Debug Fission) hash slots

```
Example using dwarf_get_xu_hash_entry()
int examplez( Dwarf_Xu_Index_Header xuhdr,
    Dwarf_Unsigned hash_slots_count,
    Dwarf_Error *error)
    /\star hash_slots_count returned by
    dwarf_get_xu_index_header() */
static Dwarf_Sig8 zerohashval;
    Dwarf_Unsigned h = 0;
    for (h = 0; h < hash_slots_count; h++) {</pre>
        Dwarf_Sig8 hashval;
Dwarf_Unsigned index = 0;
         int res = 0;
         res = dwarf_get_xu_hash_entry(xuhdr,h,
             &hashval,&index,error);
         if (res != DW_DLV_OK) {
             return res;
         if (!memcmp(&hashval,&zerohashval,
             sizeof(Dwarf_Sig8)) && index == 0 ) {
             /\star An unused hash slot \star/
             continue:
         /* Here, hashval and index (a row index into
             offsets and lengths) are valid. Do
             something with them */
    return DW_DLV_OK;
```

9.83 Reading high pc from a DIE.

```
Example get high-pc from a DIE.
```

```
int examplehighpc(Dwarf_Die die,
    Dwarf_Addr *highpc,
    Dwarf_Error *error)
               res = 0;
    Dwarf_Addr localhighpc = 0;
    Dwarf_Half form = 0;
enum Dwarf_Form_Class formclass = DW_FORM_CLASS_UNKNOWN;
    res = dwarf_highpc_b(die, &localhighpc,
        &form, &formclass, error);
    if (res != DW_DLV_OK) {
        return res;
    if (form != DW_FORM_addr &&
        !dwarf_addr_form_is_indexed(form)) {
Dwarf_Addr low_pc = 0;
        /* The localhighpc is an offset from
            DW_AT_low_pc. */
        res = dwarf_lowpc(die,&low_pc,error);
        if (res != DW_DLV_OK) {
             return res;
        } else
            localhighpc += low_pc;
    *highpc = localhighpc;
    return DW_DLV_OK;
```

9.84 Reading Split Dwarf (Debug Fission) data

Example getting cu/tu name, offset.

```
int exampleza(Dwarf_Xu_Index_Header xuhdr,
    Dwarf_Unsigned offsets_count,
    Dwarf_Unsigned index,
    Dwarf_Error *error)
    Dwarf_Unsigned col = 0;
    /\star We use 'offsets_count' returned by
        a dwarf_get_xu_index_header() call.
We use 'index' returned by a
        dwarf_get_xu_hash_entry() call. */
    for (col = 0; col < offsets_count; col++) {</pre>
        Dwarf_Unsigned off = 0;
        Dwarf_Unsigned len = 0;
        const char *name = 0;
Dwarf_Unsigned num = 0;
        int res = 0;
        res = dwarf_get_xu_section_names(xuhdr,
             col, &num, &name, error);
        if (res == DW_DLV_ERROR) {
             return res;
        if (res == DW_DLV_NO_ENTRY) {
            break;
        res = dwarf_get_xu_section_offset(xuhdr,
            index,col,&off,&len,error);
        if (res == DW_DLV_ERROR) {
            return res;
         if (res == DW_DLV_NO_ENTRY) {
             break;
         /\star Here we have the DW_SECT_ name and number
            and the base offset and length of the
             section data applicable to the hash
             that got us here.
            Use the values.*/
    return DW DLV OK;
```

9.85 Retrieving tag, attribute, etc names

Example getting tag, attribute, etc names as strings.

```
void examplezb(void)
    const char * out = "unknown something";
                   res = 0;
    int
    /\star The following is wrong, do not do it!
        Confusing TAG with ACCESS!
    res = dwarf_get_ACCESS_name(DW_TAG_entry_point,&out);
    /* Nothing one does here with 'res' or 'out'
         is meaningful. */
    out = "<unknown TAG>"; /* Not a malloc'd string! */
    /\star The following is meaningful. \!\star/
    res = dwarf_get_TAG_name(DW_TAG_entry_point,&out);
    (void)res; /* avoids unused var compiler warning */
/* If res == DW_DLV_ERROR or DW_DLV_NO_ENTRY
         out will be the locally assigned static string.
If res == DW_DLV_OK it will be a usable
         TAG name string.
         In no case should a returned string be free()d. */
```

9.86 Using GNU debuglink data

Example showing dwarf_add_debuglink_global_path.

An example using both dwarf_add_debuglink_global_path and dwarf_gnu_debuglink .

```
int exampledebuglink(Dwarf_Debug dbg, Dwarf_Error* error)
    int
              res = 0;
             *debuglink_path = 0;
    char
    unsigned char *crc = 0;
    char *debuglink_fullpath = 0;
    unsigned debuglink_fullpath_strlen = 0;
    unsigned buildid_type = 0;
    char * buildidowner_name = 0;
unsigned char *buildid_itself = 0;
unsigned buildid_length = 0;
    char ** paths = 0;
unsigned paths_count = 0;
    unsigned i = 0;
    /* This is just an example if one knows of another place full-DWARF objects
         may be. "/usr/lib/debug" is automatically
    res = dwarf_add_debuglink_global_path(dbg,
    "/some/path/debug",error);
    if (res != DW_DLV_OK) {
    /* Something is wrong*/
         return res;
    res = dwarf_gnu_debuglink(dbg,
         &debuglink_path,
         &crc,
         &debuglink_fullpath,
         &debuglink_fullpath_strlen,
         &buildid_type,
         &buildidowner_name,
         &buildid_itself,
         &buildid_length,
         &paths,
         &paths_count,
         error);
    if (res == DW_DLV_ERROR) {
         return res;
    if (res == DW_DLV_NO_ENTRY) {
         /* No such sections as .note.gnu.build-id
  or .gnu_debuglink */
         return res;
    if (debuglink_fullpath_strlen) {
         printf("%02x",crc[i]);
         printf("debuglink fullpath: %s\n",debuglink_fullpath);
    if (buildid_length) {
        /* buildid_length should be 20. */
for (i = 0; i < buildid_length;++i) {
   printf("%02x",buildid_itself[i]);
         printf("\n");
    printf("Possible paths count %u\n",paths_count);
    for ( ; i < paths_count; ++i ) {
    printf("%2u: %s\n",i,paths[i]);</pre>
    free(debuglink_fullpath);
    free (paths);
    return DW_DLV_OK;
```

9.87 Accessing accessing raw rnglist

Example showing access to rnglist.

This is accessing DWARF5 .debug_rnglists.

```
int example_raw_rnglist(Dwarf_Debug dbg,Dwarf_Error *error)
    Dwarf_Unsigned count = 0;
    int.
                      res = 0;
    Dwarf_Unsigned i = 0;
    res = dwarf_load_rnglists(dbg,&count,error);
    if (res != DW_DLV_OK) {
         return res;
    for (i =0 ; i < count ; ++i) {
         Dwarf_Unsigned header_offset = 0;
        Dwarf_Unsigned header_offset = 0;
Dwarf_Small offset_size = 0;
Dwarf_Small extension_size = 0;
unsigned version = 0; /* 5 */
Dwarf_Small address_size = 0;
Dwarf_Small segment_selector_size = 0;
Dwarf_Unsigned offset_entry_count = 0;
         Dwarf_Unsigned offset_of_offset_array = 0;
         Dwarf_Unsigned offset_of_first_rangeentry = 0;
         Dwarf_Unsigned offset_past_last_rangeentry = 0;
         res = dwarf_get_rnglist_context_basics(dbg,i,
              &header_offset,&offset_size,&extension_size,
              &version, &address_size, &segment_selector_size,
              &offset_entry_count,&offset_of_offset_array,
              &offset_of_first_rangeentry,
         &offset_past_last_rangeentry,error);
if (res != DW_DLV_OK) {
              return res:
             Dwarf_Unsigned e = 0;
              unsigned colmax = 4;
              unsigned col = 0;
              Dwarf_Unsigned global_offset_of_value = 0;
              for ( ; e < offset_entry_count; ++e) {</pre>
                  Dwarf_Unsigned value = 0;
                  int resc = 0;
                  resc = dwarf_get_rnglist_offset_index_value(dbg,
                        i,e,&value,
                        &global_offset_of_value,error);
                   if (resc != DW_DLV_OK) {
                       return resc;
                  /* Do something */
                  col++;
                  if (col == colmax) {
                       col = 0;
                  }
              }
              Dwarf_Unsigned curoffset = offset_of_first_rangeentry;
              Dwarf_Unsigned endoffset = offset_past_last_rangeentry;
                             rese = 0;
              Dwarf_Unsigned ct = 0;
              for ( ; curoffset < endoffset; ++ct ) {</pre>
                  unsigned entrylen = 0;
                  unsigned code = 0;
Dwarf_Unsigned v1 = 0;
                  Dwarf_Unsigned v2 = 0;
                  rese = dwarf_get_rnglist_rle(dbg,i,
                       curoffset, endoffset,
                       &entrylen,
                        &code, &v1, &v2, error);
                   if (rese != DW_DLV_OK) {
                        return rese;
                   ^{\prime} /* Do something with the values */
                  curoffset += entrylen;
if (curoffset > endoffset) {
                       return DW_DLV_ERROR;
             }
         }
    return DW_DLV_OK;
```

9.88 Accessing rnglists section

Example showing access to rnglists on an Attribute.

This is accessing DWARF5 .debug_rnglists. The section first appears in DWARF5.

```
int example_rnglist_for_attribute(Dwarf_Attribute attr,
    Dwarf_Unsigned attrvalue, Dwarf_Error *error)
    /* attrvalue must be the DW_AT_ranges
        DW_FORM_rnglistx or DW_FORM_sec_offset value
    extracted from attr. */
int res = 0;
Dwarf_Half theform = 0;
Dwarf_Unsigned entries_count;
Dwarf_Unsigned global_offset_of_rle_set;
    Dwarf_Rnglists_Head rnglhead = 0;
    Dwarf_Unsigned
                        i = 0;
    res = dwarf_rnglists_get_rle_head(attr,
        theform,
         &rnglhead,
        &entries_count,
        &global_offset_of_rle_set,
        error);
    if (res != DW_DLV_OK) {
        return res;
    for (i = 0; i < entries_count; ++i) {</pre>
        unsigned entrylen
                                = 0;
        unsigned
        unsigned code =
Dwarf_Unsigned rawlowpc = 0;
        Dwarf_Unsigned rawhighpc = 0;
        Dwarf_Bool debug_addr_unavailable = FALSE;
        Dwarf_Unsigned lowpc = 0;
        Dwarf_Unsigned highpc = 0;
         /* Actual addresses are most likely what one
             wants to know, not the lengths/offsets
             recorded in .debug_rnglists. */
        res = dwarf_get_rnglists_entry_fields_a(rnglhead,
            i, &entrylen, &code,
             &rawlowpc, &rawhighpc,
&debug_addr_unavailable,
             &lowpc, &highpc, error);
         if (res != DW_DLV_OK) {
             dwarf_dealloc_rnglists_head(rnglhead);
             return res;
         if (code == DW_RLE_end_of_list) {
             /* we are done */
             break;
         if (code == DW_RLE_base_addressx ||
             code == DW_RLE_base_address) {
             /\star We do not need to use these, they
                 have been accounted for already. */
             continue;
         if (debug_addr_unavailable) {
             /* lowpc and highpc are not real addresses */
             continue:
         /* Here do something with lowpc and highpc, these
             are real addresses */
    dwarf_dealloc_rnglists_head(rnglhead);
return DW_DLV_OK;
```

9.89 Demonstrating reading DWARF without a file.

```
How to read DWARF2 and later from memory.
```

```
*/
#include <config.h>
#include <stddef.h> /* NULL */
```

```
#include <stdio.h> /* printf() */
#include <stdlib.h> /* exit() */
#include <string.h> /* strcmp() */
#include "dwarf.h"
#include "libdwarf.h"
#include "libdwarf_private.h"
    This demonstates processing DWARF
    from in_memory data. For simplicity
    in this example we are using static arrays.
    The C source is src/bin/dwarfexample/jitreader.c
    The motivation is from JIT compiling, where
    at runtime of some application, it generates
    code on the file and DWARF information for it too.
    This gives an example of enabling all of libdwarf's
    functions without actually having the DWARF information
    in a file. (If you have a file in some odd format
    you can use this approach to have libdwarf access
    the format for DWARF data and work normally without
    ever exposing the format to libdwarf.)
    None of the structures defined here in this source
    (or any source using this feature)
    are ever known to libdwarf. They are totally
    private to your code.
    The code you write (like this example) you compile
    separate from libdwarf. You never place your code into libdwarf, you just link your code into
    your application and link against libdwarf.
/* Some valid DWARF2 data */
static Dwarf Small abbrevbytes[] = {
0x01, 0x11, 0x01, 0x25, 0x0e, 0x13, 0x0b, 0x03, 0x08, 0x1b,
0x0e, 0x11, 0x01, 0x12, 0x01, 0x10, 0x06, 0x00, 0x00, 0x02,
0x2e, 0x01, 0x3f, 0x0c, 0x03, 0x08, 0x3a, 0x0b, 0x3b,
                                                          0x0b
0x39, 0x0b, 0x27, 0x0c, 0x11, 0x01, 0x12, 0x01, 0x40,
                                                          0x06
0x97, 0x42, 0x0c, 0x01, 0x13, 0x00, 0x00, 0x03, 0x34, 0x00,
0x03, 0x08, 0x3a, 0x0b, 0x3b, 0x0b, 0x39, 0x0b, 0x49, 0x13, 0x02, 0x0a, 0x00, 0x00, 0x04, 0x24, 0x00, 0x0b, 0x0b, 0x3e,
0x0b, 0x03, 0x08, 0x00, 0x00, 0x00, };
static Dwarf_Small infobytes[] = {
0x60, 0x00, 0x00, 0x00, 0x02, 0x00, 0x00, 0x00, 0x00, 0x00,
0x08, 0x01, 0x00, 0x00, 0x00, 0x00, 0x0c, 0x74, 0x2e, 0x63,
0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00,
0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00,
0x00, 0x00, 0x00, 0x00, 0x00, 0x02, 0x01, 0x66, 0x00, 0x01,
0x02, 0x06, 0x01, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00,
0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00, 0x00,
0x00, 0x00, 0x00, 0x01, 0x5c, 0x00, 0x00, 0x00, 0x03, 0x69,
0x00, 0x01, 0x03, 0x08, 0x5c, 0x00, 0x00, 0x00, 0x02, 0x91,
0x6c, 0x00, 0x04, 0x04, 0x05, 0x6e, 0x74, 0x00, 0x00, static Dwarf_Small strbytes[] = {
0x47, 0x4e, 0x55, 0x20, 0x43, 0x31, 0x37, 0x20, 0x39, 0x2e,
0x33, 0x2e, 0x30, 0x20, 0x2d, 0x6d, 0x74, 0x75, 0x6e, 0x65,
0x3d, 0x67, 0x65, 0x6e, 0x65, 0x72, 0x69, 0x63, 0x20, 0x2d,
0x6d, 0x61, 0x72, 0x63, 0x68, 0x3d, 0x78, 0x38, 0x36, 0x2d,
0x36, 0x34, 0x20, 0x2d, 0x67, 0x64, 0x77, 0x61, 0x72, 0x66,
0x2d, 0x32, 0x20, 0x2d, 0x4f, 0x30, 0x20, 0x2d, 0x66, 0x61,
0x73, 0x79, 0x6e, 0x63, 0x68, 0x72, 0x6f, 0x6e, 0x6f, 0x75,
0x73, 0x2d, 0x75, 0x6e, 0x77, 0x69, 0x6e, 0x64, 0x2d,
                                                          0x74
0x61, 0x62, 0x6c, 0x65, 0x73, 0x20, 0x2d, 0x66, 0x73, 0x74,
0x61, 0x63, 0x6b, 0x2d, 0x70, 0x72, 0x6f, 0x74, 0x65, 0x63,
0x74, 0x6f, 0x72, 0x2d, 0x73, 0x74, 0x72, 0x6f, 0x6e, 0x67,
0x20, 0x2d, 0x66, 0x73, 0x74, 0x61, 0x63, 0x6b, 0x2d, 0x63,
0x6c, 0x61, 0x73, 0x68, 0x2d, 0x70, 0x72, 0x6f, 0x74, 0x65,
0x63, 0x74, 0x69, 0x6f, 0x6e, 0x20, 0x2d, 0x66, 0x63, 0x66,
0x2d, 0x70, 0x72, 0x6f, 0x74, 0x65, 0x63, 0x74, 0x69, 0x6f,
0x6e, 0x00, 0x2f, 0x76, 0x61, 0x72, 0x2f, 0x74, 0x6d, 0x70, 0x2f, 0x74, 0x69, 0x6e, 0x79, 0x64, 0x77, 0x61, 0x72, 0x66,
0x00, };
/* An internals_t , data used elsewhere but
    not directly visible elsewhere. One needs to have one
    of these but maybe the content here too little
or useless, this is just an example of sorts. */ \#define SECCOUNT 4
struct sectiondata_s {
    unsigned int sd_addr;
                    sd_objoffsetlen;
    unsigned int
    unsigned int
                  sd_objpointersize;
    Dwarf_Unsigned sd_sectionsize;
    const char * sd_secname;
```

```
Dwarf_Small * sd_content;
/\star~ The secname must not be 0 , pass "" if
    there is no name. */
static struct sectiondata_s sectiondata[SECCOUNT] = {
{0,0,0,0,"",0},
{0,32,32,sizeof(abbrevbytes),".debug_abbrev",abbrevbytes},
{0,32,32,sizeof(infobytes),".debug_info",infobytes},
{0,32,32,sizeof(strbytes),".debug_str",strbytes}
typedef struct special_filedata_s {
                  f_is_64bit;
    Dwarf_Small
                    f_object_endian;
    unsigned
                    f_pointersize;
    unsigned
                    f_offsetsize;
    Dwarf_Unsigned f_filesize;
    Dwarf_Unsigned f_sectioncount;
    struct sectiondata_s * f_sectarray;
} special_filedata_internals_t;
/* Use DW_END_little.
    Libdwarf finally sets the file-format-specific
    f_object_endianness field to a DW_END_little or
    DW_END_big (see dwarf.h).
    Here we must do that ourselves. \star/
static special_filedata_internals_t base_internals =
{ FALSE, DW_END_little, 32, 32, 200, SECCOUNT, sectiondata };
static
int gsinfo(void* obj,
    Dwarf_Unsigned section_index,
    Dwarf_Obj_Access_Section_a* return_section,
    int* error )
    special filedata internals t *internals =
        (special_filedata_internals_t *)(obj);
    struct sectiondata_s *finfo = 0;
    *error = 0; /* No error. Avoids unused arg */ if (section_index >= SECCOUNT) {
        return DW_DLV_NO ENTRY:
    finfo = internals->f_sectarray + section_index;
    return_section->as_name = finfo->sd_secname;
return_section->as_type = 0;
    return_section->as_flags = 0;
return_section->as_addr = finfo->sd_addr;
    return_section->as_offset = 0;
    return_section->as_size = finfo->sd_sectionsize;
return_section->as_link = 0;
                                = 0;
    return_section->as_info
    return_section->as_addralign = 0;
    return_section->as_entrysize = 1;
    return DW_DLV_OK;
static Dwarf_Small
gborder(void * obj)
    special filedata internals t *internals =
        (special_filedata_internals_t *)(obj);
    return internals->f_object_endian;
static
Dwarf_Small glensize(void * obj)
    /* offset size */
    special_filedata_internals_t *internals =
        (special_filedata_internals_t *)(obj);
    return internals->f_offsetsize/8;
static
Dwarf_Small gptrsize(void * obj)
    special_filedata_internals_t *internals =
        (special_filedata_internals_t *)(obj);
    return internals->f_pointersize/8;
static
Dwarf_Unsigned gfilesize(void * obj)
    special_filedata_internals_t *internals =
         (special_filedata_internals_t *)(obj);
    return internals->f_filesize;
static
```

```
Dwarf_Unsigned gseccount(void* obj)
    special_filedata_internals_t *internals =
         (special_filedata_internals_t *)(obj);
    return internals->f_sectioncount;
int gloadsec(void * obj,
    Dwarf_Unsigned secindex,
    Dwarf Small**rdata,
    int *error)
    special_filedata_internals_t *internals =
         (special_filedata_internals_t *)(obj);
    struct sectiondata_s *secp = 0;
    *error = 0; /* No Error, avoids compiler warning */
if (secindex >= internals->f_sectioncount) {
         return DW_DLV_NO_ENTRY;
    secp = secindex +internals->f_sectarray;
    *rdata = secp->sd_content;
    return DW_DLV_OK;
}
const Dwarf_Obj_Access_Methods_a methods = {
    gborder,
    glensize,
    gptrsize,
    afilesize.
    gseccount,
    0 /* no relocating anything */,
    0 /\star no file with DWARF here, so mmap impossible \star/ ,
    0 /* no destructor appropriate */
    };
struct Dwarf_Obj_Access_Interface_a_s dw_interface =
{ &base_internals, &methods };
static const Dwarf_Sig8 zerosignature;
static int
isformstring(Dwarf_Half form)
    /\star~ Not handling every form string, just the
        ones used in simple cases. */
    switch(form) {
    case DW_FORM_string:
                                    return TRUE:
    case DW_FORM_GNU_strp_alt: return TRUE;
    case DW_FORM_GNU_str_index: return TRUE;
    case DW_FORM_strx:
    case DW_FORM_strx1:
                                   return TRUE;
                                 return TRUE;
return TRUE;
return TRUE;
return TRUE;
return TRUE;
    case DW_FORM_strx2:
    case DW_FORM_strx3:
    case DW_FORM_strx4:
    case DW_FORM_strp:
    default: break;
    return FALSE;
}
static int
print_attr(Dwarf_Attribute atr,
    Dwarf_Signed anumber, Dwarf_Error *error)
    int res = 0;
    char *str = 0;
const char *attrname = 0;
    const char *formname = 0;
    Dwarf_Half form = 0;
    Dwarf_Half attrnum = 0;
    res = dwarf_whatform(atr,&form,error);
if (res != DW_DLV_OK) {
        printf("dwarf_whatform failed! res %d\n", res);
         return res;
    res = dwarf_whatattr(atr,&attrnum,error);
    if (res != DW_DLV_OK) {
         printf("dwarf_whatattr failed! res %d\n",res);
         return res;
    res = dwarf_get_AT_name(attrnum, &attrname);
    if (res == DW_DLV_NO_ENTRY) {
         printf("Bogus attrnum 0x%x\n",attrnum);
attrname = "<internal error ?>";
    }
```

```
res = dwarf_get_FORM_name(form,&formname);
    if (res == DW_DLV_NO_ENTRY) {
        printf("Bogus form 0x%x\n",attrnum);
attrname = "<internal error ?>";
    if (!isformstring(form)) {
        printf(" [%2d] Attr: %-15s Form: %-15s\n",
            (int)anumber,attrname,formname);
        return DW_DLV_OK;
    res = dwarf_formstring(atr, &str, error);
    if (res != DW_DLV_OK) {
        printf("dwarf_formstring failed! res %d\n", res);
    printf(" [%2d] Attr: %-15s Form: %-15s %s\n",
        (int) anumber, attrname, formname, str);
    return DW_DLV_OK;
static void
dealloc_list(Dwarf_Debug dbg,
    Dwarf_Attribute *attrbuf,
    Dwarf_Signed attrcount,
    Dwarf_Signed i)
    for ( ; i < attrcount; ++i) {</pre>
        dwarf_dealloc_attribute(attrbuf[i]);
    dwarf_dealloc(dbg,attrbuf,DW_DLA_LIST);
static int
print_one_die(Dwarf_Debug dbg,Dwarf_Die in_die,int level,
    Dwarf_Error *error)
    Dwarf Attribute *attrbuf = 0;
    Dwarf_Signed attrcount = 0;
    Dwarf_Half tag = 0;
    const char * tagname = 0;
    int res = 0;
    Dwarf_Signed i = 0;
    res = dwarf_tag(in_die,&tag,error);
    if (res != DW_DLV_OK) {
        printf("dwarf_tag failed! res %d\n",res);
        return res;
    res = dwarf_get_TAG_name(tag,&tagname);
    if (res != DW_DLV_OK) {
        tagname = "<bogus tag>";
    printf("%3d: Die: %s\n",level,tagname);
    res = dwarf_attrlist(in_die,&attrbuf,&attrcount,error);
if (res != DW_DLV_OK) {
        printf("dwarf_attrlist failed! res %d\n",res);
        return res;
    for (i = 0; i <attrcount;++i) {</pre>
        res =print_attr(attrbuf[i],i,error);
        if (res != DW_DLV_OK) {
            dealloc_list(dbg,attrbuf,attrcount,0);
            printf("dwarf_attr print failed! res %d\n", res);
            return res;
    dealloc_list(dbg,attrbuf,attrcount,0);
    return DW_DLV_OK;
static int
print_object_info(Dwarf_Debug dbg,Dwarf_Error *error)
    Dwarf_Bool is_info = TRUE; /* our data is not DWARF4
        .debug_types. */
    Dwarf_Unsigned cu_header_length = 0;
    Dwarf_Half version_stamp = 0;
Dwarf_Off abbrev_offset = 0;
                  address_size = 0;
length_size = 0;
extension_size = 0;
    Dwarf_Half
    Dwarf_Half
    Dwarf Half
    Dwarf_Sig8
                    type_signature;
    Dwarf_Unsigned typeoffset
                                    = 0;
    Dwarf_Unsigned next_cu_header_offset = 0;
    Dwarf_Half
                   header_cu_type = 0;
    int res = 0:
    Dwarf_Die cu_die = 0;
```

274 **Topic Documentation**

```
int level = 0;
    type_signature = zerosignature;
    res = dwarf_next_cu_header_d(dbg,
        is info,
         &cu_header_length,
         &version_stamp,
         &abbrev_offset,
         &address_size,
        &length size,
        &extension_size,
        &type signature.
         &typeoffset,
         &next_cu_header_offset,
         &header_cu_type,
    error);
if (res != DW_DLV_OK) {
        printf("Next cu header result %d. "
    "Something is wrong FAIL, line %d\n",res,__LINE__);
         if (res == DW_DLV_ERROR) {
            printf("Error is: %s\n",dwarf_errmsg(*error));
        exit(EXIT FAILURE);
    printf("CU header length.....0x%lx\n",
         (unsigned long) cu_header_length);
    printf("Version stamp.....%d\n", version_stamp);
    printf("Address size ......%d\n",address_size);
    printf("Offset size.........%d\n",length_size);
printf("Next cu header offset.....0x%lx\n",
         (unsigned long)next_cu_header_offset);
    res = dwarf_siblingof_b(dbg, NULL,is_info, &cu_die, error);
    if (res != DW_DLV_OK) {
         /* There is no CU die, which should be impossible. */
if (res == DW_DLV_ERROR) {
    printf("ERROR: dwarf_siblingof_b failed, no CU die\n");
             printf("Error is: %s\n",dwarf_errmsg(*error));
             return res;
         } else {
             printf("ERROR: dwarf_siblingof_b got NO_ENTRY, "
                 "no CU die\n");
             return res;
        }
    res = print_one_die(dbg,cu_die,level,error);
    if (res != DW_DLV_OK) {
        dwarf_dealloc_die(cu_die);
        printf("print_one_die failed! %d\n",res);
        return res:
    dwarf_dealloc_die(cu_die);
    return DW_DLV_OK;
   testing interfaces useful for embedding
    libdwarf inside another program or library. */
int main(int argc, char **argv)
    int res = 0;
    Dwarf_Debug dbg = 0;
Dwarf_Error error = 0;
    int fail = FALSE;
    int i = 1;
    if (i >= argc) {
        /* OK */
    } else {
        if (!strcmp(argv[i],"--suppress-de-alloc-tree")) {
             /\star Do nothing, ignore the argument \star/
    ^{\prime} /* Fill in interface before this call.
    We are using a static area, see above. */
res = dwarf_object_init_b(&dw_interface,
        0,0,DW_GROUPNUMBER_ANY,&dbg,
    if (res == DW_DLV_NO_ENTRY) {
        printf("FAIL Cannot dwarf_object_init_b() NO ENTRY. \n");
         exit(EXIT_FAILURE);
    } else if (res == DW_DLV_ERROR) {
        printf("FAIL Cannot dwarf_object_init_b(). \n");
        printf("msg: %s\n",dwarf_errmsg(error));
        dwarf_dealloc_error(dbg,error);
        exit (EXIT_FAILURE);
```

}

```
res = print_object_info(dbg,&error);
if (res != DW_DLV_OK) {
    if (res == DW_DLV_ERROR) {
        dwarf_dealloc_error(dbg,error);
    }
    printf("FAIL printing, res %d line %d\n",res,__LINE__);
    exit(EXIT_FAILURE);
}
dwarf_object_finish(dbg);
if (fail) {
    printf("FAIL objectaccess.c\n");
    exit(EXIT_FAILURE);
}
return 0;
}
```

9.90 A simple report on section groups.

Section groups are for Split DWARF.

```
The C source is src/bin/dwarfexample/showsectiongroups.c
#include <config.h>
#include <stdio.h> /* printf() */
#include <stdlib.h> /* calloc() exit() free() */
#include <string.h> /* strcmp() */
#include "dwarf.h"
#include "libdwarf.h"
#define FALSE 0
char trueoutpath[2000];
static int
one_file_show_groups(char *path_in,
     char *shortpath,
     int chosengroup)
                          res = 0;
                     dbg = 0;
error = 0;
     Dwarf_Debug
     Dwarf_Error
                        * path = 0;
     char
     Dwarf_Unsigned section_count = 0;
Dwarf_Unsigned group_count = 0;
     Dwarf_Unsigned
                           selected_group = 0;
    Dwarf_Unsigned selected_group = 0;
Dwarf_Unsigned map_entry_count = 0;
Dwarf_Unsigned * group_numbers_array = 0;
Dwarf_Unsigned * sec_numbers_array = 0;
const char ** sec_names_array = 0;
Dwarf_Unsigned i = 0;
const char *grpname = 0;
     switch(chosengroup) {
     case DW_GROUPNUMBER_ANY:
          grpname="DW_GROUPNUMBER_ANY";
          break;
     case DW_GROUPNUMBER_BASE:
         grpname="DW_GROUPNUMBER_BASE";
     case DW GROUPNUMBER DWO:
          grpname="DW_GROUPNUMBER_DWO";
     break;
default:
          grpname = "";
     path = path_in;
     res = dwarf_init_path(path,
         0,0,
          chosengroup,
          0,0, &dbg, &error);
     if (res == DW_DLV_ERROR) {
          printf("Error from libdwarf opening \"%s\": %s\n",
              shortpath, dwarf_errmsg(error));
          dwarf_dealloc_error(dbg,error);
error = 0;
          return res;
     if (res == DW_DLV_NO_ENTRY) {
          printf("There is no such file as \"%s\" "
                or the selected group %d (%s) does "
```

276 Topic Documentation

```
"not appear in the file\n",
        shortpath, chosengroup, grpname);
    return DW_DLV_NO_ENTRY;
}
res = dwarf_sec_group_sizes(dbg, &section_count,
    &group_count, &selected_group, &map_entry_count,
    &error);
if (res == DW_DLV_ERROR) {
    printf("Error from libdwarf getting group "
    "sizes \"%s\": %s\n",
    shortpath, dwarf_errmsg(error));
    dwarf_dealloc_error(dbg,error);
    dwarf_finish(dbg);
    return res;
if (res == DW DLV NO ENTRY) {
    printf("Impossible. libdwarf claims no groups from %s\n",
       shortpath);
    dwarf_finish(dbg);
    return res;
printf("Group Map data sizes\n");
printf(" requested group : %4lu\n",
    (unsigned long) chosengroup);
printf(" section count : %4lu\n",
(unsigned long) section_count);
printf(" group count : %41u\n
                          : %4lu\n",
    (unsigned long)group_count);
printf(" map entry count : %4lu\n",
    (unsigned long) map_entry_count);
group_numbers_array = (Dwarf_Unsigned *)calloc(map_entry_count,
    sizeof(Dwarf_Unsigned));
if (!group_numbers_array) {
    printf("Error calloc fail, group count %lu\n",
       (unsigned long)group_count);
    dwarf_finish(dbg);
    return DW_DLV_ERROR;
sec_numbers_array = (Dwarf_Unsigned *)calloc(map_entry_count,
    sizeof(Dwarf_Unsigned));
   (!sec_numbers_array) {
    free(group_numbers_array);
    printf("Error calloc fail sec numbers, section count lu\n", (unsigned long) section_count);
    dwarf_finish(dbg);
    return DW_DLV_ERROR;
if (!sec_names_array) {
    free(sec_numbers_array);
free(group_numbers_array);
    printf("Error calloc fail on names, section count %lu\n",
       (unsigned long) section_count);
    dwarf_finish(dbg);
    return DW_DLV_ERROR;
res = dwarf_sec_group_map(dbg,map_entry_count,
    group_numbers_array,
sec_numbers_array, sec_names_array, &error);
if (res == DW_DLV_ERROR) {
    free(sec_names_array);
    free(sec_numbers_array);
    free(group_numbers_array);
    "sizes \"%s\": %s\n",
shortpath, dwarf_errmsg(error));
    dwarf_dealloc_error(dbg,error);
    error = 0;
    dwarf_finish(dbg);
    return res;
if (res == DW_DLV_NO_ENTRY) {
    free(sec_names_array);
    free(sec_numbers_array);
    free(group_numbers_array);
    printf("Impossible. libdwarf claims details from %s\n",
       shortpath);
    dwarf_finish(dbg);
    return res;
printf(" [index] group section \n");
```

```
for (i = 0; i < map_entry_count;++i) {
    printf(" [%5lu] %4lu %4lu %s\n",</pre>
              (unsigned long)i,
              (unsigned long)group_numbers_array[i],
              (unsigned long)sec_numbers_array[i],
              sec_names_array[i]);
    free(sec_names_array);
    free(sec_numbers_array);
    free(group_numbers_array);
    dwarf_finish(dbg);
    return DW_DLV_OK;
}
/* Does not return */
static void
usage (void)
    printf("Usage: showsectiongroups [-group <n>] "
         "<objectfile> ...\n");
    printf("Usage: group defaults to zero (DW_GROUPNUMBER ANY)\n");
     exit(EXIT_FAILURE);
}
/* This trimming of the file path makes libdwarf regression
    testing easier by arranging baseline output not show the full path. */
static void
trimpathprefix(char *out,unsigned int outlen, char *in)
    char *cpo = out;
char *cpi = in;
    char *suffix = 0;
    unsigned int lencopied = 0;
    for ( ; *cpi ; ++cpi) {
   if (*cpi == '/') {
            suffix= cpi+1;
    if (suffix) {
         cpi = suffix;
    lencopied = 0;
    for (; lencopied < outlen; ++cpo,++cpi)</pre>
         *cpo = *cpi;
         if (! *cpi) {
             return;
         ++lencopied;
    printf("FAIL copy file name: not terminated \n");
     exit(EXIT_FAILURE);
}
int
main(int argc, char **argv)
    int res = 0;
    int i = 1:
    int chosengroup = DW_GROUPNUMBER_ANY;
    static char reportingpath[16000];
    if (argc < 2) {</pre>
         usage();
         return 0;
    for ( ; i < argc; ++i) {</pre>
         char *arg = argv[i];
         if (!strcmp(arg,"-group")) {
             if (i >= argc) {
                  usage();
              arg = argv[i];
             chosengroup = atoi(arg);
              /* We are ignoring errors to simplify
                  this source. Use strtol, carefully,
                  in real code. */
              continue:
         if (!strcmp(argv[i],"--suppress-de-alloc-tree")) {
              /\star Do nothing, ignore the argument \star/
         trimpathprefix(reportingpath, sizeof(reportingpath), arg);
res = one_file_show_groups(arg,
```

278 Topic Documentation

Chapter 10

Data Structure Documentation

10.1 Dwarf Block s Struct Reference

Data Fields

- Dwarf_Unsigned bl_len
- Dwarf Ptr bl data
- Dwarf_Small bl_from_loclist
- Dwarf_Unsigned bl_section_offset

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.2 Dwarf Cmdline Options s Struct Reference

#include <libdwarf.h>

Data Fields

• Dwarf_Bool check_verbose_mode

10.2.1 Detailed Description

check_verbose_mode defaults to FALSE. If a libdwarf-calling program sets this TRUE it means some errors in Line Table headers get a much more detailed description of the error which is reported the caller via printf← _callback() function (the caller can do something with the message). Or the libdwarf calling code can call dwarf_record_cmdline_options() to set the new value.

For convenience the type name for the struct is Dwarf_Cmdline_Options.

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.3 Dwarf Debug Fission Per CU s Struct Reference

Data Fields

- const char * pcu_type
- Dwarf_Unsigned pcu_index
- Dwarf_Sig8 pcu_hash
- Dwarf Unsigned pcu offset [12]
- Dwarf_Unsigned pcu_size [12]
- Dwarf Unsigned unused1
- Dwarf_Unsigned unused2

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.4 Dwarf_Form_Data16_s Struct Reference

Data Fields

• unsigned char fd_data [16]

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.5 Dwarf_Macro_Details_s Struct Reference

#include <libdwarf.h>

Data Fields

- Dwarf Off dmd_offset
- Dwarf_Small dmd_type
- Dwarf_Signed dmd_lineno
- Dwarf_Signed dmd_fileindex
- char * dmd macro

10.5.1 Detailed Description

This applies to DWARF3, and DWARF4 compilation units. DWARF5 .debug_macro has its own function interface which does not use this struct.

The documentation for this struct was generated from the following file:

• /home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.6 Dwarf Obj Access Interface a s Struct Reference

Data Fields

- void * ai_object
- const Dwarf Obj Access Methods a * ai methods

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.7 Dwarf Obj Access Methods a s Struct Reference

#include <libdwarf.h>

Data Fields

- int(* om_get_section_info)(void *obj, Dwarf_Unsigned section_index, Dwarf_Obj_Access_Section_a *return_section, int *error)
- Dwarf_Small(* om_get_byte_order)(void *obj)
- Dwarf Small(* om get length size)(void *obj)
- Dwarf_Small(* om_get_pointer_size)(void *obj)
- Dwarf_Unsigned(* om_get_filesize)(void *obj)
- Dwarf_Unsigned(* om_get_section_count)(void *obj)
- int(* **om_load_section**)(void *obj, Dwarf_Unsigned dw_section_index, Dwarf_Small **dw_return_data, int *dw_error)
- int(* om_relocate_a_section)(void *obj, Dwarf_Unsigned section_index, Dwarf_Debug dbg, int *error)
- int(* om_load_section_a)(void *obj, Dwarf_Unsigned dw_section_index, enum Dwarf_Sec_Alloc_Pref *dw_alloc_pref, Dwarf_Small **dw_return_data_ptr, Dwarf_Unsigned *dw_return_data_len, Dwarf_Small **dw_return_mmap_base_ptr, Dwarf_Unsigned *dw_return_mmap_offset, Dwarf_Unsigned *dw_return → _mmap_len, int *dw_error)
- void(* om_finish)(void *obj)

10.7.1 Detailed Description

The functions we need to access object data from libdwarf are declared here.

Unless you are reading object sections with your own code (as in scrobin/dwarfexample/jitreader.c) you will not need to fill in or use the struct.

om_relocate_a_section uses malloc/read to get section contents and returns a pointer to the malloc space through dw return data, which is recorded in the applicable section data.

om_load_section_a uses either malloc/read or mmap and consequently returns more data as needed for eventual free() or munmap().

The documentation for this struct was generated from the following file:

• /home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.8 Dwarf_Obj_Access_Section_a_s Struct Reference

Data Fields

- · const char * as name
- · Dwarf Unsigned as type
- Dwarf_Unsigned as_flags
- Dwarf_Addr as_addr
- Dwarf_Unsigned as_offset
- Dwarf_Unsigned as_size
- Dwarf_Unsigned as_link
- Dwarf_Unsigned as_info
- Dwarf_Unsigned as_addralign
- Dwarf_Unsigned as_entrysize

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.9 Dwarf_Printf_Callback_Info_s Struct Reference

#include <libdwarf.h>

Data Fields

- void * dp_user_pointer
- dwarf_printf_callback_function_type dp_fptr
- char * dp_buffer
- unsigned int dp_buffer_len
- int dp_buffer_user_provided
- void * dp_reserved

10.9.1 Detailed Description

If one wishes to print detailed line table information one creates an instance of this struct and fills in the fields and passes the struct to the relevant init, for example, dwarf_init_path().

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.10 Dwarf Ranges s Struct Reference

Data Fields

- Dwarf_Addr dwr_addr1
- Dwarf_Addr dwr_addr2
- enum Dwarf_Ranges_Entry_Type dwr_type

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.11 Dwarf_Regtable3_s Struct Reference

Data Fields

- struct Dwarf_Regtable_Entry3_s rt3_cfa_rule
- Dwarf_Half rt3_reg_table_size
- struct Dwarf_Regtable_Entry3_s * rt3_rules

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.12 Dwarf_Regtable_Entry3_s Struct Reference

Data Fields

- · Dwarf Small dw offset relevant
- Dwarf_Small dw_value_type
- · Dwarf Half dw regnum
- Dwarf_Unsigned dw_offset
- Dwarf_Unsigned dw_args_size
- Dwarf_Block dw_block

The documentation for this struct was generated from the following file:

• /home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

10.13 Dwarf_Sig8_s Struct Reference

Data Fields

• char signature [8]

The documentation for this struct was generated from the following file:

/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h

Chapter 11

File Documentation

286 File Documentation

Chapter 12

checkexamples.c

checkexamples.c contains what user code should be. Hence the code typed in checkexamples.c is PUBLIC DO-MAIN and may be copied, used, and altered without any restrictions.

checkexamples.c need not be compiled routinely nor should it ever be executed.

To verify syntatic correctness compile in the libdwarf-code/doc directory with:

```
cc -c -Wall -00 -Wpointer-arith \
  -Wdeclaration-after-statement \
  -Wextra -Wcomment -Wformat -Wpedantic -Wuninitialized \
  -Wno-long-long -Wshadow -Wbad-function-cast \
  -Wmissing-parameter-type -Wnested-externs \
  -I../src/lib/libdwarf checkexamples.c
```

- 12.1 /home/davea/dwarf/code/src/bin/dwarfexample/jitreader.c File Reference
- 12.2 /home/davea/dwarf/code/src/bin/dwarfexample/showsectiongroups.c File Reference

288 checkexamples.c

Chapter 13

dwarf.h

dwarf.h contains all the identifiers such as DW_TAG_compile_unit etc from the various versions of the DWARF Standard beginning with DWARF2 and containing all later Dwarf Standard identifiers.

In addition, it contains all user-defined identifiers that we have been able to find.

All identifiers here are C defines with the prefix "DW_".

13.1 dwarf.h

Go to the documentation of this file.

```
00001 /
00002 Copyright (C) 2000-2006 Silicon Graphics, Inc. All Rights Reserved.
00003 Portions Copyright 2002-2010 Sun Microsystems, Inc. All rights reserved.
00004 Portions Copyright 2007-2023 David Anderson. All rights reserved.
00005
00006 This program is free software; you can redistribute it
00007 and/or modify it under the terms of version 2.1 of the
{\tt 00008}~{\tt GNU}~{\tt Lesser}~{\tt General}~{\tt Public}~{\tt License}~{\tt as}~{\tt published}~{\tt by}~{\tt the}~{\tt Free}
00009 Software Foundation.
00010
00011 This program is distributed in the hope that it would be
00012 useful, but WITHOUT ANY WARRANTY; without even the implied
00013 warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00014 PURPOSE.
00015
00016 Further, this software is distributed without any warranty
00017 that it is free of the rightful claim of any third person
00018 regarding infringement or the like. Any license provided
00019 herein, whether implied or otherwise, applies only to this
00020 software file. Patent licenses, if any, provided herein 00021 do not apply to combinations of this program with other
00022 software, or any other product whatsoever.
00024 You should have received a copy of the GNU Lesser General
00025 Public License along with this program; if not, write the
00026 Free Software Foundation, Inc., 51 Franklin Street - Fifth
00027 Floor, Boston MA 02110-1301, USA.
00028 */
00029
00044 #ifndef __DWARF_H
00045 #define __DWARF_H
00046 #ifdef __cplusplus
00047 extern "C" {
00048 #endif
00049
00050 /*
00051
           dwarf.h DWARF debugging information values
          $Revision: 1.41 $
00052
                                 $Date: 2006/04/17 00:09:56 $
00053
00054
           The comment "DWARF3" appears where there are
00055
          new entries from DWARF3 as of 2004, "DWARF3f"
           where there are new entries as of the November 2005
```

```
public review document and other comments apply
00058
           where extension entries appear.
00059
00060
          Extensions part of DWARF4 are marked DWARF4.
00061
00062
          A few extension names have omitted the 'vendor id'
          (See chapter 7, "Vendor Extensibility"). Please
00064
          always use a 'vendor id' string in extension names.
00065
00066
          Vendors should use a vendor string in names and
00067
          wherever possible avoid duplicating values used by
00068
          other vendor extensions
00069
00070
          The DWARF1 comments indicate values unused in
00071
          DWARF2 and later but used or reserved in DWARF1.
00072 */
00073
00074 #define DW_TAG_array_type
                                                0 \times 01
00075 #define DW_TAG_class_type
                                                0x02
00076 #define DW_TAG_entry_point
00077 #define DW_TAG_enumeration_type
00078 #define DW_TAG_formal_parameter
                                                0×05
00079 /* TAG_global_subroutine
00080 /* TAG_global_variable
                                                0x06 DWARF1 only */
                                                0x07 DWARF1 only */
00081 #define DW_TAG_imported_declaration
                                                0x08
00082 /* reserved by DWARF1
                                                0x09 DWARF1 only */
00083 #define DW_TAG_label
                                                0x0a
00084 #define DW_TAG_lexical_block
                                                0x0b
00085 /* TAG_local_variable
                                                0x0c DWARF1 only. */
00086 #define DW_TAG_member
                                                0x0d
00087 /* reserved by DWARF1
                                                0x0e DWARF1 onlv */
00088 #define DW_TAG_pointer_type
                                                0x0f
00089 #define DW_TAG_reference_type
00090 #define DW_TAG_compile_unit
                                                0x11
00091 #define DW_TAG_string_type
                                                0 \times 12
00092 #define DW_TAG_structure_type
                                                0x13
00093 /* TAG_subroutine
                                                0x14 DWARF1 only */
00094 #define DW_TAG_subroutine_type
00095 #define DW_TAG_typedef
00096 #define DW_TAG_union_type
00097 #define DW_TAG_unspecified_parameters
                                                0×18
00098 #define DW_TAG_variant
                                                0 \times 19
00099 #define DW_TAG_common_block
                                                0x1a
00100 #define DW_TAG_common_inclusion
                                                0x1b
00101 #define DW_TAG_inheritance
00102 #define DW_TAG_inlined_subroutine
00103 #define DW_TAG_module
                                                0x1e
00104 #define DW_TAG_ptr_to_member_type 00105 #define DW_TAG_set_type
                                                0x1f
                                                0x20
00106 #define DW_TAG_subrange_type
                                                0x21
00107 #define DW_TAG_with_stmt
                                                0x22
00108 #define DW_TAG_access_declaration
00109 #define DW_TAG_base_type
                                                0 \times 2.4
00110 #define DW_TAG_catch_block
                                                0×25
00111 #define DW_TAG_const_type
                                                0x26
00112 #define DW_TAG_constant
                                                0x27
00113 #define DW_TAG_enumerator
00114 #define DW_TAG_file_type
                                                0x29
00115 #define DW_TAG_friend
00116 #define DW_TAG_namelist
                                                0x2h
        /* Early releases of this header had the following
00117
                  misspelled with a trailing 's' \star/
00118
00120 #define DW_TAG_namelist_items
                                                0x2c /* SGI misspelling/typo*/
00121 #define DW_TAG_packed_type
                                                0x2d
00122 #define DW_TAG_subprogram
                                               0x2e
00123 /* The DWARF2 document had two spellings of the following
                   two TAGs, DWARF3 specifies the longer spelling. */
00124
00126 #define DW_TAG_template_type_param
                                                0x2f /* DWARF2 inconsistent*/
00127 #define DW_TAG_template_value_parameter 0x30 /* DWARF all versions*/
00128 #define DW_TAG_template_value_param 0x30 /* SGI misspelling/typo*/
00129 #define DW_TAG_thrown_type
                                                0 \times 31
00130 #define DW_TAG_try_block
                                                0x32
00131 #define DW_TAG_variant_part
                                                0x33
0x34

0x35

00134 #define DW_TAG_dwarf_procedure 0x36 /* DWARF3 */
00135 #define DW_TAG_restrict_type 0x37 /* DWARF3 */
00136 #define DW_TAG_interface_type 0x38 /* DWARF3 */
00137 #define DW_TAG_namespace 0x39 /* DWARF3 */
00138 #define DW_TAG_imported_module 0x3a /* DWARF3 */
00139 #define DW_TAG_unspecified_type 0x30 /* DWARF3 */
00140 #define DW_TAG_namespace 0x30 /* DWARF3 */
00141 #define DW_TAG_imported_unit
             00142
00143 #define DW_TAG_mutable_type 0x3e /*Withdrawn from DWARF3 by DWARF3f*/
```

```
00144 #define DW_TAG_condition
                                                               0x40 /* DWARF3f */
0x41 /* DWARF4 */
00145 #define DW_TAG_shared_type
00146 #define DW_TAG_type_unit
00147 #define DW_TAG_rvalue_reference_type
                                                               0x42 /* DWARF4 */
                                                               0x43 /* DWARF4 */
0x44 /* DWARF5 */
0x45 /* DWARF5 */
00148 #define DW_TAG_template_alias
00149 #define DW_TAG_coarray_type
00150 #define DW_TAG_generic_subrange
00151 #define DW_TAG_dynamic_type
                                                               0x46 /* DWARF5 */
00152 #define DW_TAG_atomic_type
                                                               0x47 /* DWARF5 */
00153 #define DW_TAG_call_site
                                                               0x48 /* DWARF5 */
00154 #define DW_TAG_call_site_parameter
00155 #define DW_TAG_skeleton_unit
00156 #define DW_TAG_immutable_type
                                                               0x49 /* DWARF5 */
                                                               0x4a /* DWARF5 */
00156 #define DW_TAG_immutable_type
                                                               0x4b /* DWARF5 */
00158 /* TI = Texas Instruments, for DWARF in COFF */
00159 /* https://www.ti.com/lit/an/spraab5/spraab5.pdf?ts=1705994928599 */  
00160
00161 #define DW TAG TI far type
                                                                0x4080 /* TI */
00162 #define DW_TAG_lo_user
                                                               0x4080 /* TI */
00163 #define DW_TAG_MIPS_loop
00164 #define DW_TAG_TI_near_type
                                                                0x4081 /* TI */
00165 #define DW_TAG_TI_assign_register
                                                               0x4082 /* TI */
                                                               0x4083 /* TI */
00166 #define DW_TAG_TI_ioport_type
00167 #define DW_TAG_TI_restrict_type
                                                               0×4084 /* TT */
00168 #define DW_TAG_TI_onchip_type
                                                               0x4085 /* TI */
00170 /* HP extensions: ftp://ftp.hp.com/pub/lang/tools/\
00171 WDB/wdb-4.0.tar.gz */
00172 #define DW_TAG_HP_array_descriptor
                                                               0x4090 /* HP */
00173
00174 /\star GNU extensions. The first 3 missing the GNU_. \star/
                                                      0x4101 /* GNU. Fortran. */
00175 #define DW_TAG_format_label
00176 #define DW_TAG_function_template
                                                               0x4102 /* GNU. For C++ */
00176 #define DW_TAG_class_template
                                                               0x4103 /* GNU. For C++ */
00178 #define DW_TAG_GNU_BINCL
                                                               0x4104 /* GNU */
00179 #define DW_TAG_GNU_EINCL
                                                               0x4105 /* GNU */
00180
00181 /* GNU extension. http://gcc.gnu.org/wiki/TemplateParmsDwarf */
00182 #define DW_TAG_GNU_template_template_parameter 0x4106 /* GNU */
00183 #define DW_TAG_GNU_template_template_param
                                                                          0x4106 /* GNU */
00184 #define DW_TAG_GNU_template_parameter_pack
                                                                          0x4107 /* GNU */
00185 #define DW_TAG_GNU_formal_parameter_pack
                                                                         0×4108 /* GNU */
00186
00187 #define DW_TAG_GNU_call_site
                                                                           0x4109 /* GNU */
                                                                         0x410a /* GNU */
00188 #define DW_TAG_GNU_call_site_parameter
00189
00190 /* The following are SUN extensions */
0x4203 /* SUN */
00193 #define DW TAG SUN struct template
                                                                0x4204 /* SUN */
00194 #define DW_TAG_SUN_union_template
00195 #define DW_TAG_SUN_indirect_inheritance 0x4205 /* SUN */
00197 #define DW_TAG_SUN_memop_inro
00198 #define DW_TAG_SUN_omp_child_func
00199 #define DW_TAG_SUN_rtti_descriptor
000199 #define DW_TAG_SUN_rtti_descriptor
000190 #define DW_TAG_SUN_memop_inro
000190 #define DW_TAG_SUN_omp_child_func
000190 #define DW_TAG_SUN_rtti_descriptor
000190 #define DW_TAG_SUN_rtti_descriptor
000190 #define DW_TAG_SUN_rtti_descriptor
000190 #define DW_TAG_SUN_omp_child_func
000190 #define DW_TAG_SUN_rtti_descriptor
00203 #define DW_TAG_SUN_fortran_vax_structure 0x420d /* SUN */
00204 #define DW_TAG_SUN_hi 0x42ff /* SUN */
00205
00206 /* ALTIUM extensions */
            /* DSP-C/Starcore __circ qualifier */
00208 #define DW_TAG_ALTIUM_circ_type
                                                                0x5101 /* ALTIUM */
         /* Starcore __mwa_circ qualifier */
00209
00210 #define DW_TAG_ALTIUM_mwa_circ_type
                                                               0x5102 /* ALTIUM */
00211 /* Starcore __rev_carry qualifier */
00212 #define DW_TAG_ALTIUM_rev_carry_type
                                                               0x5103 /* ALTIUM */
00213 /* M16 __rom qualifier */
00214 #define DW_TAG_ALTIUM_rom
                                                               0x5111 /* ALTIUM */
00215
00216 #define DW_TAG_LLVM_annotation
                                                               0x6000 /* September 2021*/
00217
00218 /* GHS C */
00219 #define DW_TAG_ghs_namespace
00220 #define DW_TAG_ghs_using_namespace
                                                               0x8005
00221 #define DW_TAG_ghs_using_declaration
                                                             0x8006
00222 #define DW_TAG_ghs_template_templ_param 0x8007
00223
00224 /* The following 3 are extensions to support UPC */
00226 #define DW_TAG_upc_strict_type
                                                               0x8766 /* UPC */
00227 #define DW_TAG_upc_relaxed_type
                                                               0x8767 /* UPC */
00228
00229 /* PGI (STMicroelectronics) extensions. */
00230 #define DW TAG PGI kanji type
                                                                0xa000 /* PGI */
```

```
00231 #define DW_TAG_PGI_interface_block
                                                    0xa020 /* PGI */
00233 #define DW_TAG_BORLAND_property
                                                          0xb000
00234 #define DW_TAG_BORLAND_Delphi_string
                                                         0xb001
00235 #define DW_TAG_BORLAND_Delphi_dynamic_array 0xb002 00236 #define DW_TAG_BORLAND_Delphi_set 0xb003
                                                         0xb003
00237 #define DW_TAG_BORLAND_Delphi_variant
00238
00239 #define DW_TAG_hi_user
                                                   Oxffff
00240
00241 /\star~ The following two are non-standard. Use DW_CHILDREN_yes
00242 and DW_CHILDREN_no instead. These could
00243
          probably be deleted, but someone might be using them,
00244
           so they remain. */
00245 #define DW_children_no
00246 #define DW_children_yes
00247
00248 #define DW FORM addr
                                                    0x01
00249 /* FORM_REF
                                                    0x02 DWARF1 only */
00250 #define DW_FORM_block2
00251 #define DW_FORM_block4
                                                    0x04
00252 #define DW_FORM_data2
                                                    0×05
00253 #define DW_FORM_data4
                                                    0x06
00254 #define DW FORM data8
                                                    0 \times 0.7
00255 #define DW_FORM_string
                                                    0x08
00256 #define DW_FORM_block
00257 #define DW_FORM_block1
                                                    0x0a
00258 #define DW_FORM_data1
                                                    0x0b
00259 #define DW_FORM_flag
                                                    0x0c
00260 #define DW_FORM_sdata
                                                    0x0d
00261 #define DW_FORM_strp
                                                    0x0e
00262 #define DW_FORM_udata
                                                     0×0f
00263 #define DW_FORM_ref_addr
00264 #define DW_FORM_ref1
                                                    0x11
00265 #define DW_FORM_ref2
                                                    0 \times 12
00266 #define DW_FORM_ref4
                                                    0x13
00267 #define DW_FORM_ref8
                                                    0x14
                                           0x14

0x15

0x16

0x17 /* DWARF4 */

0x18 /* DWARF4 */

0x19 /* DWARF4 */

0x1a /* DWARF5 */

0x1c /* DWARF5 */

0x1c /* DWARF5 */

0x1d /* DWARF5 */

0x1e /* DWARF5 */

0x1e /* DWARF5 */

0x21 /* DWARF5 */

0x21 /* DWARF5 */

0x22 /* DWARF5 */

0x22 /* DWARF5 */

0x24 /* DWARF5 */

0x25 /* DWARF5 */

0x26 /* DWARF5 */

0x27 /* DWARF5 */

0x27 /* DWARF5 */

0x28 /* DWARF5 */

0x28 /* DWARF5 */
00268 #define DW_FORM_ref_udata
                                                    0x15
00269 #define DW_FORM_indirect
00270 #define DW_FORM_sec_offset
00271 #define DW_FORM_exprloc
00272 #define DW_FORM_flag_present
00273 #define DW_FORM_strx
00274 #define DW_FORM_addrx
00275 #define DW_FORM_ref_sup4
00276 #define DW_FORM_strp_sup
00277 #define DW_FORM_data16
00278 #define DW_FORM_line_strp
00279 #define DW_FORM_ref_sig8
00280 #define DW_FORM_implicit_const
00281 #define DW_FORM_loclistx
00282 #define DW_FORM_rnglistx
00283 #define DW_FORM_ref_sup8
00284 #define DW_FORM_strx1
00285 #define DW_FORM_strx2
                                                   0x27 /* DWARF5 */
0x28 /* DWARF5 */
00286 #define DW_FORM_strx3
00287 #define DW_FORM_strx4
00288 #define DW_FORM_addrx1
                                                    0x29 /* DWARF5 */
00289 #define DW_FORM_addrx2
                                                    0x2a /* DWARF5 */
                                                    0x2b /* DWARF5 */
00290 #define DW_FORM_addrx3
00291 #define DW FORM addrx4
                                                    0x2c /* DWARF5 */
00292
00293 /* Extensions http://gcc.gnu.org/wiki/DebugFission. */
00294 #define DW_FORM_GNU_addr_index 0x1f01 /* GNU, debug_info.dwo.*/
00295
00296 /* GNU, somewhat like DW_FORM_strp */
00297 #define DW_FORM_GNU_str_index 0x1f02
00298
00299 #define DW_FORM_GNU_ref_alt 0x1f20 /* GNU, Offset in .debuq_info. */
00301 /\star GNU extension. Offset in .debug_str of another object file. \star/
00302 #define DW_FORM_GNU_strp_alt 0x1f21
00303
00304 #define DW FORM LLVM addrx offset
                                                   0x2001
00305
00306 #define DW_AT_sibling
                                                              0x01
00307 #define DW_AT_location
                                                              0x02
00308 #define DW_AT_name
                                                              0x03
00309 /* reserved DWARF1
                                                              0x04, DWARF1 only */
00310 /* AT_fund_type
                                                              0x05, DWARF1 only */
00311 /* AT_mod_fund_type
                                                              0x06, DWARF1 only */
00312 /* AT_user_def_type
                                                              0x07, DWARF1 only */
00313 /* AT_mod_u_d_type
                                                              0x08, DWARF1 only */
00314 #define DW_AT_ordering
                                                              0×09
00315 #define DW_AT_subscr_data
                                                              0x0a
00316 #define DW_AT_byte_size
                                                              0 \times 0 b
00317 #define DW_AT_bit_offset
                                                              0x0c
```

```
00318 #define DW_AT_bit_size
 00319 /* reserved DWARF1
                                                                                                     0x0d, DWARF1 only */
 00320 #define DW_AT_element_list
                                                                                                     0x0f
 00321 #define DW_AT_stmt_list
                                                                                                     0 \times 10
 00322 #define DW_AT_low_pc
                                                                                                     0 \times 11
 00323 #define DW_AT_high_pc
                                                                                                     0x12
 00324 #define DW_AT_language
                                                                                                     0x13
00325 #define DW_AT_member
00326 #define DW_AT_discr
                                                                                                     0x15
00327 #define DW_AT_discr_value
                                                                                                    0x16
00328 #define DW_AT_visibility
                                                                                                    0x17
00329 #define DW_AT_import
                                                                                                    0x18
 00330 #define DW_AT_string_length
                                                                                                    0x19
 00331 #define DW_AT_common_reference
00331 #define DW_AT_comp_dir
                                                                                                    0x1b
 00333 #define DW_AT_const_value
                                                                                                    0x1c
00334 #define DW_AT_containing_type
                                                                                                    0x1d
00335 #define DW_AT_default_value
                                                                                                    0x1e
                                                                                                   0x1f */
 00336 /* reserved
 00337 #define DW_AT_inline
                                                                                                    0x20
 00338 #define DW_AT_is_optional
                                                                                                    0 \times 21
00339 #define DW_AT_lower_bound
                                                                                                    0x22
00340 /* reserved
00341 /* reserved
                                                                                                    0x23 * /
                                                                                                    0x24 * /
 00342 #define DW_AT_producer
                                                                                                     0x25
 00343 /* reserved
                                                                                                    0x26 */
 00344 #define DW_AT_prototyped
                                                                                                     0x27
00345 /* reserved
00346 /* reserved
                                                                                                    0×28 */
                                                                                                    0x29 */
00347 #define DW_AT_return_addr
                                                                                                     0x2a
00348 /* reserved
                                                                                                    0x2b */
 00349 #define DW_AT_start_scope
                                                                                                     0x2c
 00350 /* reserved
                                                                                                   0x2d */
00351 #define DW_AT_bit_stride
                                                                                                    0x2e /* DWARF3 name */
00352 #define DW_AT_stride_size
                                                                                                   0x2e /* DWARF2 name */
00353 #define DW_AT_upper_bound
                                                                                                    0x2f
00354 /* AT_virtual
                                                                                                    0x30, DWARF1 only */
 00355 #define DW_AT_abstract_origin
                                                                                                    0x31
 00356 #define DW_AT_accessibility
                                                                                                    0x32
 00357 #define DW_AT_address_class
00358 #define DW_AT_artificial
00359 #define DW_AT_base_types
                                                                                                    0×34
                                                                                                     0x35
00360 #define DW_AT_calling_convention
                                                                                                    0x36
 00361 #define DW_AT_count
                                                                                                     0x37
00362 #define DW_AT_data_member_location
00362 #GELINE DW_AI_GCOLUMN
                                                                                                    0x39
00364 #define DW_AT_decl_file
                                                                                                    0x3a
00365 #define DW_AT_decl_line
                                                                                                    0x3b
0 x 4 4
 00375 #define DW_AT_priority
                                                                                                     0x45
 00376 #define DW_AT_segment
                                                                                                     0x46
00370 #define DW_AT_sepcification
00378 #define DW_AT_static_link
00379 #define DW_AT_type
                                                                                                     0 \times 47
                                                                                                    0 \times 48
                                                                                                    0x49
 00380 #define DW_AT_use_location
                                                                                                    0x4a
 00380 #define DW_AT_use_location
00381 #define DW_AT_variable_parameter
                                                                                                   0x4b
 00382 #define DW_AT_virtuality
                                                                                                    0x4c
00382 #define DW_AT_vtable_elem_location
00384 #define DW AT allocated
                                                                                                   0x4d
0x4e /* DWARF3 */
00385 #define DW_AT_allocated
| Ox4e /* DWARF3 */
| Ox4f /* DWARF3 */
| Ox4f /* DWARF3 */
| Ox50 /* DWARF3 */
| Ox50 /* DWARF3 */
| Ox50 /* DWARF3 */
| Ox51 /* DWARF3 */
| Ox51 /* DWARF3 */
| Ox52 /* DWARF3 */
| Ox53 /* DWARF3 */
| Ox54 /* DWARF3 */
| Ox55 /* DWARF3 */
| Ox55 /* DWARF3 */
| Ox56 /* DWARF3 */
| Ox57 /* DWARF3 */
| Ox57 /* DWARF3 */
| Ox58 /* DWARF3 */
| Ox58
00390 #define DW_AT_use_UTF8
00391 #define DW_AT_extension
                                                                     0x54 /* DWARF3 */
0x55 /* DWARF3 */
0x56 /* DWARF3 */
0x57 /* DWARF3 */
0x58 /* DWARF3 */
0x59 /* DWARF3 */
0x59 /* DWARF3 */
0x5a /* DWARF3 */
0x5b /* DWARF3 */
0x5b /* DWARF3f */
0x5d /* DWARF3f */
0x5d /* DWARF3f */
0x5d /* DWARF3f */
0x5f /* DWARF3f */
0x5f /* DWARF3f */
0x60 /* DWARF3f */
0x61 /* DWARF3f */
                                                                                                    0x54 /* DWARF3 */
 00392 #define DW_AT_ranges
 00393 #define DW_AT_trampoline
 00394 #define DW_AT_call_column
 00395 #define DW_AT_call_file
 00396 #define DW_AT_call_line
 00397 #define DW_AT_description
 00398 #define DW_AT_binary_scale
 00399 #define DW_AT_decimal_scale
 00400 #define DW_AT_small
 00401 #define DW_AT_decimal_sign
 00402 #define DW_AT_digit_count
00403 #define DW_AT_picture_string
00404 #define DW_AT_mutable
```

```
00405 #define DW_AT_threads_scaled
                                                                  0x62 /* DWARF3f */
                                                                 0x63 /* DWARF3f */
0x64 /* DWARF3f */
00406 #define DW_AT_explicit
00407 #define DW_AT_object_pointer
                                                                  0x65 /* DWARF3f */
00408 #define DW_AT_endianity
00409 #define DW_AT_elemental
                                                                  0x66 /* DWARF3f */
00410 #define DW_AT_pure
                                                                  0x67 /* DWARF3f */
                                                                0x67 /* DWARF31 */
0x68 /* DWARF3 */
0x69 /* DWARF4 */
0x6a /* DWARF4 */
0x6b /* DWARF4 */
0x6c /* DWARF4 */
0x6d /* DWARF4 */
0x6d /* DWARF4 */
00411 #define DW_AT_recursive
00412 #define DW_AT_signature
00413 #define DW_AT_main_subprogram
00414 #define DW_AT_data_bit_offset
00415 #define DW_AT_const_expr
00416 #define DW_AT_enum_class
                                                        0x6e /* DWARF4 */
0x6f /* DWARF5 */
0x70 /* DWARF5 */
00417 #define DW_AT_linkage_name
00418 #define DW_AT_string_length_bit_size
00419 #define DW_AT_string_length_byte_size
                                                                 0x71 /* DWARF5 */
0x72 /* DWARF5 */
00420 #define DW_AT_rank
00421 #define DW_AT_str_offsets_base
                                                                  0x73 /* DWARF5 */
00422 #define DW AT addr base
00423 /* Use DW_AT_rnglists_base, DW_AT_ranges_base is obsolete as */
00424 /* it was only used in some DWARF5 drafts, not the final DWARF5. */
00425 #define DW_AT_rnglists_base
                                                                  0x74 /* DWARF5 */
00426 /* DW_AT_dwo_id, an experiment in some DWARF4+. Not DWARF5! \star/
                                                                 0x75 /* DWARF4!*/
00427 #define DW_AT_dwo_id
00428 #define DW_AT_dwo_name
                                                                   0x76 /* DWARF5 */
00429 #define DW_AT_reference
                                                                   0x77 /* DWARF5 */
00430 #define DW_AT_rvalue_reference
                                                                  0x78 /* DWARF5 */
                                                        0x78 /* DWARF5 */
0x78 /* DWARF5 */
0x7a /* DWARF5 */
0x7c /* DWARF5 */
0x7c /* DWARF5 */
0x7d /* DWARF5 */
0x7d /* DWARF5 */
0x7f /* DWARF5 */
0x81 /* DWARF5 */
0x81 /* DWARF5 */
0x82 /* DWARF5 */
0x83 /* DWARF5 */
0x83 /* DWARF5 */
0x84 /* DWARF5 */
0x85 /* DWARF5 */
0x86 /* DWARF5 */
0x87 /* DWARF5 */
0x88 /* DWARF5 */
0x88 /* DWARF5 */
0x88 /* DWARF5 */
0x88 /* DWARF5 */
0x8b /* DWARF5 */
0x8b /* DWARF5 */
00431 #define DW_AT_macros
                                                                  0x79 /* DWARF5 */
00432 #define DW_AT_call_all_calls
00433 #define DW_AT_call_all_source_calls
00434 #define DW_AT_call_all_tail_calls
00435 #define DW_AT_call_return_pc
00436 #define DW_AT_call_value
00437 #define DW_AT_call_origin
00438 #define DW_AT_call_parameter
00439 #define DW_AT_call_pc
00440 #define DW_AT_call_tail_call
00441 #define DW_AT_call_target
00442 #define DW_AT_call_target_clobbered
00443 #define DW_AT_call_data_location
00444 #define DW_AT_call_data_value
00445 #define DW_AT_noreturn
00443 #define DW_AT_noietuin
00446 #define DW_AT_alignment
00447 #define DW_AT_export_symbols
00448 #define DW_AT_deletted
00449 #define DW_AT_defaulted
00450 #define DW AT loclists base
00450 #define DW_AT_loclists_base
                                                                  0x8c /* DWARF5 */
00451 /\star~ As of 6 January 2025 the DWARF committee promises
00452
00453
           not to change the name or the assigned number of
           the following two attributes. So
           compilers are free to use these now with DWARF 5
00454
        or earlier. The applicable FORMs of are
of form class constant (See DWARF5 Section 7.5.5 Classes
00456
00457
           and Forms). \star/
00458 #define DW_AT_language_name
                                                                  0×90 /* DWARE6 */
00459 #define DW_AT_language_version
                                                                  0x91 /* DWARF6 */
00460
00461 /* GreenHills, ghs.com GHS C */
00462 #define DW_AT_ghs_namespace_alias 0x806
00463 #define DW_AT_ghs_using_namespace 0x807
00464 #define DW_AT_ghs_using_declaration 0x808
00465
00466 /\star~ In extensions, we attempt to include the vendor extension
            in the name even when the vendor leaves it out. */
00468 #define DW_AT_HP_block_index
                                                                   0x2000 /* HP */
00469 /* 0x2000 follows extension so dwarfdump prints the 00470 most-likely-useful name. */
00471 #define DW_AT_lo_user
                                                                  0 \times 2000
00472
00473 #define DW_AT_TI_veneer
                                                                  0x2000 /* TI */
00475 #define DW_AT_MIPS_fde
                                                                  0x2001 /* MIPS/SGI */
00476 #define DW_AT_TI_symbol_name
                                                                  0x2001 /* TI */
                                                                  0x2002 /* MIPS/SGT */
00477 #define DW_AT_MIPS_loop_begin
00478 #define DW_AT_MIPS_tail_loop_begin
                                                                  0x2003 /* MIPS/SGI */
00482 #define DW_AT_MIPS_linkage_name 0x2007 /* MIPS/SGI,GNU,and others.*/
                                                  0x2008 /* MIPS/SGI */
0x2009 /* MIPS/SGI */
00483 #define DW_AT_MIPS_stride
00484 #define DW_AT_MIPS_abstract_name
00485 #define DW_AT_MIPS_clone_origin
                                                                   0x200a /* MIPS/SGI */
                                                                  0x200b /* MIPS/SGI */
00486 #define DW_AT_MIPS_has_inlines
                                                                 0x200b /* MIPS/SGI */
0x200b /* TI */
0x200c /* MIPS/SGI */
0x200c /* TI */
0x200d /* MIPS/SGI */
0x200d /* MIPS/SGI */
00487 #define DW_AT_TI_version
00488 #define DW_AT_MIPS_stride_byte
00489 #define DW_AT_TI_asm
00490 #define DW_AT_MIPS_stride_elem
00491 #define DW_AT_MIPS_ptr_dopetype
                                                                   0x200e /* MIPS/SGI */
```

```
00492 #define DW_AT_TI_skeletal
                                                         0x200e /* TI */
00493 #define DW_AT_MIPS_allocatable_dopetype
                                                     0x200f /* MIPS/SGI */
0x2010 /* MIPS/SGI */
00494 #define DW_AT_MIPS_assumed_shape_dopetype
00495 #define DW_AT_MIPS_assumed_size
                                                          0x2011 /* MIPS/SGI */
                                                         0x2011 /* TI */
00496 #define DW_AT_TI_interrupt
00497
00498 /\star HP extensions. \star/
00502 #define DW_AT_HP_actuals_stmt_list 0x2010 /* conflict: MIPS */
00503 #define DW_AT_HP_proc_per_section 0x2011 /* conflict: MIPS */
00504 #define DW_AT_HP_raw_data_ptr
                                                          0x2012 /* HP */
00505 #define DW_AT_HP_pass_by_reference
                                                          0x2013 /* HP */
00506 #define DW_AT_HP_opt_level
                                                          0x2014 /* HP */
00507 #define DW_AT_HP_prof_version_id
                                                         0x2015 /* HP */
00508 #define DW_AT_HP_opt_flags
00509 #define DW_AT_HP_cold_region_low_pc
                                                         0x2016 /* HP */
                                                         0x2017 /* HP */
00510 #define DW_AT_HP_cold_region_high_pc
                                                         0x2018 /* HP */
00511 #define DW_AT_HP_all_variables_modifiable
                                                         0x2019 /* HP */
00512 #define DW_AT_HP_linkage_name
                                                          0x201a /* HP */
00513 #define DW_AT_HP_prof_flags
                                                          0x201b /* HP */
00514 #define DW_AT_HP_unit_name
                                                          0x201f /* HP */
00515 #define DW_AT_HP_unit_size
                                                         0×2020 /* HP */
                                                      0x2020 /* HP */
0x2021 /* HP */
0x2022 /* HP */
0x2023 /* HP */
0x2029 /* HP */
00516 #define DW_AT_HP_widened_byte_size
00517 #define DW_AT_HP_definition_points
00518 #define DW_AT_HP_default_location
00519 #define DW_AT_HP_is_result_param
00520
                                                        0x2001 /* COMPAQ/HP */
0x2002 /* COMPAQ/HP */
00521 #define DW_AT_CPQ_discontig_ranges
00522 #define DW_AT_CPQ_semantic_events
                                                        0x2003 /* COMPAQ/HP */
0x2004 /* COMPAQ/HP */
0x2005 /* COMPAQ/HP */
00523 #define DW_AT_CPQ_split_lifetimes_var
00524 #define DW_AT_CPQ_split_lifetimes_rtn
00525 #define DW_AT_CPQ_prologue_length
00526
00527 /* From GHS C GreenHills qhs.com */
00528 #define DW_AT_ghs_mangled
                                                     0x2007 /* conflict MIPS */
00529 #define DW_AT_ghs_rsm
                                                         0x2083
00530 #define DW_AT_ghs_frsm
                                                          0x2085
00531 #define DW_AT_ghs_frames
                                                          0x2086
00532 #define DW_AT_ghs_rso
                                                          0×2087
00533 #define DW_AT_ghs_subcpu
                                                          0 \times 2092
00534 #define DW_AT_ghs_lbrace_line
                                                          0 \times 2093
00536 #define DW_AT_INTEL_other_endian 0x2026 /* Intel, 1 if byte swapped.*/
00537
00538 /* GNU extensions. */
00539 #define DW_AT_sf_names
                                                          0x2101 /* GNU */
00540 #define DW_AT_src_info
                                                          0x2102 /* GNU */
                                                          0x2103 /* GNU */
00541 #define DW AT mac info
                                                          0x2104 /* GNU */
00542 #define DW_AT_src_coords
00543 #define DW_AT_body_begin
                                                          0x2105 /* GNU */
00544 #define DW_AT_body_end
                                                          0x2106 /* GNU */
00545 #define DW_AT_GNU_vector
                                                          0x2107 /* GNU */
00546
00547 /* Thread safety, see
00548 http://gcc.gnu.org/wiki/ThreadSafetyAnnotation .
00549 /* The values here are from gcc-4.6.2 include/dwarf2.h. The
00550 values are not given on the web page at all, nor on web pages 00551 it refers to. */
00552 #define DW_AT_GNU_guarded_by 0x2108 /* GNU */
00553 #define DW_AT_GNU_pt_guarded_by
                                                          0x2109 /* GNU */
00554 #define DW_AT_GNU_guarded
                                                          0x210a /* GNU */
00555 #define DW_AT_GNU_pt_guarded
                                                          0x210b /* GNU */
00556 #define DW_AT_GNU_locks_excluded
                                                         0x210c /* GNU */
                                                        0x210d /* GNU */
0x210e /* GNU */
00557 #define DW_AT_GNU_exclusive_locks_required
00558 #define DW_AT_GNU_shared_locks_required
00559
00560 /* See http://gcc.gnu.org/wiki/DwarfSeparateTypeInfo */
00561 #define DW_AT_GNU_odr_signature
                                                          0x210f /* GNU */
00562
00563 /* See See http://gcc.gnu.org/wiki/TemplateParmsDwarf */  
00564 /* The value here is from gcc-4.6.2 include/dwarf2.h. The value is 00565 not consistent with the web page as of December 2011. \star/
                                                          0x2110 /* GNU */
00566 #define DW_AT_GNU_template_name
00567 /* The GNU call site extension.
00568 See http://www.dwarfstd.org/ShowIssue.php?\
          issue=100909.2&type=open . */
00569
00570 #define DW_AT_GNU_call_site_value
                                                        0x2111 /* GNU */
00571 #define DW_AT_GNU_call_site_data_value 0x2112 /* GNU */
00572 #define DW_AT_GNU_call_site_target 0x2113 /* GNU */
00572 #define DW_AT_GNU_call_site_target
00573 #define DW_AT_GNU_call_site_target_clobbered 0x2114 /* GNU */
00574 #define DW_AT_GNU_tail_call
                                                         0x2115 /* GNU */
00574 #define DW_AT_GNU_tail_call
00575 #define DW_AT_GNU_all_tail_call_sites
                                                        0x2116 /* GNU */
00576 #define DW_AT_GNU_all_call_sites
                                                         0x2117 /* GNU */
00577 #define DW_AI_GNU_all_surce_call_sites
                                                          0x2118 /* GNU */
00578 /* Section offset to .debug_macro section. */
```

```
00579 #define DW_AT_GNU_macros
                                                        0x2119 /* GNU */
 00580 #define DW_AT_GNU_deleted
                                                        0x211a /* GNU */
00581 /* The GNU DebugFission project:
00582 http://gcc.gnu.org/wiki/DebugFission */
 00583 #define DW_AT_GNU_dwo_name
                                                       0x2130 /* GNU */
                                                        0x2131 /* GNU */
 00584 #define DW_AT_GNU_dwo_id
                                                        0x2132 /* GNU */
 00586 #define DW_AT_GNU_ranges_base
 00587 #define DW_AT_GNU_addr_base
                                                        0x2133 /* GNU */
                                                        0x2134 /* GNU */
 00588 #define DW_AT_GNU_pubnames
 00589 #define DW_AT_GNU_pubtypes
                                                        0x2135 /* GNU */
 00590
 00591 /\star To distinguish distinct basic blocks in a single source line. \star/
 00593 #define DW_AT_GNU_locviews
                                                        0x2137 /* GNU */
 00594 #define DW_AT_GNU_entry_view
                                                        0x2138 /* GNU */
 00595
 00596 /* Sun extensions */
 00597 #define DW_AT_SUN_template
                                                       0x2201 /* SUN */
                                                        0x2201 /* VMS */
 00598 #define DW_AT_VMS_rtnbeg_pd_address
 00599 #define DW_AT_SUN_alignment
                                                        0x2202 /* SUN */
 00600 #define DW_AT_SUN_vtable
                                                        0x2203 /* SUN */
 00601 #define DW_AT_SUN_count_guarantee
                                                        0x2204 /* SUN */
                                                        0×2205 /* SUN */
 00602 #define DW_AT_SUN_command_line
 00603 #define DW_AT_SUN_vbase
                                                        0x2206 /* SUN */
00604 #define DW_AT_SUN_compile_options
                                                       0x2207 /* SUN */
0x2208 /* SUN */
0x2230 /* SUN */
0x2231 /* SUN */
 00644
 00645 /* ALTIUM extension: ALTIUM Compliant location lists (flag) \star/
00646 #define DW_AT_ALTIUM_loclist 0x2300 /* ALTIUM */
00647 /* Ada GNAT gcc attributes. constant integer forms. */
00648 /* See http://gcc.gnu.org/wiki/DW_AT_GNAT_descriptive_type
           See http://gcc.gnu.org/wiki/DW_AT_GNAT_descriptive_type . */
 00649 #define DW_AT_use_GNAT_descriptive_type 0x2301
00650 #define DW AT GNAT descriptive_type 0x2302
00649 #define Dw_AT_GNAT_descriptive_type
00650 #define DW_AT_GNU_numerator
                                                       0x2303 /* GNU */
                                                        0x2304 /* GNU */
 00652 #define DW AT GNU denominator
 00653 /* See https://gcc.gnu.org/wiki/DW_AT_GNU_bias */
 00654 #define DW_AT_GNU_bias
                                                         0x2305 /* GNU */
 00655
 00656 /* Go-specific type attributes
00657 Naming as lower-case go instead of GO is a small mistake 00658 by the Go language folks, it seems. This is the
          by the Go language folks, it seems. This is the
          common spelling for these. */
 00659
 00660 #define DW_AT_go_kind
 00661 #define DW_AT_go_key
                                                         0x2901
 00662 #define DW_AT_go_elem
                                                        0x2902
 00663
 00664 /\star Attribute for DW_TAG_member of a struct type.
 00665
         Nonzero value indicates the struct field is an embedded field.*/
```

```
00666 #define DW_AT_go_embedded_field
                                                                                        0x2903
00668 #define DW_AT_go_runtime_type
                                                                                      0×2904
00669
00670 /* UPC extension. */
00671 #define DW_AT_upc_threads_scaled
                                                                                      0x3210 /* UPC */
                                                                                        0x393e
00673 #define DW_AT_IBM_wsa_addr
                                                                                        0x393f
00674 #define DW_AT_IBM_home_location
00675 #define DW_AT_IBM_alt_srcview
                                                                                        0x3940
00676
00677 /* PGI (STMicroelectronics) extensions. */
00678 /* PGI. Block, constant, reference. This attribute is an ASTPLAB 00679 extension used to describe the array local base. */
00680 #define DW_AT_PGI_lbase
00681
00682 /\star~ PGI. Block, constant, reference. ASTPLAB adds this attribute
00683
           to describe the section offset, or the offset to the
                first element in the dimension. \star/
00685 #define DW_AT_PGI_soffset
00686
00687 /\star~ PGI. Block, constant, reference. ASTPLAB adds this
00688 attribute to describe the linear stride or the distance
               between elements in the dimension. \star/
00689
00690 #define DW_AT_PGI_lstride
                                                                                        0x3a02
00692 #define DW_AT_BORLAND_property_read
                                                                                       0x3b11
00693 #define DW_AT_BORLAND_property_write
                                                                                        0x3b12
00694 #define DW_AT_BORLAND_property_implements
                                                                                        0x3b13
00695 #define DW_AT_BORLAND_property_index
00696 #define DW_AT_BORLAND_property_default
                                                                                        0x3b14
                                                                                        0x3b15
00697 #define DW_AT_BORLAND_Delphi_unit
                                                                                        0 \times 3 b 2 0
00698 #define DW_AT_BORLAND_Delphi_class
00699 #define DW_AT_BORLAND_Delphi_record
                                                                                        0x3b22
00700 #define DW_AT_BORLAND_Delphi_metaclass
                                                                                        0x3b23
00701 #define DW_AT_BORLAND_Delphi_constructor
                                                                                        0x3b24
00702 #define DW_AT_BORLAND_Delphi_destructor
                                                                                        0x3b25
00703 #define DW_AT_BORLAND_Delphi_anonymous_method
                                                                                        0x3b26
00704 #define DW_AT_BORLAND_Delphi_interface
                                                                                        0x3b27
00705 #define DW_AT_BORLAND_Delphi_ABI
                                                                                        0x3b28
00706 #define DW_AT_BORLAND_Delphi_frameptr
                                                                                        0x3h30
00707 #define DW_AT_BORLAND_closure
                                                                                        0x3b31
00708
00709 #define DW_AT_LLVM_include_path
                                                                                        0x3e00
00710 #define DW_AT_LLVM_config_macros
00711 #define DW_AT_LLVM_sysroot
                                                                                        0x3e02
00712 #define DW_AT_LLVM_tag_offset
                                                                                        0x3e03
00713 /* LLVM intends to use 0x3e04 - 0x3e06 */
00714 #define DW_AT_LLVM_apinotes
                                                                                        0x3e07
00715 /* Next 6 are for Heterogeneous debugging */
00716 #define DW_AT_LLVM_active_lane
                                                                                        0x3e08
00717 #define DW_AT_LLVM_augmentation
00718 #define DW_AT_LLVM_lanes
                                                                                        0x3e0a
00719 #define DW_AT_LLVM_lane_pc
                                                                                        0x3e0b
00720 #define DW_AT_LLVM_vector_size
                                                                                        0x3e0c
00721
00722 #define DW_AT_APPLE_optimized
                                                                                        0x3fe1
00723 #define DW_AT_APPLE_flags
                                                                                        0x3fe2
00724 #define DW_AT_APPLE_isa
                                                                                        0x3fe3
00725 /* 0x3fe4 Also known as DW_AT_APPLE_closure, block preferred. */
00726 #define DW_AT_APPLE_block
                                                                                        0x3fe4
00727 /\star The rest of APPLE here are in support of Objective C \star/
00727 / The feet of the feet o
00729 #define DW_AT_APPLE_runtime_class
00730 #define DW_AT_APPLE_omit_frame_ptr
                                                                                        0x3fe7
00731 #define DW_AT_APPLE_property_name
                                                                                       0x3fe8
00732 #define DW_AT_APPLE_property_getter
                                                                                        0x3fe9
00733 #define DW_AT_APPLE_property_setter
                                                                                        0x3fea
00734 #define DW_AT_APPLE_property_attribute
                                                                                       0x3feb
00735 #define DW_AT_APPLE_objc_complete_type
                                                                                        0x3fec
00736 #define DW_AT_APPLE_property
                                                                                        0x3fee
00737 #define DW_AT_APPLE_objc_direct
00738 #define DW_AT_APPLE_sdk
                                                                                        0x3fef
00739 #define DW_AT_APPLE_origin
                                                                                       0x3ff0
00740
00741 #define DW_AT_hi_user
00742
00743 /* OP values 0x01,0x02,0x04,0x05,0x07 are DWARF1 only \star/
00744 #define DW_OP_addr
                                                                           0×03
00745 #define DW_OP_deref
                                                                           0 \times 0.6
00746 #define DW OP constlu
                                                                           0x08
00747 #define DW_OP_const1s
                                                                           0x09
00748 #define DW_OP_const2u
00749 #define DW_OP_const2s
                                                                           0x0b
00750 #define DW_OP_const4u
                                                                           0x0c
00751 #define DW_OP_const4s
00752 #define DW_OP_const8u
                                                                           0x0d
                                                                           0x0e
```

00753	#define	DW OP const8s	0x0f
00/54	#deline	DW_OP_constu	0x10
00755	#define	DW_OP_consts	0x11
00756	#define	DW_OP_dup	0x12
00757	#define	DW_OP_drop	0x13
00758	#define	DW_OP_over	0x14
		DW_OP_pick	0x15
00760	#define	DW_OP_swap	0x16
00761	#define	DW OP rot	0x17
		DW_OP_xderef	0x18
00763	#define	DW_OP_abs	0x19
		DW_OP_and	0x1a
		DW_OP_div	0x1b
00766	#define	DW_OP_minus	0x1c
		DW_OP_mod	0x1d
00768	#define	DW_OP_mul	0x1e
00769	#define	DW_OP_neg	0x1f
		DW_OP_not	0x20
00771	#define	DW_OP_or	0x21
00772	#define	DW_OP_plus	0x22
00//3	#define	DW_OP_plus_uconst	0x23
00774	#define	DW_OP_shl	0x24
		DW_OP_shr	0x25
00776	#define	DW_OP_shra	0x26
00777	#define	DW_OP_xor	0x27
			0x28
		DW_OP_bra	
UU 779	#define	DW_OP_eq	0x29
00780	#define	DW_OP_ge	0x2a
00781		DW_OP_gt	0x2b
00782	#define	DW_OP_le	0x2c
		DW OP 1t	
			0x2d
00784	#define	DW_OP_ne	0x2e
		DW_OP_skip	0x2f
		DW_OP_lit0	0x30
00787	#define	DW_OP_lit1	0x31
			0x32
		DW_OP_lit2	
00789	#define	DW_OP_lit3	0x33
00790	#define	DW_OP_lit4	0x34
00791		DW_OP_lit5	0x35
00792	#define	DW_OP_lit6	0x36
		DW_OP_lit7	0x37
00794	#define	DW_OP_lit8	0x38
00795	#define	DW_OP_lit9	0x39
		DW_OP_lit10	0x3a
00797	#define	DW_OP_lit11	0x3b
00798	#define	DW_OP_lit12	0x3c
00799	#define	DW_OP_lit13	0x3d
00800	#define	DW_OP_lit14	0x3e
00801	#dofine	DW_OP_lit15	0x3f
00802	#define	DW_OP_lit16	0x40
00803	#define	DW_OP_lit17	0x41
00004	112-61	DW OD 14+10	0x42
00804	#deline	DW_OP_lit18	UX4Z
00805	#define	DW_OP_lit19	0x43
		DW_OP_lit20	0x44
	#deline	DW_OI_IICZO	
00807	#define	DW_OP_lit21	0x45
00808		DW_OP_lit22	0x46
		DW_OP_lit23	0x47
υυ810	#define	DW_OP_lit24	0x48
		DW_OP_lit25	0x49
υυσΙΖ	#uellne	DW_OP_lit26	0x4a
00813	#define	DW_OP_lit27	0x4b
		DW_OP_lit28	0x4c
	#aeiine	DW_OP_lit29	0x4d
00816	#define	DW_OP_lit30	0x4e
00817		DW_OP_lit31	0x4f
00818		DW_OP_reg0	0x50
00819	#define	DW_OP_reg1	0x51
		DW_OP_reg2	0x52
00821	#define	DW_OP_reg3	0x53
00822		DW_OP_reg4	0x54
		DW_OP_reg5	0x55
00824	#define	DW_OP_reg6	0x56
		DW_OP_reg7	0x57
		DW_OP_reg8	0x58
00827		DW_OP_reg9	0x59
00828		DW_OP_reg10	0x5a
00829	#define	DW_OP_reg11	0x5b
		DW_OP_reg12	0x5c
00831	#define	DW_OP_reg13	0x5d
00832		DW_OP_reg14	0x5e
		DW_OP_reg15	0x5f
00834	#define	DW_OP_reg16	0x60
		DW_OP_reg17	
			0x61
00836	#define	DW_OP_reg18	0x62
		DW_OP_reg19	0x63
00838	#define	DW_OP_reg20	0x64
00839	#define	DW_OP_reg21	0x65

```
00840 #define DW_OP_reg22
00841 #define DW_OP_reg23
00842 #define DW_OP_reg24
                                                0x68
00843 #define DW_OP_reg25
                                                0x69
00844 #define DW_OP_reg26
                                                0x6a
00845 #define DW_OP_reg27
                                                0x6b
00846 #define DW_OP_reg28
00847 #define DW_OP_reg29
00848 #define DW_OP_reg30
                                                0x6e
00849 #define DW_OP_reg31
                                                0x6f
00850 #define DW_OP_breg0
                                                0x70
00851 #define DW OP breg1
                                                0x71
00852 #define DW_OP_breg2
                                                0x72
00853 #define DW_OP_breg3
00854 #define DW_OP_breg4
                                                0x74
00855 #define DW_OP_breg5
                                                0 \times 75
00856 #define DW_OP_breg6
                                                0x76
00857 #define DW_OP_breg7
                                                0x77
00858 #define DW_OP_breg8
                                                0x78
00859 #define DW_OP_breg9
00860 #define DW_OP_breg10
00861 #define DW_OP_breg11
                                                0 \times 7 h
00862 #define DW_OP_breg12
                                                0x7c
00863 #define DW_OP_breg13
                                                0x7d
00864 #define DW_OP_breg14
                                                0x7e
00865 #define DW_OP_breg15
00866 #define DW_OP_breg16
                                                0x80
00867 #define DW_OP_breg17
                                                0×81
00868 #define DW_OP_breg18
                                                0x82
00869 #define DW_OP_breg19
                                                0x83
00870 #define DW_OP_breg20
                                                0x84
00871 #define DW_OP_breg21
                                                0x85
00872 #define DW_OP_breg22
                                                0x86
00873 #define DW_OP_breg23
                                                0×87
00874 #define DW_OP_breg24
                                                0x88
00875 #define DW_OP_breg25
                                                0x89
00876 #define DW_OP_breg26
                                                0x8a
00877 #define DW_OP_breg27
00878 #define DW_OP_breg28
00879 #define DW_OP_breg29
                                                0x8d
00880 #define DW_OP_breg30
                                                0x8e
00881 #define DW_OP_breg31
                                                0x8f
00882 #define DW_OP_regx
                                                0×90
00883 #define DW_OP_fbreg
                                                0x91
00884 #define DW_OP_bregx
00885 #define DW_OP_piece
00886 #define DW_OP_deref_size
                                               0x94
00887 #define DW_OP_xderef_size
                                               0 \times 95
00909 #define DW_OP_GNU_push_tls_address
                                               0xe0 /* GNU */
00910 #define DW_OP_WASM_location
00911 #define DW_OP_WASM_location_int
00912
00913 /\star Follows extension so dwarfdump prints the
00914 most-likely-useful name. */
 00915 #define DW_OP_lo_user
00916
00917
           /* LLVM extensions. */
00918 #define DW_OP_LLVM_form_aspace_address 0xe1
00919 #define DW_OP_LLVM_push_lane 0xe2
00920 #define DW_OP_LLVM_offset
                                                0xe3
00921 #define DW_OP_LLVM_offset_uconst
00922 #define DW_OP_LLVM_bit_offset
                                                0xe4
00923 #define DW_OP_LLVM_call_frame_entry_reg 0xe6
00924 #define DW_OP_LLVM_undefined 0xe7
00925 #define DW_OP_LLVM_aspace_bregx 0xe8
00926 #define DW_OP_LLVM_aspace_implicit_pointer 0xe9
```

```
00927 #define DW_OP_LLVM_piece_end
00928 #define DW_OP_LLVM_extend
00929 #define DW_OP_LLVM_select_bit_piece
                                                           0xec
         /* HP extensions. */
00930
00931 #define DW_OP_HP_unknown
                                                            0xe0 /* HP conflict: GNU */
00932 #define DW_OP_HP_is_value
                                                            0xe1 /* HP */
00933 #define DW_OP_HP_fltconst4
00934 #define DW_OP_HP_fltconst8
                                                           0xe3 /* HP */
00935 #define DW_OP_HP_mod_range
                                                           0xe4 /* HP */
                                                           0xe5 /* HP */
00936 #define DW_OP_HP_unmod_range
00937 #define DW_OP_HP_tls
                                                           0xe6 /* HP */
00938
00939 /* Intel: made obsolete by DW_OP_bit_piece above. */
00940 #define DW_OP_INTEL_bit_piece
00941
00942 /* Apple extension. */
                                                           0xf0 /* GNU */
00943 #define DW_OP_GNU_uninit

      00943 #define DW_OP_GNU_uninit
      0xf0 /* GNU */

      00944 #define DW_OP_APPLE_uninit
      0xf0 /* Apple */

      00945 #define DW_OP_GNU_encoded_addr
      0xf1 /* GNU */

      00946 #define DW_OP_GNU_implicit_pointer
      0xf2 /* GNU */

      00947 #define DW_OP_GNU_entry_value
      0xf3 /* GNU */

      00948 #define DW_OP_GNU_const_type
      0xf4 /* GNU */

      00950 #define DW_OP_GNU_regval_type
      0xf5 /* GNU */

      00951 #define DW_OP_GNU_deref_type
      0xf6 /* GNU */

      00952 #define DW_OP_GNU_convert
      0xf7 /* GNU */

      00953 #define DW_OP_GNU_parameter_ref
      0xfa /* GNU */

      00954 #define DW_OP_GNU_addr_index
      0xfb /* GNU */

      00955 #define DW_OP_GNU_const_index
      0xfb /* GNU Fission */

      00956 #define DW_OP_GNU_variable_value
      0xfd /* GNU 2017 */

00956 #define DW_OP_GNU_variable_value
                                                           0xfd /* GNU 2017 */
00959 #define DW_OP_hi_user
                                                           0xff
00960
00961 #define DW_ATE_address
                                                         0 \times 0.1
00962 #define DW_ATE_boolean
                                                         0x02
00963 #define DW_ATE_complex_float
                                                         0x03
00964 #define DW_ATE_float
                                                         0x04
00965 #define DW_ATE_signed
00966 #define DW_ATE_signed_char
                                                         0x06
00967 #define DW_ATE_unsigned
                                                         0x07
00968 #define DW_ATE_unsigned_char
                                                         0 \times 0 8
                                                         0x09 /* DWARF3 */
00969 #define DW_ATE_imaginary_float
                                                         0x0a /* DWARF3f */
0x0b /* DWARF3f */
00970 #define DW_ATE_packed_decimal
00971 #define DW_ATE_numeric_string
00972 #define DW_ATE_edited
                                                         0x0c /* DWARF3f */
00973 #define DW_ATE_signed_fixed
                                                         0x0d /* DWARF3f */
                                                         0x0e /* DWARF3f */
00974 #define DW_ATE_unsigned_fixed
                                                         0x0f /* DWARF3f */
00975 #define DW_ATE_decimal_float
                                                         0x10 /* DWARF4 */
00976 #define DW_ATE_UTF
                                                         0x11 /* DWARF5 */
00977 #define DW_ATE_UCS
00978 #define DW_ATE_ASCII
                                                         0x12 /* DWARF5 */
00979
00980 /* ALTIUM extensions. x80, x81 */
00981 #define DW_ATE_ALTIUM_fract
                                                         0x80 /* ALTIUM __fract type */
00982
00983 /\star Follows extension so dwarfdump prints
           the most-likely-useful name. */
00984
00985 #define DW_ATE_lo_user
00986
00987 /* Shown here to help dwarfdump build script. */
00988 #define DW_ATE_ALTIUM_accum 0x81 /* ALTIUM __accum type */
00988 #define DW_ATE_ALTIUM_accum
00990 /* HP extensions. */
00991 #define DW_ATE_HP_float80
                                                         0x80 / * (80 bit). HP */
00992 #define DW_ATE_HP_complex_float80
                                                         0x81 /* Complex (80 bit). HP */
                                                         0x82 /* (128 bit). HP */
00993 #define DW_ATE_HP_float128
00994 #define DW_ATE_HP_complex_float128
                                                         0x83 /* Complex (128 bit). HP */
00995 #define DW_ATE_HP_floathpintel
                                                         0x84 /* (82 bit IA64). HP */
                                                         0x85 /* HP */
00996 #define DW_ATE_HP_imaginary_float80
00997 #define DW_ATE_HP_imaginary_float128 0x86 /* HP */
00998 #define DW_ATE_HP_VAX_float
                                                         0x88 /* F or G floating. */
00999 #define DW_ATE_HP_VAX_float_d
                                                         0x89 /* D floating.
01000 #define DW_ATE_HP_packed_decimal
01001 #define DW_ATE_HP_zoned_decimal
                                                         0x8a /* Cobol. */
                                                         0x8b /* Cobol. */
01002 #define DW_ATE_HP_edited
                                                         0x8c /* Cobol. */
                                                         0x8d /* Cobol. */
0x8e /* Cobol. */
01003 #define DW_ATE_HP_signed_fixed
01004 #define DW_ATE_HP_unsigned_fixed
01005 #define DW_ATE_HP_unsigned_fixed
                                                         0x8e /* Cobol.
01005 #define DW_ATE_HP_VAX_complex_float
                                                         0x8f /* ForG floating complex.*/
01006 #define DW_ATE_HP_VAX_complex_float_d 0x90 /* D floating complex. */
01007
01008 /* Sun extensions */
01009 #define DW_ATE_SUN_interval_float
01010
01011 /* Obsolete: See DW_ATE_imaginary_float */
01012 #define DW_ATE_SUN_imaginary_float 0x92 /* Really SUN 0x86 ? */
01013
```

```
01014 #define DW_ATE_hi_user
01015
01015 /* DWARF5 Defaulted Member Encodings. */
/* DWARF5 */
                                                 /* DWARF5 */
                                                /* DWARF5 */
01019 #define DW DEFAULTED out of class 0x2
                                        01021 #define DW_IDX_compile_unit
01022 #define DW_IDX_type_unit
01023 #define DW_IDX_die_offset
01024 #define DW_IDX_parent
                                        0x4
01025 #define DW_IDX_type_hash
                                                 /* DWARF5 */
                                     0x5
0x2000
                                        0x5
01026 #define DW_IDX_GNU_internal
01027 #define DW_IDX_lo_user
                                        0x2000 /* DWARF5 */
/* DWARF5 */
01034 /\star These with not-quite-the-same-names were used in DWARF4
01035 We call then DW_LLEX.
         Never official and should not be used by anyone. \star/
01036
01037 #define DW_LLEX_end_of_list_entry
                                                  0 \times 0
01038 #define DW_LLEX_base_address_selection_entry 0x01
01039 #define DW_LLEX_start_end_entry
01040 #define DW_LLEX_start_length_entry
                                                  0x03
01041 #define DW_LLEX_offset_pair_entry
01042
01043 /* DWARF5 Location List Entries in Split Objects */
/* DWARF5 */
                                                  /* DWARF5 */
01046 #define DW_LLE_startx_endx
                                         0x02
                                                  /* DWARF5 */
01047 #define DW_LLE_startx_length
                                         0x03
                                                  /* DWARF5 */
                                               /* DWARF5 */
/* DWARF5 */
/* DWARF5 */
/* DWARF5 */
/* DWARF5 */
01048 #define DW_LLE_offset_pair
                                        0 \times 0.4
01049 #define DW_LLE_default_location
                                         0x05
01050 #define DW_LLE_base_address
                                         0x06
01051 #define DW_LLE_start_end
                                         0x07
01052 #define DW_LLE_start_length
                                         0x08
01053
01054 /* DWARF5 Range List Entries */
01055 #define DW_RLE_end_of_list
                                         0 \times 0 = 0
                                                 /* DWARF5 */
                                                /* DWARF5 */
/* DWARF5 */
/* DWARF5 */
/* DWARF5 */
/* DWARF5 */
/* DWARF5 */
/* DWARF5 */
01056 #define DW RLE base addressx
                                         0 \times 0.1
01057 #define DW_RLE_startx_endx
                                         0x02
01058 #define DW_RLE_startx_length
                                         0x03
01059 #define DW_RLE_offset_pair
                                         0x04
01060 #define DW_RLE_base_address
                                         0x05
01061 #define DW_RLE_start_end
                                         0x06
01062 #define DW_RLE_start_length
                                        0 \times 07
01063
01064 /* GNUIndex encodings non-standard. New in 2020,
         used in .debug_gnu_pubnames .debug_gnu_pubtypes
01065
01066
         but no spellings provided in documentation.
01067 #define DW_GNUIVIS_global 0
01068 #define DW_GNUIVIS_static
01069
01070 /* GNUIndex encodings non-standard. New in 2020,
01071 used in .debug_gnu_pubnames .debug_gnu_pubtypes
01072 but no spellings provided in documentation. */
01073 #define DW_GNUIKIND_none
                                  Ω
01074 #define DW_GNUIKIND_type
01075 #define DW_GNUIKIND_variable 2
01076 #define DW_GNUIKIND_function 3
01077 #define DW_GNUIKIND_other
01078
01079 /* DWARF5 Unit header unit type encodings */
01080 #define DW_UT_compile
                                        0x01 /* DWARF5 */
                                         0x02 /* DWARF5 */
01081 #define DW UT type
                                         0x03 /* DWARF5 */
01082 #define DW_UT_partial
                                         0x04 /* DWARF5 */
01083 #define DW_UT_skeleton
01084 #define DW_UT_split_compile
                                         0x05 /* DWARF5 */
01085 #define DW_UT_split_type
                                         0x06 /* DWARF5 */
                                        0x80 /* DWARF5 */
0xff /* DWARF5 */
01086 #define DW_UT_lo_user
01087 #define DW_UT_hi_user
01088
01089 /* DWARF5 DebugFission object section id values
         for .dwp object section offsets hash table.
01090
01091
         0 is reserved, not used.
01092
         2 is actually reserved, not used in DWARF5.
         But 2 may be seen in some DWARF4 objects.
01093
01094 */
01095 #define DW_SECT_INFO
                                 1 /* .debug_info.dwo
```

```
01101 #define DW_SECT_MACRO 7 /* .debug_macro.dwo DWARF5 */
01102 #define DW_SECT_RNGLISTS 8 /* .debug_rnglists.dwo DWARF5 */
 01103
 01104 /* Decimal Sign codes. */
 0x01 /* DWARF3f */
01106 #define DW_DS_leading_overpunch 0x02 /* DWARF3f */
01107 #define DW_DS_trailing_overpunch 0x03 /* DWARF3f */
01108 #define DW_DS_leading_separate 0x04 /* DWARF3f */
01109 #define DW_DS_trailing_separate 0x05 /* DWARF3f */
01110
 01110
 01111 /* Endian code name. */
                                                                                           0x00 /* DWARF3f */
 01112 #define DW_END_default
                                                                                          0x01 /* DWARF3f */
0x02 /* DWARF3f */
 01113 #define DW_END_big
 01114 #define DW_END_little
 01115
                                                                                          0x40 /* DWARF3f */
0xff /* DWARF3f */
 01116 #define DW_END_lo_user
 01117 #define DW_END_hi_user
 01118
 01119 /* For use with DW_TAG_SUN_codeflags
 01120 If DW_TAG_SUN_codeflags is accepted as a dwarf standard, then 01121 standard dwarf ATCF entries start at 0x01 \star/
                                                                                0x40 /* SUN */
 01122 #define DW_ATCF_lo_user
 01123 #define DW_ATCF_SUN_mop_bitfield
                                                                                              0×41 /* SUN */
01131 #define DW ATCF hi user
                                                                                             0xff /* SUN */
 01132
 01133 /* Accessibility code name. */
 01134 #define DW_ACCESS_public
                                                                                             0 \times 0.1
 01135 #define DW_ACCESS_protected
                                                                                              0 \times 0.2
 01136 #define DW_ACCESS_private
                                                                                              0x03
 01137
 01138 /* Visibility code name. */
 01139 #define DW_VIS_local
                                                                                              0 \times 01
 01140 #define DW_VIS_exported
                                                                                              0x02
 01141 #define DW_VIS_qualified
                                                                                              0×03
 01142
 01143 /* Virtuality code name. */
 01144 #define DW_VIRTUALITY_none
 01145 #define DW_VIRTUALITY_virtual
 01146 #define DW_VIRTUALITY_pure_virtual
 01147
                                                                                              0×0001
 01148 #define DW_LANG_C89
 01149 #define DW_LANG_C
                                                                                              0x0002
 01150 #define DW_LANG_Ada83
                                                                                             0x0003
 01151 #define DW_LANG_C_plus_plus
 01152 #define DW_LANG_Cobol74
01152 #define DW_LANG_Cobol74
01153 #define DW_LANG_Cobol85
0x0006
01154 #define DW_LANG_Fortran77
0x0007
01155 #define DW_LANG_Fortran90
0x0008
01156 #define DW_LANG_Pascal83
0x0009
01157 #define DW_LANG_Modula2
0x000a
01158 #define DW_LANG_Modula2
0x000b /* DWARF3 */
01159 #define DW_LANG_Cop9
0x000c /* DWARF3 */
01160 #define DW_LANG_Ada95
0x000c /* DWARF3 */
01161 #define DW_LANG_Fortran95
0x000c /* DWARF3 */
01162 #define DW_LANG_Fortran95
0x000c /* DWARF3 */
01163 #define DW_LANG_PLI
0x000f /* DWARF3 */
01164 #define DW_LANG_ObjC
0x0010 /* DWARF3 */
01165 #define DW_LANG_ObjC_plus_plus
0x0011 /* DWARF3f */
01166 #define DW_LANG_UPC
0x0012 /* DWARF3f */
01166 #define DW_LANG_Python
0x0014 /* DWARF3f */
01167 #define DW_LANG_OpenCL
0x0015 /* DWARF3 */
01170 #define DW_LANG_Modula3
0x0017 /* DWARF5 */
01171 #define DW_LANG_Dplus_plus_03
0x0018 /* DWARF5 */
01173 #define DW_LANG_Cplus_plus_01
0x0016 /* DWARF5 */
01174 #define DW_LANG_Cplus_plus_01
0x0016 /* DWARF5 */
01175 #define DW_LANG_Caml
0x0016 /* DWARF5 */
01176 #define DW_LANG_Cplus_plus_11
0x001a /* DWARF5 */
01177 #define DW_LANG_Coml
0x001c /* DWARF5 */
01177 #define DW_LANG_Swift
0x001c /* DWARF5 */
01178 #define DW_LANG_Suift
0x001c /* DWARF5 */
01179 #define DW_LANG_Suift
0x001c /* DWARF5 */
01179 #define DW_LANG_Cplus_plus_14
0x001c /* DWARF5 */
01181 #define DW_LANG_Fortran03
0x0012 /* DWARF5 */
01181 #define DW_LANG_Fortran03
 01153 #define DW_LANG_Cobol85
                                                                                             0×0006
0x0024 /* DWARF5 */
 01183 #define DW_LANG_RenderScript
 01184 #define DW_LANG_BLISS
                                                                                             0x0025 /* DWARF5 */
 01185 /\star The committee has, in
 01186
                   https://dwarfstd.org/languages-v6.html
 01187
                   specified that these language code, may be
```

```
used by compilers now, and promises these
01189
          will not change. */
 01190 #define DW_LANG_Kotlin
                                           0x0026 /* DWARF6 */
 01214
                                          0x8000
0x8001 /* MIPS */
 01215 #define DW_LANG_lo_user
 01216 #define DW_LANG_Mips_Assembler
 01217 #define DW LANG Upc
                                           0x8765 /* UPC, use
 01218
                                           DW LANG UPC instead. */
 01219 #define DW_LANG_GOOGLE_RenderScript
                                            0x8e57
 01219 #define DW_LANG_GOUGHE_Nemacless_,
01220 #define DW_LANG_ALTIUM_Assembler
 01221 #define DW_LANG_BORLAND_Delphi
                                           0xb000
 01222
 01223 /* Sun extensions */
 01224 #define DW_LANG_SUN_Assembler
                                          0x9001 /* SUN */
 01226 #define DW LANG hi user
                                           0xffff
 01227
 01228 /* The committee has, in
 01229 https://dwarfstd.org/languages-v6.html
         specified that these language code, may be
 01230
         used by compilers now, and promises these
         will not change. */
 01232
0x0001 /* DWARF6 */
 01233 #define DW_LNAME_Ada
                             0x0002 /* DWARF6 */
0x0003 /* DWARF6 */
 01234 #define DW_LNAME_BLISS
 01271 #define DW_LNAME_Move
                                       0x0027 /* DWARF6 */
                                      0x0028 /* DWARF6 */
0x0029 /* DWARF6 */
0x002a /* DWARF6 */
 01272 #define DW_LNAME_Hylo
 01273 #define DW_LNAME_HIP
 01274 #define DW_LNAME_Odin
```

```
0x002b /* DWARF6 */
0x002c /* DWARF6 */
0x002d /* DWARF6 */
01275 #define DW_LNAME_P4
01276 #define DW_LNAME_Metal
01277 #define DW_LNAME_V
01278 #define DW_LNAME_Algol68
                                         0x002e /* DWARF6 */
0x002f /* DWARF6 */
01279 #define DW_LNAME_Nim
01280
01281 /* Identifier case name. */
01282 #define DW_ID_case_sensitive
                                              0x00
01283 #define DW_ID_up_case
                                               0x01
01284 #define DW_ID_down_case
                                               0 \times 0.2
01285 #define DW_ID_case_insensitive
                                               0x03
01286
01287 /* Calling Convention Name. */
01288 #define DW_CC_normal
                                               0x01
                                               0x02
01289 #define DW_CC_program
01290 #define DW_CC_nocall
                                               0 \times 0.3
01291 #define DW_CC_pass_by_reference
                                               0x04 /* DWARF5 */
                                               0x05 /* DWARF5 */
01292 #define DW_CC_pass_by_value
01294 #define DW_CC_GNU_renesas_sh
                                               0x40 /* GNU */
01295 #define DW_CC_lo_user
                                               0x40
01296 #define DW_CC_GNU_borland_fastcall_i386 0x41 /* GNU */
01297
01298 /* ALTIUM extensions. */
01299 /* Function is an interrupt handler,
01300 return address on system stack. */
01301 #define DW_CC_ALTIUM_interrupt
                                               0x65 /* ALTIUM*/
01302
01303 /\star Near function model, return address on system stack. \star/
01305
01306 /* Near function model, return address on user stack.
01308
01309 /* Huge function model, return address on user stack.
01310 #define DW_CC_ALTIUM_huge_user_stack 0x68 /* ALTIUM */
01311
01312 #define DW_CC_GNU_BORLAND_safecall
01313 #define DW_CC_GNU_BORLAND_stdcall
                                             0xb1
01314 #define DW_CC_GNU_BORLAND_pascal
                                             0xb2
01315 #define DW_CC_GNU_BORLAND_msfastcall
                                             0xh3
01316 #define DW_CC_GNU_BORLAND_msreturn
                                             0xb4
01317 #define DW_CC_GNU_BORLAND_thiscall 01318 #define DW_CC_GNU_BORLAND_fastcall
                                             0xb5
                                             0xb6
01319
01320 #define DW_CC_LLVM_vectorcall
                                             0xc0
01321 #define DW_CC_LLVM_Win64
01322 #define DW_CC_LLVM_X86_64SysV
                                             0xc1
                                             0xc2
01323 #define DW CC LLVM AAPCS
                                             0xc3
01324 #define DW_CC_LLVM_AAPCS_VFP
                                             0xc4
01325 #define DW_CC_LLVM_IntelOclBicc
                                             0xc5
01326 #define DW_CC_LLVM_SpirFunction
                                             0xc6
01327 #define DW_CC_LLVM_OpenCLKernel
                                             0xc7
01328 #define DW_CC_LLVM_Swift
                                             0xc8
01329 #define DW_CC_LLVM_PreserveMost
                                             0xc9
01330 #define DW_CC_LLVM_PreserveAll
                                             0xca
01331 #define DW_CC_LLVM_X86RegCall
01332 #define DW_CC_GDB_IBM_OpenCL
                                             0xff
01333
01334 #define DW_CC_hi_user
                                              0xff
01335
01336 /* Inline Code Name. */
01337 #define DW_INL_not_inlined
01338 #define DW_INL_inlined
01339 #define DW_INL_declared_not_inlined
                                               0×02
01340 #define DW_INL_declared_inlined
01341
01342 /* Ordering Name. */
01343 #define DW_ORD_row_major
01344 #define DW_ORD_col_major
01345
01346 /* Discriminant Descriptor Name. */
01347 #define DW_DSC_label
                                               0 \times 0.0
01348 #define DW_DSC_range
                                               0x01
01349
01350 /* Line number header entry format encodings. DWARF5 */
                                       0x1 /* DWARF5 */
01351 #define DW_LNCT_path
01352 #define DW_LNCT_directory_index
                                               0x2 /* DWARF5 */
01352 #define DW_LNCT_timestamp
                                               0x3 /* DWARF5 */
01354 #define DW_LNCT_size
                                               0x4 /* DWARF5 */
                                               0x5 /* DWARF5 */
01355 #define DW LNCT MD5
01356 /* Experimental two-level line tables. Non standard */
01357 #define DW_LNCT_GNU_subprogram_name 0x6
01358 #define DW_LNCT_GNU_decl_file
                                               0 \times 7
01359 #define DW_LNCT_GNU_decl_line
                                               0×8
01360 #define DW_LNCT_lo_user
01361 #define DW_LNCT_LLVM_source
                                               0x2000 /* DWARF5 */
                                               0x2001
```

```
01362 #define DW_LNCT_LLVM_is_MD5
                                             0x2002
01363 #define DW_LNCT_hi_user
                                             0x3fff /* DWARF5 */
01364
01365 /* Line number standard opcode name. */
01366 #define DW_LNS_copy
                                             0 \times 01
01367 #define DW_LNS_advance_pc
                                             0 \times 02
01368 #define DW_LNS_advance_line
01369 #define DW_LNS_set_file
01370 #define DW_LNS_set_column
                                             0x05
01371 #define DW_LNS_negate_stmt
                                             0x06
01372 #define DW_LNS_set_basic_block
                                             0x07
01373 #define DW_LNS_const_add_pc
                                             0x08
                                       0x0s
0x0a /* DWARL
0x0b /* DWARF3 */
0x0c /* DWARF3 */
01374 #define DW_LNS_fixed_advance_pc
01375 #define DW_LNS_set_prologue_end
01376 #define DW_LNS_set_epilogue_begin
01377 #define DW_LNS_set_isa
01378
01379 /* Experimental two-level line tables. NOT STD DWARF5 */
01380 /* Not saying GNU or anything. There are no
         DW_LNS_lo_user or DW_LNS_hi_user values though.
01382
         DW_LNS_set_address_from_logical and
01383
         DW_LNS_set_subprogram being both 0xd
01384
         to avoid using up more space in the special opcode table.
01385
         EXPERIMENTAL DW LNS follow.
01386 */
01387 #define DW_LNS_set_address_from_logical 0x0d /* Actuals table only */
01389 #define DW_LNS_inlined_call
                                             0x0e /* Logicals table only */
01390 #define DW_LNS_pop_context
                                             0x0f /* Logicals table only */
01391
01392 /* Line number extended opcode name. */
01397
01398 /* HP extensions. */
                                               0x11 /* 17 HP */
01399 #define DW_LNE_HP_negate_is_UV_update
01400 #define DW_LNE_HP_push_context
                                                 0x12 /* 18 HP */
01401 #define DW_LNE_HP_pop_context
                                                 0x13 /* 19 HP */
01402 #define DW_LNE_HP_set_file_line_column
                                                0x14 /* 20 HP */
01403 #define DW_LNE_HP_set_routine_name
                                                0x15 /* 21 HP */
01404 #define DW_LNE_HP_set_sequence
                                                0x16 /* 22 HP */
                                             0x17 /* 23 HP */
01405 #define DW_LNE_HP_negate_post_semantics
01406 #define DW_LNE_HP_negate_function_exit
                                                 0x18 /* 24 HP */
01407 #define DW_LNE_HP_negate_front_end_logical 0x19 /\star 25 HP \star/
01408 #define DW_LNE_HP_define_proc
                                                0x20 /* 32 HP */
01409
01410 #define DW_LNE_HP_source_file_correlation
                                                 0x80 /* HP */
01410 #define DW_LNE_lo_user
                                           0x80 /* DWARF3 */
0xff /* DWARF3 */
01412 #define DW_LNE_hi_user
01413
01414 /\star These are known values for DW_LNS_set_isa. \star/
01415 /\star These identifiers are not defined by any DWARFn standard. \star/
01416 #define DW ISA UNKNOWN 0
01417 /* The following two are ARM specific. */
01418 #define DW_ISA_ARM_thumb 1 /* ARM ISA */
01419 #define DW_ISA_ARM_arm 2 /* ARM ISA */
01420
01421 /* Macro information, DWARF5 */
01422 #define DW_MACRO_define
                                              0x01 /* DWARF5 */
01423 #define DW_MACRO_undef
                                              0x02 /* DWARF5 */
01424 #define DW_MACRO_start_file
                                              0x03 /* DWARF5 */
                                          0x03 /* DWARF5 */
0x04 /* DWARF5 */
0x05 /* DWARF5 */
0x06 /* DWARF5 */
0x07 /* DWARF5 */
0x08 /* DWARF5 */
0x09 /* DWARF5 */
0x0a /* DWARF5 */
0x0b /* DWARF5 */
0x0c /* DWARF5 */
0x0c /* DWARF5 */
0xe0
01425 #define DW_MACRO_end_file
01426 #define DW_MACRO_define_strp
01427 #define DW_MACRO_undef_strp
01428 #define DW_MACRO_import
01429 #define DW_MACRO_define_sup
01430 #define DW_MACRO_undef_sup
01431 #define DW_MACRO_import_sup
01432 #define DW_MACRO_define_strx
01433 #define DW_MACRO_undef_strx
01434 #define DW_MACRO_lo_user
                                              0xe0
01435 #define DW_MACRO_hi_user
                                              0xff
01436
01437 /* Macro information, DWARF2-DWARF4. */
01438 #define DW_MACINFO_define
01439 #define DW_MACINFO_undef
                                             0x02
01440 #define DW_MACINFO_start_file
                                             0×03
01441 #define DW_MACINFO_end_file
                                             0 \times 0.4
01442 #define DW MACINFO vendor ext
                                             0xff
01444 /\star CFA operator compaction (a space saving measure, see
01445 the DWARF standard) means DW_CFA_extended and DW_CFA_nop
         have the same value here. \star/
01446
                                   0x40
01447 #define DW_CFA_advance_loc
01448 #define DW_CFA_offset
                                       0x80
```

```
01449 #define DW_CFA_restore
01450 #define DW_CFA_nop
01451 #define DW_CFA_extended
                                      0 \times 0.1
01452 #define DW_CFA_set_loc
01453 #define DW_CFA_advance_loc1
                                      0 \times 0.2
01454 #define DW_CFA_advance_loc2
                                      0x03
01455 #define DW_CFA_advance_loc4
01456 #define DW_CFA_offset_extended
01457 #define DW_CFA_restore_extended 0x06
01458 #define DW_CFA_undefined
                                      0 \times 0.7
01459 #define DW_CFA_same_value
                                      0x08
01460 #define DW_CFA_register
                                      0x09
01461 #define DW_CFA_remember_state
                                      0x0a
01462 #define DW_CFA_restore_state
01463 #define DW_CFA_def_cfa
                                      0x0c
01464 #define DW_CFA_def_cfa_register 0x0d
01465 #define DW_CFA_def_cfa_offset 0x0e
01466 #define DW_CFA_def_cfa_expression 0x0f /* DWARF3 */
01467 #define DW_CFA_expression
                                        0x10 /* DWARF3 */
01468 #define DW_CFA_offset_extended_sf 0x11 /* DWARF3 */
01469 #define DW_CFA_def_cfa_sf
                                      0x12 /* DWARF3 */
01470 #define DW_CFA_def_cfa_offset_sf 0x13 /* DWARF3 */
01470 #define DW_CFA_val_offset
01472 #define DW_CFA_val_offset_sf
                                       0x14 /* DWARF3f */
                                        0x15 /* DWARF3f */
01473 #define DW_CFA_val_expression
                                        0x16 /* DWARF3f */
01474 #define DW_CFA_TI_soffset_extended 0x1c /* TI */
01475 #define DW_CFA_lo_user
                                        0x1c
01476 #define DW_CFA_low_user
                               0x1c /* Incorrect spelling, do not use. */
01477
01478 /* SGI/MIPS extension. */
01479 #define DW_CFA_MIPS_advance_loc8  0x1d  /* MIPS */
01480 #define DW_CFA_TI_def_cfa_soffset 0x1d
                                              /* TT */
01481
01482 /* GNU extensions. */
01483 #define DW_CFA_GNU_window_save
                                                    0x2d /* GNU */
01484 #define DW_CFA_AARCH64_negate_ra_state
                                                    0x2d
                                                    0x2e /* GNU */
01485 #define DW CFA GNU args size
01486 #define DW_CFA_GNU_negative_offset_extended
                                                   0x2f /* GNU */
01487 #define DW_CFA_LLVM_def_aspace_cfa
                                                    0x30
01488 #define DW_CFA_LLVM_def_aspace_cfa_sf
01489
01490 /* Metaware if HC is augmentation, apparently meaning High C
01491
         and the op has a single uleb operand.
          See http://sourceforge.net/p/elftoolchain/tickets/397/ */
01492
01493 #define DW_CFA_METAWARE_info
01494
01495 #define DW_CFA_hi_user
                                       0x3f
                                       0x3f /* Misspelled. Do not use. */
01496 #define DW_CFA_high_user
01497
01498 /* GNU exception header encoding. See the Generic
        Elf Specification of the Linux Standard Base (LSB).
01499
        http://refspecs.freestandards.org/LSB_3.0.0/\
01500
01501
         LSB-Core-generic/LSB-Core-generic/dwarfext.html
01502
        The upper 4 bits indicate how the value is to be applied.
        The lower 4 bits indicate the format of the data.
01503
        These identifiers are not defined by any DWARFn standard.
01504
01505 */
01506 #define DW_EH_PE_absptr
                                0x00 /* GNU */
01507 #define DW_EH_PE_uleb128 0x01 /* GNU */
01508 #define DW_EH_PE_udata2
                                0 \times 02
                                      /* GNII */
01509 #define DW EH PE udata4
                                0 \times 0.3
                                      /* GNU */
01510 #define DW_EH_PE_udata8
                                0x04
                                      /* GNU */
01511 #define DW_EH_PE_sleb128
                                0x09 /* GNU */
01512 #define DW_EH_PE_sdata2
                                0x0A
                                     /* GNU */
01513 #define DW_EH_PE_sdata4
                                0×0B
                                      /* GNU */
01514 #define DW_EH_PE_sdata8
                                0x0C /* GNU */
01515
                                0x10 /* GNU */
01516 #define DW EH PE pcrel
01517 #define DW_EH_PE_textrel 0x20 /* GNU */
                                      /* GNU */
01518 #define DW_EH_PE_datarel
                                0x30
01519 #define DW_EH_PE_funcrel
                                0x40
                                      /* GNU */
01520 #define DW_EH_PE_aligned 0x50 /* GNU */
01521
                                0xff /* GNU. Means no value present. */
01522 #define DW EH PE omit
01523
01524 /\star Mapping from machine registers and pseudo-regs into the
         .debug_frame table. DW_FRAME entries are machine specific.
01525
         These describe MIPS/SGI R3000, R4K, R4400 and all later
01526
01527
         MIPS/SGI IRIX machines. They describe a mapping from
         hardware register number to the number used in the table
01528
01529
        to identify that register.
01531
         The CFA (Canonical Frame Address) described in DWARF is
01532
         called the Virtual Frame Pointer on MIPS/SGI machines.
01533
         The DW FRAME* names here are MIPS/SGI specific.
01534
01535
         Libdwarf interfaces defined in 2008 make the
```

```
frame definitions here (and the fixed table sizes
01537
        they imply) obsolete. They are left here for compatibility.
01538 */
01539 /* These identifiers are not defined by any DWARFn standard. */
01540
                               /* integer reg 1 */
2 /* integer reg 2 */
3 /* integer
01541 #define DW_FRAME_REG1
01542 #define DW_FRAME_REG2
01543 #define DW_FRAME_REG3
01544 #define DW_FRAME_REG4
                                4 /* integer reg 4 */
01545 #define DW FRAME REG5
                                   /* integer reg 5 */
01546 #define DW_FRAME_REG6
                                6 /* integer reg 6 */
                                7 /* integer reg 7 */
01547 #define DW FRAME REG7
01548 #define DW_FRAME_REG8
                                8 /* integer reg 8 */
01549 #define DW_FRAME_REG9
                                    /* integer reg 9 */
01550 #define DW_FRAME_REG10 10 /* integer reg 10 */
01551 #define DW_FRAME_REG11 11 /* integer reg 11 */
01552 #define DW FRAME REG12
                                 12 /* integer reg 12 */
01553 #define DW FRAME REG13
                                 13 /* integer reg 13 */
01554 #define DW_FRAME_REG14
                                 14 /* integer reg 14 */
01555 #define DW_FRAME_REG15
                                 15 /* integer reg 15 */
01556 #define DW_FRAME_REG16
                                 16 /* integer reg 16 */
01557 #define DW_FRAME_REG17
                                 17 /* integer reg 17 */
01558 #define DW FRAME REG18 18 /* integer reg 18 */
01559 #define DW_FRAME_REG19
                                19 /* integer reg 19 */
01560 #define DW_FRAME_REG20 20 /* integer reg 20 */
01561 #define DW FRAME REG21
                                 21 /* integer reg 21 */
01562 #define DW_FRAME_REG22
                                 22 /* integer reg 22
01563 #define DW_FRAME_REG23 23 /* integer reg 23 */
01564 #define DW_FRAME_REG24 24 /* integer reg 24 */
01565 #define DW_FRAME_REG25 25 /* integer reg 25 */
01566 #define DW FRAME REG26 26 /* integer reg 26 */
01567 #define DW_FRAME_REG27
                                 27 /* integer reg 27 */
01568 #define DW_FRAME_REG28 28 /* integer reg 28 */
01569 #define DW_FRAME_REG29 29 /* integer reg 29 */
01570 #define DW_FRAME_REG30 30 /* integer reg 30 */ 01571 #define DW_FRAME_REG31 31 /* integer reg 31, aka ra */
01572
           /\star MIPS1,2 have only some of these 64-bit registers.
01574
           ** MIPS1 save/restore takes 2 instructions per 64-bit reg, and
           ** in that case, the register is considered stored after
01575
           ** the second swc1. */
01576
01577 #define DW_FRAME_FREGO 32 /* 64-bit floating point reg 0 */
01578 #define DW_FRAME_FREGI 33 /* 64-bit floating point reg 1 */
01579 #define DW_FRAME_FREG2 34 /* 64-bit floating point reg 2 */
01580 #define DW_FRAME_FREG3 35 /* 64-bit floating point reg 3 */
01581 #define DW_FRAME_FREG4 36 /* 64-bit floating point reg
01582 #define DW_FRAME_FREG5 37 /* 64-bit floating point reg 5 */
01583 #define DW_FRAME_FREG6 38 /* 64-bit floating point reg 6 */
01584 #define DW_FRAME_FREG7 39 /* 64-bit floating point reg 7 */
01585 #define DW_FRAME_FREG8 40 /* 64-bit floating point reg 8 */
01586 #define DW_FRAME_FREG9 41 /* 64-bit floating point reg 9
01587 #define DW_FRAME_FREG10 42 /* 64-bit floating point reg 10 *,
01588 #define DW_FRAME_FREG11 43 /\star 64-bit floating point reg 11 \star/
01589 #define DW_FRAME_FREG12 44 /* 64-bit floating point reg 12 */
01590 #define DW_FRAME_FREG13 45 /* 64-bit floating point reg 13 */
01591 #define DW_FRAME_FREG14 46 /* 64-bit floating point reg 14 */
01592 #define DW_FRAME_FREG15 47 /* 64-bit floating point reg 15 */
01593 #define DW_FRAME_FREG16 48 /* 64-bit floating point reg 16 */
01594 #define DW_FRAME_FREG17 49 /* 64-bit floating point reg 17 */
01595 #define DW_FRAME_FREG18 50 /\star 64-bit floating point reg 18 \star/
01596 #define DW FRAME FREG19 51 /* 64-bit floating point reg 19 */
01597 #define DW FRAME FREG20 52 /* 64-bit floating point reg 20 */
01598 #define DW_FRAME_FREG21 53 /* 64-bit floating point reg 21 */
01599 #define DW_FRAME_FREG22 54 /* 64-bit floating point reg 22 *,
01600 #define DW_FRAME_FREG23 55 /* 64-bit floating point reg 23 */
01601 #define DW_FRAME_FREG24 56 /* 64-bit floating point reg 24 */
01602 #define DW_FRAME_FREG25 57 /* 64-bit floating point reg 25 */
01603 #define DW_FRAME_FREG26 58 /* 64-bit floating point reg 26 */
01604 #define DW_FRAME_FREG27 59 /* 64-bit floating point reg 27 */
01605 #define DW_FRAME_FREG28 60 /* 64-bit floating point reg 28
01606 #define DW_FRAME_FREG29 61 /\star 64-bit floating point reg 29 \star/
01607 #define DW_FRAME_FREG30 62 /\star 64-bit floating point reg 30 \star/
01608 #define DW_FRAME_FREG31 63 /\star 64-bit floating point reg 31 \star/
01609
01610 #define DW_FRAME_FREG32 64 /* 64-bit floating point reg 32 */
01611 #define DW_FRAME_FREG33 65 /* 64-bit floating point reg 33 */
01612 #define DW_FRAME_FREG34 66 /* 64-bit floating point reg 34 */
01613 #define DW_FRAME_FREG35 67 /* 64-bit floating point reg 35 */
01614 #define DW_FRAME_FREG36 68 /\star 64-bit floating point reg 36 \star/
01615 #define DW FRAME FREG37 69 /* 64-bit floating point reg 37 */
01616 #define DW_FRAME_FREG38 70 /* 64-bit floating point reg 38 */
01617 #define DW_FRAME_FREG39 71 /* 64-bit floating point reg 39 */
01618 #define DW_FRAME_FREG40 72 /* 64-bit floating point reg 40 *,
01619 #define DW_FRAME_FREG41 73 /* 64-bit floating point reg 41 */
01620 #define DW_FRAME_FREG42 74 /* 64-bit floating point reg 42 */ 01621 #define DW_FRAME_FREG43 75 /* 64-bit floating point reg 43 */ 01622 #define DW_FRAME_FREG44 76 /* 64-bit floating point reg 44 */
```

```
01623 #define DW_FRAME_FREG45 77 /* 64-bit floating point reg 45 */
01624 #define DW_FRAME_FREG46 78 /* 64-bit floating point reg 46 */
01625 #define DW_FRAME_FREG47 79 /* 64-bit floating point reg 47 */
01626 #define DW_FRAME_FREG48 80 /* 64-bit floating point reg 48 */
01627 #define DW_FRAME_FREG49 81 /* 64-bit floating point reg 49 */
01628 #define DW_FRAME_FREG50 82 /* 64-bit floating point reg 50 */
01629 #define DW_FRAME_FREG51 83 /* 64-bit floating point reg 51 */
01630 #define DW_FRAME_FREG52 84 /* 64-bit floating point reg 52 */
01631 #define DW_FRAME_FREG53 85 /* 64-bit floating point reg 53 */
01632 #define DW_FRAME_FREG54 86 /\star 64-bit floating point reg 54 \star/
01633 #define DW_FRAME_FREG55 87 /* 64-bit floating point reg 55 */
01634 #define DW_FRAME_FREG56 88 /* 64-bit floating point reg 56 */
01635 #define DW_FRAME_FREG57 89 /* 64-bit floating point reg 57 */
01636 #define DW_FRAME_FREG58 90 /* 64-bit floating point reg 58 */
01637 #define DW_FRAME_FREG59 91 /* 64-bit floating point reg 59 */
01638 #define DW_FRAME_FREG60 92 /* 64-bit floating point reg 60 */ 01639 #define DW_FRAME_FREG61 93 /* 64-bit floating point reg 61 */
01640 #define DW_FRAME_FREG62 94 /* 64-bit floating point reg 62 */
01641 #define DW_FRAME_FREG63 95 /* 64-bit floating point reg 63 */
01642 #define DW_FRAME_FREG64 96 /* 64-bit floating point reg 64 */
01643 #define DW_FRAME_FREG65 97 /* 64-bit floating point reg 65 */
01644 #define DW_FRAME_FREG66 98 /\star 64-bit floating point reg 66 \star/
01645 #define DW_FRAME_FREG67 99 /\star 64-bit floating point reg 67 \star/
01646 #define DW_FRAME_FREG68 100 /* 64-bit floating point reg 68 */
01647 #define DW_FRAME_FREG69 101 /* 64-bit floating point reg 69 */
01648 #define DW_FRAME_FREG70 102 /* 64-bit floating point reg 70 */
01649 #define DW_FRAME_FREG71 103 /* 64-bit floating point reg 71 */
01650 #define DW_FRAME_FREG72 104 /* 64-bit floating point reg 72 */
01651 #define DW_FRAME_FREG73 105 /\star 64-bit floating point reg 73 \star/
01652 #define DW_FRAME_FREG74 106 /* 64-bit floating point reg 74 */
01653 #define DW_FRAME_FREG75 107 /* 64-bit floating point reg 75 */
01654 #define DW_FRAME_FREG76 108 /* 64-bit floating point reg 76 */
01655
01656 /* Having DW_FRAME_HIGHEST_NORMAL_REGISTER be higher than
01657
          is strictly needed \dots is safe.
01658
          These values can be changed at runtime by libdwarf.
01659 */
01660 #ifndef DW_FRAME_HIGHEST_NORMAL_REGISTER
01661 #define DW_FRAME_HIGHEST_NORMAL_REGISTER 188
01662 #endif
01663 /* This is the number of columns in the Frame Table.
01664 */
01665 #ifndef DW FRAME LAST REG NUM
01666 #define DW_FRAME_LAST_REG_NUM (DW_FRAME_HIGHEST_NORMAL_REGISTER + 1)
01667 #endif
01668
01669 #define DW_CHILDREN_no
                                              0×00
01670 #define DW_CHILDREN_yes
                                             0 \times 01
01671
01672 #define DW ADDR none
                                        0x0008
01673 #define DW_ADDR_TI_PTR8
                                                 /* TI */
01674 #define DW_ADDR_TI_PTR16
                                         0x0010
                                                  /* TI */
                                                   /* TI */
01675 #define DW_ADDR_TI_PTR22
                                          0x0016
01676 #define DW_ADDR_TI_PTR23
                                         0 \times 0.017
                                                   /* TT */
01677 #define DW_ADDR_TI_PTR24
                                                   /* TI */
                                         0x0018
01678 #define DW_ADDR_TI_PTR32
                                                   /* TI */
                                         0x0020
01680 #ifdef __cplusplus
01681 }
01682 #endif
01683 #endif /* __DWARF_H */
```

Chapter 14

libdwarf.h

libdwarf.h contains all the type declarations and function function declarations needed to use the library. It is essential that coders include dwarf.h before including libdwarf.h.

All identifiers here in the public namespace begin with DW_ or Dwarf_ or dwarf_ . All function argument names declared here begin with dw_ .

14.1 libdwarf.h

Go to the documentation of this file.

```
00002
        Copyright (C) 2000-2010 Silicon Graphics, Inc. All Rights Reserved.
        Portions Copyright 2007-2010 Sun Microsystems, Inc. All rights reserved.
00003
        Portions Copyright 2008-2024 David Anderson. All rights reserved.
00004
00005
        Portions Copyright 2008-2010 Arxan Technologies, Inc. All rights reserved.
        Portions Copyright 2010-2012 SN Systems Ltd. All rights reserved.
00007
80000
        This program is free software; you can redistribute it
00009
        and/or modify it under the terms of version 2.1\ \mathrm{of}\ \mathrm{the}
00010
        GNU Lesser General Public License as published by the Free
00011
        Software Foundation.
00012
00013
        This program is distributed in the hope that it would be
00014
        useful, but WITHOUT ANY WARRANTY; without even the implied
00015
        warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR
00016
        PHRPOSE.
00017
00018
        Further, this software is distributed without any warranty
00019
        that it is free of the rightful claim of any third person
00020
         regarding infringement or the like. Any license provided
00021
        herein, whether implied or otherwise, applies only to this
00022
        software file. Patent licenses, if any, provided herein do not apply to combinations of this program with other
00023
00024
        software, or any other product whatsoever.
00025
00026
        You should have received a copy of the GNU Lesser General
00027
        Public License along with this program; if not, write the
        Free Software Foundation, Inc., 51 Franklin Street - Fifth Floor, Boston MA 02110-1301, USA.
00028
00029
00030
00031 */
00046 #ifndef _LIBDWARF_H
00047 #define _LIBDWARF_H
00048
00049 #ifdef DW API
00050 #undef DW_API
00051 #endif /* DW_API */
00052
00053 #ifndef LIBDWARF_STATIC
00054 # if defined(_WIN32) || defined(__CYGWIN__)
00055 # ifdef LIBDWARF_BUILD
00056 # define DW_API __declspec(dllexport)
00057 # else /* !LIBDWARF_BUILD */
          define DW_API __declspec(dllimport)
```

```
00059 # endif /* LIBDWARF_BUILD */
00060 # elif (defined(__SUNPRO_C) || defined(__SUNPRO_CC))
00061 # if defined(PIC) || defined(__PIC__)
00062 # define DW_API __global
00067 # define DW_API __attribute__ ((visibility("default")))
00068 # endif /* PIC */
00069 # endif /* WIN32 SUNPRO GNUC */
00070 #endif /* !LIBDWARF_STATIC */
00072 #ifndef DW_API
00073 #define DW_API
00074 #endif /* DW_API */
00075
00076 #ifdef __cplusplus
00077 extern "C" {
00078 #endif /* __cplusplus */
00079
00080 /*
00081
             libdwarf.h
00082
            Revision: #9 Date: 2008/01/17
00083
00084
             For libdwarf consumers (reading DWARF2 and later)
00085
00086
             The interface is defined as having 8\text{-byte} signed and unsigned
00087
             values so it can handle 64-or-32bit target on 64-or-32bit host.
00088
             Dwarf_Ptr is the native size: it represents pointers on
00089
            the host machine (not the target!).
00090
00091
             This contains declarations for types and all producer
00092
            and consumer functions.
00093
00094
            Function declarations are written on a single line each here
            so one can use grep to each declaration in its entirety. The declarations are a little harder to read this way, but...
00095
00097 */
00101 /* Semantic Version identity for this libdwarf.h */
00102 #define DW_LIBDWARF_VERSION "0.12.0"
00103 #define DW_LIBDWARF_VERSION_MAJOR 0
00104 #define DW_LIBDWARF_VERSION_MINOR 12
00105 #define DW_LIBDWARF_VERSION_MICRO 0
00107 #define DW_PATHSOURCE_unspecified 0
00108 #define DW_PATHSOURCE_basic 1 00109 #define DW_PATHSOURCE_dsym 2 /* MacOS dSYM */
00110 #define DW_PATHSOURCE_debuglink 3 /* GNU debuglink */
00111
00112 #ifndef DW_FTYPE_UNKNOWN
00113 #define DW_FTYPE_UNKNOWN
                                           1 /* Unix/Linux/etc */
00114 #define DW_FTYPE_ELF
00115 #define DW_FTYPE_MACH_O
                                          2 /* MacOS. */
3 /* Windows */
4 /* unix archi
00116 #define DW_FTYPE_PE
00117 #define DW_FTYPE_ARCHIVE 4 /*
00118 #define DW_FTYPE_APPLEUNIVERSAL
                                                /* unix archive */
00119 #endif /* DW_FTYPE_UNKNOWN */
00120 /* standard return values for functions */
00121 #define DW_DLV_NO_ENTRY -1
00122 #define DW_DLV_OK
00123 #define DW_DLV_ERROR
00124 /* These support opening DWARF5 split dwarf objects and 00125 Elf SHT_GROUP blocks of DWARF sections. */
00126 #define DW_GROUPNUMBER_ANY 0
00127 #define DW_GROUPNUMBER_BASE 1
00128 #define DW_GROUPNUMBER DWO 2
00129
00130 /* FRAME special values */
00131 /* The following 3 are assigned numbers, but 00132 are only present at run time.
00133 Must not conflict with DW_FRAME values in dwarf.h */
00134 /* Taken as meaning 'undefined value', this is not
00135 a column or register number. */
00136 #ifndef DW_FRAME_UNDEFINED_VAL
00137 #define DW_FRAME_UNDEFINED_VAL
00138 #endif
00139 /* Taken as meaning 'same value' as caller had, 00140 not a column or register number */ 00141 #ifndef DW_FRAME_SAME_VAL
00142 #define DW FRAME SAME VAL
00143 #endif
00144 /* DW_FRAME_CFA_COL is assigned a virtual table position 00145 but is accessed via CFA specific calls. \star/
00146 #ifndef DW_FRAME_CFA_COL
00147 #define DW_FRAME_CFA_COL
00148 #endif
```

```
00149 #define DW_FRAME_CFA_COL3 DW_FRAME_CFA_COL /*compatibility name*/
00150 /* END FRAME special values */
00151
00152 /\star dwarf_pcline function, slide arguments
00153 */
00154 #define DW_DLS_BACKWARD -1 /* slide backward to find line */
00155 #define DW_DLS_NOSLIDE 0 /* match exactly without sliding */
00156 #define DW_DLS_FORWARD 1 /* slide forward to find line */
00157
00158 /* Defined larger than necessary.
          struct Dwarf_Debug_Fission_Per_CU_s,
00159
00160
          being visible, will be difficult to change:
          binary compatibility. The count is for arrays
00161
          inside the struct, the struct itself is
00162
00163
          a single struct. */
00164 #define DW_FISSION_SECT_COUNT 12
00165
00196 typedef unsigned long long Dwarf_Unsigned; 00197 typedef signed long long Dwarf_Signed;
00198 typedef unsigned long long Dwarf_Off;
00199 typedef unsigned long long Dwarf_Addr;
00200 /* Dwarf_Bool as int is wasteful, but for compatibility
00201
               it must stay as int, not unsigned char. \star/
00202 typedef int
                                 Dwarf_Bool;
Dwarf_Half;
Dwarf_Small;
                                                  /* boolean type */
/* 2 byte unsigned value */
00203 typedef unsigned short
                                                  /* 1 byte unsigned value */
00204 typedef unsigned char
00205 /* If sizeof(Dwarf_Half) is greater than 2
00206 we believe libdwarf still works properly. */
00207
00208 typedef void*
                             Dwarf_Ptr;
                                                    /* host machine pointer */
00234 enum Dwarf_Ranges_Entry_Type { DW_RANGES_ENTRY,
          DW_RANGES_ADDRESS_SELECTION,
          DW_RANGES_END
00236
00237 };
00238
00269 enum Dwarf Form Class {
          DW_FORM_CLASS_UNKNOWN = 0,
00270
           DW_FORM_CLASS_ADDRESS = 1,
00271
00272
           DW_FORM_CLASS_BLOCK
00273
           DW_FORM_CLASS_CONSTANT =3,
00274
          DW_FORM_CLASS_EXPRLOC = 4,
          DW_FORM_CLASS_FLAG
00275
          DW_FORM_CLASS_LINEPTR = 6,
00276
00277
          DW_FORM_CLASS_LOCLISTPTR=7,
                                            /* DWARF2,3,4 only */
                                            /* DWARF2,3,4 only */
           DW_FORM_CLASS_MACPTR = 8,
00278
00279
           DW_FORM_CLASS_RANGELISTPTR=9, /* DWARF2,3,4 only */
00280
          DW_FORM_CLASS_REFERENCE=10,
00281
           DW_FORM_CLASS_STRING = 11,
           DW_FORM_CLASS_FRAMEPTR= 12, /* MIPS/IRIX DWARF2 only */
00282
                                           /* DWARF5 */
           DW_FORM_CLASS_MACROPTR= 13,
00283
                                             /* DWARF5 */
00284
           DW_FORM_CLASS_ADDRPTR = 14,
           DW_FORM_CLASS_LOCLIST = 15,
00285
                                            /* DWARF5 */
00286
           DW_FORM_CLASS_LOCLISTSPTR=16, /* DWARF5 */
00287
          DW_FORM_CLASS_RNGLIST =17, /* DWARF5 */
DW_FORM_CLASS_RNGLISTSPTR=18, /* DWARF5 */
00288
00289
          DW_FORM_CLASS_STROFFSETSPTR=19 /* DWARF5 */
00290 1:
00302 typedef struct Dwarf_Form_Data16_s {
00303
          unsigned char fd_data[16];
00304 } Dwarf_Form_Data16;
00305
00313 typedef struct Dwarf_Sig8_s {
00314
          char signature[8];
00315 } Dwarf_Sig8;
00316
00330 typedef struct Dwarf_Block_s {
00331
        Dwarf_Unsigned bl_len;
00332
          Dwarf Ptr
                           bl data:
          Dwarf_Small
                           bl_from_loclist;
00333
          Dwarf_Unsigned bl_section_offset;
00334
00335 } Dwarf_Block;
00336
00342 typedef struct Dwarf_Locdesc_c_s * Dwarf_Locdesc_c;
00347 typedef struct Dwarf_Loc_Head_c_s * Dwarf_Loc_Head_c;
00348
00357 typedef struct Dwarf_Gnu_Index_Head_s * Dwarf_Gnu_Index_Head;
00358
00363 typedef struct Dwarf_Dsc_Head_s * Dwarf_Dsc_Head;
00364
00370 typedef struct Dwarf_Frame_Instr_Head_s * Dwarf_Frame_Instr_Head;
00371
00393 typedef void (* dwarf_printf_callback_function_type)
00394
           (void * dw_user_pointer, const char * dw_linecontent);
00395
00413 struct Dwarf_Printf_Callback_Info_s {
00414
          void *
                                            dp_user_pointer;
          dwarf_printf_callback_function_type dp_fptr;
00415
```

```
char *
00416
                                         dp_buffer;
          unsigned int
00417
                                          dp_buffer_len;
00418
          int
                                          dp_buffer_user_provided;
                                          dp_reserved;
00419
          void *
00420 };
00421
00441 struct Dwarf_Cmdline_Options_s {
00442
          Dwarf_Bool check_verbose_mode;
00443 };
00447 typedef struct Dwarf_Cmdline_Options_s Dwarf_Cmdline_Options;
00448
00455 typedef struct Dwarf Str Offsets Table s * Dwarf Str Offsets Table:
00456
00469 typedef struct Dwarf_Ranges_s {
00470
          Dwarf_Addr dwr_addr1;
00471
          Dwarf_Addr dwr_addr2;
00472
          enum Dwarf_Ranges_Entry_Type dwr_type;
00473 } Dwarf_Ranges;
00553 typedef struct Dwarf_Regtable_Entry3_s {
                             dw_offset_relevant;
00554
         Dwarf_Small
00555
          Dwarf_Small
                               dw_value_type;
                           dw_offset; /* Should be Dwarf_Signed */
dw_args_size; /* Always zero. */
dw_block;
00556
          Dwarf_Half
00557
         Dwarf_Unsigned
        Dwarf_Unsigned
Dwarf_Block
00558
00559
00560 } Dwarf_Regtable_Entry3;
00561
00581 typedef struct Dwarf_Regtable3_s {
00582 struct Dwarf_Regtable_Entry3_s
00583 Dwarf_Half
                                            rt3 cfa rule;
                                             rt3 reg table size:
00584
          struct Dwarf_Regtable_Entry3_s * rt3_rules;
00585 } Dwarf_Regtable3;
00586
00587 /* Opaque types for Consumer Library. */
00597 typedef struct Dwarf_Error_s* Dwarf_
                                          Dwarf Error:
00598
00603 typedef struct Dwarf_Debug_s*
                                          Dwarf Debug:
00608 typedef struct Dwarf_Section_s*
                                          Dwarf_Section;
00609
00613 typedef struct Dwarf_Die_s*
                                          Dwarf Die:
00614
00618 typedef struct Dwarf Debug Addr Table s* Dwarf Debug Addr Table;
00619
00624 typedef struct Dwarf_Line_s*
                                          Dwarf Line;
00625
00630 typedef struct Dwarf_Global_s*
                                          Dwarf Global:
00631
00639 typedef struct Dwarf Type s*
                                          Dwarf Type:
00640
00646 typedef struct Dwarf_Func_s*
                                          Dwarf_Func;
00652 typedef struct Dwarf_Var_s*
                                           Dwarf_Var;
00658 typedef struct Dwarf_Weak_s*
                                          Dwarf_Weak;
00659
00663 typedef struct Dwarf_Attribute_s* Dwarf_Attribute;
00664
00670 typedef struct Dwarf_Abbrev_s*
00671
00676 typedef struct Dwarf_Fde_s*
                                          Dwarf_Fde;
00681 typedef struct Dwarf_Cie_s*
                                          Dwarf_Cie;
00682
00687 typedef struct Dwarf_Arange_s*
                                          Dwarf_Arange;
00692 typedef struct Dwarf_Gdbindex_s* Dwarf_Gdbindex;
00698 typedef struct Dwarf_Xu_Index_Header_s *Dwarf_Xu_Index_Header;
00702 typedef struct Dwarf_Line_Context_s
                                                *Dwarf_Line_Context;
00703
                                             *Dwarf_Macro_Context;
00707 typedef struct Dwarf_Macro_Context_s
00708
00714 typedef struct Dwarf_Dnames_Head_s
                                               *Dwarf Dnames Head:
00723 typedef void (*Dwarf_Handler)(Dwarf_Error dw_error,
00724
          Dwarf_Ptr dw_errarg);
00725
00733 struct Dwarf_Macro_Details_s {
       Dwarf_Off
00734
                     dmd_offset; /* offset, in the section,
          of this macro info */
Dwarf_Small dmd_type;
00735
00736
                                   /* the type, DW_MACINFO_define etc*/
00737
          Dwarf_Signed dmd_lineno; /* the source line number where
          applicable and vend_def number if
00738
00739
              vendor_extension op */
00740
          Dwarf_Signed dmd_fileindex;/* the source file index */
         char *
00741
                       dmd_macro; /* macro name string */
00742 };
00747 typedef struct Dwarf_Macro_Details_s Dwarf_Macro_Details;
00748
00753 typedef struct Dwarf_Debug_Fission_Per_CU_s
00754
          Dwarf Debug Fission Per CU:
```

```
00756 /* ===== BEGIN Obj_Access data ===== */
00762 typedef struct Dwarf_Obj_Access_Interface_a_s
00763
         Dwarf_Obj_Access_Interface_a;
00764
00770 typedef struct Dwarf_Obj_Access_Methods_a_s
         Dwarf_Obj_Access_Methods_a;
00771
00772
00781 typedef struct Dwarf_Obj_Access_Section_a_s
00782
         Dwarf_Obj_Access_Section_a;
00783 struct Dwarf_Obj_Access_Section_a_s {
00784
       const char* as_name;
00785
          Dwarf_Unsigned as_type;
00786
         Dwarf_Unsigned as_flags;
         Dwarf_Addr as_addr;
00787
00788
         Dwarf_Unsigned as_offset;
00789
         Dwarf_Unsigned as_size;
00790
         Dwarf Unsigned as link;
          Dwarf_Unsigned as_info;
00792
          Dwarf_Unsigned as_addralign;
          Dwarf_Unsigned as_entrysize;
00793
00794 };
00795
00808 enum Dwarf Sec Alloc Pref {
00809
         /* No dynamic allocation */
          Dwarf_Alloc_None=0,
00811
          /* alternative allocations */
00812
         Dwarf_Alloc_Malloc=1,
00813
         Dwarf_Alloc_Mmap=2};
00814
00836 struct Dwarf Obj Access Methods a s {
00837
         int
                (*om_get_section_info)(void* obj,
             Dwarf_Unsigned
00838
                                         section_index,
00839
              Dwarf_Obj_Access_Section_a* return_section,
00840
             int
                                        * error);
          Dwarf_Small
                           (*om_get_byte_order) (void* obj);
00841
00842
          Dwarf Small
                           (*om_get_length_size) (void* obj);
          Dwarf_Small
                           (*om_get_pointer_size) (void* obj);
00844
          Dwarf_Unsigned
                           (*om_get_filesize)(void* obj);
          Dwarf_Unsigned (*om_get_section_count)(void* obj);
00845
00846
          /* Always uses malloc/read */
                          (*om_load_section)(void* obj,
00847
         int
             Dwarf_Unsigned dw_section_index,
00848
             Dwarf_Small **dw_return_data,
int *dw_error);
00849
00850
00851
                           (*om_relocate_a_section)(void* obj,
00852
             Dwarf_Unsigned section_index,
00853
             Dwarf_Debug dbg,
00854
                     * error);
              int
          /* Added in 0.12.0 to allow mmap in section loading.
00855
              If you are just using malloc for section loading
              and referring to this struct in your code
00857
00858
             you should leave this function pointer NULL (zero). \star/
00859
                          (*om_load_section_a)(void* obj,
00860
              Dwarf_Unsigned
                                        dw_section_index,
              /* dw_alloc_pref is input preference and also output with the actual alloced type */
00861
              enum Dwarf_Sec_Alloc_Pref *dw_alloc_pref,
00863
00864
              Dwarf_Small
                                      **dw_return_data_ptr,
00865
              Dwarf_Unsigned
                                       *dw_return_data_len,
00866
              Dwarf_Small
                                       **dw_return_mmap_base_ptr,
00867
              Dwarf Unsigned
                                       *dw return mmap offset,
00868
              Dwarf_Unsigned
                                        *dw_return_mmap_len,
00869
                                         *dw_error);
00870
                           (*om_finish)(void * obj);
00871 };
00872 struct Dwarf_Obj_Access_Interface_a_s {
00873
                                            ai object:
         void*
00874
          const Dwarf_Obj_Access_Methods_a *ai_methods;
00876 /* ===== END Obj_Access data ===== */
00877
00878 /* User code must allocate this struct, zero it,
00879
         and pass a pointer to it
          into dwarf_get_debugfission_for_cu . */
00880
00881 struct Dwarf_Debug_Fission_Per_CU_s {
         /* Do not free the string. It contains "cu" or "tu". */
00882
00883
         /* If this is not set (ie, not a CU/TU in DWP Package File)
00884
             then pcu_type will be NULL. */
00885
         const char * pcu_type;
         /\star pcu_index is the index (range 1 to N )
00886
              into the tu/cu table of offsets and the table
              of sizes. 1 to N as the zero index is reserved
00888
00889
              for special purposes. Not a value one
00890
             actually needs. */
00891
         Dwarf_Unsigned pcu_index;
                      pcu_hash; /* 8 byte */
00892
         Dwarf Sig8
```

```
/* [0] has offset and size 0.
                 [1]-[8] are DW_SECT_* indexes and the
00895
                values are the offset and size
00896
                 of the respective section contribution
00897
                of a single .dwo object. When pcu_size[n] is
            zero the corresponding section is not present. */
Dwarf_Unsigned pcu_offset[DW_FISSION_SECT_COUNT];
00898
00900
            Dwarf_Unsigned pcu_size[DW_FISSION_SECT_COUNT];
00901
            Dwarf_Unsigned unused1;
00902
           Dwarf Unsigned unused2;
00903 1:
00904
00909 typedef struct Dwarf_Rnglists_Head_s * Dwarf_Rnglists_Head;
00910
00916 /* Special values for offset_into_exception_table field
00917
           of dwarf fde's
00918
            The following value indicates that there is no
00919
           Exception table offset
           associated with a dwarf frame.
00921 */
00922 #define DW_DLX_NO_EH_OFFSET
                                                  (-1LL)
00923 /\star\,\, The following value indicates that the producer
00924
           was unable to analyze the
00925
           source file to generate Exception tables for this function.
00926 */
00927 #define DW DLX EH OFFSET UNAVAILABLE (-2LL)
00928
00929 /\star The augmenter string for CIE \star/
00930 #define DW_CIE_AUGMENTER_STRING_V0 "z"
00931
00932 /* ***IMPORTANT NOTE, TARGET DEPENDENCY ****
           DW_REG_TABLE_SIZE must be at least as large as
            the number of registers
00934
00935
           DW_FRAME_LAST_REG_NUM as defined in dwarf.h
00936 +/
00937 #ifndef DW_REG_TABLE_SIZE
00938 #define DW_REG_TABLE_SIZE DW_FRAME_LAST_REG_NUM
00939 #endif
00940
00941 /* For MIPS, DW_FRAME_SAME_VAL is the correct default value
00942
         for a frame register value. For other CPUS another value
         may be better, such as DW_FRAME_UNDEFINED_VAL. See dwarf_set_frame_rule_table_size
00943
00944
00946 #ifndef DW_FRAME_REG_INITIAL_VALUE
00947 #define DW_FRAME_REG_INITIAL_VALUE DW_FRAME_SAME_VAL
00948 #endif
00949
00950 /* The following are all needed to evaluate DWARF3 register rules.
00951 These have nothing to do simply printing
          frame instructions.
00953 */
00954 #define DW_EXPR_OFFSET
                                            0 /* offset is from CFA reg */
00955 #define DW_EXPR_VAL_OFFSET
00956 #define DW_EXPR_EXPRESSION
00957 #define DW_EXPR_VAL_EXPRESSION 3
00957 #define DW_DLA_EAPR_VAL_EAPRESSION 3
00968 #define DW_DLA_LOC 0x01 /* char* */
00969 #define DW_DLA_LOC 0x02 /* Dwarf_Loc */
00970 #define DW_DLA_LOCDESC 0x03 /* Dwarf_Locdesc */
00971 #define DW_DLA_ELLIST 0x04 /* Dwarf_Ellist (not used) */
                                           0x04 /* Dwarf_Bilst (not used) */
0x05 /* Dwarf_Bounds (not used) */
0x06 /* Dwarf_Block */
0x07 /* Dwarf_Debug */
0x08 /* Dwarf_Die */
0x09 /* Dwarf_Line */
00972 #define DW_DLA_BOUNDS
00973 #define DW_DLA_BLOCK
00974 #define DW_DLA_DEBUG
00975 #define DW_DLA_DIE
00976 #define DW_DLA_LINE
                                           0x09 /* Dwarf_Line */
0x0a /* Dwarf_Attribute */
0x0b /* Dwarf_Type (not used) */
0x0c /* Dwarf_Subscr (not used) */
0x0d /* Dwarf_Global */
0x0e /* Dwarf_Error */
0x0f /* a list */
0x10 /* Dwarf_Line* (not used) */
0x11 /* Dwarf_Arange */
00977 #define DW_DLA_ATTR
00978 #define DW_DLA_TYPE
00979 #define DW DLA SUBSCR
00980 #define DW_DLA_GLOBAL
00981 #define DW_DLA_ERROR
00982 #define DW_DLA_LIST
00983 #define DW_DLA_LINEBUF
                                            0x11 /* Dwarf_Arange */
0x12 /* Dwarf_Abbrev */
00984 #define DW_DLA_ARANGE
00985 #define DW_DLA_ABBREV
00986 #define DW_DLA_FRAME_INSTR_HEAD
                                               0x13 /* Dwarf_Frame_Instr_Head */
                                  0x14 /* Dwarf_Cie */
0x15 /* Dwarf_Fde */
CK 0x16 /* Dwarf_Loc */
00987 #define DW_DLA_CIE
00988 #define DW_DLA_FDE
00989 #define DW_DLA_LOC_BLOCK
00990
00991 #define DW DLA FRAME OP
                                            0x17 /* Dwarf_Frame_Op (not used) */
                                            0x18 /* Dwarf_Func */
00992 #define DW DLA FUNC
                                             0x19 /* Array of Dwarf_Off:Jan2023 */
00993 #define DW_DLA_UARRAY
00994 #define DW_DLA_VAR
                                             0x1a /* Dwarf_Var */
00995 #define DW_DLA_WEAK
                                            0x1b /* Dwarf_Weak */
                                            0x1c /* Dwarf_Addr sized entries */
0x1d /* Dwarf_Ranges */
00996 #define DW_DLA_ADDR
00997 #define DW_DLA_RANGES
00998 /* 0xle (30) to 0x34 (52) reserved for internal to libdwarf types. */
```

```
00999 /* .debug_gnu_typenames/pubnames, 2020 */
01000 #define DW DLA GNU INDEX HEAD 0x35
01001
01005 #define DW_DLA_LOC_BLOCK_C
                                      0x39 /* Dwarf_Loc_c*/
01006 #define DW_DLA_LOC_HEAD_C
                                      0x3a /* Dwarf_Locdesc_c */
                                      0x3b /* Dwarf_Loc_Head_c */
                                    0x3b /* DWarr_boc_ncas_ .
0x3c /* Dwarf_Macro_Context */
01008 #define DW_DLA_MACRO_CONTEXT
01009 /* 0x3d (61) is for libdwarf internal use.
0x3f /* Dwarf_Dnames_Head */
01011 #define DW_DLA_DNAMES_HEAD
01012
01013 /* struct Dwarf_Str_Offsets_Table_s */
                                     0x40
01014 #define DW_DLA_STR_OFFSETS
01015 /* struct Dwarf_Debug_Addr_Table_s */
01016 #define DW DLA DEBUG ADDR
01028 /* libdwarf error numbers */
01029 #define DW_DLE_NE 0 /* no error */ 01030 #define DW_DLE_VMM 1 /* dwarf format/library version mismatch */
                          01031 #define DW_DLE_MAP
01032 #define DW_DLE_LEE
01033 #define DW_DLE_NDS
01034 #define DW_DLE_NLS
01035 #define DW_DLE_ID
01036 #define DW_DLE_IOF
01037 #define DW_DLE_MAF ~~ 8 /\star memory allocation failure \star/
01038 #define DW_DLE_IA
                             10 /* mangled debugging entry */
01039 #define DW_DLE_MDE
01040 #define DW_DLE_MLE
                             11 /* mangled line number entry */
01041 #define DW_DLE_FNO
                             12 /* file not open */
01042 #define DW_DLE_FNR
                             13 /* file not a regular file */
01043 #define DW_DLE_FWA
                             14 /* file open with wrong access */
01044 #define DW_DLE_NOB
                             15 /* not an object file */
                             16 /* mangled object file header */
01045 #define DW_DLE_MOF
01046 #define DW_DLE_EOLL
                             17 /* end of location list entries */
01047 #define DW_DLE_NOLL
                             18 /* no location list section */
01048 #define DW_DLE_BADOFF 19 /* Invalid offset */
01049 #define DW_DLE_EOS 20 /* end of section */
01050 #define DW_DLE_ATRUNC 21 /* abbreviations section appears truncated*/
01051 #define DW_DLE_BADBITC 22 /* Address size passed to dwarf bad,*/
01052 /* It is not an allowed size (64 or 32) */
          /* Error codes defined by the current Libdwarf Implementation. */
01054 #define DW_DLE_DBG_ALLOC
01055 #define DW_DLE_FSTAT_ERROR
01056 #define DW_DLE_FSTAT_MODE_ERROR
01057 #define DW_DLE_INIT_ACCESS_WRONG
01058 #define DW_DLE_ELF_BEGIN_ERROR
01059 #define DW_DLE_ELF_GETEHDR_ERROR
01060 #define DW_DLE_ELF_GETSHDR_ERROR
01061 #define DW_DLE_ELF_STRPTR_ERROR
01062 #define DW_DLE_DEBUG_INFO_DUPLICATE
01063 #define DW_DLE_DEBUG_INFO_NULL
01064 #define DW_DLE_DEBUG_ABBREV_DUPLICATE
01065 #define DW_DLE_DEBUG_ABBREV_NULL
01066 #define DW_DLE_DEBUG_ARANGES_DUPLICATE
01067 #define DW_DLE_DEBUG_ARANGES_NULL
01068 #define DW_DLE_DEBUG_LINE_DUPLICATE
01069 #define DW_DLE_DEBUG_LINE_NULL
01070 #define DW_DLE_DEBUG_LOC_DUPLICATE
01071 #define DW_DLE_DEBUG_LOC_NULL
01072 #define DW_DLE_DEBUG_MACINFO_DUPLICATE
                                                        40
01073 #define DW_DLE_DEBUG_MACINFO_NULL
01074 #define DW_DLE_DEBUG_PUBNAMES_DUPLICATE
                                                        43
01075 #define DW_DLE_DEBUG_PUBNAMES_NULL
                                                        44
01076 #define DW_DLE_DEBUG_STR_DUPLICATE 01077 #define DW_DLE_DEBUG_STR_NULL
                                                        4.5
01078 #define DW_DLE_CU_LENGTH_ERROR
01079 #define DW_DLE_VERSION_STAMP_ERROR
01080 #define DW_DLE_ABBREV_OFFSET_ERROR
01081 #define DW_DLE_ADDRESS_SIZE_ERROR
                                                        50
01082 #define DW_DLE_DEBUG_INFO_PTR_NULL
                                                        51
01083 #define DW_DLE_DIE_NULL
01084 #define DW_DLE_STRING_OFFSET_BAD
01085 #define DW_DLE_DEBUG_LINE_LENGTH_BAD
01086 #define DW_DLE_LINE_PROLOG_LENGTH_BAD
01087 #define DW_DLE_LINE_NUM_OPERANDS_BAD
01088 #define DW_DLE_LINE_SET_ADDR_ERROR
01089 #define DW_DLE_LINE_EXT_OPCODE_BAD
01090 #define DW_DLE_DWARF_LINE_NULL
                                                        59
01091 #define DW_DLE_INCL_DIR_NUM_BAD
01092 #define DW_DLE_LINE_FILE_NUM_BAD
01093 #define DW_DLE_ALLOC_FAIL
01094 #define DW_DLE_NO_CALLBACK_FUNC
                                                        63
01095 #define DW_DLE_SECT_ALLOC
01096 #define DW_DLE_FILE_ENTRY_ALLOC
                                                        64
```

01097	#define	DW DLE	_LINE_ALLOC	66
			FPGM_ALLOC	67
01099	#define	DW_DLE	INCDIR_ALLOC	68
01100	#define	DW_DLE_	_STRING_ALLOC	69
01101	#define	DW_DLE_	_CHUNK_ALLOC	70
01102	#define	DW_DLE_	_BYTEOFF_ERR	71
			_CIE_ALLOC	72
			_FDE_ALLOC	73
			_REGNO_OVFL	74
			_CIE_OFFS_ALLOC	75
			_WRONG_ADDRESS	76
			_EXTRA_NEIGHBORS	77
			_WRONGTAG	78
			_DIE_ALLOC	79 80
			_PARENT_EXISTS _DBG_NULL	81
			_DEBUGLINE_ERROR	82
			_DEBUGFRAME_ERROR	83
				84
			_ATTR_ALLOC	85
01117	#define	DW_DLE_	_ABBREV_ALLOC	86
01118	#define	DW_DLE_	_OFFSET_UFLW	87
01119	#define	DW_DLE_	_ELF_SECT_ERR	88
			_DEBUG_FRAME_LENGTH_BAD	89
			_FRAME_VERSION_BAD	90
			_CIE_RET_ADDR_REG_ERROR	91
			FDE_NULL	92
			_FDE_DBG_NULL _CIE_NULL	93 94
			_CIE_NULL _CIE_DBG_NULL	95
			FRAME TABLE COL BAD	96
			_PC_NOT_IN_FDE_RANGE	97
			_CIE_INSTR_EXEC_ERROR	98
			FRAME_INSTR_EXEC_ERROR	99
01131	#define	DW_DLE_	_FDE_PTR_NULL	100
			_RET_OP_LIST_NULL	101
			_LINE_CONTEXT_NULL	102
			_DBG_NO_CU_CONTEXT	103
			_DIE_NO_CU_CONTEXT	104
			_FIRST_DIE_NOT_CU	105
01137			_NEXT_DIE_PTR_NULL _DEBUG_FRAME_DUPLICATE	106 107
			_DEBUG_FRAME_NULL	108
			_ABBREV_DECODE_ERROR	100
			_DWARF_ABBREV_NULL	110
			ATTR_NULL	111
01143	#define	DW_DLE_	_DIE_BAD	112
01144	#define	DW_DLE_	_DIE_ABBREV_BAD	113
			_ATTR_FORM_BAD	114
			_ATTR_NO_CU_CONTEXT	115
			_ATTR_FORM_SIZE_BAD	116
			_ATTR_DBG_NULL	117
			_BAD_REF_FORM ATTR FORM OFFSET BAD	118 119
			LINE OFFSET BAD	120
			_DEBUG_STR_OFFSET_BAD	121
			STRING_PTR_NULL	122
			PUBNAMES_VERSION_ERROR	123
01155	#define	DW_DLE_	_PUBNAMES_LENGTH_BAD	124
			_GLOBAL_NULL	125
			_GLOBAL_CONTEXT_NULL	126
			_DIR_INDEX_BAD	127
			_LOC_EXPR_BAD _DIE_LOC_EXPR_BAD	128
			_ADDR_ALLOC	129 130
			_ADDR_ADDC _OFFSET_BAD	131
			_OFFSET_BAD _MAKE_CU_CONTEXT_FAIL	132
			_REL_ALLOC	133
01165	#define	DW_DLE_	_ARANGE_OFFSET_BAD	134
01166	#define	DW_DLE_	_SEGMENT_SIZE_BAD	135
			_ARANGE_LENGTH_BAD	136
			_ARANGE_DECODE_ERROR	137
			_ARANGES_NULL	138
			_ARANGE_NULL	139
			_NO_FILE_NAME _NO_COMP_DIR	140 141
			_NO_COMP_DIR _CU_ADDRESS_SIZE_BAD	141
			_CO_ADDRESS_S1ZE_BAD _INPUT_ATTR_BAD	143
			_EXPR_NULL	144
			BAD_EXPR_OPCODE	145
			EXPR_LENGTH_BAD	146
			MULTIPLE_RELOC_IN_EXPR	147
			_ELF_GETIDENT_ERROR	148
			NO_AT_MIPS_FDE	149
			NO_CIE_FOR_FDE	150
			_DIE_ABBREV_LIST_NULL	151
01183	#deline	~w_⊓ਜੂਜੂ_	_DEBUGFUNCNAMESDUPLICATE	152

```
01184 #define DW_DLE_DEBUG_FUNCNAMES_NULL
01185 #define DW_DLE_DEBUG_FUNCNAMES_VERSION_ERROR
01186 #define DW_DLE_DEBUG_FUNCNAMES_LENGTH_BAD
                                                        155
01187 #define DW_DLE_FUNC_NULL
01188 #define DW_DLE_FUNC_CONTEXT_NULL
01189 #define DW_DLE_DEBUG_TYPENAMES_DUPLICATE
01190 #define DW_DLE_DEBUG_TYPENAMES_NULL
01191 #define DW_DLE_DEBUG_TYPENAMES_VERSION_ERROR
01192 #define DW_DLE_DEBUG_TYPENAMES_LENGTH_BAD
01193 #define DW_DLE_TYPE_NULL
                                                        162
01194 #define DW_DLE_TYPE_CONTEXT_NULL
                                                        163
01195 #define DW_DLE_DEBUG_VARNAMES_DUPLICATE
01196 #define DW_DLE_DEBUG_VARNAMES_NULL
                                                         165
01197 #define DW_DLE_DEBUG_VARNAMES_VERSION_ERROR
01198 #define DW_DLE_DEBUG_VARNAMES_LENGTH_BAD
                                                        167
01199 #define DW_DLE_VAR_NULL
01200 #define DW_DLE_VAR_CONTEXT_NULL
                                                        169
01201 #define DW_DLE_DEBUG_WEAKNAMES_DUPLICATE
                                                        170
01202 #define DW_DLE_DEBUG_WEAKNAMES_NULL
01203 #define DW_DLE_DEBUG_WEAKNAMES_VERSION_ERROR
01204 #define DW_DLE_DEBUG_WEAKNAMES_LENGTH_BAD
01205 #define DW_DLE_WEAK_NULL
                                                        174
01206 #define DW_DLE_WEAK_CONTEXT_NULL
01207 #define DW_DLE_LOCDESC_COUNT_WRONG
01208 #define DW_DLE_MACINFO_STRING_NULL
01209 #define DW_DLE_MACINFO_STRING_EMPTY
01210 #define DW_DLE_MACINFO_INTERNAL_ERROR_SPACE
                                                        179
01211 #define DW_DLE_MACINFO_MALLOC_FAIL
                                                        180
01212 #define DW_DLE_DEBUGMACINFO_ERROR
                                                        181
01213 #define DW_DLE_DEBUG_MACRO_LENGTH_BAD
                                                        182
01214 #define DW_DLE_DEBUG_MACRO_MAX_BAD
01215 #define DW_DLE_DEBUG_MACRO_INTERNAL_ERR
01216 #define DW_DLE_DEBUG_MACRO_MALLOC_SPACE
                                                        185
01217 #define DW_DLE_DEBUG_MACRO_INCONSISTENT
                                                        186
01218 #define DW_DLE_DF_NO_CIE_AUGMENTATION
                                                        187
01219 #define DW_DLE_DF_REG_NUM_TOO_HIGH
                                                        188
01220 #define DW_DLE_DF_MAKE_INSTR_NO_INIT
                                                        189
01221 #define DW_DLE_DF_NEW_LOC_LESS_OLD_LOC
01222 #define DW_DLE_DF_POP_EMPTY_STACK
                                                        191
01223 #define DW_DLE_DF_ALLOC_FAIL
                                                         192
01224 #define DW_DLE_DF_FRAME_DECODING_ERROR
                                                        193
01225 #define DW_DLE_DEBUG_LOC_SECTION_SHORT
01226 #define DW_DLE_FRAME_AUGMENTATION_UNKNOWN
                                                        195
01227 #define DW_DLE_PUBTYPE_CONTEXT
                                                         196 /* Unused. */
01228 #define DW_DLE_DEBUG_PUBTYPES_LENGTH_BAD
01229 #define DW_DLE_DEBUG_PUBTYPES_VERSION_ERROR
                                                        198
01230 #define DW_DLE_DEBUG_PUBTYPES_DUPLICATE
                                                        199
01231 #define DW_DLE_FRAME_CIE_DECODE_ERROR
01232 #define DW_DLE_FRAME_REGISTER_UNREPRESENTABLE
                                                        201
01233 #define DW DLE FRAME REGISTER COUNT MISMATCH
01234 #define DW_DLE_LINK_LOOP
01235 #define DW_DLE_STRP_OFFSET_BAD
01236 #define DW_DLE_DEBUG_RANGES_DUPLICATE
01237 #define DW_DLE_DEBUG_RANGES_OFFSET_BAD
01238 #define DW_DLE_DEBUG_RANGES_MISSING_END
                                                        207
01239 #define DW_DLE_DEBUG_RANGES_OUT_OF_MEM
                                                        2.08
01240 #define DW_DLE_DEBUG_SYMTAB_ERR
01241 #define DW_DLE_DEBUG_STRTAB_ERR
                                                        210
01242 #define DW_DLE_RELOC_MISMATCH_INDEX
01243 #define DW_DLE_RELOC_MISMATCH_RELOC_INDEX
01244 #define DW_DLE_RELOC_MISMATCH_STRTAB_INDEX
01245 #define DW_DLE_RELOC_SECTION_MISMATCH
01246 #define DW_DLE_RELOC_SECTION_MISSING_INDEX
                                                        214
                                                        215
01247 #define DW_DLE_RELOC_SECTION_LENGTH_ODD
01248 #define DW_DLE_RELOC_SECTION_PTR_NULL
01249 #define DW_DLE_RELOC_SECTION_MALLOC_FAIL
                                                        218
01250 #define DW_DLE_NO_ELF64_SUPPORT
01251 #define DW_DLE_MISSING_ELF64_SUPPORT
                                                        219
                                                        220
01252 #define DW_DLE_ORPHAN_FDE
                                                        221
01253 #define DW_DLE_DUPLICATE_INST_BLOCK
01254 #define DW_DLE_BAD_REF_SIG8_FORM
01255 #define DW_DLE_ATTR_EXPRLOC_FORM_BAD
                                                        224
01256 #define DW_DLE_FORM_SEC_OFFSET_LENGTH_BAD
                                                    225
01257 #define DW_DLE_NOT_REF_FORM
                                                        226
01258 #define DW_DLE_DEBUG_FRAME_LENGTH_NOT_MULTIPLE 227
01259 #define DW_DLE_REF_SIG8_NOT_HANDLED
01260 #define DW_DLE_DEBUG_FRAME_POSSIBLE_ADDRESS_BOTCH 229
01261 #define DW_DLE_LOC_BAD_TERMINATION
01262 #define DW_DLE_SYMTAB_SECTION_LENGTH_ODD
01263 #define DW_DLE_RELOC_SECTION_SYMBOL_INDEX_BAD 232
01264 #define DW_DLE_RELOC_SECTION_RELOC_TARGET_SIZE_UNKNOWN 233
01264 #define DW_DLE_SYMTAB_SECTION_ENTRYSIZE_ZERO
01266 #define DW_DLE_LINE_NUMBER_HEADER_ERROR
01267 #define DW_DLE_DEBUG_TYPES_NULL
                                                        236
01268 #define DW_DLE_DEBUG_TYPES_DUPLICATE
01269 #define DW_DLE_DEBUG_TYPES_ONLY_DWARF4 01270 #define DW_DLE_DEBUG_TYPEOFFSET_BAD
```

```
01271 #define DW_DLE_GNU_OPCODE_ERROR
01272 #define DW_DLE_DEBUGPUBTYPES_ERROR
01273 #define DW_DLE_AT_FIXUP_NULL
                                                         242
01274 #define DW_DLE_AT_FIXUP_DUP
                                                         243
01275 #define DW_DLE_BAD_ABINAME
                                                         2.44
01276 #define DW_DLE_TOO_MANY_DEBUG
                                                         245
01277 #define DW_DLE_DEBUG_STR_OFFSETS_DUPLICATE
01278 #define DW_DLE_SECTION_DUPLICATION
                                                         247
01279 #define DW_DLE_SECTION_ERROR
                                                         248
01280 #define DW_DLE_DEBUG_ADDR_DUPLICATE
                                                         249
01281 #define DW_DLE_DEBUG_CU_UNAVAILABLE_FOR_FORM
                                                         250
01282 #define DW_DLE_DEBUG_FORM_HANDLING_INCOMPLETE 251
01283 #define DW_DLE_NEXT_DIE_PAST_END
01284 #define DW_DLE_NEXT_DIE_WRONG_FORM
01285 #define DW_DLE_NEXT_DIE_NO_ABBREV_LIST
                                                         254
01286 #define DW_DLE_NESTED_FORM_INDIRECT_ERROR
01287 #define DW_DLE_CU_DIE_NO_ABBREV_LIST
01288 #define DW_DLE_MISSING_NEEDED_DEBUG_ADDR_SECTION 257
01289 #define DW_DLE_ATTR_FORM_NOT_ADDR_INDEX 258
01290 #define DW_DLE_ATTR_FORM_NOT_STR_INDEX
                                                         259
01291 #define DW_DLE_DUPLICATE_GDB_INDEX
01292 #define DW_DLE_ERRONEOUS_GDB_INDEX_SECTION
                                                         261
01293 #define DW_DLE_GDB_INDEX_COUNT_ERROR
01294 #define DW_DLE_GDB_INDEX_COUNT_ADDR_ERROR
01294 #define DW_DLE_GDB_INDEX_INDEX_ERROR
                                                         264
01296 #define DW_DLE_GDB_INDEX_CUVEC_ERROR
01296 #define DW_DLE_GUB_INDEA_GOODE
01297 #define DW_DLE_DUPLICATE_CU_INDEX
                                                         266
                                                       267
268
01298 #define DW_DLE_DUPLICATE_TU_INDEX
01299 #define DW_DLE_XU_TYPE_ARG_ERROR
01300 #define DW_DLE_XU_IMPOSSIBLE_ERROR
                                                         269
01301 #define DW_DLE_XU_NAME_COL_ERROR
01302 #define DW_DLE_XU_HASH_ROW_ERROR
01303 #define DW_DLE_XU_HASH_INDEX_ERROR
                                                         270
01304 /* ..._FAILSAFE_ERRVAL is an aid when out of memory.
01305 #define DW_DLE_FAILSAFE_ERRVAL
01306 #define DW_DLE_ARANGE_ERROR
                                                         274
01307 #define DW_DLE_PUBNAMES_ERROR
01308 #define DW_DLE_FUNCNAMES_ERROR
01309 #define DW_DLE_TYPENAMES_ERROR
                                                         277
01310 #define DW_DLE_VARNAMES_ERROR
                                                         278
01311 #define DW_DLE_WEAKNAMES_ERROR
                                                         279
01312 #define DW_DLE_RELOCS_ERROR
                                                        2.80
01313 #define DW_DLE_ATTR_OUTSIDE_SECTION
                                                        2.81
01314 #define DW_DLE_FISSION_INDEX_WRONG
                                                         282
01316 #define DW_DLE_FISSION_VERSION_ERROR
01317 #define DW_DLE_NEXT_DIE_LOW_ERROR
01318 #define DW_DLE_CU_UT_TYPE_ERROR
                                                         284
01318 #define DW_DLE_CU_UT_TYPE_ERROR
01318 #define DW_DLE_NO_SUCH_SIGNATURE_FOUND
01319 #define DW_DLE_CTOWNER
                                                         285
                                                         286
01319 #define DW_DLE_SIGNATURE_SECTION_NUMBER_WRONG 287
01320 #define DW_DLE_ATTR_FORM_NOT_DATA8 288
01321 #define DW_DLE_SIG_TYPE_WRONG_STRING
01322 #define DW_DLE_MISSING_REQUIRED_TU_OFFSET_HASH 290
01323 #define DW_DLE_MISSING_REQUIRED_CU_OFFSET_HASH 291
01324 #define DW_DLE_DWP_MISSING_DWO_ID 292
01325 #define DW_DLE_DWP_SIBLING_ERROR
                                                         293
01326 #define DW_DLE_DEBUG_FISSION_INCOMPLETE
01327 #define DW_DLE_FISSION_SECNUM_ERR
01328 #define DW_DLE_DEBUG_MACRO_DUPLICATE
01329 #define DW_DLE_DEBUG_MACRO_DUPLICATE
                                                         296
01329 #define DW_DLE_DEBUG_NAMES_DUPLICATE
                                                         297
01330 #define DW_DLE_DEBUG_LINE_STR_DUPLICATE
01331 #define DW_DLE_DEBUG_SUP_DUPLICATE
01332 #define DW_DLE_NO_SIGNATURE_TO_LOOKUP
                                                         299
01333 #define DW_DLE_NO_TIED_ADDR_AVAILABLE
01334 #define DW_DLE_NO_TIED_SIG_AVAILABLE
01335 #define DW_DLE_STRING_NOT_TERMINATED
01336 #define DW_DLE_BAD_LINE_TABLE_OPERATION
                                                         304
01337 #define DW_DLE_LINE_CONTEXT_BOTCH
01338 #define DW_DLE_LINE_CONTEXT_INDEX_WRONG
                                                        307
01339 #define DW_DLE_NO_TIED_STRING_AVAILABLE
01340 #define DW_DLE_NO_TIED_FILE_AVAILABLE
01341 #define DW_DLE_CU_TYPE_MISSING
                                                         309
01342 #define DW_DLE_LLE_CODE_UNKNOWN
                                                         310
01343 #define DW_DLE_LOCLIST_INTERFACE_ERROR 01344 #define DW_DLE_LOCLIST_INDEX_ERROR
                                                        311
01345 #define DW_DLE_INTERFACE_NOT_SUPPORTED
01346 #define DW_DLE_ZDEBUG_REQUIRES_ZLIB
01347 #define DW_DLE_ZDEBUG_INPUT_FORMAT_ODD
01348 #define DW_DLE_ZLIB_BUF_ERROR
01349 #define DW_DLE_ZLIB_DATA_ERROR
                                                         317
01350 #define DW_DLE_MACRO_OFFSET_BAD
01351 #define DW DLE MACRO OPCODE BAD
01352 #define DW_DLE_MACRO_OPCODE_FORM_BAD
01353 #define DW_DLE_UNKNOWN_FORM
01354 #define DW_DLE_BAD_MACRO_HEADER_POINTER
                                                         322
01355 #define DW_DLE_BAD_MACRO_INDEX
                                                         323
01356 #define DW_DLE_MACRO_OP_UNHANDLED
                                                         324
01357 #define DW_DLE_MACRO_PAST_END
```

```
01358 #define DW_DLE_LINE_STRP_OFFSET_BAD
01359 #define DW_DLE_STRING_FORM_IMPROPER
01360 #define DW_DLE_ELF_FLAGS_NOT_AVAILABLE
                                                      328
01361 #define DW_DLE_LEB_IMPROPER
01362 #define DW_DLE_DEBUG_LINE_RANGE_ZERO
01363 #define DW_DLE_DEBUG_LINE_RANGE_ZERO
                                                      329
01363 #define DW_DLE_READ_LITTLEENDIAN_ERROR
                                                      331
01364 #define DW_DLE_READ_BIGENDIAN_ERROR
01365 #define DW_DLE_RELOC_INVALID
01366 #define DW_DLE_INFO_HEADER_ERROR
                                                      334
01367 #define DW_DLE_ARANGES_HEADER_ERROR
                                                      335
01368 #define DW_DLE_LINE_OFFSET_WRONG_FORM
01369 #define DW_DLE_FORM_BLOCK_LENGTH_ERROR
01370 #define DW_DLE_ZLIB_SECTION_SHORT
                                                      338
01371 #define DW_DLE_CIE_INSTR_PTR_ERROR
                                                      339
01372 #define DW_DLE_FDE_INSTR_PTR_ERROR
                                                      340
01373 #define DW_DLE_FISSION_ADDITION_ERROR
                                                      341
01374 #define DW_DLE_HEADER_LEN_BIGGER_THAN_SECSIZE
                                                      342
01375 #define DW_DLE_LOCEXPR_OFF_SECTION_END
                                                      343
01376 #define DW_DLE_POINTER_SECTION_UNKNOWN
01377 #define DW_DLE_ERRONEOUS_XU_INDEX_SECTION
01378 #define DW_DLE_DIRECTORY_FORMAT_COUNT_VS_DIRECTORIES_MISMATCH 346
01379 #define DW_DLE_COMPRESSED_EMPTY_SECTION 347
01380 #define DW_DLE_SIZE_WRAPAROUND
                                                      348
01381 #define DW_DLE_ILLOGICAL_TSEARCH
01382 #define DW_DLE_BAD_STRING_FORM
                                                      349
01383 #define DW_DLE_DEBUGSTR_ERROR
01384 #define DW_DLE_DEBUGSTR_UNEXPECTED_REL
01385 #define DW_DLE_DISCR_ARRAY_ERROR
                                                      353
01386 #define DW_DLE_LEB_OUT_ERROR
                                                      354
01387 #define DW_DLE_SIBLING_LIST_IMPROPER
01388 #define DW_DLE_LOCLIST_OFFSET_BAD
01389 #define DW_DLE_LINE_TABLE_BAD
01390 #define DW_DLE_DEBUG_LOCIISTS_DUPLICATE
01391 #define DW_DLE_DEBUG_RNGLISTS_DUPLICATE
                                                      359
01392 #define DW_DLE_ABBREV_OFF_END
                                                      360
01393 #define DW_DLE_FORM_STRING_BAD_STRING
01394 #define DW_DLE_AUGMENTATION_STRING_OFF_END
01395 #define DW_DLE_STRING_OFF_END_PUBNAMES_LIKE
01396 #define DW_DLE_LINE_STRING_BAD
01397 #define DW_DLE_DEFINE_FILE_STRING_BAD
                                                      365
01398 #define DW_DLE_MACRO_STRING_BAD
01399 #define DW_DLE_MACINFO_STRING_BAD
01400 #define DW_DLE_ZLIB_UNCOMPRESS_ERROR
01401 #define DW_DLE_IMPROPER_DWO_ID
01402 #define DW_DLE_GROUPNUMBER_ERROR
                                                      370
01403 #define DW_DLE_ADDRESS_SIZE_ZERO
                                                      371
01404 #define DW_DLE_DEBUG_NAMES_HEADER_ERROR
                                                      372
01405 #define DW_DLE_DEBUG_NAMES_AUG_STRING_ERROR
                                                      373
01406 #define DW_DLE_DEBUG_NAMES_PAD_NON_ZERO
                                                      374
01407 #define DW DLE DEBUG NAMES OFF END
                                                      375
01408 #define DW_DLE_DEBUG_NAMES_ABBREV_OVERFLOW
01409 #define DW_DLE_DEBUG_NAMES_ABBREV_CORRUPTION
                                                      377
01410 #define DW_DLE_DEBUG_NAMES_NULL_POINTER
                                                      378
01411 #define DW_DLE_DEBUG_NAMES_BAD_INDEX_ARG
                                                      379
01412 #define DW_DLE_DEBUG_NAMES_ENTRYPOOL_OFFSET
                                                      380
01413 #define DW_DLE_DEBUG_NAMES_UNHANDLED_FORM
                                                      381
01414 #define DW_DLE_LNCT_CODE_UNKNOWN
01415 #define DW_DLE_LNCT_FORM_CODE_NOT_HANDLED
                                                      383
01416 #define DW_DLE_LINE_HEADER_LENGTH_BOTCH
                                                      384
01417 #define DW_DLE_STRING_HASHTAB_IDENTITY_ERROR
                                                      385
01418 #define DW_DLE_UNIT_TYPE_NOT_HANDLED
01419 #define DW_DLE_GROUP_MAP_ALLOC
                                                      386
                                                      387
01420 #define DW_DLE_GROUP_MAP_DUPLICATE
                                                      388
01421 #define DW_DLE_GROUP_COUNT_ERROR
01422 #define DW_DLE_GROUP_INTERNAL_ERROR
                                                      390
01423 #define DW_DLE_GROUP_LOAD_ERROR
                                                      391
01424 #define DW_DLE_GROUP_LOAD_READ_ERROR
                                                      392
01425 #define DW_DLE_AUG_DATA_LENGTH_BAD
                                                      393
01426 #define DW_DLE_ABBREV_MISSING
                                                      394
01427 #define DW_DLE_NO_TAG_FOR_DIE
01428 #define DW_DLE_LOWPC_WRONG_CLASS
01429 #define DW_DLE_HIGHPC_WRONG_FORM
                                                      397
01430 #define DW_DLE_STR_OFFSETS_BASE_WRONG_FORM
01431 #define DW_DLE_DATA16_OUTSIDE_SECTION
01431 #define DW_DLE_LNCT_MD5_WRONG_FORM
                                                      400
01433 #define DW_DLE_LINE_HEADER_CORRUPT
01434 #define DW_DLE_STR_OFFSETS_NULLARGUMENT
                                                      402
01435 #define DW_DLE_STR_OFFSETS_NULL_DBG
                                                      403
01436 #define DW_DLE_STR_OFFSETS_NO_MAGIC
                                                      404
01437 #define DW_DLE_STR_OFFSETS_ARRAY_SIZE
                                                      405
01438 #define DW_DLE_STR_OFFSETS_VERSION_WRONG
                                                      406
01439 #define DW_DLE_STR_OFFSETS_ARRAY_INDEX_WRONG
01440 #define DW_DLE_STR_OFFSETS_EXTRA_BYTES
                                                      408
01441 #define DW_DLE_DUP_ATTR_ON_DIE
                                                      409
01442 #define DW_DLE_SECTION_NAME_BIG
                                                      410
01443 #define DW_DLE_FILE_UNAVAILABLE
01444 #define DW_DLE_FILE_WRONG_TYPE
                                                      412
```

01445	#define	DW_DLE_SIBLING_OFFSET_WRONG	413
		DW_DLE_OPEN_FAIL	414
		DW_DLE_OFFSET_SIZE	415
			416
		DW_DLE_MACH_O_SEGOFFSET_BAD	
		DW_DLE_FILE_OFFSET_BAD	417
		DW_DLE_SEEK_ERROR	418
01451	#define	DW_DLE_READ_ERROR	419
01452	#define	DW_DLE_ELF_CLASS_BAD	420
		DW_DLE_ELF_ENDIAN_BAD	421
		DW_DLE_ELF_VERSION_BAD	422
		DW_DLE_FILE_TOO_SMALL	423
		DW_DLE_PATH_SIZE_TOO_SMALL	424
01457	#define	DW_DLE_BAD_TYPE_SIZE	425
01458	#define	DW_DLE_PE_SIZE_SMALL	426
01459	#define	DW_DLE_PE_OFFSET_BAD	427
		DW_DLE_PE_STRING_TOO_LONG	428
		DW_DLE_IMAGE_FILE_UNKNOWN_TYPE	429
		DW_DLE_LINE_TABLE_LINENO_ERROR	430
01463	#define	DW_DLE_PRODUCER_CODE_NOT_AVAILABLE	431
01464	#define	DW_DLE_NO_ELF_SUPPORT	432
		DW_DLE_NO_STREAM_RELOC_SUPPORT	433
		DW_DLE_RETURN_EMPTY_PUBNAMES_ERROR	434
		DW_DLE_SECTION_SIZE_ERROR	435
		DW_DLE_INTERNAL_NULL_POINTER	436
01469	#define	DW_DLE_SECTION_STRING_OFFSET_BAD	437
01470	#define	DW_DLE_SECTION_INDEX_BAD	438
		DW_DLE_INTEGER_TOO_SMALL	439
		DW_DLE_ELF_SECTION_LINK_ERROR	440
		DW_DLE_ELF_SECTION_GROUP_ERROR	441
01474	#define	DW_DLE_ELF_SECTION_COUNT_MISMATCH	442
01475	#define	DW_DLE_ELF_STRING_SECTION_MISSING	443
		DW_DLE_SEEK_OFF_END	444
		DW_DLE_READ_OFF_END	445
			446
		DW_DLE_ELF_SECTION_ERROR	
		DW_DLE_ELF_STRING_SECTION_ERROR	447
01480	#define	DW_DLE_MIXING_SPLIT_DWARF_VERSIONS	448
01481	#define	DW_DLE_TAG_CORRUPT	449
		DW_DLE_FORM_CORRUPT	450
		DW_DLE_ATTR_CORRUPT	451
		DW_DLE_ABBREV_ATTR_DUPLICATION	452
		DW_DLE_DWP_SIGNATURE_MISMATCH	453
01486	#define	DW_DLE_CU_UT_TYPE_VALUE	454
01487	#define	DW_DLE_DUPLICATE_GNU_DEBUGLINK	455
		DW_DLE_CORRUPT_GNU_DEBUGLINK	456
		DW_DLE_CORRUPT_NOTE_GNU_DEBUGID	457
		DW_DLE_CORRUPT_GNU_DEBUGID_SIZE	458
		DW_DLE_CORRUPT_GNU_DEBUGID_STRING	459
01492	#define	DW_DLE_HEX_STRING_ERROR	460
01493	#define	DW_DLE_DECIMAL_STRING_ERROR	461
01494	#define	DW_DLE_PRO_INIT_EXTRAS_UNKNOWN	462
		DW_DLE_PRO_INIT_EXTRAS_ERR	463
			464
		DW_DLE_NULL_ARGS_DWARF_ADD_PATH	
		DW_DLE_DWARF_INIT_DBG_NULL	465
		DW_DLE_ELF_RELOC_SECTION_ERROR	466
		DW_DLE_USER_DECLARED_ERROR	467
01500	#define	DW_DLE_RNGLISTS_ERROR	468
		DW_DLE_LOCLISTS_ERROR	469
		DW_DLE_SECTION_SIZE_OR_OFFSET_LARGE	470
		DW_DLE_GDBINDEX_STRING_ERROR	471
		DW_DLE_GNU_PUBNAMES_ERROR	472
01505		DW_DLE_GNU_PUBTYPES_ERROR	473
01506	#define	DW_DLE_DUPLICATE_GNU_DEBUG_PUBNAMES	474
01507		DW_DLE_DUPLICATE_GNU_DEBUG_PUBTYPES	475
01508		DW_DLE_DEBUG_SUP_STRING_ERROR	476
		DW_DLE_DEBUG_SUP_ERROR	477
01510		DW_DLE_LOCATION_ERROR	478
01511		DW_DLE_DEBUGLINK_PATH_SHORT	479
01512	#define	DW_DLE_SIGNATURE_MISMATCH	480
01513	#define	DW_DLE_MACRO_VERSION_ERROR	481
01514		DW_DLE_NEGATIVE_SIZE	482
01514		DW_DLE_UDATA_VALUE_NEGATIVE	483
			484
01516		DW_DLE_DEBUG_NAMES_ERROR	
01517		DW_DLE_CFA_INSTRUCTION_ERROR	485
01518	#define	DW_DLE_MACHO_CORRUPT_HEADER	486
01519	#define	DW_DLE_MACHO_CORRUPT_COMMAND	487
01520		DW_DLE_MACHO_CORRUPT_SECTIONDETAILS	488
01521		DW_DLE_RELOCATION_SECTION_SIZE_ERROR	489
			490
01522		DW_DLE_SYMBOL_SECTION_SIZE_ERROR	
01523		DW_DLE_PE_SECTION_SIZE_ERROR	491
		DW_DLE_DEBUG_ADDR_ERROR	492
01525	#define	DW_DLE_NO_SECT_STRINGS	493
01526		DW_DLE_TOO_FEW_SECTIONS	494
01527		DW_DLE_BUILD_ID_DESCRIPTION_SIZE	495
01528		DW_DLE_BAD_SECTION_FLAGS	496
		DW_DLE_IMPROPER_SECTION_ZERO	497
		DW_DLE_INVALID_NULL_ARGUMENT	498
01531	#define	DW_DLE_LINE_INDEX_WRONG	499

```
01532 #define DW_DLE_LINE_COUNT_WRONG
01533 #define DW_DLE_ARITHMETIC_OVERFLOW
                                                        501
01534 #define DW_DLE_UNIVERSAL_BINARY_ERROR
                                                        502
01535 #define DW_DLE_UNIV_BIN_OFFSET_SIZE_ERROR
                                                        503
01536 #define DW_DLE_PE_SECTION_SIZE_HEURISTIC_FAIL 01537 #define DW_DLE_LLE_ERROR
                                                        505
01538 #define DW_DLE_RLE_ERROR
01539 #define DW_DLE_MACHO_SEGMENT_COUNT_HEURISTIC_FAIL 507
01540
01542 #define DW_DLE_LAST
01543 #define DW_DLE_LO_USER
                                  507
                                  0x10000
01608 DW_API int dwarf_init_path(const char * dw_path,
                             dw_true_path_out_buffer,
01609
          char *
01610
          unsigned int
                             dw_true_path_bufferlen,
01611
          unsigned int
                             dw_groupnumber,
01612
          Dwarf_Handler
                             dw_errhand,
01613
          Dwarf Ptr
                             dw_errarg,
          Dwarf_Debug*
                             dw dbq,
01614
01615
          Dwarf_Error*
                             dw_error);
01629 DW_API int dwarf_init_path_a(const char * dw_path,
01630
          char *
                             dw_true_path_out_buffer,
          unsigned int
01631
                             dw_true_path_bufferlen,
01632
          unsigned int
                             dw groupnumber,
01633
          unsigned int
                             dw_universalnumber,
01634
          Dwarf_Handler
                             dw_errhand,
01635
          Dwarf_Ptr
                             dw_errarg,
01636
          Dwarf_Debug*
                             dw_dbg,
01637
          Dwarf_Error*
                             dw_error);
01638
01695 DW_API int dwarf_init_path_dl(const char * dw_path,
01696
          char *
                             dw_true_path_out_buffer,
01697
          unsigned int
                             dw_true_path_bufferlen,
01698
          unsigned int
                             dw_groupnumber,
01699
          Dwarf_Handler
                             dw_errhand,
01700
          Dwarf Ptr
                             dw_errarg,
01701
          Dwarf Debug*
                             dw dba,
01702
          char **
                             dw_dl_path_array,
01703
          unsigned int
                             dw_dl_path_array_size,
01704
          unsigned char
                          * dw_dl_path_source,
01705
          Dwarf_Error*
                             dw_error);
01706
01723 DW_API int dwarf_init_path_dl_a(const char * dw_path,
01724
                             dw_true_path_out_buffer,
          char *
          unsigned int
01725
                             dw_true_path_bufferlen,
                             dw_groupnumber,
01726
          unsigned int
01727
          unsigned int
                             dw_universalnumber,
01728
          Dwarf_Handler
                             dw_errhand,
01729
          Dwarf Ptr
                             dw_errarg,
01730
          Dwarf_Debug*
                             dw_dbg,
01731
          char **
                             dw_dl_path_array,
01732
          unsigned int
                            dw_dl_path_array_size,
01733
          unsigned char
                          * dw_dl_path_source,
01734
          Dwarf_Error*
                            dw_error);
01735
01769 DW API int dwarf init b(int dw fd,
                           dw_groupnumber,
01770
         unsigned int
01771
          Dwarf_Handler
                             dw_errhand,
01772
          Dwarf_Ptr
                             dw_errarg,
01773
          Dwarf Debug*
                             dw_dbg,
01774
          Dwarf Error*
                           dw_error);
01775
01791 DW_API int dwarf_finish(Dwarf_Debug dw_dbg);
01792
01826 DW_API int dwarf_object_init_b(Dwarf_Obj_Access_Interface_a* dw_obj,
01827
          Dwarf_Handler dw_errhand,
01828
          Dwarf Ptr
                        dw_errarg,
          unsigned int dw_groupnumber,
01829
01830
          Dwarf_Debug* dw_dbg,
          Dwarf_Error* dw_error);
01832
01847 DW_API int dwarf_object_finish(Dwarf_Debug dw_dbg);
01848
01879 DW_API int dwarf_set_tied_dbg(Dwarf_Debug dw_split_dbg,
01880 Dwarf_Debug dw_tied_dbg,
01881 Dwarf_Error* dw_error);
01882
01916 DW_API int dwarf_get_tied_dbg(Dwarf_Debug dw_dbg,
          Dwarf_Debug * dw_tieddbg_out,
Dwarf_Error * dw_error);
01917
01918
01999 DW_API int dwarf_next_cu_header_e(Dwarf_Debug dw_dbg,
02000
          Dwarf_Bool
                          dw_is_info,
02001
          Dwarf_Die
                          *dw_cu_die,
02002
          Dwarf_Unsigned *dw_cu_header_length,
02003
          Dwarf_Half *dw_version_stamp,
02004
          Dwarf Off
                          *dw_abbrev_offset,
02005
          Dwarf_Half
                          *dw address size.
```

```
02006
          Dwarf_Half
                         *dw_length_size,
                         *dw_extension_size,
02007
          Dwarf_Half
02008
          Dwarf_Sig8
                         *dw_type_signature,
          Dwarf_Unsigned *dw_typeoffset,
02009
02010
         Dwarf_Unsigned *dw_next_cu_header_offset,
02011
                         *dw_header_cu_type,
          Dwarf Half
02012
         Dwarf_Error
                         *dw_error);
02013
02044 DW_API int dwarf_next_cu_header_d(Dwarf_Debug dw_dbg,
02045
         Dwarf Bool
                         dw_is_info,
         Dwarf_Unsigned *dw_cu_header_length,
02046
02047
                       *dw_version_stamp,
          Dwarf Half
02048
          Dwarf_Off
                         *dw_abbrev_offset,
02049
          Dwarf_Half
                         *dw_address_size,
02050
         Dwarf_Half
                         *dw_length_size,
02051
         Dwarf_Half
                         *dw_extension_size,
02052
         Dwarf Sig8
                         *dw_type_signature,
02053
         Dwarf_Unsigned *dw_typeoffset,
02054
         Dwarf_Unsigned *dw_next_cu_header_offset,
02055
          Dwarf_Half
                         *dw_header_cu_type,
02056
         Dwarf_Error
                         *dw error);
02057
02073 DW_API int dwarf_siblingof_c(Dwarf_Die
                                               dw die,
02074
         Dwarf_Die *dw_return_siblingdie,
02075
         Dwarf_Error *dw_error);
02076
02111 DW_API int dwarf_siblingof_b(Dwarf_Debug dw_dbg,
                     dw_die,
dw_is_info,
02112 Dwarf_Die
02113
         Dwarf Bool
         Dwarf_Die *dw_return_siblingdie,
02114
02115
         Dwarf Error *dw error);
02116
02157 DW_API int dwarf_cu_header_basics(Dwarf_Die dw_die,
02158
         Dwarf_Half
                         *dw_version,
02159
         Dwarf_Bool
                         *dw_is_info,
02160
         Dwarf Bool
                         *dw_is_dwo,
02161
         Dwarf Half
                         *dw offset size,
02162
         Dwarf_Half
                         *dw_address_size,
02163
          Dwarf_Half
                         *dw_extension_size,
02164
         Dwarf_Sig8
                        **dw_signature,
02165
         Dwarf Off
                         *dw_offset_of_length,
         Dwarf_Unsigned *dw_total_byte_length,
02166
02167
         Dwarf Error
                        *dw error);
02168
02188 DW_API int dwarf_child(Dwarf_Die dw_die,
         Dwarf_Die* dw_return_childdie,
Dwarf_Error* dw_error);
02189
02190
02191
02199 DW API void dwarf dealloc die ( Dwarf Die dw die);
02200
02218 DW_API int dwarf_die_from_hash_signature(Dwarf_Debug dw_dbg,
02219
         Dwarf_Sig8 * dw_hash_sig,
02220
          const char * dw_sig_type,
02221
         Dwarf Die*
                        dw_returned_CU_die,
         Dwarf_Error* dw_error);
02222
02223
02254 DW_API int dwarf_offdie_b(Dwarf_Debug dw_dbg,
                     dw_offset,
02255
         Dwarf_Off
02256
         Dwarf_Bool
                           dw_is_info,
02257
         Dwarf Die*
                           dw_return_die,
02258
         Dwarf Error*
                          dw_error);
02259
02281 DW_API int dwarf_find_die_given_sig8(Dwarf_Debug dw_dbg,
02281 DW_AFI IIIC dwaII__IIIC____
02282 Dwarf_Sig8 *dw_ref,
02283 Dwarf_Die *dw_die_out,
         Dwarf_Bool *dw_is_info,
02284
02285
         Dwarf Error *dw error);
02286
02297 DW_API Dwarf_Bool dwarf_get_die_infotypes_flag(Dwarf_Die dw_die);
02327 DW_API int dwarf_die_abbrev_global_offset(Dwarf_Die dw_die,
02328
       Dwarf_Off
                         * dw_abbrev_offset,
         Dwarf_Unsigned * dw_abbrev_count,
02329
02330
         Dwarf_Error*
                            dw_error);
02331
02342 DW_API int dwarf_tag(Dwarf_Die dw_die,
02343
         Dwarf_Half*
                          dw_return_tag,
02344
         Dwarf_Error*
                           dw_error);
02345
02358 DW_API int dwarf_dieoffset(Dwarf_Die dw_die,
02359
         Dwarf Off*
                           dw return offset,
02360
         Dwarf Error*
                           dw error);
02361
02380 DW_API int dwarf_debug_addr_index_to_addr(Dwarf_Die dw_die,
02381
         Dwarf_Unsigned dw_index,
         02382
02383
02384
```

```
02393 DW_API Dwarf_Bool dwarf_addr_form_is_indexed(int dw_form);
02394
02418 DW_API int dwarf_CU_dieoffset_given_die(Dwarf_Die dw_die,
02419
          Dwarf_Off*
                            dw_return_offset,
02420
          Dwarf_Error*
                             dw_error);
02421
02442 DW_API int dwarf_get_cu_die_offset_given_cu_header_offset_b(
02443
          Dwarf_Debug dw_dbg,
          Dwarf_Off dw_in_cu_header_offset,
Dwarf_Bool dw_is_info,
Dwarf_Off * dw_out_cu_die_offset,
02444
02445
02446
          Dwarf_Error *dw_error);
02447
02448
02466 DW_API int dwarf_die_CU_offset(Dwarf_Die dw_die,
                         dw_return_offset,
dw_error);
02467
          Dwarf_Off*
02468
          Dwarf_Error*
02469
02490 DW_API int dwarf_die_CU_offset_range(Dwarf_Die dw_die,
        Dwarf_Off* dw_return_CU_header_offset,
Dwarf_Off* dw_return_CU_length_bytes,
02492
02493
          Dwarf_Error* dw_error);
02494
02512 DW_API int dwarf_attr(Dwarf_Die dw_die,
02513
          Dwarf Half
                              dw_attrnum,
02514
           Dwarf_Attribute * dw_returned_attr,
02515
          Dwarf_Error*
                             dw_error);
02516
02538 DW_API int dwarf_die_text(Dwarf_Die dw_die,
          Dwarf_Half dw_attrnum, char ** dw_ret_name,
02539
02540
02541
          Dwarf Error * dw error);
02542
02562 DW_API int dwarf_diename(Dwarf_Die dw_die,
          char
02563
                            dw_diename,
                  **
02564
          Dwarf Error*
                             dw_error);
02565
02583 DW API Dwarf Unsigned dwarf die abbrev code (Dwarf Die dw die);
02598 DW_API int dwarf_die_abbrev_children_flag(Dwarf_Die dw_die,
02599
         Dwarf_Half * dw_ab_has_child);
02600
02624 DW API int dwarf validate die sibling (Dwarf Die dw sibling,
02625
          Dwarf Off* dw offset);
02626
02627 /\star convenience functions, alternative to using dwarf_attrlist \star/
02628
02647 DW_API int dwarf_hasattr(Dwarf_Die dw_die,
          Dwarf_Half dw_attrnum,
Dwarf_Bool * dw_returned_bool,
02648
02649
          Dwarf_Error* dw_error);
02650
02651
02687 DW_API int dwarf_offset_list(Dwarf_Debug dw_dbg,
                          dw_offset,
02688
          Dwarf_Off
02689
           Dwarf_Bool
                              dw_is_info,
                           ** dw_offbuf,
02690
          Dwarf Off
          Dwarf_Unsigned * dw_offcount,
Dwarf_Error * dw_error);
02691
02692
02693
02706 DW_API int dwarf_get_die_address_size(Dwarf_Die dw_die,
          Dwarf_Half * dw_addr_size,
Dwarf_Error * dw_error);
02707
02708
02709
02710 /\star Get both offsets (local and global) \star/
02730 DW_API int dwarf_die_offsets(Dwarf_Die dw_die,
          Dwarf_Off*
Dwarf_Off*
02731
                         dw_global_offset,
02732
                          dw_local_offset,
          Dwarf_Error* dw_error);
02733
02734
02751 DW_API int dwarf_get_version_of_die(Dwarf_Die dw_die,
          Dwarf_Half * dw_version,
Dwarf_Half * dw_offset_size);
02753
02754
02768 DW_API int dwarf_lowpc(Dwarf_Die dw_die,
02769
          Dwarf_Addr * dw_returned_addr,
02770
           Dwarf_Error* dw_error);
02771
02803 DW_API int dwarf_highpc_b(Dwarf_Die dw_die,
02804
       Dwarf_Addr * dw_return_addr,
Dwarf Half * dw return form,
02805
                                     dw_return_form,
           enum Dwarf_Form_Class * dw_return_class,
02806
02807
          Dwarf Error *
                                     dw error);
02808
02834 DW_API int dwarf_dietype_offset(Dwarf_Die dw_die,
          Dwarf_Off * dw_return_offset,
Dwarf_Bool * dw_is_info,
02835
02836
          Dwarf_Error * dw_error);
02837
02838
```

```
02850 DW_API int dwarf_bytesize(Dwarf_Die dw_die,
          Dwarf_Unsigned * dw_returned_size,
02852
          Dwarf_Error*
                             dw_error);
02853
02865 DW_API int dwarf_bitsize(Dwarf_Die dw_die,
          Dwarf_Unsigned * dw_returned_size,
Dwarf_Error* dw_error);
02866
02868
02889 DW_API int dwarf_bitoffset(Dwarf_Die dw_die,
          Dwarf_Half * dw_attrnum,
Dwarf_Unsigned * dw_returned_offset,
02890
          Dwarf Half
02891
02892
          Dwarf Error*
                            dw_error);
02893
02907 DW_API int dwarf_srclang(Dwarf_Die dw_die,
02908
          Dwarf_Unsigned * dw_returned_lang,
02909
          Dwarf_Error
                         * dw_error);
02910
02931 DW API int dwarf language version string(
         Dwarf_Unsigned dw_lang_name,
02933
                          dw_default_lower_bound,
02934
           const char **dw_version_string);
02935
02948 DW_API int dwarf_arrayorder(Dwarf_Die dw_die,
02949
          Dwarf_Unsigned * dw_returned_order,
           Dwarf_Error*
02950
                            dw_error);
02980 DW_API int dwarf_attrlist(Dwarf_Die dw_die,
          Dwarf_Attribute** dw_attrbuf,
02981
          Dwarf_Signed * dw_attrcount,
Dwarf_Error* dw_error);
02982
02983
02984
03003 DW_API int dwarf_hasform(Dwarf_Attribute dw_attr,
03004 Dwarf_Half dw_form,
03005 Dwarf_Bool * dw_returned_bool,
03006
          Dwarf_Error* dw_error);
03007
03026 DW_API int dwarf_whatform(Dwarf_Attribute dw_attr,
03027 Dwarf_Half * dw_returned_final_form,
03028 Dwarf_Error* dw_error);
03029
03046 DW_API int dwarf_whatform_direct(Dwarf_Attribute dw_attr,
03047
          Dwarf_Half * dw_returned_initial_form,
          Dwarf_Error* dw_error);
03048
03049
03065 DW_API int dwarf_whatattr(Dwarf_Attribute dw_attr,
03066
          Dwarf_Half * dw_returned_attrnum,
03067
          Dwarf_Error* dw_error);
03068
03093 DW_API int dwarf\_formref(Dwarf\_Attribute\ dw\_attr,
          Dwarf_Off* dw_return_offset,
Dwarf_Bool *dw_is_info,
03094
03095
          Dwarf_Error *dw_error);
03097
03130 DW_API int dwarf_global_formref_b(Dwarf_Attribute dw_attr,
         Dwarf_Off *dw_return_offset,
Dwarf_Bool *dw_offset_is_info,
03131
03132
03133
          Dwarf Error *dw error);
03134
03145 DW_API int dwarf_global_formref(Dwarf_Attribute dw_attr,
                           dw_return_offset,
03146
          Dwarf_Off*
03147
          Dwarf Error*
                             dw_error);
0.3148
Dwarf_Error* dw_error);
03169
03170
03189 DW_API int dwarf_formsig8_const(Dwarf_Attribute dw_attr,
          Dwarf_Sig8 * dw_returned_sig_bytes,
0.3190
          Dwarf_Error* dw_error);
03191
03192
03212 DW_API int dwarf_formaddr(Dwarf_Attribute dw_attr,
03213
          Dwarf_Addr * dw_returned_addr,
03214
          Dwarf_Error* dw_error);
03215
03235 DW_API int dwarf_get_debug_addr_index(Dwarf_Attribute dw_attr,
          Dwarf_Unsigned * dw_return_index,
Dwarf_Error * dw_error);
03236
03237
03238
03252 DW_API int dwarf_formflag(Dwarf_Attribute dw_attr,
03253
          Dwarf Bool *
                             dw_returned_bool,
03254
          Dwarf Error*
                             dw error);
03255
03271 DW_API int dwarf_formudata(Dwarf_Attribute dw_attr,
03272
          Dwarf_Unsigned * dw_returned_val,
03273
          Dwarf_Error*
                            dw_error);
03274
03289 DW_API int dwarf_formsdata(Dwarf_Attribute dw_attr,
03290
          Dwarf Signed * dw returned val.
```

```
03291
          Dwarf_Error*
                           dw_error);
03292
03310 DW_API int dwarf_formdata16(Dwarf_Attribute dw_attr,
03311
          Dwarf_Form_Data16 * dw_returned_val,
03312
          Dwarf Error*
                               dw error);
03313
03332 DW_API int dwarf_formblock(Dwarf_Attribute dw_attr,
          Dwarf_Block ** dw_returned_block,
Dwarf_Error* dw_error);
03333
03334
03335
03350 DW_API int dwarf_formstring(Dwarf_Attribute dw_attr,
03351
          char
                            dw_returned_string,
03352
          Dwarf_Error*
                            dw error);
03353
03369 DW_API int dwarf_get_debug_str_index(Dwarf_Attribute dw_attr,
         Dwarf_Unsigned * dw_return_index,
Dwarf_Error * dw_error);
03370
03371
03372
03391 DW_API int dwarf_formexprloc(Dwarf_Attribute dw_attr,
03392
          Dwarf_Unsigned * dw_return_exprlen,
                        * dw_block_ptr,
03393
          Dwarf_Ptr
03394
          Dwarf_Error
                          * dw_error);
03395
03415 DW_API enum Dwarf_Form_Class dwarf_get_form_class(
          Dwarf_Half dw_version,
03416
          Dwarf_Half dw_attrnum,
03417
          Dwarf_Half dw_offset_size,
03418
03419
          Dwarf_Half dw_form);
03420
03436 DW_API int dwarf_attr_offset(Dwarf_Die dw_die,
03437
          Dwarf_Attribute dw_attr,
03438
          Dwarf_Off
                        * dw_return_offset,
03439
          Dwarf_Error
                        * dw_error);
03440
03448 DW_API int dwarf_uncompress_integer_block_a(Dwarf_Debug dw_dbg,
         Dwarf_Unsigned dw_input_length_in_bytes,
void * dw_input_block,
03449
03450
          Dwarf_Unsigned * dw_value_count,
          Dwarf_Signed ** dw_value_array,
Dwarf_Error * dw_error);
03452
03453
03454
03462 DW_API void dwarf_dealloc_uncompressed_block(Dwarf_Debug dw_dbg,
03463
          void *dw value array);
03464
03484 DW_API int dwarf_convert_to_global_offset(Dwarf_Attribute dw_attr,
          Dwarf_Off dw_offset,
Dwarf_Off* dw_return_offset,
03485
03486
          Dwarf_Error* dw_error);
03487
03488
03494 DW API void dwarf dealloc attribute (Dwarf Attribute dw attr);
03495
03522 DW_API int dwarf_discr_list(Dwarf_Debug dw_dbg,
          Dwarf_Small * dw_blockpointer,
Dwarf_Unsigned dw_blocklen,
Dwarf_Dsc_Head * dw_dsc_head_out,
03523
03524
03525
          Dwarf_Unsigned * dw_dsc_array_length_out,
03526
                          * dw_error);
          Dwarf Error
03528
03554 DW_API int dwarf_discr_entry_u(Dwarf_Dsc_Head dw_dsc,
          Dwarf_Half & dw_entrynum,
Dwarf_Half & dw_out_type,
03555
03556
          Dwarf_Unsigned * dw_out_discr_low,
03557
03558
          Dwarf_Unsigned * dw_out_discr_high,
03559
                         * dw_error);
          Dwarf Error
03560
03566 DW_API int dwarf_discr_entry_s(Dwarf_Dsc_Head dw_dsc,
03567
          Dwarf_Unsigned dw_entrynum,
                          * dw_out_type,
03568
          Dwarf Half
          Dwarf_Signed * dw_out_discr_low,
03569
          Dwarf Error + dw_error).
03571
                          * dw_error);
03572
03650 DW_API int dwarf_srcfiles(Dwarf_Die dw_cu_die,
03651
          char
                     *** dw_srcfiles,
          Dwarf_Signed * dw_filecount,
03652
03653
          Dwarf_Error * dw_error);
03654
03681 DW_API int dwarf_srclines_b(Dwarf_Die dw_cudie,
                            * dw_version_out,
* dw_table_count,
03682
          Dwarf_Unsigned
03683
          Dwarf Small
          Dwarf_Line_Context * dw_linecontext,
03684
03685
                               * dw_error);
          Dwarf_Error
03686
03707 DW_API int dwarf_srclines_from_linecontext(
03708
          Dwarf_Line_Context dw_linecontext,
03709
          Dwarf_Line ** dw_linebuf,
          Dwarf_Signed * dw_linecount,
03710
```

```
03711
          Dwarf_Error * dw_error);
03712
03729 DW_API int dwarf_srclines_two_level_from_linecontext(
03730
          Dwarf_Line_Context dw_context,
03731
          Dwarf_Line ** dw_linebuf ,
03732
          Dwarf_Signed *
                             dw linecount.
03733
          Dwarf_Line **
                            dw_linebuf_actuals,
          Dwarf_Signed *
03734
                            dw_linecount_actuals,
          Dwarf_Error * dw_error);
03735
03736
03746 DW_API void dwarf_srclines_dealloc_b(Dwarf_Line_Context dw_context);
03747
03763 DW_API int dwarf_srclines_table_offset(Dwarf_Line_Context dw_context,
03764
          Dwarf_Unsigned * dw_offset,
03765
          Dwarf_Error * dw_error);
03766
03782 DW_API int dwarf_srclines_comp_dir(Dwarf_Line_Context dw_context, 03783 const char ** dw_compilation_directory,
          Dwarf_Error * dw_error);
03785
03801 DW_API int dwarf_srclines_subprog_count(Dwarf_Line_Context dw_context,
          Dwarf_Signed * dw_count,
Dwarf_Error * dw_error);
03802
03803
03804
03823 DW_API int dwarf_srclines_subproq_data(Dwarf_Line_Context dw_context,
          Dwarf_Signed dw_index,
                        ** dw_name,
03825
          const char
03826
          Dwarf_Unsigned * dw_decl_file,
          Dwarf_Unsigned * dw_decl_line,
03827
03828
          Dwarf Error
                         * dw_error);
03829
03854 DW_API int dwarf_srclines_files_indexes(
03855
         Dwarf_Line_Context dw_context,
03856
          Dwarf_Signed * dw_baseindex,
          Dwarf_Signed * dw_count,
Dwarf_Signed * dw_endindex,
03857
03858
          Dwarf_Error * dw_error);
03859
03860
03912 DW_API int dwarf_srclines_files_data_b(
03913
          Dwarf_Line_Context dw_context,
03914
          Dwarf_Signed
                                 dw_index_in,
                             ** dw_name,
03915
          const char
                             * dw_directory_index,
03916
          Dwarf Unsigned
03917
          Dwarf_Unsigned
                              * dw_last_mod_time,
          Dwarf_Unsigned
                              * dw_file_length,
03918
03919
          Dwarf_Form_Data16 ** dw_md5ptr,
03920
          Dwarf_Error
                               * dw_error);
03921
03936 DW API int dwarf srclines include dir count(
         Dwarf_Line_Context dw_line_context,
03937
03938
          Dwarf_Signed * dw_count,
03939
          Dwarf_Error * dw_error);
03940
03963 DW_API int dwarf_srclines_include_dir_data(
          Dwarf_Line_Context dw_line_context,
03964
          Dwarf_Signed dw_index,
const char ** dw_name,
03965
03966
          Dwarf_Error * dw_error);
03967
03968
03997 DW_API int dwarf_srclines_version(Dwarf_Line_Context dw_line_context,
03998
          Dwarf_Unsigned * dw_version,
03999
          Dwarf Small
                        * dw table count,
04000
          Dwarf_Error
                           * dw_error);
04001
04017 DW_API int dwarf_linebeginstatement(Dwarf_Line dw_line,
          Dwarf_Bool * dw_returned_bool,
Dwarf_Error * dw_error);
04018
04019
04020
04036 DW_API int dwarf_lineendsequence(Dwarf_Line dw_line,
          Dwarf_Bool * dw_returned_bool,
Dwarf_Error * dw_error);
04038
04039
04054 DW_API int dwarf_lineno(Dwarf_Line dw_line,
          Dwarf_Unsigned * dw_returned_linenum,
Dwarf_Error * dw_error);
04055
04056
04057
04072 DW_API int dwarf_line_srcfileno(Dwarf_Line dw_line,
         Dwarf_Unsigned * dw_returned_filenum,
Dwarf_Error * dw_error);
04073
04074
04075
04089 DW_API int dwarf_line_is_addr_set(Dwarf_Line dw_line,
          Dwarf_Bool * dw_is_addr_set,
Dwarf_Error * dw_error);
04091
04092
04107 DW_API int dwarf_lineaddr(Dwarf_Line dw_line,
04108
          Dwarf_Addr *
                            dw_returned_addr,
04109
          Dwarf_Error*
                            dw error):
```

```
04125 DW_API int dwarf_lineoff_b(Dwarf_Line dw_line,
04126
          Dwarf_Unsigned * dw_returned_lineoffset,
                          dw_error);
04127
          Dwarf Error*
04128
04153 DW_API int dwarf_linesrc(Dwarf_Line dw_line,
          char
                   ** dw_returned_name,
04155
          Dwarf_Error* dw_error);
04156
04171 DW_API int dwarf_lineblock(Dwarf_Line dw_line,
                          dw_returned_bool,
          Dwarf_Bool *
Dwarf_Error*
04172
04173
                            dw_error);
04174
04175 /* We gather these into one call as it's likely one
04176
          will want all or none of them. */
04200 DW_API int dwarf_prologue_end_etc(Dwarf_Line dw_line,
          Dwarf_Bool * dw_prologue_end,
Dwarf_Bool * dw_epilogue_begin,
04201
04202
          Dwarf_Unsigned * dw_isa,
          Dwarf_Unsigned * dw_discriminator,
Dwarf_Error * dw_error);
04204
04205
04206 /\star End line table operations \star/
04207
04213 DW_API int dwarf_linelogical(Dwarf_Line dw_line,
          Dwarf_Unsigned * dw_returned_logical,
Dwarf_Error* dw_error);
04214
04215
04216
04223 DW_API int dwarf_linecontext(Dwarf_Line dw_line,
04224
          Dwarf_Unsigned * dw_returned_context,
04225
          Dwarf Error*
                            dw_error);
04226
04235 DW_API int dwarf_line_subprogno(Dwarf_Line /*line*/,
        Dwarf_Unsigned * /*ret_subprogno*/,
Dwarf_Error * /*error*/);
04236
04237
04238
04245 DW_API int dwarf_line_subprog(Dwarf_Line /*line*/,
        char ** /*returned_subprog_name*/,
char ** /*returned_filename*/,
04246
                            /*returned_filename*/,
04248
          Dwarf_Unsigned * /*returned_lineno*/,
04249
          Dwarf_Error *
                           /*error*/);
04250
04271 DW_API int dwarf_check_lineheader_b(Dwarf_Die dw_cu_die,
04272
          int
                      * dw errcount out,
          Dwarf_Error * dw_error);
04273
04274
04304 DW_API int dwarf_print_lines(Dwarf_Die dw_cu_die,
04305
        Dwarf_Error * dw_error,
04306
          int * dw_errorcount_out);
04307
04328 DW_API struct Dwarf_Printf_Callback_Info_s
          dwarf_register_printf_callback(Dwarf_Debug dw_dbg,
04329
04330
          struct Dwarf_Printf_Callback_Info_s * dw_callbackinfo);
04331
04391 DW_API int dwarf_get_ranges_b(Dwarf_Debug dw_dbg,
                         dw_rangesoffset,
04392
          Dwarf_Off
04393
          Dwarf Die
                            dw die,
04394
          Dwarf_Off *
                            dw_return_realoffset,
04395
          Dwarf_Ranges ** dw_rangesbuf,
          Dwarf_Signed * dw_rangecount,
Dwarf_Unsigned * dw_bytecount,
04396
04397
04398
          Dwarf Error *
                           dw_error);
04399
04409 DW_API void dwarf_dealloc_ranges(Dwarf_Debug dw_dbg,
        Dwarf_Ranges * dw_rangesbuf,
Dwarf_Signed dw_rangecount);
04410
04411
04412
{\tt 04452~DW\_API~int~dwarf\_get\_ranges\_baseaddress\,(Dwarf\_Debug~dw\_dbg,}
04453
          Dwarf Die
                        dw_die,
*dw_known_base,
04454
          Dwarf_Bool
04455
          Dwarf_Unsigned *dw_baseaddress,
04456
          Dwarf_Bool
                          *dw_at_ranges_offset_present,
04457
          Dwarf_Unsigned *dw_at_ranges_offset,
04458
          Dwarf_Error
                         *dw_error);
04459
04505 DW_API int dwarf_rnglists_get_rle_head(Dwarf_Attribute dw_attr,
          Dwarf_Half
                                  dw_theform,
04506
04507
          Dwarf_Unsigned
                                  dw_index_or_offset_value,
04508
          Dwarf_Rnglists_Head * dw_head_out,
                               dw_count_of_entries_in_head,
04509
          Dwarf_Unsigned *
04510
          Dwarf Unsigned *
                                  dw_global_offset_of_rle_set,
04511
          Dwarf Error
                                  dw error);
04512
04555 DW_API int dwarf_get_rnglists_entry_fields_a(
04556
          Dwarf_Rnglists_Head dw_head,
          Dwarf_Unsigned dw_entrynum, unsigned int * dw_entrylen,
04557
04558
          unsigned int * dw_rle_value_out,
04559
```

```
Dwarf_Unsigned * dw_raw1,
04561
           Dwarf_Unsigned * dw_raw2,
04562
           Dwarf Bool
                           * dw_debug_addr_unavailable,
           Dwarf_Unsigned * dw_cooked1,
04563
04564
           Dwarf_Unsigned * dw_cooked2,
04565
           Dwarf Error *
                            dw error);
04566
04574 DW_API void dwarf_dealloc_rnglists_head(Dwarf_Rnglists_Head dw_head);
04575
04606 DW_API int dwarf_load_rnglists(Dwarf_Debug dw_dbg,
04607
          Dwarf_Unsigned * dw_rnglists_count,
                          * dw_error);
04608
           Dwarf Error
04609
04636 DW_API int dwarf_get_rnglist_offset_index_value(Dwarf_Debug dw_dbg,
          Dwarf_Unsigned dw_context_index,
Dwarf_Unsigned dw_offsetentry_index,
Dwarf_Unsigned * dw_offset_value_out,
04637
04638
04639
           Dwarf_Unsigned * dw_global_offset_value_out,
04640
                          * dw_error);
04641
          Dwarf_Error
04642
04649 DW_API int dwarf_get_rnglist_head_basics(Dwarf_Rnglists_Head dw_head,
04650
          Dwarf_Unsigned * dw_rle_count,
           Dwarf_Unsigned * dw_rnglists_version,
04651
           Dwarf_Unsigned * dw_rnglists_index_returned,
04652
04653
           Dwarf_Unsigned * dw_bytes_total_in_rle,
                         * dw_offset_size,
04654
           Dwarf_Half
04655
                            * dw_address_size,
           Dwarf_Half
04656
          Dwarf_Half
                           * dw_segment_selector_size,
           Dwarf_Unsigned * dw_overall_offset_of_this_context,
04657
04658
           Dwarf_Unsigned * dw_total_length_of_this_context,
04659
           Dwarf_Unsigned * dw_offset_table_offset,
04660
           Dwarf_Unsigned * dw_offset_table_entrycount,
04661
           Dwarf_Bool
                           * dw_rnglists_base_present,
04662
           Dwarf_Unsigned * dw_rnglists_base,
04663
           Dwarf_Bool
                           * dw_rnglists_base_address_present,
           Dwarf_Unsigned * dw_rnglists_base_address,
04664
           Dwarf Bool * dw rnglists debug addr base present,
04665
           Dwarf_Unsigned * dw_rnglists_debug_addr_base,
04666
04667
           Dwarf Error
                           * dw_error);
04668
{\tt 04684\ DW\_API\ int\ dwarf\_get\_rnglist\_context\_basics(Dwarf\_Debug\ dw\_dbg,}
          Dwarf_Unsigned dw_index,
Dwarf_Unsigned * dw_header_offset,
04685
04686
          Dwarf_Small * dw_offset_size,
Dwarf_Small * dw_extension_size,
04687
04688
          unsigned int * dw_version,

Dwarf_Small * dw_address_size,

Dwarf_Small * dw_segment_selector_size,
04689
04690
04691
           Dwarf_Unsigned * dw_offset_entry_count,
04692
04693
           Dwarf_Unsigned * dw_offset_of_offset_array,
           Dwarf_Unsigned * dw_offset_of_first_rangeentry,
04694
04695
           Dwarf_Unsigned * dw_offset_past_last_rangeentry,
          Dwarf_Error *
04696
                             dw_error);
04697
04707 DW_API int dwarf_get_rnglist_rle(Dwarf_Debug dw_dbg,
04708
           Dwarf_Unsigned dw_contextnumber,
04709
           Dwarf_Unsigned dw_entry_offset,
04710
           Dwarf_Unsigned dw_endoffset,
          unsigned int * dw_entrylen,
unsigned int * dw_entry_kir
04711
                           * dw_entry_kind,
04712
          Dwarf_Unsigned * dw_entry_operand1,
Dwarf_Unsigned * dw_entry_operand2,
04713
04714
04715 Dwarf_Error * dw_error);
04745 Dw_API int dwarf_get_loclist_c(Dwarf_Attribute dw_attr,
04742
          Dwarf_Loc_Head_c * dw_loclist_head,
          Dwarf_Unsigned * dw_locentry_count,
Dwarf_Error * dw_error);
04743
04744
04745
04746 #define DW_LKIND_expression 0 /* DWARF2,3,4,5 */
04747 #define DW_LKIND_loclist 1 /* DWARF 2,3,4 */
04748 #define DW_LKIND_GNU_exp_list 2 /* GNU DWARF4 .dwo extension */
04749 #define DW_LKIND_loclists 5 /* DWARF5 loclists */
04750 #define DW_LKIND_unknown
04751
04764 DW_API int dwarf_get_loclist_head_kind(
04765
          Dwarf_Loc_Head_c dw_loclist_head,
           unsigned int * dw_lkind,
Dwarf_Error * dw_error);
04766
04767
04768
04823 DW_API int dwarf_get_locdesc_entry_d(Dwarf_Loc_Head_c dw_loclist_head,
          Dwarf_Unsigned dw_index,
Dwarf_Small * dw_lle_value_out,
04824
04825
           Dwarf_Unsigned * dw_rawlowpc,
04826
04827
          Dwarf_Unsigned * dw_rawhipc,
04828
          * dw_lowpc_cooked,
* dw_hipc_cooked,
04829
          Dwarf Addr
04830
           Dwarf Addr
```

```
Dwarf_Unsigned * dw_locexpr_op_count_out,
          Dwarf_Locdesc_c * dw_locentry_out,
04832
04833
          Dwarf Small
                         * dw_loclist_source_out,
          Dwarf_Unsigned * dw_expression_offset_out,
04834
          Dwarf_Unsigned * dw_locdesc_offset_out,
Dwarf_Error * dw_error);
04835
04836
04857 DW_API int dwarf_get_locdesc_entry_e(Dwarf_Loc_Head_c dw_loclist_head,
          Dwarf_Unsigned dw_index,
Dwarf_Small * dw_lle_value_out,
04858
04859
          Dwarf_Unsigned * dw_rawlowpc,
04860
04861
          Dwarf_Unsigned * dw_rawhipc,
                       * dw_debug_addr_unavailable,
* dw_lowpc_cooked,
04862
          Dwarf_Bool
04863
          Dwarf_Addr
04864
          Dwarf_Addr
                          * dw_hipc_cooked,
          Dwarf_Unsigned * dw_locexpr_op_count_out,
Dwarf_Unsigned * dw_lle_bytecount,
04865
04866
04867
          Dwarf_Locdesc_c * dw_locentry_out,
04868
          Dwarf_Small
                         * dw_loclist_source_out,
          Dwarf_Unsigned * dw_expression_offset_out,
04869
04870
          Dwarf_Unsigned * dw_locdesc_offset_out,
                         * dw_error);
04871
          Dwarf_Error
04872
04898 DW_API int dwarf_get_location_op_value_c(Dwarf_Locdesc_c dw_locdesc,
          Dwarf_Unsigned dw_index,
Dwarf_Small * dw_operator_out,
04899
04900
          Dwarf_Unsigned * dw_operand1,
04901
04902
          Dwarf_Unsigned * dw_operand2,
          Dwarf_Unsigned * dw_operand3,
04903
          Dwarf_Unsigned * dw_offset_for_branch,
Dwarf_Error* dw_error);
04904
04905
04937 DW_API int dwarf_loclist_from_expr_c(Dwarf_Debug dw_dbg,
04938
         Dwarf_Ptr
                         dw_expression_in,
04939
          Dwarf_Unsigned dw_expression_length,
04940
          Dwarf_Half
                        dw_address_size,
04941
          Dwarf Half
                          dw_offset_size,
                          dw_dwarf_version,
04942
          Dwarf Half
04943
          Dwarf_Loc_Head_c* dw_loc_head,
04944
          Dwarf_Unsigned * dw_listlen,
04945
                         * dw_error);
          Dwarf_Error
04946
04954 DW_API void dwarf_dealloc_loc_head_c(Dwarf_Loc_Head_c dw_head);
04955
04956 /* These interfaces allow reading the .debug_loclists
04957
          section. Independently of DIEs.
04958
          Normal use of .debug_loclists uses
04959
          dwarf\_get\_loclist\_c() to open access to any kind of location
04960
          or loclist and uses dwarf_loc_head_c_dealloc() to
04961
          deallocate that memory once one is finished with
          that data. So for most purposes you do not need
04962
04963
          to use these functions
04964
          See dwarf_get_loclist_c() to open a Dwarf_Loc_Head_c
04965
          on any type of location list or expression. \star
04966
04967 /* Loads all the loclists headers and
          returns DW_DLV_NO_ENTRY if the section
04968
04969
          is missing or empty.
04970
          Intended to be done quite early and
04971
          it is automatically
04972
          done if .debug_info is loaded.
04973
          Doing it more than once is never necessary
04974
          or harmful. There is no deallocation call
04975
          made visible, deallocation happens
04976
          when dwarf_finish() is called.
04977
          With DW_DLV_OK it returns the number of
04978
          loclists headers in the section through
04979
          loclists_count. */
05009 DW_API int dwarf_load_loclists(Dwarf_Debug dw_dbg,
05010
          Dwarf_Unsigned * dw_loclists_count,
          Dwarf_Error
                          * dw_error);
05012
05038 DW_API int dwarf_get_loclist_offset_index_value(Dwarf_Debug dw_dbg,
          Dwarf_Unsigned dw_context_index,
Dwarf_Unsigned dw_offsetentry_index,
05039
05040
05041
          Dwarf_Unsigned * dw_offset_value_out,
05042
          Dwarf_Unsigned * dw_global_offset_value_out,
05043
          Dwarf_Error
                         * dw_error);
05044
05059 DW_API int dwarf_get_loclist_head_basics(Dwarf_Loc_Head_c dw_head,
                         * dw_lkind,
05060
          Dwarf Small
          Dwarf_Unsigned * dw_lle_count,
05061
05062
          Dwarf_Unsigned * dw_loclists_version,
05063
          Dwarf_Unsigned * dw_loclists_index_returned,
05064
          Dwarf_Unsigned * dw_bytes_total_in_rle,
                       * dw_offset_size,
05065
          Dwarf_Half
05066
          Dwarf Half
                          * dw_address_size,
05067
          Dwarf_Half
                          * dw_segment_selector_size,
```

```
05068
          Dwarf_Unsigned * dw_overall_offset_of_this_context,
05069
          Dwarf_Unsigned * dw_total_length_of_this_context,
05070
          Dwarf_Unsigned * dw_offset_table_offset,
05071
          Dwarf_Unsigned * dw_offset_table_entrycount,
05072
          Dwarf Bool
                        * dw_loclists_base_present,
05073
          Dwarf_Unsigned * dw_loclists_base,
05074
          Dwarf Bool
                        * dw_loclists_base_address_present,
05075
          Dwarf_Unsigned * dw_loclists_base_address,
05076
          Dwarf_Bool
                        * dw_loclists_debug_addr_base_present,
          Dwarf_Unsigned * dw_loclists_debug_addr_base,
05077
05078
          Dwarf_Unsigned * dw_offset_this_lle_area,
05079
                        * dw error);
         Dwarf Error
05080
05089 DW_API int dwarf_get_loclist_context_basics(Dwarf_Debug dw_dbg,
         Dwarf_Unsigned dw_index,
Dwarf_Unsigned * dw_header_offset,
05090
05091
                        * dw_offset_size,
05092
         Dwarf Small
                         * dw_extension_size,
05093
         Dwarf Small
05094
          unsigned int
                        * dw_version,
05095
          Dwarf_Small
                         * dw_address_size,
05096
          Dwarf_Small
                        * dw_segment_selector_size,
05097
         Dwarf_Unsigned * dw_offset_entry_count,
05098
          Dwarf_Unsigned * dw_offset_of_offset_array,
         Dwarf_Unsigned * dw_offset_of_first_locentry,
05099
05100
          Dwarf_Unsigned * dw_offset_past_last_locentry,
05101
          Dwarf_Error
                       * dw_error);
05102
05107 DW_API int dwarf_get_loclist_lle( Dwarf_Debug dw_dbg,
05108
         Dwarf_Unsigned dw_contextnumber,
05109
          Dwarf_Unsigned
                           dw_entry_offset,
05110
         Dwarf_Unsigned dw_endoffset,
         unsigned int * dw_entrylen,
unsigned int * dw_entry_kind,
05111
05112
          Dwarf_Unsigned * dw_entry_operand1,
05113
05114
          Dwarf_Unsigned * dw_entry_operand2,
         Dwarf_Unsigned * dw_expr_ops_blocksize,
05115
05116
         Dwarf_Unsigned * dw_expr_ops_offset,
          Dwarf_Small ** dw_expr_opsdata,
Dwarf_Error * dw_error);
05117
05118
05198 DW_API int dwarf_debug_addr_table(Dwarf_Debug dw_dbg,
05199
         Dwarf_Unsigned
                            dw_section_offset,
         Dwarf_Debug_Addr_Table *dw_table_header,
05200
05201
         Dwarf_Unsigned *dw_length,
05202
          Dwarf_Half
                           *dw_version,
          Dwarf_Small
05203
                           *dw_address_size,
                           *dw_at_addr_base,
05204
         Dwarf_Unsigned
05205
         Dwarf_Unsigned
                           *dw_entry_count,
05206
         Dwarf Unsigned
                           *dw_next_table_offset,
05207
         Dwarf Error
                           *dw_error);
05208
05231 DW_API int dwarf_debug_addr_by_index(Dwarf_Debug_Addr_Table dw_dat,
05232
          Dwarf_Unsigned dw_entry_index,
05233
         Dwarf_Unsigned
                           *dw_address,
05234
         Dwarf Error
                           *dw_error);
05235
05243 DW_API void dwarf_dealloc_debug_addr_table(
         Dwarf_Debug_Addr_Table dw_dat);
05244
05245
05282 DW_API int dwarf_get_macro_context(Dwarf_Die dw_die,
05283
         Dwarf_Unsigned
                             * dw_version_out,
          Dwarf_Macro_Context * dw_macro_context,
05284
                          * dw_macro_unit_offset_out,
* dw_macro_ops_count_out,
05285
         Dwarf Unsigned
05286
         Dwarf_Unsigned
          Dwarf_Unsigned
                             * dw_macro_ops_data_length_out,
05287
05288
         Dwarf_Error
                              * dw_error);
05289
05317 DW_API int dwarf_get_macro_context_by_offset(Dwarf_Die dw_die,
         Dwarf Unsigned
                          dw_offset,
* dw_version_out,
05318
05319
         Dwarf_Unsigned
          Dwarf_Macro_Context * dw_macro_context,
05320
         05321
05322
05323
         Dwarf_Error
                              * dw_error);
05324
05325 /*
         New December 2020. libdwarf 0.1.0
          Sometimes its necessary to know
05326
05327
          a context total length including macro 5 header */
05340 DW_API int dwarf_macro_context_total_length(
05341
         Dwarf_Macro_Context dw_context,
05342
          Dwarf_Unsigned * dw_mac_total_len,
                        * dw_error);
05343
          Dwarf Error
05344
05352 DW API void dwarf dealloc macro context (Dwarf Macro Context dw mc);
05353
05359 DW_API int dwarf_macro_context_head(Dwarf_Macro_Context dw_mc,
05360
         Dwarf Half
                        * dw_version,
         Dwarf_Unsigned * dw_mac_offset,
05361
```

```
Dwarf_Unsigned * dw_mac_len,
05363
          Dwarf_Unsigned * dw_mac_header_len,
05364
          unsigned int * dw_flags,
                         * dw_has_line_offset,
05365
          Dwarf_Bool
         Dwarf_Unsigned * dw_line_offset,
Dwarf_Bool * dw_has_offset_size_64,
Dwarf_Bool * dw_has_operands_table,
05366
05367
05368
         05369
05370
05371
05394 DW_API int dwarf_macro_operands_table(Dwarf_Macro_Context dw_mc,
                              dw_index, /* 0 to opcode_count -1 */
         Dwarf_Half
05395
                           * dw_opcode_number,
05396
          Dwarf_Half
05397
                             * dw_operand_count,
         Dwarf_Half
05398
         const Dwarf_Small ** dw_operand_array,
05399
        Dwarf_Error
                             * dw_error);
05400
05425 DW_API int dwarf_get_macro_op(Dwarf_Macro_Context dw_macro_context,
        Dwarf_Unsigned
                           dw_op_number,
    * dw_op_start_section_offset,
05426
          Dwarf_Unsigned
05427
                            * dw_macro_operator,
05428
          Dwarf_Half
05429
         Dwarf_Half
                             * dw_forms_count,
         const Dwarf_Small ** dw_formcode_array,
05430
05431
         Dwarf Error
                             * dw error);
05432
05470 DW_API int dwarf_get_macro_defundef(
05471
          Dwarf_Macro_Context dw_macro_context,
         Dwarf_Unsigned dw_op_number,
Dwarf_Unsigned * dw_line_number,
05472
05473
         Dwarf_Unsigned * dw_index,
05474
         Dwarf_Unsigned * dw_offset,
05475
         05476
05477
05478
05479
05507 DW_API int dwarf_get_macro_startend_file(
         Dwarf Macro Context dw macro context,
05508
          Dwarf_Unsigned dw_op_number,
05510
          Dwarf_Unsigned * dw_line_number,
05511
         Dwarf_Unsigned * dw_name_index_to_line_tab,
                       05512
          const char
05513
         Dwarf Error
05514
05530 DW_API int dwarf_get_macro_import(
         Dwarf_Macro_Context dw_macro_context,
05531
         Dwarf_Unsigned dw_op_number,
Dwarf_Unsigned * dw_target_offset,
05532
05533
05534
         Dwarf_Error * dw_error);
05563 DW_API char* dwarf_find_macro_value_start(char * dw_macro_string);
05564
05590 DW_API int dwarf_get_macro_details(Dwarf_Debug dw_dbg,
         Dwarf_Unsigned dw maximum Dwarf_Signs'
05591
       Dwarf_Off
05592
                                 dw_maximum_count,
05593
         Dwarf_Signed
                               * dw_entry_count,
05594
         Dwarf_Macro_Details ** dw_details,
05595
         Dwarf Error *
                                 dw error);
05596
05639 DW_API int dwarf_get_fde_list(Dwarf_Debug dw_dbg,
                         dw_cie_data,
05640
       ____Dwarf_Cie**
05641
         Dwarf Signed*
                           dw_cie_element_count,
         Dwarf_Fde**
05642
                           dw_fde_data,
05643
         Dwarf Signed*
                           dw fde element count,
05644
          Dwarf_Error*
                           dw_error);
05654 DW_API int dwarf_get_fde_list_eh(Dwarf_Debug dw_dbg,
05655
         Dwarf_Cie**
                           dw_cie_data,
         Dwarf_Signed* dw_cie_element_count,
05656
05657
         Dwarf_Fde**
                           dw_fde_data,
         Dwarf_Signed*
05658
                           dw fde element count.
05659
         Dwarf Error*
                           dw error);
05660
05680 DW_API void dwarf_dealloc_fde_cie_list(Dwarf_Debug dw_dbg,
         Dwarf_Cie * dw_cie_data,
Dwarf_Signed dw_cie_element_count,
05681
05682
05683
         Dwarf Fde * dw_fde_data,
         Dwarf_Signed dw_fde_element_count);
05684
05685
05713 DW_API int dwarf_get_fde_range(Dwarf_Fde dw_fde,
         Dwarf_Addr* dw_low_pc,
Dwarf_Unsigned* dw_func_length,
05714
       Dwarf_Addr*
05715
05716
          Dwarf_Small **dw_fde_bytes,
05717
          Dwarf_Unsigned* dw_fde_byte_length,
05718
          Dwarf_Off*
                          dw_cie_offset,
          Dwarf_Signed* dw_cie_index,
0.5719
05720
         Dwarf Off*
                           dw_fde_offset,
05721
         Dwarf_Error*
                        dw_error);
05722
05728 DW_API int dwarf_get_fde_exception_info(Dwarf_Fde dw_fde,
```

```
05729
          Dwarf_Signed*
                            dw_offset_into_exception_tables,
05730
          Dwarf Error*
                            dw error);
05731
05743 DW_API int dwarf_get_cie_of_fde(Dwarf_Fde dw_fde,
          Dwarf_Cie *
05744
                           dw cie returned,
05745
          Dwarf Error*
                            dw error);
05746
05780 DW_API int dwarf_get_cie_info_b(Dwarf_Cie dw_cie,
05781
          Dwarf_Unsigned * dw_bytes_in_cie,
05782
          Dwarf_Small*
                           dw version,
                        ** dw_augmenter,
05783
          char
          Dwarf_Unsigned* dw_code_alignment_factor,
05784
05785
          Dwarf_Signed* dw_data_alignment_factor,
05786
          Dwarf_Half*
                            dw_return_address_register_rule,
05787
          Dwarf_Small
                         ** dw_initial_instructions,
05788
          Dwarf_Unsigned* dw_initial_instructions_length,
05789
          Dwarf Half*
                           dw_offset_size,
05790
          Dwarf Error*
                            dw error);
05791
05804 DW_API int dwarf_get_cie_index(Dwarf_Cie dw_cie,
05805
          Dwarf_Signed* dw_index,
          Dwarf_Error * dw_error);
05806
05807
05826 DW_API int dwarf_get_fde_instr_bytes(Dwarf_Fde dw_fde, 05827 Dwarf_Small ** dw_outinstrs,
          Dwarf_Unsigned * dw_outlen,
05828
                         * dw_error);
05829
          Dwarf_Error
05830
05863 DW_API int dwarf_get_fde_info_for_all_regs3_b(Dwarf_Fde dw_fde,
05864
          Dwarf_Addr
                           dw_pc_requested,
05865
          Dwarf_Regtable3* dw_reg_table,
05866
          Dwarf_Addr*
                         dw_row_pc,
05867
          Dwarf_Bool*
                            dw_has_more_rows,
05868
          Dwarf_Addr*
                            dw_subsequent_pc,
                         dw_error);
05869
         Dwarf_Error*
05870
05880 DW_API int dwarf_get_fde_info_for_all_regs3(Dwarf_Fde dw_fde,
05881
          Dwarf_Addr
                           dw_pc_requested,
05882
          Dwarf_Regtable3* dw_reg_table,
05883
          Dwarf_Addr*
                         dw_row_pc,
05884
          Dwarf_Error*
                            dw_error);
05885
05886 /* See discussion of dw_value_type, libdwarf.h. */
05946 DW_API int dwarf_get_fde_info_for_reg3_c(Dwarf_Fde dw_fde,
          Dwarf_Half
05947
                            dw_table_column,
05948
          Dwarf_Addr
                            dw_pc_requested,
05949
          Dwarf_Small
                         * dw_value_type,
          Dwarf_Unsigned * dw_offset_relevant,
05950
          Dwarf_Unsigned * dw_register,
05951
05952
          Dwarf_Signed * dw_offset,
05953
          Dwarf_Block
                         * dw_block_content,
05954
          Dwarf_Addr
                          * dw_row_pc_out,
05955
          Dwarf_Bool
                         * dw_has_more_rows,
05956
          Dwarf_Addr
                         * dw_subsequent_pc,
                        * dw_error);
05957
          Dwarf Error
05958
05968 DW_API int dwarf_get_fde_info_for_reg3_b(Dwarf_Fde dw_fde,
                        dw_table_column,
dw_pc_requested,
05969
          Dwarf_Half
05970
          Dwarf_Addr
05971
          Dwarf Small
                          * dw_value_type,
          Dwarf_Unsigned * dw_offset_relevant,
05972
05973
          Dwarf Unsigned * dw register,
05974
          Dwarf_Unsigned * dw_offset,
05975
          05976
          Dwarf_Addr
                         * dw_row_pc_out,
                        * dw_has_more_rows,
* dw_subsequent_pc,
* dw_error);
05977
          Dwarf_Bool
05978
          Dwarf Addr
05979
          Dwarf Error
05980
06004 DW_API int dwarf_get_fde_info_for_cfa_reg3_c(Dwarf_Fde dw_fde,
06005
          Dwarf_Addr
                         dw_pc_requested,
                        * dw_value_type,
06006
          Dwarf Small
06007
          Dwarf_Unsigned* dw_offset_relevant,
          Dwarf_Unsigned* dw_register,
06008
          Dwarf_Signed * dw_offset,
Dwarf_Block * dw_block,
06009
06010
06011
          Dwarf_Addr
                        * dw_row_pc_out,
06012
          Dwarf_Bool
                        * dw_has_more_rows,
06013
          Dwarf Addr
                        * dw_subsequent_pc,
06014
          Dwarf Error
                         * dw_error);
06024 DW_API int dwarf_get_fde_info_for_cfa_reg3_b(Dwarf_Fde dw_fde,
          Dwarf_Addr dw_pc_requested,
Dwarf_Small * dw_value_type,
06025
06026
06027
          Dwarf_Unsigned* dw_offset_relevant,
06028
          Dwarf_Unsigned* dw_register,
          Dwarf_Unsigned* dw_offset,
06029
06030
          Dwarf_Block
                        * dw_block,
```

```
06031
          Dwarf_Addr
                         * dw_row_pc_out,
          Dwarf_Bool
06032
                         * dw_has_more_rows,
06033
          Dwarf Addr
                         * dw_subsequent_pc,
06034
          Dwarf_Error * dw_error);
06035
06044 DW_API int dwarf_get_fde_for_die(Dwarf_Debug dw_dbg,
                           dw_subr_die,
          Dwarf_Die
          Dwarf_Fde *
06046
                            dw_returned_fde,
06047
          Dwarf_Error*
                          dw_error);
06048
06056 DW_API int dwarf_get_fde_n(Dwarf_Fde* dw_fde_data,
         Dwarf_Unsigned dw_fde_index,
Dwarf_Fde * dw_returned_fde,
Dwarf_Error * dw_error);
06057
06058
06059
06060
06091 DW_API int dwarf_get_fde_at_pc(Dwarf_Fde* dw_fde_data,
          Dwarf_Addr dw_pc_of_interest,
Dwarf_Fde * dw_returned_fde,
06092
06093
          Dwarf_Addr * dw_lopc,
06094
          Dwarf_Addr * dw_hipc,
06095
06096
         Dwarf_Error* dw_error);
06097
06117 DW_API int dwarf_get_cie_augmentation_data(Dwarf_Cie dw_cie,
          Dwarf_Small ** dw_augdata,
06118
          Dwarf_Unsigned * dw_augdata_len,
06119
06120
          Dwarf_Error*
                          dw_error);
06121
06141 DW_API int dwarf_get_fde_augmentation_data(Dwarf_Fde dw_fde,
06142
          Dwarf_Small
                         ** dw_augdata,
          Dwarf_Unsigned * dw_augdata_len,
06143
06144
          Dwarf Error*
                            dw error);
06145
06179 DW_API int dwarf_expand_frame_instructions(Dwarf_Cie dw_cie,
          Dwarf_Small * dw_instructionspointer,
Dwarf_Unsigned dw_length_in_bytes,
06180
06181
06182
          Dwarf_Frame_Instr_Head * dw_head,
          Dwarf_Unsigned * dw_instr_count,
Dwarf_Error * dw_error);
06183
06184
06185
06258 DW_API int dwarf_get_frame_instruction(
06259
          Dwarf_Frame_Instr_Head dw_head,
                              dw_instr_index,
06260
          Dwarf Unsigned
          Dwarf_Unsigned * dw_instr_offset_in_instrs,
06261
                        * dw_inser_oriset_in_ins
* dw_cfa_operation,
** dw_fields_description,
06262
          Dwarf_Small
06263
          const char
06264
          Dwarf_Unsigned * dw_u0,
06265
          Dwarf_Unsigned * dw_u1,
06266
          Dwarf_Signed
                          * dw_s0,
06267
          Dwarf Signed
                           * dw_s1,
06268
          Dwarf_Unsigned * dw_code_alignment_factor,
          06269
06270
06271
06272
06294 DW_API int dwarf_get_frame_instruction_a(
06295
          Dwarf_Frame_Instr_Head dw_/* head*/,
           Dwarf_Unsigned
                              dw_instr_index,
06296
06297
          Dwarf_Unsigned * dw_instr_offset_in_instrs,
                        * dw_cfa_operation,
** dw_fields_description,
06298
          Dwarf_Small
06299
          const char
          Dwarf_Unsigned * dw_u0,
Dwarf_Unsigned * dw_u1,
06300
06301
06302
          Dwarf_Unsigned * dw_u2,
06303
          Dwarf_Signed
                           * dw_s0,
06304
          Dwarf_Signed
                               dw_s1,
06305
          Dwarf_Unsigned * dw_code_alignment_factor,
06306
          Dwarf_Signed * dw_data_alignment_factor,
06307
          Dwarf Block
                           * dw_expression_block,
                           * dw_error);
06308
          Dwarf Error
06309
06318 DW_API void dwarf_dealloc_frame_instr_head(Dwarf_Frame_Instr_Head
06319
          dw_head);
06320
06337 DW_API int dwarf_fde_section_offset(Dwarf_Debug dw_dbg,
          Dwarf_Fde dw_in_fde,
Dwarf_Off * dw_fde_off,
06338
06339
06340
          Dwarf_Off
                       * dw_cie_off,
06341
          Dwarf_Error * dw_error);
06342
06357 DW_API int dwarf_cie_section_offset(Dwarf_Debug dw_dbg,
        Dwarf_Cie dw_in_cie,
Dwarf_Off * dw_cie_off,
06358
06359
06360
          Dwarf_Error * dw_error);
06361
06371 DW_API Dwarf_Half dwarf_set_frame_rule_table_size(
          Dwarf_Debug dw_dbg,
Dwarf_Half dw_value);
06372
06373
```

```
06385 DW_API Dwarf_Half dwarf_set_frame_rule_initial_value(
         Dwarf_Debug dw_dbg,
06387
          Dwarf_Half dw_value);
06397 DW_API Dwarf_Half dwarf_set_frame_cfa_value(
06398
          Dwarf_Debug dw_dbg,
          Dwarf_Half dw_value);
06399
06410 DW_API Dwarf_Half dwarf_set_frame_same_value(
06411
         Dwarf_Debug dw_dbg,
06412
          Dwarf_Half dw_value);
06422 DW_API Dwarf_Half dwarf_set_frame_undefined_value(
06423 Dwarf_Debug dw_dbg,
06424 Dwarf_Half dw_value);
06478 DW_API int dwarf_get_abbrev(Dwarf_Debug dw_dbg,
06479
          Dwarf_Unsigned dw_offset,
          Dwarf_Abbrev * dw_returned_abbrev,
Dwarf_Unsigned* dw_length,
06480
06481
06482
          Dwarf_Unsigned* dw_attr_count,
06483
          Dwarf_Error*
                          dw_error);
06484
06496 DW_API int dwarf_get_abbrev_tag(Dwarf_Abbrev dw_abbrev,
          Dwarf_Half* dw_return_tag_number,
Dwarf_Error* dw_error);
06497
06498
06499
06513 DW_API int dwarf_get_abbrev_code(Dwarf_Abbrev dw_abbrev,
          Dwarf_Unsigned* dw_return_code_number,
06515
          Dwarf_Error*
                           dw_error);
06516
06530 DW_API int dwarf_get_abbrev_children_flag(Dwarf_Abbrev dw_abbrev,
                           dw_return_flag,
06531
          Dwarf_Signed*
06532
          Dwarf Error*
                            dw error);
06533
06567 DW_API int dwarf_get_abbrev_entry_b(Dwarf_Abbrev dw_abbrev,
          Dwarf_Unsigned dw_indx,
Dwarf_Bool dw_filter_outliers,
06568
06569
          Dwarf_Unsigned * dw_returned_attr_num,
06570
06571
          Dwarf Unsigned * dw returned form,
          Dwarf_Signed * dw_returned_implicit_const,
06573
          Dwarf_Off
                          * dw_offset,
06574
          Dwarf_Error
                        * dw_error);
06575
06609 DW_API int dwarf_get_str(Dwarf_Debug dw_dbg,
          Dwarf_Off
06610
                            dw offset,
06611
           char**
                             dw_string,
           Dwarf_Signed * dw_strlen_of_string,
06613
          Dwarf_Error*
                            dw_error);
06614
06625 /\star Allows applications to print the .debug_str_offsets
06626
           section.
06627
           Beginning at starting offset zero.
           returns data about the first table found.
06629
           The value *next_table_offset is the value
06630
           of the next table (if any), one byte past
          the end of the table whose data is returned..
Returns DW_DLV_NO_ENTRY if the starting offset
06631
06632
06633
          is past the end of valid data.
06635
           There is no guarantee that there are no non-0 nonsense
06636
          bytes in the section outside of useful tables,
06637
           so this can fail and return nonsense or
          {\tt DW\_DLV\_ERROR} \quad {\tt if such garbage exists.}
06638
06639 */
06640
06657 DW_API int dwarf_open_str_offsets_table_access(Dwarf_Debug dw_dbg,
06658
          Dwarf_Str_Offsets_Table * dw_table_data,
06659
          Dwarf_Error
                                    * dw_error);
06660
06678 DW API int dwarf close str offsets table access(
06679
          Dwarf_Str_Offsets_Table dw_table_data,
          Dwarf Error
                                    * dw error);
06681
06715 DW_API int dwarf_next_str_offsets_table(
          Dwarf_Str_Offsets_Table dw_table_data,
Dwarf_Unsigned * dw_unit_length,
06716
06717
          Dwarf_Unsigned * dw_unit_length_offset,
06718
06719
           Dwarf_Unsigned * dw_table_start_offset,
06720
          Dwarf_Half
                         * dw_entry_size,
06721
          Dwarf_Half
                          * dw_version,
                          * dw_padding,
06722
          Dwarf Half
06723
          Dwarf_Unsigned * dw_table_value_count,
06724
                          * dw_error);
          Dwarf Error
06745 DW_API int dwarf_str_offsets_value_by_index(
06746
          Dwarf_Str_Offsets_Table dw_table_data,
          Dwarf_Unsigned dw_index_to_entry,
Dwarf_Unsigned * dw_entry_value,
06747
06748
06749
                          * dw_error);
          Dwarf Error
```

```
06768 DW_API int dwarf_str_offsets_statistics(
06769
          Dwarf_Str_Offsets_Table dw_table_data,
          Dwarf_Unsigned * dw_wasted_byte_count,
Dwarf_Unsigned * dw_table_count,
06770
06771
06772
                          * dw_error);
          Dwarf Error
06773
06785 DW_API Dwarf_Unsigned dwarf_errno(Dwarf_Error dw_error);
06792 DW_API char* dwarf_errmsg(Dwarf_Error dw_error);
06800 DW_API char* dwarf_errmsg_by_number(Dwarf_Unsigned dw_errornum);
06801
06815 DW API void dwarf error creation (Dwarf Debug dw dbg ,
06816
          Dwarf_Error * dw_error, char * dw_errmsg);
06817
06826 DW_API void dwarf_dealloc_error(Dwarf_Debug dw_dbg,
06827
          Dwarf_Error dw_error);
06869 DW_API void dwarf_dealloc(Dwarf_Debug dw_dbg, 06870 void* dw_space, Dwarf_Unsigned dw_type);
06890 DW_API int dwarf_get_debug_sup(Dwarf_Debug dw_dbg,
                         * dw_version,
* dw_is_supplementary,
06891
          Dwarf_Half
06892
          Dwarf_Small
                         ** dw_filename,
06893
          char
          Dwarf_Unsigned * dw_checksum_len,
06894
          Dwarf_Small ** dw_checksum,
Dwarf_Error * dw_error);
06895
06896
06932 DW_API int dwarf_dnames_header(Dwarf_Debug dw_dbg,
                               dw_starting_offset,
06933
          Dwarf_Off
          Dwarf_Dnames_Head * dw_dn,
06934
                          * dw_offset_of_next_table,
   dw_error);
06935
          Dwarf Off
06936
          Dwarf Error *
06937
06945 DW_API void dwarf_dealloc_dnames(Dwarf_Dnames_Head dw_dn);
06946
06991 DW_API int dwarf_dnames_abbrevtable(Dwarf_Dnames_Head dw_dn,
          Dwarf_Unsigned dw_index,
Dwarf_Unsigned *dw_abbrev_offset,
06992
06993
06994
          Dwarf Unsigned *dw abbrev code,
          Dwarf_Unsigned *dw_abbrev_tag,
06996
          Dwarf_Unsigned dw_array_size,
06997
          Dwarf_Half *dw_idxattr_array,
06998
          Dwarf Half
                          *dw_form_array,
          Dwarf_Unsigned *dw_idxattr_count);
06999
07000
07018 DW_API int dwarf_dnames_sizes(Dwarf_Dnames_Head dw_dn,
07019
          Dwarf_Unsigned * dw_comp_unit_count,
07020
          Dwarf_Unsigned * dw_local_type_unit_count,
          Dwarf_Unsigned * dw_foreign_type_unit_count,
Dwarf_Unsigned * dw_bucket_count,
07021
07022
          Dwarf_Unsigned * dw_name_count,
07023
07024
          /\star The following are counted in bytes \star/
          Dwarf_Unsigned * dw_abbrev_table_size,
07025
          Dwarf_Unsigned * dw_entry_pool_size,
07026
07027
          Dwarf_Unsigned * dw_augmentation_string_size,
07028
          char
                        ** dw_augmentation_string,
          Dwarf_Unsigned * dw_section_size,
07029
                       * dw_table_version,
07030
          Dwarf_Half
07031
          Dwarf_Half
                          * dw_offset_size,
07032
          Dwarf Error *
                            dw_error);
07033
07044 DW_API int dwarf_dnames_offsets(Dwarf_Dnames_Head dw_dn,
          Dwarf_Unsigned * dw_header_offset,
07045
          Dwarf_Unsigned * dw_cu_table_offset,
07046
07047
          Dwarf_Unsigned * dw_tu_local_offset,
07048
          Dwarf_Unsigned * dw_foreign_tu_offset,
07049
          Dwarf_Unsigned * dw_bucket_offset,
07050
          Dwarf_Unsigned * dw_hashes_offset,
          Dwarf_Unsigned * dw_stringoffsets_offset,
07051
          Dwarf_Unsigned * dw_entryoffsets_offset,
07052
          Dwarf_Unsigned * dw_abbrev_table_offset,
07053
07054
          Dwarf_Unsigned * dw_entry_pool_offset,
07055
          Dwarf_Error *
                          dw_error);
07056
07085 DW_API int dwarf_dnames_cu_table(Dwarf_Dnames_Head dw_dn,
07086
                           * dw_type,
  dw_index_number,
          const char
07087
          Dwarf_Unsigned
          Dwarf_Unsigned
07088
                             * dw_offset,
07089
          Dwarf_Sig8
                             * dw_sig,
07090
          Dwarf_Error
                             * dw_error);
07091
07113 DW API int dwarf dnames bucket (Dwarf Dnames Head dw dn,
          Dwarf_Unsigned
07114
                            dw_bucket_number,
07115
          Dwarf_Unsigned
                              * dw_index,
07116
          Dwarf_Unsigned
                             * dw_indexcount,
07117
          Dwarf_Error *
                               dw_error);
07118
07168 DW_API int dwarf_dnames_name(Dwarf_Dnames_Head dw_dn,
07169
          Dwarf Unsigned
                                dw name index,
```

```
07170
          Dwarf_Unsigned
                             * dw_bucket_number,
          Dwarf_Unsigned
07171
                             * dw_hash_value,
07172
          Dwarf_Unsigned
                             * dw_offset_to_debug_str,
07173
          char *
                             * dw_ptrtostr,
07174
          Dwarf Unsigned
                             * dw_offset_in_entrypool,
07175
          Dwarf Unsigned
                             * dw abbrev number,
07176
          Dwarf_Half
                             * dw_abbrev_tag,
07177
          Dwarf_Unsigned
                               dw_array_size,
07178
          Dwarf_Half
                             * dw_idxattr_array,
07179
          Dwarf Half
                             * dw form array,
07180
          Dwarf_Unsigned
                            * dw_idxattr_count,
07181
          Dwarf Error *
                              dw error);
07182
07224 DW_API int dwarf_dnames_entrypool(Dwarf_Dnames_Head dw_dn,
07225
          Dwarf_Unsigned dw_offset_in_entrypool,
          Dwarf_Unsigned * dw_abbrev_code,
07226
07227
          Dwarf Half
                         * dw_tag,
          Dwarf_Unsigned * dw_value_count,
07228
07229
          Dwarf_Unsigned * dw_index_of_abbrev,
07230
          Dwarf_Unsigned * dw_offset_of_initial_value,
07231
                        * dw_error);
          Dwarf Error
07232
07292 DW_API int dwarf_dnames_entrypool_values(Dwarf_Dnames_Head dw_dn,
         Dwarf_Unsigned dw_index_of_abbrev,
Dwarf_Unsigned dw_offset_in_entrypool_of_values,
07293
07294
          Dwarf_Unsigned dw_arrays_length,
07295
07296
                         *dw_array_idx_number,
          Dwarf_Half
07297
          Dwarf_Half
                         *dw_array_form,
07298
          Dwarf_Unsigned *dw_array_of_offsets,
07299
          Dwarf_Sig8 *dw_array_of_signatures,
07300
          Dwarf Bool
                          *dw single cu.
07301
          Dwarf_Unsigned *dw_cu_offset,
07302
          Dwarf_Unsigned *dw_offset_of_next_entrypool,
07303
          Dwarf_Error
                         *dw_error);
07304
07331 DW_API int dwarf_get_aranges(Dwarf_Debug dw_dbg,
          Dwarf_Arange** dw_aranges,
Dwarf_Signed * dw_arange_count,
07332
07333
07334
          Dwarf Error*
                           dw_error);
07335
07355 DW_API int dwarf_get_arange(Dwarf_Arange* dw_aranges,
07356
         Dwarf_Unsigned dw_arange_count,
07357
          Dwarf Addr
                            dw address,
07358
          Dwarf_Arange *
                           dw_returned_arange,
07359
         Dwarf Error*
                           dw_error);
07360
07373 DW_API int dwarf_get_cu_die_offset(Dwarf_Arange dw_arange,
07374
         Dwarf_Off * dw_return_offset,
07375
          Dwarf_Error* dw_error);
07376
07389 DW_API int dwarf_get_arange_cu_header_offset (Dwarf_Arange dw_arange,
07390
          Dwarf_Off * dw_return_cu_header_offset,
07391
          Dwarf_Error* dw_error);
07392
07418 DW_API int dwarf_get_arange_info_b(Dwarf_Arange dw_arange,
          Dwarf_Unsigned* dw_segment,
07419
07420
          Dwarf_Unsigned* dw_segment_entry_size,
07421
          Dwarf Addr
                        * dw_start,
07422
          Dwarf_Unsigned* dw_length,
                      * dw_cu_die_offset,
* dw_error);
07423
          Dwarf Off
07424
          Dwarf Error
07474 DW_API int dwarf_get_globals(Dwarf_Debug dw_dbg, 07475 Dwarf_Global** dw_globals,
07476
          Dwarf_Signed * dw_number_of_globals,
07477
         Dwarf_Error * dw_error);
07478
07479 #define DW_GL_GLOBALS 0 /* .debug_pubnames and .debug_names */ 07480 #define DW_GL_PUBTYPES 1 /* .debug_pubtypes */
07481 /* the following are IRIX ONLY */
07482 #define DW_GL_FUNCS 2 /\star .debug_funcnames \star/
07483 #define DW_GL_TYPES
                              3 /* .debug_typenames */
07484 #define DW_GL_VARS
                              4 /* .debug_varnames */
                            5 /* .debug_weaknames */
07485 #define DW_GL_WEAKS
07510
          Dwarf_Signed * dw_number_of_pubtypes,
          Dwarf_Error * dw_error);
07511
07512
07538 DW_API int dwarf_globals_by_type(Dwarf_Debug dw_dbg,
07539
          int
                          dw requested section,
          Dwarf_Global **dw_contents,
07540
07541
          Dwarf_Signed
                         *dw_count,
07542
          Dwarf_Error
                          *dw error);
07543
07554 DW_API void dwarf_globals_dealloc(Dwarf_Debug dw_dbg,
         Dwarf_Global* dw_global_like,
Dwarf_Signed dw_count);
07555
07556
```

```
07570 DW_API int dwarf_globname(Dwarf_Global dw_global,
07571
          char
                    ** dw_returned_name,
          Dwarf_Error* dw_error);
07572
07573
07586 DW_API int dwarf_global_die_offset(Dwarf_Global dw_global,
          Dwarf_Off * dw_die_offset,
07588
          Dwarf_Error * dw_error);
07589
07604 DW_API int dwarf_global_cu_offset(Dwarf_Global dw_global,
07605
          Dwarf_Off*
                            dw_cu_header_offset,
07606
          Dwarf Error*
                            dw_error);
07607
07626 DW_API int dwarf_global_name_offsets(Dwarf_Global dw_global,
07627
          char
                            dw_returned_name,
07628
          Dwarf Off*
                            dw_die_offset,
07629
          Dwarf Off*
                            dw_cu_die_offset,
07630
         Dwarf Error*
                          dw error);
07631
07644 DW_API Dwarf_Half dwarf_global_tag_number(Dwarf_Global dw_global);
07645
07656 DW_API int dwarf_get_globals_header(Dwarf_Global dw_global,
                     * dw_category, /* DW_GL_GLOBAL for example */
* dw_offset_pub_header,
07657
          int
          Dwarf Off
07658
07659
          Dwarf_Unsigned * dw_length_size,
          Dwarf_Unsigned * dw_length_pub,
07660
07661
          Dwarf_Unsigned * dw_version,
07662
          Dwarf_Unsigned * dw_header_info_offset,
          Dwarf_Unsigned * dw_info_length,
07663
07664
          Dwarf Error
                        * dw_error);
07665
07688 DW_API int dwarf_return_empty_pubnames(Dwarf_Debug dw_dbg,
07689
                        dw_flag);
07690
{\tt 07724~DW\_API~int~dwarf\_get\_gnu\_index\_head\,(Dwarf\_Debug~dw\_dbg,}
07725
          Dwarf_Bool
                                 dw_which_section,
07726
          Dwarf_Gnu_Index_Head *dw_head,
                              *dw_index_block_count_out,
07727
          Dwarf_Unsigned
07728
          Dwarf Error
                                 *dw_error);
07736 DW_API void dwarf_gnu_index_dealloc(Dwarf_Gnu_Index_Head dw_head);
07775 DW_API int dwarf_get_gnu_index_block(Dwarf_Gnu_Index_Head dw_head,
          Dwarf_Unsigned dw_number,
Dwarf_Unsigned *dw_block_length,
07776
07777
07778
                          *dw_version,
          Dwarf_Half
07779
          Dwarf_Unsigned *dw_offset_into_debug_info,
07780
          Dwarf_Unsigned *dw_size_of_debug_info_area,
07781
          Dwarf_Unsigned *dw_count_of_index_entries,
07782
          Dwarf Error
                          *dw_error);
07783
07815 DW_API int dwarf_get_gnu_index_block_entry(
          Dwarf_Gnu_Index_Head dw_head,
07817
          Dwarf_Unsigned dw_blocknumber,
07818
          Dwarf_Unsigned
                            dw_entrynumber,
07819
          Dwarf_Unsigned *dw_offset_in_debug_info,
07820
                         **dw_name_string,
          const char
                          *dw_flagbyte,
*dw_staticorglobal,
07821
          unsigned char
07822
          unsigned char
07823
          unsigned char
                          *dw_typeofentry,
07824
          Dwarf_Error
                           *dw_error);
07825
07886 DW API int dwarf gdbindex header (Dwarf Debug dw dbg,
          Dwarf_Gdbindex * dw_gdbindexptr,
Dwarf_Unsigned * dw_version,
07887
07888
07889
          Dwarf_Unsigned * dw_cu_list_offset,
07890
          Dwarf_Unsigned * dw_types_cu_list_offset,
07891
          Dwarf_Unsigned * dw_address_area_offset,
          Dwarf_Unsigned * dw_symbol_table_offset,
07892
          Dwarf_Unsigned * dw_constant_pool_offset,
07893
          Dwarf_Unsigned * dw_section_size,
07894
          const char  ** dw_section_name,
Dwarf_Error  * dw_error);
07895
07896
07897
07905 DW_API void dwarf_dealloc_gdbindex(Dwarf_Gdbindex dw_gdbindexptr);
07906
07917 DW API int dwarf gdbindex culist array(
          Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned * dw_list_length,
07918
07919
07920
          Dwarf_Error
                          * dw_error);
07921
07939 DW APT int dwarf gdbindex culist entry(
          Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned dw_entryindex,
07940
07942
          Dwarf_Unsigned * dw_cu_offset,
07943
          Dwarf_Unsigned * dw_cu_length,
07944
          Dwarf_Error
                         * dw_error);
07945
07957 DW_API int dwarf_gdbindex_types_culist_array(
```

```
Dwarf_Gdbindex dw_gdbindexptr,
           Dwarf_Unsigned * dw_types_list_length,
07959
07960
          Dwarf_Error
                           * dw_error);
07961
           entryindex: 0 to types_list_length -1 \ */
07962 /*
07984 DW_API int dwarf_gdbindex_types_culist_entry(
          Dwarf_Gdbindex dw_gdbindexptr,
07986
           Dwarf_Unsigned
                              dw_types_entryindex,
           Dwarf_Unsigned * dw_cu_offset,
07987
          Dwarf_Unsigned * dw_tu_offset,
07988
          Dwarf_Unsigned * dw_type_signature,
07989
07990
                          * dw_error);
          Dwarf Error
07991
08006 DW_API int dwarf_gdbindex_addressarea(
          Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned * dw_addressarea_list_length,
08007
08008
08009
          Dwarf Error
                           * dw_error);
08010
08029 DW_API int dwarf_gdbindex_addressarea_entry(
          Dwarf_Gdbindex dw_gdbindexptr,
08030
          Dwarf_Unsigned dw_entryindex,
Dwarf_Unsigned * dw_low_address,
08031
08032
          Dwarf_Unsigned * dw_high_address,
08033
08034
          Dwarf_Unsigned * dw_cu_index,
08035
                          * dw_error);
          Dwarf_Error
08036
08049 DW_API int dwarf_gdbindex_symboltable_array(
          Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned * dw_symtab_list_length,
08050
08051
08052
          Dwarf Error
                         * dw_error);
08053
08073 DW_API int dwarf_gdbindex_symboltable_entry(
        Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned dw_entryindex,
08074
08075
          Dwarf_Unsigned * dw_string_offset,
Dwarf_Unsigned * dw_cu_vector_offset,
08076
08077
08078
                         * dw_error);
          Dwarf Error
08097 DW_API int dwarf_gdbindex_cuvector_length(
         Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned dw_cuvector_offset,
08098
08099
          Dwarf_Unsigned * dw_innercount,
08100
08101
                         * dw_error);
          Dwarf Error
08102
08119 DW_API int dwarf_gdbindex_cuvector_inner_attributes(
08120
          Dwarf_Gdbindex dw_gdbindexptr,
          Dwarf_Unsigned dw_cuvector_of dw_innerindex,
08121
                             dw_cuvector_offset_in,
08122
           Dwarf_Unsigned * dw_field_value,
08123
08124
                          * dw_error);
          Dwarf Error
08148 DW_API int dwarf_gdbindex_cuvector_instance_expand_value(
          Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned dw_field_value,
08149
08150
          Dwarf_Unsigned * dw_cu_index,
08151
          Dwarf_Unsigned * dw_symbol_kind,
08152
          Dwarf_Unsigned * dw_is_static,
08154
          Dwarf Error
                          * dw_error);
08155
08171 DW_API int dwarf_gdbindex_string_by_offset(
          Dwarf_Gdbindex dw_gdbindexptr,
Dwarf_Unsigned dw_stringoffset,
08172
08173
           const char ** dw_string_ptr,
Dwarf_Error * dw_error);
08174
08175
08216 DW_API int dwarf_get_xu_index_header(Dwarf_Debug dw_dbg,
08217
          const char * dw_section_type, /* "tu" or "cu" */
08218
           Dwarf_Xu_Index_Header * dw_xuhdr,
08219
          Dwarf Unsigned
                                * dw_version_number,
* dw_section_count,
08220
          Dwarf_Unsigned
                                  * dw_units_count,
* dw_hash_slots_count,
          Dwarf_Unsigned
08221
          Dwarf_Unsigned
08222
08223
           const char
                                  ** dw_sect_name,
08224
          Dwarf_Error
                                   * dw_error);
08225
08234 DW_API void dwarf_dealloc_xu_header(Dwarf_Xu_Index_Header dw_xuhdr);
08250 DW_API int dwarf_get_xu_index_section_type(
08251 Dwarf_Xu_Index_Header dw_xuhdr,
08252
           const char ** dw_typename,
           const char ** dw_sectionname,
08253
           Dwarf_Error * dw_error);
08254
08287 DW_API int dwarf_get_xu_hash_entry(Dwarf_Xu_Index_Header dw_xuhdr,
          Dwarf_Unsigned dw_index,
Dwarf_Sig8 * dw_hash_value,
08288
08289
           Dwarf_Unsigned * dw_index_to_sections,
08290
08291
          Dwarf Error
                           * dw error);
```

```
08293 /* Columns 0 to L-1, valid. */
08316 DW_API int dwarf_get_xu_section_names(Dwarf_Xu_Index_Header dw_xuhdr,
08317
          Dwarf_Unsigned dw_column_index,
08318
          Dwarf_Unsigned* dw_SECT_number,
          const char ** dw_SECT_name,
Dwarf_Error * dw_error);
08319
08320
08321
08350 DW_API int dwarf_get_xu_section_offset(
08351
          Dwarf_Xu_Index_Header dw_xuhdr,
          Dwarf_Unsigned dw_row_index,
Dwarf_Unsigned dw_column_index,
08352
08353
08354
          Dwarf_Unsigned* dw_sec_offset,
08355
          Dwarf_Unsigned* dw_sec_size,
08356
          Dwarf_Error
                        * dw_error);
08357
08379 DW_API int dwarf_get_debugfission_for_die(Dwarf_Die dw_die,
08380
          Dwarf_Debug_Fission_Per_CU * dw_percu_out,
                                      * dw_error);
08381
          Dwarf_Error
08382
08400 DW_API int dwarf_get_debugfission_for_key(Dwarf_Debug dw_dbg,
08401
          Dwarf_Sig8
                                      * dw_hash_sig,
                                       * dw_cu_type,
08402
          const char
08403
          Dwarf_Debug_Fission_Per_CU * dw_percu_out,
08404
          Dwarf_Error
                                      * dw_error);
08406 /\star END debugfission dwp .debug_cu_index
08407
          and .debug_tu_index meaningful operations. */
08408
08502 DW_API int dwarf_gnu_debuglink(Dwarf_Debug dw_dbg,
08503
                        ** dw_debuglink_path_returned,
          char
08504
          unsigned char ** dw_crc_returned,
                       ** dw_debuglink_fullpath_returned,

** dw_debuglink_path_length_returned,
08505
08506
          unsigned int
08507
          unsigned int
                         * dw_buildid_type_returned,
                         ** dw_buildid_owner_name_returned,
08508
          char
08509
          unsigned char ** dw buildid returned,
08510
          unsigned int * dw_buildid_length_returned,
08511
          char
                       *** dw_paths_returned,
08512
          unsigned int * dw_paths_length_returned,
08513
          Dwarf_Error*
                           dw_error);
08514
08547 DW API int dwarf suppress debuglink crc(int dw suppress);
08548
08567 DW_API int dwarf_add_debuglink_global_path(Dwarf_Debug dw_dbg,
08568
          const char * dw_pathname,
08569
          Dwarf_Error* dw_error);
08570
08598 DW API int dwarf_crc32(Dwarf_Debug dw_dbg,
         unsigned char * dw_crcbuf,
08599
          Dwarf_Error * dw_error);
08600
08601
08625 DW_API unsigned int dwarf_basic_crc32(const unsigned char * dw_buf,
        unsigned long dw_len, unsigned int dw_init);
08626
08627
08646 #define DW_HARMLESS_ERROR_CIRCULAR_LIST_DEFAULT_SIZE 4
08690 DW_API int dwarf_get_harmless_error_list(Dwarf_Debug dw_dbg,
         unsigned int dw_count,
const char ** dw_errmsg_ptrs_array,
08691
08692
          unsigned int * dw_newerr_count);
08693
08694
08715 DW_API unsigned int dwarf_set_harmless_error_list_size(
08716
        Dwarf_Debug dw_dbg,
08717
          unsigned int dw_maxcount);
08718
08730 DW_API void dwarf_insert_harmless_error(Dwarf_Debug dw_dbg,
08731
          char * dw newerror);
08767 DW_API int dwarf_get_ACCESS_name(unsigned int dw_val_in,
          const char ** dw_s_out);
08771 DW_API int dwarf_get_ADDR_name(unsigned int dw_val_in,
08772
         const char ** dw_s_out);
08775 DW_API int dwarf_get_AT_name(unsigned int dw_val_in,
08776
         const char ** dw_s_out);
08779 DW_API int dwarf_get_ATCF_name(unsigned int dw_val_in,
08780
          const char ** dw_s_out);
08783 DW_API int dwarf_get_ATE_name(unsigned int dw_val_in,
08784
          const char ** dw_s_out);
08787 DW_API int dwarf_get_CC_name(unsigned int dw_val_in,
08788
          const char ** dw_s_out);
08791 DW_API int dwarf_get_CFA_name(unsigned int dw_val_in,
          const char ** dw_s_out);
08795 DW_API int dwarf_get_children_name(unsigned int dw_val_in,
08796
         const char ** dw_s_out);
08799 DW_API int dwarf_get_CHILDREN_name(unsigned int dw_val_in,
08800 const char ** dw_s_out);
08803 DW_API int dwarf_get_DEFAULTED_name(unsigned int dw_val_in,
```

```
const char ** dw_s_out);
08807 DW_API int dwarf_get_DS_name(unsigned int dw_val_in,
08808
         const char ** dw_s_out);
08811 DW_API int dwarf_get_DSC_name(unsigned int dw_val_in,
08812
         const char ** dw_s_out);
08817 DW_API int dwarf_get_GNUIKIND_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08823 DW_API int dwarf_get_EH_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08824
08827 DW_API int dwarf_get_END_name(unsigned int dw_val_in,
08828
         const char ** dw_s_out);
08831 DW_API int dwarf_get_FORM_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08832
08839 DW_API int dwarf_get_FRAME_name(unsigned int dw_val_in,
08840
         const char ** dw_s_out);
08845 DW_API int dwarf\_get\_GNUIVIS\_name (unsigned int dw\_val\_in,
08846
         const char ** dw_s_out);
08847
08850 DW_API int dwarf_get_ID_name(unsigned int dw_val_in,
          const char ** dw_s_out);
08854 DW_API int dwarf_get_IDX_name(unsigned int dw_val_in,
08855
         const char ** dw_s_out);
08858 DW_API int dwarf_get_INL_name(unsigned int dw_val_in,
08859
         const char ** dw_s_out);
08862 DW_API int dwarf_get_ISA_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08866 DW_API int dwarf_get_LANG_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08867
08870 DW_API int dwarf_get_LLE_name(unsigned int dw_val_in,
08871
         const char ** dw_s_out);
08877 DW_API int dwarf_get_LLEX_name(unsigned int dw_val_in,
08878
         const char ** dw_s_out );
08879
08882 DW_API int dwarf_get_LNAME_name (unsigned int dw_val_in,
         const char ** dw_s_out);
08883
08886 DW_API int dwarf_get_LNCT_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08887
08890 DW_API int dwarf_get_LNE_name(unsigned int dw_val_in,
08891
          const char ** dw_s_out);
08894 DW_API int dwarf_get_LNS_name(unsigned int dw_val_in,
08895
         const char ** dw_s_out);
08900 DW API int dwarf get MACINFO name (unsigned int dw val in,
08901
         const char ** dw_s_out);
08906 DW_API int dwarf_get_MACRO_name(unsigned int dw_val_in,
08907
         const char ** dw_s_out);
08910 DW_API int dwarf\_get\_OP\_name(unsigned int dw\_val\_in,
08911
         const char ** dw_s_out);
08914 DW_API int dwarf\_get\_ORD\_name (unsigned int dw\_val\_in,
08915
         const char ** dw_s_out);
08918 DW API int dwarf get RLE name (unsigned int dw val in.
          const char ** dw_s_out);
08922 DW_API int dwarf_get_SECT_name(unsigned int dw_val_in,
08923
         const char ** dw_s_out);
08926 DW_API int dwarf_get_TAG_name(unsigned int dw_val_in,
08927
         const char ** dw_s_out);
08930 DW_API int dwarf_get_UT_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08934 DW_API int dwarf_get_VIRTUALITY_name(unsigned int dw_val_in,
         const char ** dw_s_out);
08935
08938 DW_API int dwarf_get_VIS_name(unsigned int dw_val_in,
08939
         const char ** dw_s_out);
08940
08951 DW_API int dwarf_get_FORM_CLASS_name(enum Dwarf_Form_Class dw_fc,
          const char ** dw_s_out);
08952
09006 DW_API int dwarf_get_die_section_name(Dwarf_Debug dw_dbg,
         Dwarf_Bool dw_is_info, const char **dw_sec_name,
09007
09008
09009
         Dwarf Error *dw error):
09010
09017 DW_API int dwarf_get_die_section_name_b(Dwarf_Die dw_die,
09018
         const char ** dw_sec_name,
09019
         Dwarf_Error * dw_error);
09020
09023 DW_API int dwarf_get_macro_section_name(Dwarf_Debug dw_dbg,
         const char ** dw_sec_name_out,
09024
          Dwarf_Error * dw_err);
09025
09026
09069 DW_API int dwarf_get_real_section_name(Dwarf_Debug dw_dbg,
09070
         const char
                         * dw_std_section_name,
                        ** dw_actual_sec_name_out,
09071
          const char
09072
          Dwarf Small
                        * dw_marked_zcompressed,
          Dwarf_Small
                         * dw_marked_zlib_compressed,
09074
          Dwarf Small
                         * dw_marked_shf_compressed,
09075
         Dwarf_Unsigned * dw_compressed_length,
09076
         Dwarf_Unsigned * dw_uncompressed_length,
09077
         Dwarf Error
                        * dw_error);
09078
```

```
09083 DW_API int dwarf_get_frame_section_name(Dwarf_Debug dw_dbg,
          const char ** dw_section_name_out,
09084
09085
          Dwarf_Error * dw_error);
09086
09092 DW_API int dwarf_get_frame_section_name_eh_gnu(Dwarf_Debug dw_dbg, 09093 const char ** dw_section_name_out,
          Dwarf_Error * dw_error);
09095
09099 DW_API int dwarf_get_aranges_section_name(Dwarf_Debug dw_dbg,
09100
          const char ** dw_section_name_out,
          Dwarf_Error * dw_error);
09101
09102
09106 DW_API int dwarf_get_ranges_section_name(Dwarf_Debug dw_dbg,
         const char ** dw_section_name_out,
09107
09108
          Dwarf_Error * dw_error);
09109
09110 /\star\,\, These two get the offset or address size as defined
09111
          by the object format (not by DWARF). */
09117 DW_API int dwarf_get_offset_size(Dwarf_Debug dw_dbg,
09118
          Dwarf_Half *
                            dw_offset_size,
09119
          Dwarf_Error *
                           dw error);
09120
09126 DW_API int dwarf_get_address_size(Dwarf_Debug dw_dbg,
                          dw_addr_size,
09127
          Dwarf Half *
          Dwarf_Error *
09128
                           dw_error);
09129
09133 DW_API int dwarf_get_string_section_name(Dwarf_Debug dw_dbg,
09134
          const char ** dw_section_name_out,
09135
          Dwarf_Error * dw_error);
09136
09140 DW_API int dwarf_get_line_section_name(Dwarf_Debug dw_dbg, 09141 const char ** dw_section_name_out,
09142
          Dwarf_Error * dw_error);
09143
09157 DW_API int dwarf_get_line_section_name_from_die(Dwarf_Die dw_die,
09158
          const char ** dw_section_name_out,
          Dwarf_Error * dw_error);
09159
09160
09207 DW_API int dwarf_get_section_info_by_name_a(Dwarf_Debug dw_dbg,
         const char * dw_section_name,
Dwarf_Addr * dw_section_addr,
09208
09209
          Dwarf_Unsigned* dw_section_size,
09210
          Dwarf_Unsigned* dw_section_flags,
09211
09212
          Dwarf_Unsigned* dw_section_offset,
09213
          Dwarf_Error * dw_error);
09214
09227 DW_API int dwarf_get_section_info_by_name(Dwarf_Debug dw_dbg,
         09228
09229
09230
          Dwarf_Unsigned* dw_section_size,
          Dwarf_Error * dw_error);
09232
09278 DW_API int dwarf_get_section_info_by_index_a(Dwarf_Debug dw_dbg,
                          dw_section_index,
09279
         int
09280
          const char **
                           dw_section_name,
09281
          Dwarf Addr*
                            dw section addr,
          Dwarf_Unsigned* dw_section_size,
09282
09283
          Dwarf_Unsigned* dw_section_flags,
          Dwarf_Unsigned* dw_section_offset,
09284
09285
          Dwarf_Error*
                            dw_error);
09286
09299 DW_API int dwarf_get_section_info_by_index(Dwarf_Debug dw_dbg,
09300
                            dw_section_index,
          int
09301
          const char **
                          dw_section_name,
09302
          Dwarf_Addr*
                            dw_section_addr,
09303
          Dwarf_Unsigned* dw_section_size,
09304
          Dwarf Error*
                            dw_error);
09305
09392 DW_API int dwarf_machine_architecture_a(Dwarf_Debug dw_dbg,
09393
          Dwarf_Small
                        *dw_ftype,
09394
          Dwarf_Small
                          *dw_obj_pointersize,
09395
          Dwarf Bool
                          *dw_obj_is_big_endian,
          Dwarf_Unsigned *dw_obj_machine, /*Elf e_machine */
Dwarf_Unsigned *dw_obj_type, /* Elf e_type */
09396
09397
09398
          Dwarf Unsigned *dw obj flags,
          Dwarf_Small
09399
                         *dw_path_source,
          Dwarf_Unsigned *dw_ub_offset,
09400
          Dwarf_Unsigned *dw_ub_count,
09401
09402
          Dwarf_Unsigned *dw_ub_index,
09403
          Dwarf_Unsigned *dw_comdat_groupnumber);
09404
09412 DW_API int dwarf_machine_architecture(Dwarf_Debug dw_dbg,
09413
          Dwarf_Small
                         *dw_ftype,
09414
          Dwarf_Small
                          *dw_obj_pointersize,
09415
          Dwarf_Bool
                          *dw_obj_is_big_endian,
09416
          Dwarf_Unsigned *dw_obj_machine, /*architecture*/
09417
          Dwarf Unsigned *dw obi flags.
```

```
09418
          Dwarf_Small
                         *dw_path_source,
09419
          Dwarf_Unsigned *dw_ub_offset,
09420
          Dwarf_Unsigned *dw_ub_count,
09421
          Dwarf_Unsigned *dw_ub_index,
09422
          Dwarf_Unsigned *dw_comdat_groupnumber);
09423
09435 DW_API Dwarf_Unsigned dwarf_get_section_count(Dwarf_Debug dw_dbg);
09436
09455 DW_API int dwarf_get_section_max_offsets_d(Dwarf_Debug dw_dbg,
09456
          Dwarf_Unsigned * dw_debug_info_size,
09457
          Dwarf_Unsigned * dw_debug_abbrev_size,
09458
          Dwarf_Unsigned * dw_debug_line_size,
          Dwarf_Unsigned * dw_debug_loc_size,
09459
          Dwarf_Unsigned * dw_debug_aranges_size,
09460
09461
09462
          Dwarf_Unsigned * dw_debug_macinfo_size,
          Dwarf_Unsigned * dw_debug_pubnames_size,
09463
          Dwarf_Unsigned * dw_debug_str_size,
09464
          Dwarf_Unsigned * dw_debug_frame_size,
09465
09466
          Dwarf_Unsigned * dw_debug_ranges_size,
09467
09468
          Dwarf_Unsigned * dw_debug_pubtypes_size,
09469
          Dwarf_Unsigned * dw_debug_types_size,
          Dwarf_Unsigned * dw_debug_macro_size,
09470
09471
          Dwarf_Unsigned * dw_debug_str_offsets_size,
          Dwarf_Unsigned * dw_debug_sup_size,
09472
09473
09474
          Dwarf_Unsigned * dw_debug_cu_index_size,
09475
          Dwarf_Unsigned * dw_debug_tu_index_size,
09476
          Dwarf_Unsigned * dw_debug_names_size,
09477
          Dwarf_Unsigned * dw_debug_loclists_size,
          Dwarf_Unsigned * dw_debug_rnglists_size);
09527 DW_API int dwarf_sec_group_sizes(Dwarf_Debug dw_dbg,
09528
          Dwarf_Unsigned *dw_section_count_out,
09529
          Dwarf_Unsigned *dw_group_count_out,
09530
          Dwarf_Unsigned *dw_selected_group_out,
          Dwarf_Unsigned *dw_map_entry_count_out,
09531
09532
          Dwarf_Error
                         *dw_error);
09533
09564 DW_API int dwarf_sec_group_map(Dwarf_Debug dw_dbg,
         Dwarf_Unsigned dw_map_entry_count,
Dwarf_Unsigned *dw_group_numbers_array,
09565
09566
09567
          Dwarf Unsigned *dw sec numbers array,
         const char  **dw_sec_names_array,
Dwarf_Error  *dw_error);
09568
09569
09584 DW_API int dwarf_encode_leb128(Dwarf_Unsigned dw_val,
09585
        int *dw_nbytes,
09586
         char *dw_space,
09587
          int dw_splen);
09588 DW_API int dwarf_encode_signed_leb128(Dwarf_Signed dw_val,
         int *dw_nbytes,
09590
          char *dw_space,
09591
          int
               dw_splen);
09592 /\star~ Same for LEB decoding routines.
09593
         caller sets endptr to an address one past the last valid
         address the library should be allowed to
09594
09595
          access. */
09596 DW_API int dwarf_decode_leb128(char *dw_leb,
09597
          Dwarf_Unsigned *dw_leblen,
09598
          Dwarf_Unsigned *dw_outval,
09599
          char
                         *dw endptr);
09600 DW_API int dwarf_decode_signed_leb128(char *dw_leb,
09601
          Dwarf_Unsigned *dw_leblen,
09602
          Dwarf_Signed *dw_outval,
          char
09603
                         *dw_endptr);
09620 DW_API const char * dwarf_package_version(void);
09621
09637 DW_API int dwarf_set_stringcheck(int dw_stringcheck);
09638
09660 DW_API int dwarf_set_reloc_application(int dw_apply);
09661
09686 DW_API void (*dwarf_get_endian_copy_function(Dwarf_Debug dw_dbg))
09687
          (void *, const void *, unsigned long);
09688
09689 /* A global flag in libdwarf. Applies to all Dwarf_Debug */
09690 DW_API extern Dwarf_Cmdline_Options dwarf_cmdline_options;
09691
09706 DW_API void dwarf_record_cmdline_options(
09707
         Dwarf_Cmdline_Options dw_dd_options);
09708
09727 DW API int dwarf set de alloc flag(int dw v);
09757 DW_API int dwarf_library_allow_dup_attr(int dw_v);
09758
09780 DW_API Dwarf_Small dwarf_set_default_address_size(
         Dwarf_Debug dw_dbg,
Dwarf_Small dw_value);
09781
09782
```

```
09809 DW_API int dwarf_get_universalbinary_count(
09810
          Dwarf_Debug dw_dbg,
          Dwarf_Unsigned *dw_current_index,
09811
09812
          Dwarf_Unsigned *dw_available_count);
09813
09832 DW_API int dwarf_object_detector_path_b(const char * dw_path,
09833
                          *dw_outpath_buffer,
09834
          unsigned long
                         dw_outpathlen,
09835
          char **
                           dw_gl_pathnames,
          unsigned int
09836
                          dw_gl_pathcount,
          unsigned int
09837
                          *dw_ftype,
          unsigned int
unsigned int
09838
                          *dw_endian,
09839
                          *dw_offsetsize,
09840
          Dwarf_Unsigned *dw_filesize,
09841
          unsigned char *dw_pathsource,
09842
          int * dw_errcode);
09843
09844 /* Solely looks for dSYM */
09845 DW_API int dwarf_object_detector_path_dSYM(const char * dw_path,
                         dw_outpath,
09846
          char *
                          dw_outpath_len,
09847
          unsigned long
09848
          char **
                           dw_gl_pathnames,
09849
          unsigned int
                          dw_gl_pathcount,
09850
          unsigned int
                          *dw_ftype,
09851
          unsigned int
                          *dw_endian,
09852
          unsigned int
                          *dw_offsetsize,
          Dwarf_Unsigned *dw_filesize,
09853
09854
          unsigned char *dw_pathsource,
09855
          int *
                          dw_errcode);
09856
09857 DW_API int dwarf_object_detector_fd(int dw_fd,
         unsigned int *dw_ftype,
unsigned int *dw_endian,
09858
09859
          unsigned int *dw_offsetsize,
09860
09861
          Dwarf_Unsigned *dw_filesize,
09862
           int
                          *dw_errcode);
09927 DW_API enum Dwarf_Sec_Alloc_Pref dwarf_set_load_preference(
09928
          enum Dwarf_Sec_Alloc_Pref dw_load_preference);
09929
09969 DW_API int dwarf_get_mmap_count(Dwarf_Debug dw_dbg,
          Dwarf_Unsigned *dw_mmap_count,
Dwarf_Unsigned *dw_mmap_size,
09970
09971
          Dwarf_Unsigned *dw_malloc_count,
09972
09973
          Dwarf_Unsigned *dw_malloc_size);
09977 #ifdef __cplusplus
09978 }
09979 #endif /* __cplusplus */
09980 #endif /* _LIBDWARF_H */
```

Index

```
.debug addr access: DWARF5, 134
                                                                                                            dwarf_next_cu_header_e, 69
        dwarf dealloc debug addr table, 136
                                                                                                            dwarf offdie b, 74
        dwarf debug addr by index, 135
                                                                                                            dwarf siblingof b, 72
        dwarf debug addr table, 134
                                                                                                            dwarf siblingof c, 71
/home/davea/dwarf/code/src/bin/dwarfexample/jitreader.c,
                                                                                                   Debugging Information Entry (DIE) content, 76
                 287
/home/davea/dwarf/code/src/bin/dwarfexample/showsection grouble action group group
                                                                                                            dwarf_arrayorder, 89
                                                                                                            dwarf_attr, 81
/home/davea/dwarf/code/src/lib/libdwarf/dwarf.h, 289
                                                                                                            dwarf bitoffset, 88
/home/davea/dwarf/code/src/lib/libdwarf/libdwarf.h, 309
                                                                                                            dwarf bitsize, 88
A Consumer Library Interface to DWARF, 1
                                                                                                            dwarf bytesize, 87
                                                                                                            dwarf_CU_dieoffset_given_die, 79
A simple report on section groups., 275
Abbreviations Section Details, 160
                                                                                                            dwarf debug addr index to addr, 78
        dwarf get abbrev, 161
                                                                                                            dwarf die abbrev children flag, 83
        dwarf get abbrev children flag, 162
                                                                                                            dwarf die abbrev code, 82
        dwarf get abbrev code, 162
                                                                                                            dwarf die abbrev global offset, 77
        dwarf get abbrev_entry_b, 163
                                                                                                            dwarf die CU offset, 80
        dwarf_get_abbrev_tag, 161
                                                                                                            dwarf_die_CU_offset_range, 81
Access GNU .gnu_debuglink, build-id., 201
                                                                                                            dwarf_die_offsets, 85
        dwarf_add_debuglink_global_path, 205
                                                                                                            dwarf_die_text, 82
        dwarf basic crc32, 206
                                                                                                            dwarf diename, 82
        dwarf crc32, 205
                                                                                                            dwarf dieoffset, 78
        dwarf gnu debuglink, 202
                                                                                                            dwarf dietype offset, 87
        dwarf suppress debuglink crc, 204
                                                                                                            dwarf get cu die offset given cu header offset b,
Access to Section .debug sup, 170
        dwarf_get_debug_sup, 171
                                                                                                            dwarf_get_die_address_size, 85
Accessing accessing raw rnglist, 267
                                                                                                            dwarf_get_version_of_die, 85
Accessing rnglists section, 269
                                                                                                            dwarf hasattr, 84
Attaching a tied dbg, 231
                                                                                                            dwarf highpc b, 86
                                                                                                            dwarf_language_version_string, 89
Basic Library Datatypes Group, 39
                                                                                                            dwarf lowpc, 86
        Dwarf Addr, 39
                                                                                                            dwarf offset list, 84
         Dwarf_Bool, 40
                                                                                                            dwarf srclang, 89
         Dwarf Half, 40
                                                                                                            dwarf tag, 78
         Dwarf Off, 39
                                                                                                            dwarf validate die sibling, 83
         Dwarf Ptr. 40
                                                                                                   Default stack frame macros, 51
         Dwarf Signed, 39
                                                                                                   Defined and Opaque Structs, 42
         Dwarf Small, 40
                                                                                                            Dwarf_Abbrev, 48
         Dwarf Unsigned, 39
                                                                                                            Dwarf_Arange, 48
                                                                                                            Dwarf Attribute, 48
checkexamples.c, 31, 287
                                                                                                            Dwarf Block, 43
Compilation Unit (CU) Access, 69
                                                                                                            Dwarf_Cie, 48
        dwarf child, 73
                                                                                                            Dwarf_Debug, 46
        dwarf_cu_header_basics, 72
                                                                                                            Dwarf Debug Addr Table, 47
        dwarf dealloc die, 74
                                                                                                            Dwarf_Debug_Fission_Per_CU, 50
        dwarf_die_from_hash_signature, 74
                                                                                                            Dwarf Die, 47
        dwarf find die given sig8, 75
                                                                                                            Dwarf Dnames Head, 49
        dwarf get die infotypes flag, 75
                                                                                                            Dwarf Dsc Head, 44
        dwarf next cu header d, 71
                                                                                                            Dwarf Error, 46
```

dwarf_hasform, 92
dwarf_uncompress_integer_block_a, 101
dwarf_whatattr, 93
dwarf_whatform, 92
dwarf_whatform_direct, 93
Documenting Form_Block, 241
DW_DLA alloc/dealloc typename&number, 51
DW_DLE Dwarf_Error numbers, 52
DW DLE LAST, 61
DW DLE LAST
DW_DLE Dwarf_Error numbers, 61
dwarf.h, 27, 289
Dwarf Abbrev
Defined and Opaque Structs, 48
dwarf_add_debuglink_global_path
Access GNU .gnu_debuglink, build-id., 205
Dwarf Addr
Basic Library Datatypes Group, 39
dwarf_addr_form_is_indexed
Debugging Information Entry (DIE) content, 79
Dwarf_Arange
Defined and Opaque Structs, 48
dwarf_arrayorder
Debugging Information Entry (DIE) content, 89
dwarf_attr
Debugging Information Entry (DIE) content, 81
dwarf_attr_offset
DIE Attribute and Attribute-Form Details, 100
Dwarf_Attribute
Defined and Opaque Structs, 48
dwarf_attrlist
DIE Attribute and Attribute-Form Details, 92
dwarf_basic_crc32
Access GNU .gnu_debuglink, build-id., 206
dwarf_bitoffset
Debugging Information Entry (DIE) content, 88
Debugging Information Entry (DIE) content, 88 dwarf_bitsize
dwarf_bitsize
dwarf_bitsize Debugging Information Entry (DIE) content, 88
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48 dwarf_cie_section_offset
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48 dwarf_cie_section_offset Stack Frame Access, 158
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48 dwarf_cie_section_offset Stack Frame Access, 158 dwarf_close_str_offsets_table_access
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48 dwarf_cie_section_offset Stack Frame Access, 158 dwarf_close_str_offsets_table_access Str_Offsets section details, 165
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48 dwarf_cie_section_offset Stack Frame Access, 158 dwarf_close_str_offsets_table_access Str_Offsets section details, 165 Dwarf_Cmdline_Options_s, 279
dwarf_bitsize Debugging Information Entry (DIE) content, 88 Dwarf_Block Defined and Opaque Structs, 43 Dwarf_Block_s, 279 Dwarf_Bool Basic Library Datatypes Group, 40 dwarf_bytesize Debugging Information Entry (DIE) content, 87 dwarf_check_lineheader_b Line Table For a CU, 117 dwarf_child Compilation Unit (CU) Access, 73 Dwarf_Cie Defined and Opaque Structs, 48 dwarf_cie_section_offset Stack Frame Access, 158 dwarf_close_str_offsets_table_access Str_Offsets section details, 165

dwarf_crc32	Debugging Information Entry (DIE) content, 80
Access GNU .gnu_debuglink, build-id., 205	dwarf_die_CU_offset_range
dwarf_CU_dieoffset_given_die	Debugging Information Entry (DIE) content, 81
Debugging Information Entry (DIE) content, 79	dwarf_die_from_hash_signature
dwarf cu header basics	Compilation Unit (CU) Access, 74
Compilation Unit (CU) Access, 72	dwarf_die_offsets
dwarf dealloc	Debugging Information Entry (DIE) content, 85
Generic dwarf_dealloc Function, 170	dwarf die text
dwarf_dealloc_attribute	Debugging Information Entry (DIE) content, 82
DIE Attribute and Attribute-Form Details, 102	dwarf diename
dwarf_dealloc_debug_addr_table	Debugging Information Entry (DIE) content, 82
.debug_addr access: DWARF5, 136	dwarf dieoffset
dwarf_dealloc_die	Debugging Information Entry (DIE) content, 78
Compilation Unit (CU) Access, 74	dwarf_dietype_offset
dwarf_dealloc_dnames	Debugging Information Entry (DIE) content, 87
Fast Access to .debug_names DWARF5, 173	dwarf_discr_entry_s
dwarf_dealloc_error	DIE Attribute and Attribute-Form Details, 103
Dwarf_Error Functions, 169	dwarf_discr_entry_u
dwarf_dealloc_fde_cie_list	DIE Attribute and Attribute-Form Details, 103
Stack Frame Access, 146	dwarf discr list
dwarf_dealloc_frame_instr_head	DIE Attribute and Attribute-Form Details, 102
Stack Frame Access, 157	dwarf_dnames_abbrevtable
dwarf_dealloc_gdbindex	Fast Access to .debug_names DWARF5, 173
Fast Access to Gdb Index, 191	dwarf_dnames_bucket
dwarf_dealloc_loc_head_c	Fast Access to .debug_names DWARF5, 175
Locations of data: DWARF2-DWARF5, 131	dwarf_dnames_cu_table
dwarf_dealloc_macro_context	Fast Access to .debug_names DWARF5, 174
Macro Access: DWARF5, 138	dwarf_dnames_entrypool
dwarf_dealloc_ranges	Fast Access to .debug_names DWARF5, 176
Ranges: code addresses in DWARF3-4, 120	dwarf_dnames_entrypool_values
dwarf_dealloc_rnglists_head	Fast Access to .debug_names DWARF5, 177
Rnglists: code addresses in DWARF5, 123	Dwarf_Dnames_Head
dwarf_dealloc_uncompressed_block	Defined and Opaque Structs, 49
DIE Attribute and Attribute-Form Details, 101	dwarf_dnames_header
dwarf_dealloc_xu_header	Fast Access to .debug_names DWARF5, 172
Fast Access to Split Dwarf (Debug Fission), 198	dwarf_dnames_name
Dwarf_Debug	Fast Access to .debug_names DWARF5, 175
Defined and Opaque Structs, 46	dwarf_dnames_offsets
dwarf_debug_addr_by_index	Fast Access to .debug_names DWARF5, 174
.debug_addr access: DWARF5, 135	dwarf_dnames_sizes
dwarf_debug_addr_index_to_addr	Fast Access to .debug_names DWARF5, 174
Debugging Information Entry (DIE) content, 78	Dwarf_Dsc_Head
Dwarf_Debug_Addr_Table	Defined and Opaque Structs, 44
Defined and Opaque Structs, 47	dwarf_errmsg
dwarf_debug_addr_table	Dwarf_Error Functions, 168
.debug_addr access: DWARF5, 134	dwarf_errmsg_by_number
Dwarf_Debug_Fission_Per_CU	Dwarf_Error Functions, 168
Defined and Opaque Structs, 50	dwarf_errno
Dwarf_Debug_Fission_Per_CU_s, 280	Dwarf_Error Functions, 168
Dwarf_Die	Dwarf_Error
Defined and Opaque Structs, 47	Defined and Opaque Structs, 46
dwarf_die_abbrev_children_flag	Dwarf_Error Functions, 167
Debugging Information Entry (DIE) content, 83	dwarf_dealloc_error, 169
dwarf_die_abbrev_code	dwarf_errmsg, 168
Debugging Information Entry (DIE) content, 82	dwarf_errmsg_by_number, 168
dwarf_die_abbrev_global_offset	dwarf_errno, 168
Debugging Information Entry (DIE) content, 77	dwarf_error_creation, 169
dwarf_die_CU_offset	dwarf_error_creation

Dwarf_Error Functions, 169	dwarf_gdbindex_cuvector_length
dwarf_expand_frame_instructions	Fast Access to Gdb Index, 195
Stack Frame Access, 155	dwarf_gdbindex_header
Dwarf_Fde	Fast Access to Gdb Index, 191
Defined and Opaque Structs, 48	dwarf_gdbindex_string_by_offset
dwarf_fde_section_offset	Fast Access to Gdb Index, 196
Stack Frame Access, 158	dwarf_gdbindex_symboltable_array
dwarf_find_die_given_sig8	Fast Access to Gdb Index, 194
Compilation Unit (CU) Access, 75	dwarf gdbindex symboltable entry
dwarf_find_macro_value_start	Fast Access to Gdb Index, 194
Macro Access: DWARF2-4, 142	dwarf_gdbindex_types_culist_array
dwarf finish	Fast Access to Gdb Index, 192
Libdwarf Initialization Functions, 66	dwarf_gdbindex_types_culist_entry
Dwarf_Form_Class	Fast Access to Gdb Index, 193
Enumerators with various purposes, 41	dwarf_get_abbrev
Dwarf_Form_Data16	Abbreviations Section Details, 161
Defined and Opaque Structs, 43	dwarf_get_abbrev_children_flag
Dwarf_Form_Data16_s, 280	Abbreviations Section Details, 162
dwarf_formaddr	dwarf_get_abbrev_code
DIE Attribute and Attribute-Form Details, 96	Abbreviations Section Details, 162
dwarf_formblock	dwarf_get_abbrev_entry_b
DIE Attribute and Attribute-Form Details, 98	Abbreviations Section Details, 163
dwarf_formdata16	dwarf_get_abbrev_tag
DIE Attribute and Attribute-Form Details, 98	Abbreviations Section Details, 161
dwarf_formexprloc	dwarf_get_address_size
DIE Attribute and Attribute-Form Details, 99	Object Sections Data, 215
dwarf_formflag	dwarf_get_arange
DIE Attribute and Attribute-Form Details, 96	Fast Access to a CU given a code address, 179
dwarf_formref	dwarf_get_arange_cu_header_offset
DIE Attribute and Attribute-Form Details, 94	Fast Access to a CU given a code address, 180
dwarf_formsdata	dwarf_get_arange_info_b
DIE Attribute and Attribute-Form Details, 97	Fast Access to a CU given a code address, 180
dwarf_formsig8	dwarf_get_aranges
DIE Attribute and Attribute-Form Details, 95	Fast Access to a CU given a code address, 179
dwarf_formsig8_const	dwarf_get_cie_augmentation_data
DIE Attribute and Attribute-Form Details, 95	Stack Frame Access, 154
dwarf_formstring	dwarf_get_cie_index
DIE Attribute and Attribute-Form Details, 99	Stack Frame Access, 149
dwarf formudata	dwarf_get_cie_info_b
DIE Attribute and Attribute-Form Details, 97	Stack Frame Access, 148
Dwarf_Frame_Instr_Head	dwarf_get_cie_of_fde
Defined and Opaque Structs, 44	Stack Frame Access, 148
Dwarf_Func	dwarf_get_cu_die_offset
Defined and Opaque Structs, 47	Fast Access to a CU given a code address, 180
Dwarf Gdbindex	dwarf_get_cu_die_offset_given_cu_header_offset_b
_	
Defined and Opaque Structs, 49	Debugging Information Entry (DIE) content, 80
dwarf_gdbindex_addressarea	dwarf_get_debug_addr_index
Fast Access to Gdb Index, 193	DIE Attribute and Attribute-Form Details, 96
dwarf_gdbindex_addressarea_entry	dwarf_get_debug_str_index
Fast Access to Gdb Index, 193	DIE Attribute and Attribute-Form Details, 99
dwarf_gdbindex_culist_array	dwarf_get_debug_sup
Fast Access to Gdb Index, 191	Access to Section .debug_sup, 171
dwarf_gdbindex_culist_entry	dwarf_get_debugfission_for_die
Fast Access to Gdb Index, 192	Fast Access to Split Dwarf (Debug Fission), 200
dwarf_gdbindex_cuvector_inner_attributes	dwarf_get_debugfission_for_key
Fast Access to Gdb Index, 195	Fast Access to Split Dwarf (Debug Fission), 201
dwarf_gdbindex_cuvector_instance_expand_value	dwarf_get_die_address_size
Fast Access to Gdb Index, 196	Debugging Information Entry (DIE) content, 85

dwarf_get_die_infotypes_flag	dwarf_get_gnu_index_block
Compilation Unit (CU) Access, 75	Fast Access to GNU .debug_gnu_pubnames, 188
dwarf_get_die_section_name	dwarf_get_gnu_index_block_entry
Object Sections Data, 213	Fast Access to GNU .debug_gnu_pubnames, 188
dwarf_get_die_section_name_b	dwarf_get_gnu_index_head
Object Sections Data, 214	Fast Access to GNU .debug_gnu_pubnames, 187
dwarf_get_EH_name	dwarf_get_GNUIKIND_name
Names DW_TAG_member etc as strings, 210	Names DW_TAG_member etc as strings, 210
dwarf_get_endian_copy_function	dwarf_get_GNUIVIS_name
Miscellaneous Functions, 226	Names DW_TAG_member etc as strings, 211
dwarf_get_fde_at_pc	dwarf_get_harmless_error_list
Stack Frame Access, 153	Harmless Error recording, 207
dwarf_get_fde_augmentation_data	dwarf_get_line_section_name_from_die
Stack Frame Access, 155	Object Sections Data, 215
dwarf_get_fde_exception_info	dwarf_get_LLEX_name
Stack Frame Access, 147	Names DW_TAG_member etc as strings, 211
dwarf_get_fde_for_die	dwarf_get_location_op_value_c
Stack Frame Access, 153	Locations of data: DWARF2-DWARF5, 130
dwarf_get_fde_info_for_all_regs3	dwarf_get_locdesc_entry_d
Stack Frame Access, 150	Locations of data: DWARF2-DWARF5, 128
dwarf_get_fde_info_for_all_regs3_b	dwarf_get_locdesc_entry_e
Stack Frame Access, 150	Locations of data: DWARF2-DWARF5, 129
dwarf_get_fde_info_for_cfa_reg3_b	dwarf_get_loclist_c
Stack Frame Access, 152	Locations of data: DWARF2-DWARF5, 128
dwarf_get_fde_info_for_cfa_reg3_c	dwarf_get_loclist_context_basics
Stack Frame Access, 152	Locations of data: DWARF2-DWARF5, 133
dwarf_get_fde_info_for_reg3_b	dwarf_get_loclist_head_basics
Stack Frame Access, 151	Locations of data: DWARF2-DWARF5, 133
dwarf_get_fde_info_for_reg3_c	dwarf_get_loclist_head_kind
Stack Frame Access, 150	Locations of data: DWARF2-DWARF5, 128
dwarf_get_fde_instr_bytes	dwarf_get_loclist_lle
Stack Frame Access, 149	Locations of data: DWARF2-DWARF5, 133
dwarf_get_fde_list	dwarf_get_loclist_offset_index_value
Stack Frame Access, 146	Locations of data: DWARF2-DWARF5, 132
dwarf_get_fde_list_eh	dwarf_get_MACINFO_name
Stack Frame Access, 146	Names DW_TAG_member etc as strings, 211
dwarf_get_fde_n	dwarf_get_macro_context
Stack Frame Access, 153	Macro Access: DWARF5, 137
dwarf_get_fde_range	dwarf_get_macro_context_by_offset
Stack Frame Access, 147	Macro Access: DWARF5, 137
dwarf_get_form_class	dwarf_get_macro_defundef
DIE Attribute and Attribute-Form Details, 100	Macro Access: DWARF5, 140
dwarf_get_FORM_CLASS_name	dwarf_get_macro_details
Names DW_TAG_member etc as strings, 211	Macro Access: DWARF2-4, 142
dwarf_get_frame_instruction	dwarf_get_macro_import
Stack Frame Access, 156	Macro Access: DWARF5, 141
dwarf_get_frame_instruction_a	dwarf_get_MACRO_name
Stack Frame Access, 157	Names DW_TAG_member etc as strings, 211
dwarf_get_FRAME_name	dwarf_get_macro_op
Names DW_TAG_member etc as strings, 210	Macro Access: DWARF5, 139
dwarf_get_frame_section_name	dwarf_get_macro_startend_file
Object Sections Data, 215	Macro Access: DWARF5, 141
dwarf_get_frame_section_name_eh_gnu	dwarf_get_mmap_count
Object Sections Data, 215	Section allocation: malloc or mmap, 228
dwarf_get_globals	dwarf_get_offset_size
Fast Access to .debug_pubnames and more., 182	Object Sections Data, 215
dwarf_get_globals_header	dwarf_get_pubtypes
Fast Access to .debug_pubnames and more., 186	Fast Access to .debug_pubnames and more., 183

dwarf_get_ranges_b	dwarf_global_tag_number
Ranges: code addresses in DWARF3-4, 119	Fast Access to .debug_pubnames and more., 185
dwarf_get_ranges_baseaddress	dwarf_globals_by_type
Ranges: code addresses in DWARF3-4, 120	Fast Access to .debug_pubnames and more., 183
dwarf_get_real_section_name	dwarf_globals_dealloc
Object Sections Data, 214	Fast Access to .debug_pubnames and more., 184
dwarf_get_rnglist_context_basics	dwarf globname
Rnglists: code addresses in DWARF5, 125	Fast Access to .debug_pubnames and more., 184
dwarf get rnglist head basics	dwarf_gnu_debuglink
Rnglists: code addresses in DWARF5, 125	Access GNU .gnu_debuglink, build-id., 202
dwarf_get_rnglist_offset_index_value	dwarf_gnu_index_dealloc
Rnglists: code addresses in DWARF5, 124	Fast Access to GNU .debug gnu pubnames, 188
dwarf_get_rnglist_rle	Dwarf_Gnu_Index_Head
Rnglists: code addresses in DWARF5, 126	Defined and Opaque Structs, 44
dwarf_get_rnglists_entry_fields_a	Dwarf Half
Rnglists: code addresses in DWARF5, 123	Basic Library Datatypes Group, 40
dwarf get section count	Dwarf Handler
Object Sections Data, 219	Defined and Opaque Structs, 49
dwarf_get_section_info_by_index	dwarf hasattr
Object Sections Data, 217	Debugging Information Entry (DIE) content, 84
dwarf_get_section_info_by_index_a	dwarf hasform
Object Sections Data, 217	DIE Attribute and Attribute-Form Details, 92
dwarf_get_section_info_by_name	dwarf_highpc_b
Object Sections Data, 216	Debugging Information Entry (DIE) content, 86
dwarf_get_section_info_by_name_a	dwarf init b
Object Sections Data, 216	Libdwarf Initialization Functions, 65
dwarf_get_section_max_offsets_d	dwarf_init_path
Object Sections Data, 220	Libdwarf Initialization Functions, 63
dwarf get str	dwarf_init_path_a
String Section .debug_str Details, 164	Libdwarf Initialization Functions, 63
dwarf_get_tied_dbg	dwarf_init_path_dl
Libdwarf Initialization Functions, 68	Libdwarf Initialization Functions, 64
dwarf get universalbinary count	dwarf_init_path_dl_a
Miscellaneous Functions, 226	Libdwarf Initialization Functions, 65
dwarf_get_version_of_die	dwarf insert harmless error
Debugging Information Entry (DIE) content, 85	Harmless Error recording, 208
dwarf_get_xu_hash_entry	dwarf_language_version_string
Fast Access to Split Dwarf (Debug Fission), 199	Debugging Information Entry (DIE) content, 89
dwarf get xu index header	dwarf_library_allow_dup_attr
Fast Access to Split Dwarf (Debug Fission), 197	Miscellaneous Functions, 225
dwarf_get_xu_index_section_type	Dwarf_Line
Fast Access to Split Dwarf (Debug Fission), 198	Defined and Opaque Structs, 47
dwarf_get_xu_section_names	Dwarf Line Context
Fast Access to Split Dwarf (Debug Fission), 199	Defined and Opaque Structs, 49
dwarf_get_xu_section_offset	dwarf line is addr set
Fast Access to Split Dwarf (Debug Fission), 200	Line Table For a CU, 114
Dwarf_Global	dwarf line srcfileno
Defined and Opaque Structs, 47	Line Table For a CU, 114
dwarf_global_cu_offset	dwarf lineaddr
Fast Access to .debug_pubnames and more., 185	Line Table For a CU, 115
dwarf_global_die_offset	dwarf_linebeginstatement
Fast Access to .debug_pubnames and more., 184	Line Table For a CU, 113
dwarf_global_formref	dwarf_lineblock
DIE Attribute and Attribute-Form Details, 95	Line Table For a CU, 116
dwarf_global_formref_b	dwarf_lineendsequence
DIE Attribute and Attribute-Form Details, 94	Line Table For a CU, 113
dwarf_global_name_offsets	dwarf_lineno
Fast Access to .debug_pubnames and more., 185	
r asi Access to luebuy_publiantes and inote., 165	Line Table For a CU, 114

dwarf_lineoff_b	dwarf_package_version
Line Table For a CU, 115	Miscellaneous Functions, 223
dwarf_linesrc	dwarf_print_lines
Line Table For a CU, 115	Line Table For a CU, 117
dwarf_load_loclists	dwarf_printf_callback_function_type
Locations of data: DWARF2-DWARF5, 131	Defined and Opaque Structs, 44
dwarf_load_rnglists	Dwarf_Printf_Callback_Info_s, 282
Rnglists: code addresses in DWARF5, 124	dwarf_prologue_end_etc
Dwarf_Loc_Head_c	Line Table For a CU, 116
Defined and Opaque Structs, 44	Dwarf_Ptr
Dwarf_Locdesc_c	Basic Library Datatypes Group, 40
Defined and Opaque Structs, 43	Dwarf_Ranges
dwarf_loclist_from_expr_c	Defined and Opaque Structs, 45
Locations of data: DWARF2-DWARF5, 130	Dwarf_Ranges_Entry_Type
dwarf_lowpc	Enumerators with various purposes, 41
Debugging Information Entry (DIE) content, 86	Dwarf_Ranges_s, 283
dwarf_machine_architecture	dwarf_record_cmdline_options
Object Sections Data, 219	Miscellaneous Functions, 224
dwarf_machine_architecture_a	dwarf register printf callback
Object Sections Data, 218	Line Table For a CU, 118
Dwarf Macro Context	Dwarf_Regtable3
Defined and Opaque Structs, 49	Defined and Opaque Structs, 46
dwarf_macro_context_head	Dwarf_Regtable3_s, 283
Macro Access: DWARF5, 139	Dwarf_Regtable_Entry3
dwarf_macro_context_total_length	Defined and Opaque Structs, 45
Macro Access: DWARF5, 138	Dwarf_Regtable_Entry3_s, 283
Dwarf_Macro_Details	dwarf_return_empty_pubnames
Defined and Opaque Structs, 49	Fast Access to .debug_pubnames and more., 186
Dwarf_Macro_Details_s, 280	dwarf_rnglists_get_rle_head
dwarf_macro_operands_table	Rnglists: code addresses in DWARF5, 122
Macro Access: DWARF5, 139	Dwarf_Rnglists_Head
dwarf_next_cu_header_d	Defined and Opaque Structs, 50
Compilation Unit (CU) Access, 71	Dwarf_Sec_Alloc_Pref
dwarf_next_cu_header_e	Defined and Opaque Structs, 50
Compilation Unit (CU) Access, 69	dwarf sec group map
dwarf next str offsets table	Section Groups Objectfile Data, 221
Str_Offsets section details, 166	dwarf_sec_group_sizes
Dwarf_Obj_Access_Interface_a	Section Groups Objectfile Data, 221
Defined and Opaque Structs, 50	Dwarf_Section
Dwarf_Obj_Access_Interface_a_s, 281	Defined and Opaque Structs, 47
Dwarf_Obj_Access_Methods_a	dwarf_set_de_alloc_flag
Defined and Opaque Structs, 50	Miscellaneous Functions, 224
Dwarf_Obj_Access_Methods_a_s, 281	dwarf set default address size
Dwarf Obj Access Section a	Miscellaneous Functions, 225
Defined and Opaque Structs, 50	dwarf set frame cfa value
Dwarf_Obj_Access_Section_a_s, 282	Stack Frame Access, 159
dwarf object finish	dwarf_set_frame_rule_initial_value
Libdwarf Initialization Functions, 67	Stack Frame Access, 159
dwarf_object_init_b	dwarf_set_frame_rule_table_size
Libdwarf Initialization Functions, 66	Stack Frame Access, 158
Dwarf_Off	dwarf_set_frame_same_value
Basic Library Datatypes Group, 39	Stack Frame Access, 159
dwarf_offdie_b	dwarf_set_frame_undefined_value
Compilation Unit (CU) Access, 74	Stack Frame Access, 160
dwarf_offset_list	dwarf_set_harmless_error_list_size
Debugging Information Entry (DIE) content, 84	Harmless Error recording, 207
dwarf_open_str_offsets_table_access	dwarf_set_load_preference
Str_Offsets section details, 165	Section allocation: malloc or mmap, 228
on_onsets section details, 100	occion anocation. mailor of minap, 220

dwarf_set_reloc_application	Defined and Opaque Structs, 47
Miscellaneous Functions, 224	dwarf_uncompress_integer_block_a
dwarf_set_stringcheck	DIE Attribute and Attribute-Form Details, 101
Miscellaneous Functions, 223	Dwarf_Unsigned
dwarf_set_tied_dbg	Basic Library Datatypes Group, 39
Libdwarf Initialization Functions, 67	dwarf_validate_die_sibling
dwarf_siblingof_b	Debugging Information Entry (DIE) content, 83
Compilation Unit (CU) Access, 72	Dwarf_Var
dwarf_siblingof_c	Defined and Opaque Structs, 48
Compilation Unit (CU) Access, 71	Dwarf_Weak
Dwarf_Sig8	Defined and Opaque Structs, 48
Defined and Opaque Structs, 43	dwarf_whatattr
Dwarf_Sig8_s, 283	DIE Attribute and Attribute-Form Details, 93
Dwarf_Signed	dwarf_whatform
Basic Library Datatypes Group, 39	DIE Attribute and Attribute-Form Details, 92
Dwarf_Small	dwarf_whatform_direct
Basic Library Datatypes Group, 40	DIE Attribute and Attribute-Form Details, 93
dwarf_srcfiles	Dwarf_Xu_Index_Header
Line Table For a CU, 105	Defined and Opaque Structs, 49
dwarf srclang	
Debugging Information Entry (DIE) content, 89	Enumerators with various purposes, 40
dwarf_srclines_b	Dwarf_Form_Class, 41
Line Table For a CU, 106	Dwarf_Ranges_Entry_Type, 41
dwarf_srclines_comp_dir	Examining Section Group data, 232
Line Table For a CU, 109	Example getting .debug_ranges data, 261
dwarf_srclines_dealloc_b	Example walking CUs(d), 238
Line Table For a CU, 108	Example walking CUs(e), 236
dwarf_srclines_files_data_b	Extracting fde, cie lists., 257
Line Table For a CU, 110	
dwarf_srclines_files_indexes	Fast Access to .debug_names DWARF5, 171
Line Table For a CU, 110	dwarf_dealloc_dnames, 173
dwarf_srclines_from_linecontext	dwarf_dnames_abbrevtable, 173
Line Table For a CU, 107	dwarf_dnames_bucket, 175
dwarf_srclines_include_dir_count	dwarf_dnames_cu_table, 174
Line Table For a CU, 111	dwarf_dnames_entrypool, 176
dwarf srclines include dir data	dwarf_dnames_entrypool_values, 177
Line Table For a CU, 112	dwarf_dnames_header, 172
dwarf_srclines_subprog_count	dwarf_dnames_name, 175
Line Table For a CU, 109	dwarf_dnames_offsets, 174
dwarf_srclines_subprog_data	dwarf_dnames_sizes, 174
Line Table For a CU, 109	Fast Access to .debug_pubnames and more., 181
dwarf_srclines_table_offset	dwarf_get_globals, 182
Line Table For a CU, 108	dwarf_get_globals_header, 186
dwarf srclines two level from linecontext	dwarf_get_pubtypes, 183
Line Table For a CU, 108	dwarf_global_cu_offset, 185
dwarf_srclines_version	dwarf_global_die_offset, 184
Line Table For a CU, 112	dwarf_global_name_offsets, 185
dwarf str offsets statistics	dwarf_global_tag_number, 185
Str_Offsets section details, 167	dwarf_globals_by_type, 183
Dwarf_Str_Offsets_Table	dwarf_globals_dealloc, 184
Defined and Opaque Structs, 44	dwarf_globname, 184
dwarf_str_offsets_value_by_index	dwarf_return_empty_pubnames, 186
Str_Offsets section details, 166	Fast Access to a CU given a code address, 178
dwarf_suppress_debuglink_crc	dwarf_get_arange, 179
Access GNU .gnu_debuglink, build-id., 204	dwarf_get_arange_cu_header_offset, 180
dwarf_tag	dwarf_get_arange_info_b, 180
Debugging Information Entry (DIE) content, 78	dwarf_get_aranges, 179
Dwarf_Type	dwarf_get_cu_die_offset, 180
- · · - · ·] ,] P C	Fast Access to Gdb Index, 189

dwarf_dealloc_gdbindex, 191	dwarf_lineblock, 116
dwarf_gdbindex_addressarea, 193	dwarf_lineendsequence, 113
dwarf_gdbindex_addressarea_entry, 193	dwarf_lineno, 114
dwarf_gdbindex_culist_array, 191	dwarf_lineoff_b, 115
dwarf_gdbindex_culist_entry, 192	dwarf_linesrc, 115
dwarf_gdbindex_cuvector_inner_attributes, 195	dwarf_print_lines, 117
dwarf_gdbindex_cuvector_instance_expand_value,	dwarf_prologue_end_etc, 116
196	dwarf_register_printf_callback, 118
dwarf_gdbindex_cuvector_length, 195	dwarf_srcfiles, 105
dwarf_gdbindex_header, 191	dwarf_srclines_b, 106
dwarf_gdbindex_string_by_offset, 196	dwarf_srclines_comp_dir, 109
dwarf_gdbindex_symboltable_array, 194	dwarf_srclines_dealloc_b, 108
dwarf_gdbindex_symboltable_entry, 194	dwarf_srclines_files_data_b, 110
dwarf_gdbindex_types_culist_array, 192	dwarf_srclines_files_indexes, 110
dwarf_gdbindex_types_culist_entry, 193	dwarf_srclines_from_linecontext, 107
Fast Access to GNU .debug_gnu_pubnames, 187	dwarf_srclines_include_dir_count, 111
dwarf_get_gnu_index_block, 188	dwarf_srclines_include_dir_data, 112
dwarf_get_gnu_index_block_entry, 188	dwarf_srclines_subprog_count, 109
dwarf_get_gnu_index_head, 187	dwarf_srclines_subprog_data, 109
dwarf_gnu_index_dealloc, 188	dwarf srclines table offset, 108
Fast Access to Split Dwarf (Debug Fission), 197	dwarf_srclines_two_level_from_linecontext, 108
dwarf_dealloc_xu_header, 198	dwarf_srclines_version, 112
dwarf_get_debugfission_for_die, 200	Location/expression access, 243
dwarf_get_debugfission_for_key, 201	Locations of data: DWARF2-DWARF5, 126
dwarf_get_xu_hash_entry, 199	dwarf_dealloc_loc_head_c, 131
dwarf_get_xu_index_header, 197	dwarf_get_location_op_value_c, 130
dwarf_get_xu_index_section_type, 198	dwarf_get_locdesc_entry_d, 128
dwarf_get_xu_section_names, 199	dwarf_get_locdesc_entry_e, 129
dwarf_get_xu_section_offset, 200	dwarf_get_loclist_c, 128
aago:aoooo,	dwarf_get_loclist_context_basics, 133
Generic dwarf_dealloc Function, 169	dwarf_get_loclist_head_basics, 133
dwarf_dealloc, 170	dwarf_get_loclist_head_kind, 128
_ ,	dwarf get loclist lle, 133
Harmless Error recording, 206	dwarf_get_loclist_offset_index_value, 132
dwarf_get_harmless_error_list, 207	dwarf_load_loclists, 131
dwarf_insert_harmless_error, 208	dwarf loclist from expr c, 130
dwarf_set_harmless_error_list_size, 207	awan_100110t_110t11_0xp1_0, 100
	Macro Access: DWARF2-4, 142
JIT and special case DWARF, 21	dwarf_find_macro_value_start, 142
	dwarf_get_macro_details, 142
LEB Encode and Decode, 222	Macro Access: DWARF5, 136
Libdwarf Initialization Functions, 62	dwarf_dealloc_macro_context, 138
dwarf_finish, 66	dwarf get macro context, 137
dwarf_get_tied_dbg, 68	dwarf_get_macro_context_by_offset, 137
dwarf_init_b, 65	dwarf get macro defundef, 140
dwarf_init_path, 63	dwarf_get_macro_import, 141
dwarf_init_path_a, 63	dwarf get macro op, 139
dwarf_init_path_dl, 64	dwarf_get_macro_startend_file, 141
dwarf_init_path_dl_a, 65	dwarf_macro_context_head, 139
dwarf_object_finish, 67	dwarf_macro_context_total_length, 138
dwarf_object_init_b, 66	dwarf_macro_operands_table, 139
dwarf_set_tied_dbg, 67	Miscellaneous Functions, 223
libdwarf.h, 29, 309	dwarf_get_endian_copy_function, 226
Line Table For a CU, 103	dwarf_get_universalbinary_count, 226
dwarf_check_lineheader_b, 117	dwarf_library_allow_dup_attr, 225
dwarf_line_is_addr_set, 114	dwarf_package_version, 223
dwarf_line_srcfileno, 114	dwarf_record_cmdline_options, 224
dwarf_lineaddr, 115	dwarf_set_de_alloc_flag, 224
dwarf_linebeginstatement, 113	dwarf_set_de_alloc_nag, 224 dwarf_set_default_address_size, 225
	awan_50i_a0iauii_addie55_5i2E, <u>22</u> 5

dwarf_set_reloc_application, 224	dwarf_get_rnglist_rle, 126
dwarf_set_stringcheck, 223	dwarf_get_rnglists_entry_fields_a, 123
	dwarf_load_rnglists, 124
Names DW_TAG_member etc as strings, 208	dwarf_rnglists_get_rle_head, 122
dwarf_get_EH_name, 210	0 11 11 11 11 11 10 10 10 10 10 10 10 10
dwarf_get_FORM_CLASS_name, 211	Section allocation: malloc or mmap, 227
dwarf_get_FRAME_name, 210	dwarf_get_mmap_count, 228
dwarf_get_GNUIKIND_name, 210	dwarf_set_load_preference, 228
dwarf_get_GNUIVIS_name, 211	Section Groups Objectfile Data, 220
dwarf_get_LLEX_name, 211	dwarf_sec_group_map, 221
dwarf_get_MACINFO_name, 211	dwarf_sec_group_sizes, 221
dwarf_get_MACRO_name, 211	Stack Frame Access, 143
Object Sections Data, 212	dwarf_cie_section_offset, 158
dwarf_get_address_size, 215	dwarf_dealloc_fde_cie_list, 146
dwarf_get_die_section_name, 213	dwarf_dealloc_frame_instr_head, 157
dwarf_get_die_section_name_b, 214	dwarf_expand_frame_instructions, 155
dwarf_get_frame_section_name, 215	dwarf_fde_section_offset, 158
dwarf get frame section name eh gnu, 215	dwarf_get_cie_augmentation_data, 154
dwarf_get_line_section_name_from_die, 215	dwarf_get_cie_index, 149
— - — — — — — —	dwarf_get_cie_info_b, 148
dwarf_get_offset_size, 215	dwarf_get_cie_of_fde, 148
dwarf_get_real_section_name, 214 dwarf_get_section_count, 219	dwarf_get_fde_at_pc, 153
dwarf get section info by index, 217	dwarf_get_fde_augmentation_data, 155
	dwarf_get_fde_exception_info, 147
dwarf_get_section_info_by_index_a, 217	dwarf_get_fde_for_die, 153
dwarf_get_section_info_by_name, 216 dwarf_get_section_info_by_name_a, 216	dwarf_get_fde_info_for_all_regs3, 150
dwarf_get_section_mino_by_name_a, 216 dwarf_get_section_max_offsets_d, 220	dwarf_get_fde_info_for_all_regs3_b, 150
dwarf_machine_architecture, 219	dwarf_get_fde_info_for_cfa_reg3_b, 152
	dwarf_get_fde_info_for_cfa_reg3_c, 152
dwarf_machine_architecture_a, 218	dwarf_get_fde_info_for_reg3_b, 151
Ranges: code addresses in DWARF3-4, 119	dwarf_get_fde_info_for_reg3_c, 150
dwarf_dealloc_ranges, 120	dwarf_get_fde_instr_bytes, 149
dwarf_get_ranges_b, 119	dwarf_get_fde_list, 146
dwarf_get_ranges_baseaddress, 120	dwarf_get_fde_list_eh, 146
Reading gdbindex addressarea, 263	dwarf_get_fde_n, 153
Reading .debug_funcnames (nonstandard), 250	dwarf_get_fde_range, 147
Reading .debug_macinfo (DWARF2-4), 256	dwarf_get_frame_instruction, 156
Reading .debug macro data (DWARF5), 254	dwarf_get_frame_instruction_a, 157
Reading .debug_names data, 251	dwarf_set_frame_cfa_value, 159
Reading .debug_types (nonstandard), 250	dwarf_set_frame_rule_initial_value, 159
Reading .debug_varnames data (nonstandard), 251	dwarf_set_frame_rule_table_size, 158
Reading .debug_weaknames (nonstandard), 250	dwarf_set_frame_same_value, 159
Reading a location expression, 244	dwarf_set_frame_undefined_value, 160
Reading an aranges section, 260	Str_Offsets section details, 164
Reading cu and tu Debug Fission data, 264	dwarf_close_str_offsets_table_access, 165
Reading gdbindex data, 262	dwarf_next_str_offsets_table, 166
Reading high pc from a DIE., 265	dwarf_open_str_offsets_table_access, 165
Reading Split Dwarf (Debug Fission) data, 265	dwarf_str_offsets_statistics, 167
Reading Split Dwarf (Debug Fission) hash slots, 265	dwarf_str_offsets_value_by_index, 166
Reading string offsets section data, 258	String Section .debug_str Details, 163
Reading the .eh_frame section, 257	dwarf_get_str, 164
Reading the gdbindex symbol table, 263	Lloing dwarf attrliat/\ 240
Retrieving tag, attribute, etc names, 266	Using dwarf_attrlist(), 240
Rnglists: code addresses in DWARF5, 121	Using dwarf_expand_frame_instructions, 258
dwarf_dealloc_rnglists_head, 123	Using dwarf_attrlist(), 231
dwarf_get_rnglist_context_basics, 125	Using dwarf_child(), 234
dwarf_get_rnglist_head_basics, 125	Using dwarf_discr_list(), 242
dwarf get rnglist offset index value, 124	Using dwarf_get_globals(), 249 Using dwarf_globals_by_type(), 249
and got right oncot mack value, it	Cama avall alouals by typen 744

Using dwarf_init_path(), 229
Using dwarf_init_path_dl(), 230
Using dwarf_offdie_b(), 239
Using dwarf_offset_given_die(), 240
Using dwarf_offset_list(), 240
Using dwarf_siblingof_b(), 234
Using dwarf_siblingof_c(), 233
Using dwarf_srcfiles(), 248
Using dwarf_srclines_b(), 245
Using dwarf_srclines_b() and linecontext, 247
using dwarf_validate_die_sibling, 235
Using GNU debuglink data, 266