

7-2. Assembly

Seongil Wi



Our Environment



*

- Linux (Debian/Ubuntu) on x86
- GNU Binutils (objdump, readelf, strip, etc.)
- GNU Debugger (GDB)
- No IDA Pro
- Vagrant VM for exercise and homework
 - Install latest version of VirtualBox: https://www.virtualbox.org/
 - Install latest version of Vagrant: https://www.vagrantup.com/downloads.html
 - -mkdir YOUR_PATH; cd YOUR_PATH
 - Download box from <u>https://www.dropbox.com/scl/fi/3ssmv98wky2uvpju5q66s/cse467.box?rlkey=s</u> su5llgq9n548ugp4fgyfmm6x&dl=1

Our Environment



- Vagrant VM for exercise and homework
 - -vagrant box add cse467 cse467.box
 - -vagrant init cse467
 - -vagrant up
 - -vagrant ssh

Just use these two after installation is complete

- (Just for your reference) A Vagrant box is created with
 - Virtual box 7.0.10 r158379
 - Vagrant 1.9.8
 - Debian 9.1.0
 - -ID: vagrant
 - -PW: vagrant

Our Goal in Software Security

• Find out whether a program is secure or not.

• To do so, we need to see how the *binary code* (= executable code) executes on a machine!

Compilation



 Converting a <u>high-level language</u> into a <u>machine language</u> that the computer can understand


```
int test (int a){
    return 32;
}
```

High-level language




Machine language

Compilation Process



code



Source code



Intermediate code



Assembly code




Binary code

test.ll



```
define dso_local i32 @test(i32) #0
{
    %2 = alloca i32, align 4
    store i32 %0, i32* %2, align 4
    ret i32 32
}
```

test.s



```
test: # @test

# %bb.0:

push ebp

mov ebp, esp

mov eax, dword ptr [ebp + 8]

mov eax, 32

pop ebp

ret
```

Source code



Intermediate code




Assembly code



Binary code

test.II



Intel syntax

test.s

```
$11c --x86-asm-syntax=intel
test.11
```

```
test: # @test

# %bb.0:

push ebp

mov ebp, esp


mov eax, dword ptr [ebp + 8]

mov eax, 32


pop ebp

ret
```


The last human-readable format



test.s



test.o




GNU AS (Assembler)


```
*
```

```
$as -o test.o test.s
$1s test.o
              .intel_syntax noprefix
              mov eax, ebx
```












Assembly code



Binary code

Our goal:
Understanding binary

Disassembling Binary Code



Binary code

Disassembly!

Disassembler:

- Objdump
- IDA
- B2R2

- ...


GNU objdump



- One of the GNU Binutils
- Perform disassembly on the file

GNU objdump







Intermediate code



Assembly code



Binary code

00000000 <test>:

0: 55 push ebp

1: 89 e5 mov ebp,esp

3: 8b 45 08 mov eax, DWORD PTR [ebp+0x8]

6: b8 20 00 00 00 mov eax,0x20

b: 5d pop ebp

c: c3 ret



\$ objdump -M intel -d test.o

test.o

GNU objdump

Address

Binary code

Disassembled assembly code

Source



Intermediate code



Assembly code



Binary code

00 000000 <test>:

```
0: 55
```

1: 89 e5

3: 8b 45 08

6: b8 20 00 00 00

b: 5d

c: c3

push ebp

mov ebp, esp

mov eax,DWORD PTR [ebp+0x8]

mov eax, 0x20

pop ebp

ret




\$ objdump -M intel -d test.o

test.o

(FYI) Disassembly is Difficult

- The very first step of binary analysis, but it is extremely challenging because of
 - Indirect branches
 - jmp eax
 - call eax
 - Mixture of code and data


Linking



Executable binary code (= Executable)

Linking


Executable Binary (=Executable, Binary)



Executable binary

Executable Binary (=Executable, Binary)





Segmentation Fault

• a.k.a., SegFault or Access violation

Happens when we reference an unmapped memory address

VMA

VMA

Virtual memory

x86 (IA-32) Architecture

x86 Instruction Set Architecture

- Developed by Intel in 1985
- CISC (Complex Instruction Set Computer) architecture
- 32-bit address space
- One of the most common architecture


History of x86 ISA






- (8086) 16-bit address space (in 1978)
- (x86 or IA-32) 32-bit address space (in 1985)
- (x86-64 or x64 or AMD64) 64-bit address space (in 2003)


Memory Layout and CPU Registers



Memory Layout and CPU Registers




File system




Memory Layout and CPU Registers





File system



Registers in x86



- Program counter (instruction pointer)
 - **-EIP:** points to the instruction to execute
- Stack pointers
 - **-ESP:** points to the top of the stack
 - **-EBP:** points to the base of the current stack frame
- Status register (FLAGS register)
 - -EFLAGS: contains the current condition flags
- Other general purpose registers
 - -EAX, EBX, ECX, EDX, ESI, EDI

All of them have a size of a *double word* (=32 bit)

Size of Registers



- x86 registers are 32-bit
- A word is the natural unit of data used by a processor.
 - Typically, a word size is 32 bits on a 32-bit machine

• However, Intel says a word is 16 bits on x86 (32-bit machine)

History of Intel/AMD Processors

- 1978: 8086
- 1982: 80286
- 1985: 80386
- 1989: 80486
- •
- 2003: Opteron
- 2005: Prescott
- 2006: Core 2
- 2008: Core i7

• ...

```
16-bit processor,
Registers (SP, BP, IP, ...)

32-bit processor,
Registers (ESP, EBP, EIP, ...)
```

64-bit processor, Registers (RSP, RBP, RIP, ...)


x86 Convention




- Word = 16 bits
- Double Word (DWORD) = 32 bits

• Linear address space = $0 \sim 2^{32}$ bits


















x86 Memory Access = Byte Addressing




x86 Assembly Basics

Basic Formats




- Three formats of Instructions
 - -2 operands
 - -1 operands
 - -0 operands

Basic Format #1: Instructions with 2 Operands




Basic Format #2: Instructions with 1 Operand 40





Basic Format #3: Instructions with 0 Operand **





Intel vs AT&T Format





• There are two ways to represent x86 assembly code

AT&T

mov %eax, %ebx

Intel

mov ebx, eax

We will use the Intel syntax

Recap: Compilation Process



Source

code



Intermediate code



Assembly code




Binary code

test.ll

```
define dso_local i32 @test(i32) #0
{
    %2 = alloca i32, align 4
    store i32 %0, i32* %2, align 4
    ret i32 32
}
```

Intel syntax

test.s



```
test: # @test

# %bb.0:

push ebp

mov ebp, esp

mov eax, dword ptr [ebp + 8]

mov eax, 32

pop ebp


ret
```

The last human-readable format

Recap: GNU objdump









Intermediate code



Assembly code



Binary code

00000000 <test>:

0: 55 push ebp

1: 89 e5 mov ebp,esp

3: 8b 45 08 mov eax, DWORD PTR [ebp+0x8]

6: b8 20 00 00 00 mov eax,0x20

b: 5d pop ebp

c: c3 ret



\$ objdump -M intel -d test.o

test.o

Intel syntax

Opcode Decides Semantics

mov eax, ebx

sub esp, 0x8


inc eax


eax ← ebx

esp ← esp – 0x8

 $eax \leftarrow eax + 1$

Operand Types





Registers

eax

ebx

0x00000004








mov eax, [ebx]

Register



Registers

eax

0x273faace

ebx


0x00000004

Operand Types



sub esp, 0x8

Constant
integer



Operand Types



mov cl, BYTE ptr [eax]

Pointer directive

Pointer Directive



```
mov [esi], al ; ok
mov [esi], 1 ; error
```

Error: ambiguous operand size for 'mov'

Because it could be any of the followings

- mov BYTE PTR [esi], 1
- mov WORD PTR [esi], 1
- mov DWORD PTR [esi], 1
- mov QWORD PTR [esi], 1

Therefore, we need pointer directive ©

Moving Data Around (mov)

```
mov eax, ebxmov al, blRegister to Register
• mov [eax], ebx } Register to Memory
• mov eax, [ebx]
• mov eax, [ebx + edx * 4] | Memory to Register
• mov al, BYTE PTR [esi]

mov eax, 42
mov BYTE PTR [eax], 42

Constant to Memory/Register
```


Example: Storing a DWORD in Memory

mov [eax], 0xdeadbeef ; eax = 0x1000


0xdfaa2312 0x1000 0x273faace 0xFF8 0xbffa0220 0xFF0

Example: Storing a DWORD in Memory

```
mov [eax], 0xdeadbeef; eax = 0x1000
```



Example: Storing a DWORD in Memory



Endianness



- The order in which a sequence of bytes are stored in memory
- Big Endian = The MSB goes to the lowest address
- Little Endian = The LSB goes to the lowest address

x86 uses Little Endian

Exercise



Pointer directive

mov cl, BYTE ptr [eax]

0xc 0x4122a13c 8x0 0x273faace 0x4 0xbffa0220 0x0

Registers

eax 0x00000009

ecx 0x13ef0c2e

What value will be after the instruction?

Addressing Modes



Specify how a memory operand is interpreted to derive an effective address

register

```
√mov eax, [eax]
```

• register + register

```
✓mov eax, [eax + ebx]
```

displacement

```
✓mov eax, [0x1000]
```


register + register × scale + displacement

```
✓mov eax, [eax + ebx * 4 + 0x1000]
```

Addressing Modes



Specify how a memory operand is interpreted to derive an effective address



Loading Address (lea)

```
lea eax, [ebx]
lea eax, [ebp-0x8]

Memory address to Register
```

What is the Difference?



```
mov eax, [ebp + 0x10]
vs.
lea eax, [ebp + 0x10]
```

```
eax ← *(ebp + 0x10)
vs.
eax ← (ebp + 0x10)
```


Stack Memory






 Stack stores data in a LIFO (Last-In-First-Out) fashion. When a function is invoked, a new stack frame is allocated at the top of the stack memory


Stack Operations




Virtual memory

Low
















Stack Operations (push)

push eax

Push register on the stack

push 0x42

Push constant on the stack


push [eax]

Push a value at the memory address on the stack


push x

mov [esp], x














Stack Operations (pop)





pop eax

pop [eax]

Pop the top element of the stack into register

Pop the top element of the stack into the memory address

```
pop x mov x, [esp] add esp, 4
```

Stack Operations (leave)





leave mov esp, ebp

pop ebp

Function Call (call)









Function Call (call)











Function Call (call)








Function Return (ret)

*

ret **=** pop eip




Function Return (ret)





eip nextret



Arithmetic and Logical Operations

79

- add eax, [ebx]
- sub esp, 0x40
- •inc ecx
- dec edx
- and [eax + ecx], ebx
- xor edx, ebx
- •shl eax, 1
- •

Control Flows





```
if ( x ) {
   /* A */
}
else {
   /* B */
}
```

```
while (x) {
}
```

```
for (i = 0; i < n; i++) {
}</pre>
```

How to represent in assembly?

Control Flows in Assembly (1)

There are only "if" and "goto" (no "else")


```
How assembly looks like...
                         if (!x) goto F;
if ( x ) {
                        /* A */
  /* A */
                        goto DONE;
else {
                        /* B */
  /* B */
                       DONE:
```



Control Flows in Assembly (2)

There are only "if" and "goto" (no "else")

```
while (x) {
   /* body */
```



```
How assembly looks like...
WHILE:
   if (!x) goto DONE;
   /* body */
   goto WHILE;
DONE:
```

Control Flows in Assembly (3)

There are only "if" and "goto" (no "else")

```
for (i = 0; i < n; i++) {
   /* body */
}</pre>
```



```
How assembly looks like...
i = 0;
LOOP:
if (i >= n) goto DONE;
/* body */
i++;
goto LOOP;
```

DONE:

Control Flows in Assembly (Example)

Test if x is zero

if (!x) goto F;



cmp x, 0

If x=zero then goto F

If i >= n then goto F

Control Flows in Assembly (Example)

Control Flows in Assembly (Example)


Where do we store the result of comparison (cmp)?

EFLAGS: Storing the Processor State



• EFLAGS is a status register used in x86, which is essentially a collection of status flag bits.

- There are approximately 20 different flag bits used in x86, but we are mainly interested in 6 condition flags:
 - OF: Overflow flag
 - -SF: Sign flag
 - ZF: Zero flag
 - AF: Auxiliary carry flag
 - PF: Parity flag
 - CF: Carry flag



cmp Only Affects EFLAGS

89

 cmp is the same as sub, except that it only affects EFLAGS, but not the destination operand. For example, cmp eax, ebx will not change the eax register

Branch Instructions



Assume that a comparison instruction (cmp) precedes the branch instruction

Branch Instruction	Condition	Description
ja	CF = 0 and ZF = 0	Jump if above
jb	CF = 1	Jump if below
je	ZF = 1	Jump if equal
jl	SF ≠ F	Jump if less
jle	$ZF = 1 \text{ or } SF \neq F$	Jump if less or equal
jna	CF = 1 or ZF = 1	Jump if not above
jnb	CF = 0	Jump if not below
jz	ZF = 1	Jump if zero
(many more)		

Summary So Far

- *
- We learned how to move around data
 - mov, lea, push, pop, etc.
- We learned how to perform arithmetic and logical operations
 - add, sub, and, or, etc.
- We also learned how to control program flows
 - cmp, jmp, ja, jz, etc.

Already Turing Complete!

x86 Execution Model

Our Example

```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
int red(int a1) {
    return blue(a1 - 42);
```

Our Example – Stack

```
*
```

```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
                       Start
int red(int a1) {
    return blue(a1 - 42);
```

Higher Memory Address

Frame for function red

esp

Our Example – Stack

```
*
```

```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + purple(a1, b);
int red(int a1)
    return blue(a1 - 42);
```

Higher Memory Address

Frame for function red

Frame for function blue

esp

Our Example – Stack



```
int purple(int a1, int a2) {
    return 2 + a1 - a2;
int blue(int a1) {
    return 1 + púrple(a1, b);
int red(int a1) {
    return blue(a1 - 42);
```

Higher Memory Address

Frame for function red


Frame for function blue

Frame for function purple

esp

Questions






- How do we pass function parameters?
- When a function returns, how do we restore the register values of the caller
- Where do we store local variables?

We can easily get the answer by compiling the example program and disassembling the resulting binary

Disassembled Code (x86)

```
<red>:
                                                   32:
                                                                   DWORD PTR [esp+0x4], eax
                                                         mov
   0:
       push
               ebp
                                                                   eax, DWORD PTR [ebp+0x8]
                                                   36:
                                                         mov
   1:
               ebp,esp
       mov
                                                                   DWORD PTR [esp], eax
                                                   39:
                                                         mov
   3:
       sub
               esp,0x28
                                                   3c:
                                                         call
                                                                   purple
   6:
               DWORD PTR [ebp-0xc],0x0
       mov
                                                   41:
                                                                   edx, DWORD PTR [ebp-0xc]
                                                         mov
   d:
               eax, DWORD PTR [ebp+0x8]
       mov
                                                   44:
                                                         add
                                                                   eax, edx
               eax,0x2a
  10:
       sub
                                                   46:
                                                         leave
  13:
       mov
               DWORD PTR [esp],eax
                                                   47:
                                                        ret
               Blue
  16:
       call
                                                <purple>:
               edx,DWORD PTR [ebp-0xc]
  1b:
       mov
               eax,edx
  1e:
       add
                                                   48:
                                                         push
                                                                   ebp
  20:
       leave
                                                   49:
                                                         mov
                                                                   ebp,esp
  21:
       ret
                                                   4b:
                                                         sub
                                                                   esp,0x10
                                                                   DWORD PTR [ebp -0x4],0x2
                                                   4e:
                                                         mov
<blue>:
                                                   55:
                                                                   eax,DWORD PTR [ebp+0x8]
                                                         mov
  22:
               ebp
       push
                                                                   eax,DWORD PTR [ebp-0x4]
                                                   58:
                                                         mov
  23:
               ebp,esp
       mov
                                                   5b:
                                                         add
                                                                   eax,edx
  25:
       sub
               esp,0x28
                                                   5d:
                                                                   eax,DWORD PTR [ebp+0xc]
                                                         sub
  28:
               DWORD PTR [ebp-0xc],0x1
       mov
                                                   60:
                                                         leave
  2f:
               eax, DWORD PTR [ebp-0xc]
       mov
                                                   61:
                                                         ret
```



Currently executed instruction



• 0xbfff0008

0x100

return address

0xbfff0000

Points to instruction to be executed

eip: 0x1

ebp: 0xbfff0008

esp: 0xbfff0000

Execution context

```
<red>:
    0: push ebp
```

1: mov ebp,esp

3: sub esp,0x28

6: mov DWORD PTR [ebp-0xc],0x0

d: mov eax,DWORD PTR [ebp+0x8]

10: sub eax, 0x2a

13: mov DWORD PTR [esp],eax

16: call blue

1b: mov edx, DWORD PTR [ebp-0xc]

1e: add eax,edx

20: leave

21: ret

<blue>:

22: push ebp

23: mov ebp,esp

• •

46: leave

47: ret

Save the base address of the previous function's stack frame



```
0xbfff0008
   0x100
return address
                0xbffefffc
0xbfff0008
                 eip: 0x1
                 ebp: 0xbfff0008
                 esp: 0xbffefffc
```


Execution context

```
<red>:
      push
             ebp
             ebp, esp
      mov
   3:
      sub
             esp.0x28
             DWORD PTR [ebp-0xc],0x0
   6:
      mov
             eax,DWORD PTR [ebp+0x8]
  d:
      mov
  10:
      sub
             eax, 0x2a
             DWORD PTR [esp],eax
  13:
      mov
  16: call
             blue
  1b:
             edx, DWORD PTR [ebp-0xc]
      mov
  1e: add
             eax,edx
      leave
  20:
 21: ret
<blue>:
 22: push
              ebp
  23:
      mov
              ebp, esp
       leave
 46:
```

47:

ret





Execution context

47:

ret

```
0:
              ebp
       push
              ebp, esp
       mov
   3:
       sub
              esp,0x28
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax, 0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16: call
             blue
              edx,DWORD PTR [ebp-0xc]
  1b:
       mov
  1e: add
              eax,edx
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
              ebp, esp
  23:
       mov
       leave
  46:
```

Now, ebp points to the base of the current stack frame



```
0x100
```

return address

0xbfff0008

0xbfff0008

0xbffefffc

eip: 0x3

ebp: 0xbffefffc

esp: 0xbffefffc

Execution context

```
%red>:
    0: push    ebp
    1: mov    ebp,esp
    3: sub    esp,0x28
    6: mov    DWORD PTR [ebp-0xc],0x0
```

d: mov eax,DWORD PTR [ebp+0x8]

10: sub eax,0x2a

13: mov DWORD PTR [esp],eax

16: call blue

1b: mov edx, DWORD PTR [ebp-0xc]

1e: add eax,edx

20: leave

21: ret

<blue>:

22: push ebp

23: mov ebp,esp

• •

46: leave

47: ret

02

0x100

return address

0xbfff0008

0xbfff0008

0xbffefffc

eip: 0x6

ebp: 0xbffefffc

esp: 0xbffefffc

Execution context

0: push ebp

1: mov ebp,esp

3: sub esp,0x28

6: mov DWORD PTR [ebp-0xc],0x0

d: mov eax,DWORD PTR [ebp+0x8]

10: sub eax,0x2a

13: mov DWORD PTR [esp],eax

16: call blue

1b: mov edx, DWORD PTR [ebp-0xc]

1e: add eax,edx

20: leave

21: ret

<blue>:

22: push ebp

23: mov ebp,esp

• •


46: leave

47: ret

47:


ret

0




```
0:
              ebp
       push
              ebp, esp
       mov
              esp,0x28
   3:
       sub
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax, 0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16:
       call
              blue
              edx,DWORD PTR [ebp-0xc]
  1b:
       mov
       add
              eax,edx
  1e:
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
              ebp, esp
  23:
       mov
       leave
  46:
```















Virtual memory


ret






```
0xbfff0008
   0x100
                    8x0
return address
                 0xbffefffc
0xbfff0008
    0x0
                  eip: 0x10
                  ebp: 0xbffefffc
                  esp: 0xbffeffd4
                  eax: 0x100
                   Execution context
 Virtual memory
```


```
int red(int a1) {
    return blue(a1 - 42);
<red>:
   0:
      push
             ebp
             ebp, esp
      mov
   3:
      sub
             esp.0x28
             DWORD PTR [ebp-0xc],0x0
   6:
      mov
             eax,DWORD PTR [ebp+0x8]
   d:
      mov
  10:
      sub
             eax, 0x2a
             DWORD PTR [esp],eax
  13:
      mov
  16:
      call
             blue
             edx,DWORD PTR [ebp-0xc]
  1b:
      mov
      add
             eax,edx
  1e:
      leave
  20:
  21: ret
<blue>:
  22: push
              ebp
              ebp, esp
  23:
      mov
       leave
  46:
  47:
       ret
```





```
Execution Example
                0xbfff0008
   0x100
return address
                0xbffefffc
0xbfff0008
    0x0
                eip: 0x13
                 ebp: 0xbffefffc
                 esp: 0xbffeffd4
                eax: 0xd6
                  Execution context
 Virtual memory
```

```
int red(int a1) {
    return blue(a1 - 42);
<red>:
   0:
      push
             ebp
             ebp, esp
      mov
   3:
      sub
             esp,0x28
             DWORD PTR [ebp-0xc],0x0
   6:
      mov
             eax,DWORD PTR [ebp+0x8]
   d:
      mov
  10:
      sub
             eax,0x2a
             DWORD PTR [esp],eax
  13:
      mov
  16: call
             blue
             edx,DWORD PTR [ebp-0xc]
  1b:
      mov
      add
             eax,edx
  1e:
      leave
  20:
  21: ret
<blue>:
  22: push
              ebp
              ebp, esp
  23:
      mov
       leave
  46:
  47:
       ret
```











```
0xbfff0008
    0x100
 return address
                   0xbffefffc
  0xbfff0008
     0x0
                   eip: 0x23
     0xd6
                   ebp: 0xbffefffc
Return address (0x1b)
                   esp: 0xbffeffd0
                   eax: 0xd6
                    Execution context
```

```
0:
              ebp
       push
              ebp, esp
       mov
   3:
       sub
              esp.0x28
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax, 0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16: call
             blue
              edx,DWORD PTR [ebp-0xc]
  1b:
       mov
      add
              eax,edx
  1e:
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
  23:
       mov
              ebp, esp
```

leave

ret

46:

47:

0xbfff0008 0x100 return address 0xbffefffc 0xbfff0008 0x0 eip: 0x23 0xd6 ebp: 0xbffefffc Return address (0x1b) esp: 0xbffeffcc 0xbffefffc eax: 0xd6

Execution context

0: ebp push ebp, esp mov 3: sub esp,0x28DWORD PTR [ebp-0xc],0x0 6: mov eax,DWORD PTR [ebp+0x8] d: mov 10: sub eax, 0x2a DWORD PTR [esp],eax 13: mov 16: call blue edx,DWORD PTR [ebp-0xc] 1b: mov add eax,edx 1e: 20: leave 21: ret <blue>: 22: push ebp 23: mov ebp, esp

leave

ret

46:

47:

Execution Example

0xbfff0008 0x100 return address 0xbffefffc 0xbfff0008 0x0 eip: 0x25 0xd6 ebp: 0xbffefffc Return address (0x1b) esp: 0xbffeffcc 0xbffefffc eax: 0xd6

Execution context

47:

ret

0: ebp push ebp, esp mov 3: sub esp,0x28DWORD PTR [ebp-0xc],0x0 6: mov eax,DWORD PTR [ebp+0x8] d: mov 10: sub eax, 0x2a DWORD PTR [esp],eax 13: mov 16: call blue edx,DWORD PTR [ebp-0xc] 1b: mov add eax,edx 1e: 20: leave 21: ret <blue>: 22: push ebp ebp, esp 23: mov leave 46:

Execution Example

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbfff0008

0xbffefffc

eip: 0x25

ebp: 0xbffeffcc

esp: 0xbffeffcc

eax: 0xd6

Execution context

0: push ebp

1: mov ebp,esp

3: sub esp,0x28

6: mov DWORD PTR [ebp-0xc],0x0

d: mov eax,DWORD PTR [ebp+0x8]

10: sub eax,0x2a

13: mov DWORD PTR [esp],eax

16: call blue

1b: mov edx, DWORD PTR [ebp-0xc]

1e: add eax,edx

20: leave

21: ret

<blue>:

22: push ebp

23: mov ebp,esp

• •

46: leave

47: ret

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbfff0008

0xbffefffc

eip: 0x46

ebp: 0xbffeffcc

esp: 0xbffeffac

Execution context

0: ebp push

ebp, esp mov

3: sub esp,0x28

DWORD PTR [ebp-0xc],0x0 6: mov

eax,DWORD PTR [ebp+0x8] d: mov

10: sub eax, 0x2a

DWORD PTR [esp],eax 13: mov

16: call blue

edx,DWORD PTR [ebp-0xc] 1b: mov

1e: add eax,edx

20: leave

21: ret

<blue>:

22: push ebp

23: mov ebp, esp Skip!

leave

46: 47: ret



mov esp, ebp

pop ebp

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbfff0008

0xbffefffc

eip: 0x47

ebp: 0xbffeffcc

esp: 0xbffeffac

Execution context

0: push ebp

1: mov ebp,esp

3: sub esp,0x28

6: mov DWORD PTR [ebp-0xc],0x0

d: mov eax,DWORD PTR [ebp+0x8]

10: sub eax,0x2a

13: mov DWORD PTR [esp],eax

16: call blue

1b: mov edx, DWORD PTR [ebp-0xc]

1e: add eax,edx

20: leave

21: ret

<blue>:

22: push ebp

23: mov

ebp

46: leave

47: ret



pop ebp

0x100

return address

0xbfff0008

0x0

0xd6

Return address (0x1b)

0xbffefffc

0xbfff0008

0xbffefffc

eip: 0x47

ebp: 0xbffeffcc

esp: 0xbffeffcc

Execution context

0: ebp push ebp, esp mov

3: sub esp,0x28

DWORD PTR [ebp-0xc],0x0 6: mov

eax,DWORD PTR [ebp+0x8] d: mov

10: sub eax, 0x2a

DWORD PTR [esp],eax 13: mov

16: call blue

1b: edx, DWORD PTR [ebp-0xc] mov

eax,edx add 1e:

20: leave


21: ret

<blue>:


46: leave

47: ret

22: push ebp 23: ebp mov



Execution Example




```
0:
              ebp
       push
              ebp, esp
       mov
   3:
       sub
              esp,0x28
              DWORD PTR [ebp-0xc],0x0
   6:
       mov
              eax,DWORD PTR [ebp+0x8]
   d:
       mov
  10:
       sub
              eax, 0x2a
              DWORD PTR [esp],eax
  13:
       mov
  16: call
             blue
              edx,DWORD PTR [ebp-0xc]
  1b:
       mov
       add
              eax,edx
  1e:
  20:
       leave
  21: ret
<blue>:
  22: push
              ebp
              ebp, esp
  23:
       mov
                        pop eip
  46:
       leave
```

47:

ret





Calling Convention

47:

ret

```
2
```

```
<blue>:
                                         int blue(int a1) {
  22:
       push
              ebp
                                              return 1 + purple(a1, b);
  23:
              ebp,esp
       mov
       sub
              esp,0x28
  25:
              DWORD PTR [ebp\0xc],0x1
  28:
       mov
  2f:
              eax, DWORD PTR [ebp-0xc]
       mov
              DWORD PTR [esp+0x4], eax
  32:
       mov
  36:
              eax, DWORD PTR [ebp+0x8]
       mov
              DWORD PTR [esp] eax
                                                          Value in b
  39:
       mov
       call
              purple
  3c:
                                                         Value in a1
                                            a1
                                                                           esp
              edx, DWORD PTR [ebp-0xc]
  41:
       mov
  44:
       add
              eax, edx
                                                         Virtual memory
  46:
       leave
```

Passing parameter values in a reverse order

Calling Convention

```
<blue>:
                                         int blue(int a1) {
       push
  22:
              ebp
                                              return 1 + purple(a1, b);
  23:
              ebp, esp
       mov
  25:
              esp,0x28
       sub
              DWORD PTR [ebp\0xc],0x1
  28:
       mov
  2f:
              eax, DWORD PTR [ebp-0xc]
       mov
              DWORD PTR [esp+0x4], eax
  32:
       mov
  36:
              eax, DWORD PTR [ebp+0x8]
       mov
              DWORD PTR [esp] eax
  39:
       mov
  3c:
       call
               purple
              edx, DWORD PTR [ebp-0xc]
  41:
       mov
              eax, edx
  44:
       add
  46:
       leave
                               Storing a return value in
  47:
       ret
                                        eax
```

Key Concepts

29

- Compilation pipeline
- x86 architecture
- Assembly
- Disassembly

Question?