

Function Call Convention

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch

Content



Intel Architecture

Memory Layout

C Arrays

Assembler

Shellcode

Function Calls

Debugging

Buffer Overflow

BoF Exploit

Remote Exploit

Exploit Mitigations

Defeat Exploit Mitigations

Function Call Convention



Function call convention:


- → How functions work
- → Program-metadata on the stack

Stack based buffer overflow:

→ Overwrite program-metadata on the stack

x32 Memory Layout










How do they work?







0x10000

0x00010

/ push

pop



push 0x1
push 0x2
push 0x3
pop
push 0x4



push 0x1

push 0x2

push 0x3

pop

push 0x4

0x01



push 0x1

push 0x2

push 0x3

pop

push 0x4

0x01

0x02



push 0x1

push 0x2

push 0x3

pop push 0x4

0 x 03	
0x02	
0x01	



push 0x1

push 0x2

push 0x3

pop

push 0x4

1	
0x01	
0x02	



push 0x1

push 0x2

push 0x3

pop

push 0x4

0x04
0x02
0x01
1


Stack on intel

COMPASS SECURITY

Intel stack registers:

- ★ ESP: Stack Pointer
- → EBP: (Stack-) Base Pointer

EBP = 0x1000ESP = 0x0FF8



Stack in computers



Stack is using process memory as basis

CPU instruction support (because stack is so useful)

Note:

- ★ CPU instructions like push/pop are just for ease of use
- The "stack values" can be accessed (read, write) like every other memory address
- → You can point the stack (ebp, esp) to wherever in the memory you want
- There's usually just ONE stack per process (thread)





Functions and the Stack

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch



What is a function?

- **→** Self contained subroutine
- ★ Re-usable
- → Can be called from anywhere
- ★ After function is finished: Jump to the calling function (calee)



```
void main(void) {
 int blubb = 0;
 foobar (blubb) ;
 return;
void foobar (int arg1) {
 char compass1[];
 char compass2[];
```



What does the function foobar() need?

- **→** Function Argument:
 - **→** blubb
- **★** Local variables
 - **+**Compass1
 - **+**Compass2
- → And: Address of next instruction in main()
 - **★**&return



Saved IP (&__libc_start)
Saved Frame Pointer
Local Variables <main>

SIP SFP blubb

Stack Frame <main>

Argument for <foobar>
Saved IP (&return)

Saved Frame Pointer

Local Variables <foobar>

&blubb SIP

SFP

compass1

compass2

Stack Frame <foobar>

push pop



```
void main(void) {
                      Pointer
 int blubb = 0; <---
 foobar(&blubb);
                               &blubb
 return; <
                               SIP
                Pointer
                               SFP
                               compass1
void foobar(int *arg1)
                               compass2
 char compass1[];
 char compass2[];
                    allocate
```



Saved IP (&__libc_start)
Saved Frame Pointer
Local Variables <main>

SIP
SFP
blubb

Stack Frame <main>

Stack Frame

<foobar>

Argument for <foobar>

Saved IP (&return)

Saved Frame Pointer

Local Variables <foobar>

SIP (&return)

SFP

&blubb

compass1

compass2

ass2

push / por

© Compass Security Schweiz AG

www.csnc.ch



SIP: Stored Instruction Pointer

- ◆ Copy of EIP
- → Points to the address where control flow continues after end of function
 - ★(return, ret)
- → Usually points into the code section

Slide 23



Attention! Assembler ahead!

→ AT&T vs Intel syntax

Intel syntax:

mov eax, 1

mov ebx, 0ffh

int 80h

AT&T syntax:

movl \$1,%eax

movl \$0xff, %ebx

int \$0x80

Don't hang me if I messed this up somewhere



In ASM:

call 0x11223344 <&foobar>



<function code> (0x11223344)

ret
pop eip



In ASM:

call 0x11223344 <&foobar>



mov ebp, esp
<function code>
mov esp, ebp
ret





In ASM:

call 0x11223344 <&foobar>

push EIP+4

jmp 0x11223344

mov ebp, esp

<function code>

mov esp, ebp

ret


pop eip


Prolog

Function

Epilog









Recap:

- User data is on the stack
- Also: important stuff is on the stack (Instruction Pointer, SIP)

www.csnc.ch

Stack grows down 🔱



→ Writes go up



Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch



```
int add(int x, int y) {
  int sum;
  sum = x + y;
  return sum;
}
```



$$c = add(3, 4)$$

C

ASM

ASM, detailed



add():

push 4
push 3
push EIP
jmp add

push ebp mov ebp, esp, sub esp, 0x10

mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp - 0x04], eax
mov eax, DWORD PTR [ebp - 0x04]

leave

ret



add():

```
push 4
push 3
push EIP
jmp add
```

```
push ebp
mov ebp, esp,
sub esp, 0x10
mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp - 0x04], eax
mov eax, DWORD PTR [ebp – 0x04]
mov esp, ebp
              ; leave
pop ebp
               ; leave
ret
```



add():

```
push 4
push 3
push EIP
jmp add
```

```
push ebp
mov ebp, esp,
sub esp, 0x10
mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp - 0x04], eax
mov eax, DWORD PTR [ebp – 0x04]
mov esp, ebp
               ; leave
pop ebp
               ; leave
pop eip
               ; ret
```



add():

push 4
push 3
push EIP
jmp add

push ebp mov ebp, esp, sub esp, 0x10

mov esp, ebp ; leave

pop ebp ; leave

pop eip ; ret







Function Prolog


Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch













www.csnc.ch







push 4
push 3
call add
...




push ebp ←
mov ebp, esp,
sub esp, 0x10

mov esp, ebp
pop ebp
pop eip

www.csnc.ch

Slide 41





push ebp ←
mov ebp, esp,
sub esp, 0x10

mov esp, ebp
pop ebp

pop eip


www.csnc.ch

Slide 42




mov ebp, esp, sub esp, 0x10


mov esp, ebp
pop ebp
pop eip



From: <add>









From: <add>

From:

<main>







From: <main>

From: <add>



push ebp


mov ebp, esp,

sub esp, 0x10

mov esp, ebp

pop ebp

pop eip







Execute Function

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch

x32 Call Convention - Execute Function



EBP

mov eax, DWORD PTR [ebp + 0xc]
mov edx, DWORD PTR [ebp + 0x8]
add eax, edx
mov DWORD PTR [ebp - 0x04], eax
mov eax, DWORD PTR [ebp - 0x04]

SIP SFP EBP+0xc EBP+0x8 SIP **SBP EBP-0x04** sum

From: <main>

From: <add>





Function Epilog

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch



push ebp


mov ebp, esp,

sub esp, 0x10

mov esp, ebp

pop ebp

pop eip







push ebp
mov ebp, esp,
sub esp, 0x10
mov esp, ebp

pop ebp


pop eip
















x32 Call Convention - Function Calling



```
call <addr> =
 push EIP+1
  jmp <addr>
leave =
 mov esp, ebp
 pop ebp
ret =
 pop eip
```

x32 Call Convention - Function Calling



Why "leave"?

→ Opposite of "enter"

"enter":

```
push ebp
mov ebp, esp
sub esp, imm
```

Why no "enter" used?

- enter:
 - ★ 8 cycle latency
 - **→** 10-20 micro ops
- call <addr>; mov ebp, esp; sub esp, imm:
 - → 3 cycles latency
 - → 4-6 micro ops

x32 Call Convention - Function Calling



Recap:

- When a function is called:
 - ★ EIP is pushed on the stack (=SIP)
 - → ("call" is doing implicit "push EIP")
- At the end of the function:
 - → SIP is recovered into EIP
 - ★ ("ret" is doing implicit "pop EIP")






Accessing the Stack

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch

Accessing the stack: triple view





- A) push 0x1
- B) mov [ebp-0x10], 0x1
- C) mov eax, 0x1000 mov [eax], 0x1





Function Calls in x64

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch

x32 Call Convention - Function Call in x64



Differences between x32 and x64 function calls:

Arguments are in registers (not on stack)

RDI, RSI, RDX, R8, R9



Differences between x32 and x64 function calls

Different ASM commands doing the same thing

```
callq (call)
leaveq (leave)
retq (ret)
```

x32 Call Convention - Function Call in x64



Some random x64 architecture facts:

The stack should stay 8-byte aligned at all times

An n-byte item should start at an address divisible by n

→ E.g. 64 bit number: 8 bytes, can be at 0x00, 0x08, 0x10, 0x18, ...

%rsp points to the lowest occupied stack location

not the next one to use!

Function Call Convention Cheat Sheet



x32	Parameter	Syscall nr in
x32 userspace	stack	
x32 syscalls	ebx, ecx, edx, esi, edi, ebp	eax

x64	Parameter	Syscall nr in
x64 userspace	rdi, rsi, rdx, rcx, r8, r9	
x64 syscall	rdi, rsi, rdx, r10, r8, r9	rax

http://stackoverflow.com/questions/2535989/what-are-the-calling-conventions-for-unix-linux-system-calls-on-x86-64





Outro

Compass Security Schweiz AG Werkstrasse 20 Postfach 2038 CH-8645 Jona Tel +41 55 214 41 60 Fax +41 55 214 41 61 team@csnc.ch www.csnc.ch

Further questions



Can you implement push/pop in ASM? (without actually using push/pop)

Answers



Pseudocode:

```
# EAX is the new ESP
push:
    sub eax, 4
    mov (%eax), <data>

pop:
    add eax, 4
```