#### CS 305 Computer Networks

## Chapter 3 Transport Layer (3)

Jin Zhang

Department of Computer Science and Engineering

Southern University of Science and Technology

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP flow control

application may remove data from TCP socket buffers ....

... slower than TCP receiver is delivering (sender is sending)

## process application OS TCP socket receiver buffers TCP<sup>2</sup> code IP code from sender


application

#### flow control

receiver controls sender, so sender won't overflow receiver's buffer by transmitting too much, too fast

## TCP flow control

- receiver "advertises" free buffer space by including rwnd value in TCP header of receiver-to-sender segments
  - RcvBuffer size set via socket options (typical default is 4096 bytes)
  - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow



receiver-side buffering

## Chapter 3 outline


- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters



```
Socket clientSocket =
  newSocket("hostname","port
  number");
```

```
application


connection state: ESTAB
connection Variables:
  seq # client-to-server
      server-to-client
  rcvBuffer size
  at server, client

network
```

```
Socket connectionSocket =
  welcomeSocket.accept();
```

## Two general's problem

- AI and A2 need to attack B simultaneously
- AI and A2 should agree on the attack time first
- Communication between AI and A2 may be captured by B
- How can they agree on the attack plan?




Two general's problem (From wiki)

- \* The result is: no matter how many rounds of confirmation are made, no may to guarantee they agreed on the plan.
- How about AI and A2 are the radio transceiver?
  - 3-way handshaking is enough


### Agreeing to establish a connection

#### 3-way handshake:




- TI: B knows A's transmitter and B's receiver is OK
- T2: A knows A's transceiver and B's transceiver is OK, B has no more information than TI
- T3: Both A and B know their transceiver are OK, they can start the communication!

## TCP 3-way handshake



## TCP: closing a connection



## TCP: closing a connection

- Four-way handshaking
- client, server each close their side of connection
  - send TCP segment with FIN bit = I
- respond to received FIN with ACK
  - on receiving FIN, ACK can be combined with own FIN
- Why FIN and ACK can not be sent in one msg as SYNACK in connection establishment?
  - The other side may still have packets need to be sent. It can not send FIN until the transmission is finished.

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer

- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## Principles of congestion control

#### congestion:


- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
  - lost packets (buffer overflow at routers)
  - long delays (queueing in router buffers)
- a top-10 problem!


two senders, two receivers

one router, infinite buffers


output link capacity: R

no retransmission






maximum per-connection throughput: R/2




 large delays as arrival rate, λ<sub>in</sub>, approaches capacity


- one router, finite buffers
- sender retransmission of timed-out packet
  - application-layer input = application-layer output:  $\lambda_{\text{in}}$  =  $\lambda_{\text{out}}$
  - transport-layer input includes retransmissions :  $\lambda'_{in} \ge \lambda_{in}$



## idealization: perfect knowledge

 sender sends only when router buffers available






#### Idealization: known loss


packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost



# Idealization: known loss packets can be lost, dropped at router due to full buffers


sender only resends if packet known to be lost






#### Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





#### Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




#### "costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
  - decreasing goodput


- four senders
- multihop paths
- timeout/retransmit

Q: what happens as  $\lambda_{in}$  and  $\lambda_{in}$  increase?

A: as red  $\lambda_{in}$  increases, all arriving blue pkts at upper queue are dropped, blue throughput  $\rightarrow 0$ 







#### another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

## Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
  - segment structure
  - reliable data transfer
  - flow control
  - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

## TCP congestion control: additive increase multiplicative decrease


- \* approach: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
  - additive increase: increase cwnd by I MSS every RTT until loss detected
  - multiplicative decrease: cut cwnd in half after loss

AIMD saw tooth behavior: probing for bandwidth

cwnd: TCP sender



## TCP Congestion Control: details



sender limits transmission:


 cwnd is dynamic, function of perceived network congestion

#### TCP sending rate:

roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes

## TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
  - initially cwnd = I MSS
  - double cwnd every RTT
  - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast




## TCP: detecting, reacting to loss

- loss indicated by timeout:
  - cwnd set to I MSS;
  - window then grows exponentially (as in slow start) to threshold, then grows linearly
- loss indicated by 3 duplicate ACKs: TCP RENO
  - dup ACKs indicate network capable of delivering some segments
  - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to I (timeout or 3 duplicate acks)

## TCP: switching from slow start to CA

Q: when should the exponential increase switch to linear?


A: when **cwnd** gets to 1/2 of its value before timeout.



#### **Implementation:**

- \* variable ssthresh
- on loss event, ssthresh is set to 1/2 of cwnd just before loss event


## Summary: TCP Congestion Control



## TCP throughput

- avg. TCP thruput as function of window size, RTT?
  - ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
  - avg. window size (# in-flight bytes) is <sup>3</sup>/<sub>4</sub> W
  - avg. thruput is 3/4W per RTT

avg TCP thruput = 
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec



## TCP Futures: TCP over "long, fat pipes"


- example: I500 byte segments, I00ms RTT, want
   I0 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

TCP throughput = 
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

- ⇒ to achieve 10 Gbps throughput, need a loss rate of L =  $2 \cdot 10^{-10}$  a very small loss rate!
- new versions of TCP for high-speed

## **TCP Fairness**


fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



## Why is TCP fair?

#### two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally



## Fairness (more)

#### Fairness and UDP

- multimedia apps often do not use TCP
  - do not want rate throttled by congestion control
- instead use UDP:
  - send audio/video at constant rate, tolerate packet loss


## Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
  - new app asks for I TCP, gets rate R/10
  - new app asks for 11 TCPs, gets R/2

## Explicit Congestion Notification (ECN)

#### network-assisted congestion control:

- two bits in IP header (ToS field) marked by network router to indicate congestion
- congestion indication carried to receiving host
- receiver (seeing congestion indication in IP datagram) )
   sets ECE bit on receiver-to-sender ACK segment to
   notify sender of congestion



## Chapter 3: summary

- principles behind transport layer services:
  - multiplexing, demultiplexing
  - reliable data transfer
  - flow control
  - congestion control
- instantiation, implementation in the Internet
  - UDP
  - TCP

- Many more transport layer protocols:
  - DCCP
  - QUIC
  - DCTCP...
  - Better vs. good enough

#### next:

- leaving the network "edge" (application, transport layers)
- into the network "core"
  Transport Layer 3-36

#### Midterm

- Nov. 8, 2pm-4pm, liyuan building 1, 101, 102, 201 Closed-book
- Content covered: Chapter 1- Chapter 3
- Q and A session: Nov. 7, 2-4pm, Teaching Building 1, 505