ChatScript Command Line Parameters

Copyright Bruce Wilcox, gowilcox@gmail.com www.brilligunderstanding.com Revision $11/21/2021~{\rm cs}11.6$

Command Line Parameters

You can give parameters on the run command or in a config file or via a http request. The default config file is <code>cs_init.txt</code> at the top level of CS (if the file exists). A second file if present can add or override values - <code>cs_initmore.txt</code> And then third level named after the current language chosen can override those two <code>cs_initenglish.txt</code> being the default. The language one, in particular is useful to rebalance memory sizings (dictionary entries in particular) since foreign languages require more entries than English.

Or you can name where the file is on a command line parameter config=xxx. And config2=xxx for the initmore file. If you have secret information that you don't want stored in a config file or exposed on a command line then you can request the config data from a URL. Use the command line parameter configurl=http://xxx to specify the address of the data. Additional command line parameters, configheader=xxx, can be included to define HTTP request headers. If there are several headers then use separate configheader=xxx configheader=yyy etc parameters for each header name/value pair.

Config file data are command line parameters, 1 per line, like below:

noboot port=20

Some parameters require a value and use the = format with no spaces. Other parameters may only require you name the parameter (they have no choices of values).

Actual command line parameters have priority over config file values, and those have priority over http requested values.

Memory options

Chatscript statically allocates its memory and so (barring unusual circumstance) will not allocate memory ever during its interactions with users. These parameters can control those allocations. Done typically in a memory poor environment like a cellphone.

option	description
buffer=50	how many buffers to allocate for general use (80 is default)

option	description
buffer=15x80	allocate 15 buffers of 80k bytes each (default buffer size is 80k)

fullinputlimith450000put buffer (default buffer size is 80k)

Most chat doesn't require huge output and buffers around 20k each will be more than enough. 20 buffers is often enough too (depends on recursive issues in your scripts).

If the system runs out of buffers, it will perform emergency allocations to try to get more, but in limited memory environments (like phones) it might fail. You are not allowed to allocate less than a 20K buffer size.

option	description
dict=n	limit dictionary to this size entries
text=n	limit string space to this many bytes
fact=n	limit fact pool to this number of facts
hash=n	use this hash size for finding dictionary words (bigger $=$ faster
cache=50x1	access) allocate a 50K buffer for handling 1 user file at a time. A server might want to cache multiple users at a time.

A default version of ChatScript will allocate much more than it needs, because it doesn't know what you might need.

If you want to use the least amount of memory (multiple servers on a machine or running on a mobile device), you should look at the USED line on startup and add small amounts to the entries (unless your application does unusual things with facts).

If you want to know how much, try doing :show stats and then :source REGRESS/bigregress.txt. This will run your bot against a wide range of input and the stats at the end will include the maximum values needed during a volley. To be paranoid, add beyond those values. Take your max dict value and double it. Same with max fact. Add 10000 to max text.

Just for reference, for our most advanced bot, the actual max values used were: max dict: 346 max fact: 689 max text: 38052.

And the maximum rules executed to find an answer to an input sentence was 8426 (not that you control or care). Typical rules executed for an input sentence was 500-2000 rules. For example, add 1000 to the dict and fact used amounts and 10 (kb) to the string space to have enough normal working room.

Output options

option	description
output=nnn	limits output line length for a bot to that amount (forcing
	crnl as needed). 0 is unlimited.
outputsize=80000s the maximum output that can be shipped by a volley	
from the bot without getting truncated.	

Actually the outputsize value is somewhat less, because routines generating partial data for later incorporation into the output also use the buffer and need some usually small amount of clearance. You can find out how close you have approached the max in a session by typing :memstats. If you need to ship a lot of data around, you can raise this into the megabyte range and expect CS will continue to function. 80K is the default. For normal operation, when you change outputsize you should also change logsize to be at least as much, so that the system can do complete logs. You are welcome to set log size lots smaller if you don't care about the log.

File options

option	description
livedata=xxx	name relative or absolute path to your own private
	LIVEDATA folder. Do not add trailing / on this
	pathRecommended is you use
	RAWDATA/yourbotfolder/LIVEDATA to keep all your data in
	one place. You can have your own live data, yet use
	ChatScripts default LIVEDATA/SYSTEM and
	LIVEDATA/ENGLISH by providing paths to the system= and
	english= parameters as well as the livedata= parameter
topic=xxx	name relative or absolute path to your own private TOPIC
	folder. Do not add trailing / on this path /
buildfiles=xxxame relative or absolute path to your own folder where	
	filesxxx.txt is found. Do not add trailing / on this path /
users=xxx	name relative or absolute path to where you want the USERS
	folder to be. Do not add trailing /
logs=xxx	name relative or absolute path to where you want the LOGS
	folder to be. Do not add trailing /
userlog	Store a user-bot log in USERS directory (default)
userlog=1	alternate form of request, you can use 0 for off and 1 for on
	(file). 2 means stdout 4 means stderr - you may combine
userlogging=	fpilienary form of request, you can use none for off and file,
nougonlog	stdout, stderr you may combine userlogging=file,stdout
nouserlog	Don't store a user-bot log
serverlog	Store a server log in LOGS directory (default)

option	description
serverlog=1	alternate form of request, you can use 0 for off and 1 for on (file). 2 means stdout 4 means stderr - you may combine
serverloggin	gentialery form of request, you can use none for off and file, stdout, stderr you may combine serverlogging=file,stdout
noserverlog	Don't store a server log
noretrybacku	pDon't save volley backup files for :retry when in standalone mode
tmp=xxx	name relative or absolute path to where you want the TMP folder to be. Do not add trailing /
crashpath=xx	xfile to write about fatal Linux signals that will be outside of the cs folder /
windowsbuglo	gradues a WINDOWS directory to replicate the BUGS.txt log file outside of the CS directory area
linuxsbuglog	= xxxxes a LINUX directory to replicate the BUGS.txt log file outside of the CS directory area
Vcs_new_user=iftieptit has given text within it, treat user as new and dont	
	read the topic file
deployloggin	gdella yn5 ble server logging for 5 minutes after a deploy before using default logging value

Execution options

option	description
source=xxxx login=xxxx	Analogous to the :source command. The file is executed The same as you would name when asked for a login, this avoids having to ask for it. Can be login=george or login=george:harry or whatever
build0=filenar	meuns: build on the filename as level0 and exits with 0 on
	success or 4 on failure
build1=filenar	meuns: build on the filename as level1 and exits with 0 on
	success or 4 on failure. Eg. ChatScript build0=files0.txt will rebuild the usual level 0
debug=:xxx	xxx runs the given debug command and then exits. Useful for :trim, for example or more specific :build commands
param=xxxxx	data to be passed to your private code
bootcmd=xxx	(see Advanced Layers manual)
trace	turn on all tracing.
redo	see documentation for :redo in ChatScript Debugging
	Manual manual
noboot	Do not run any boot script on engine startup
logsize=n	When server log file exceeds n megabytes, rename it and start with a new file.

option	description
defaultbot=nar	neverrides defaultbot table for what bot to default to
inputlimit=n	truncate user input line to this size
trustpos	obey word~n and other pos restrictions in keywords
autoreload	in event of cs engine crash, output a dummy message and reload on next input (see \$cs_crashmsg and \$cs_crash)
nofastload	If you suspect fast loading is faulty, you can set this to see if things work without it
syslogstr=xxx	In linux will output this as part of Microsoft sql trace data to the syslog
buildflags=xxx	this data will be used to control :build (quiet and
	nomixedcase are xxx values)
autorestartde	Lany € went of cs engine internal restart, delay n milliseconds
	before accepts users
crnl_safe	tells system it does not need to search for cr or nl to remove
	from inputs.
blockapitrace	disables any %trace_on in ^testpattern and ^testoutput.
	Used for production servers.
traceboot	turns on tracing while cs_boot is running at startup
parselimit=n	if input is larger than n characters, disable intense
	spellchecking, pos-tagging, and parsing for speed
nl_save=1	for ^testpattern, enables results of nl analysis to be saved
	onto the \$cs_nlinfo variable so that outside can pass it back
	in on future calls
parselimit=1	inputs longer than this will get no pos-tagging, parsing, or
	spellchecking - speeds up

Trustpos is normally off by default because CS is only about 94% accurate in its built-in pos-tagging. So it prefers to wrongly match by allowing all pos values Of a word rather than miss a match. Ergo concept: $_{\rm all(feel}n)$ will match any use of "feel" rather than just noun meaning. But combining CS with Treetagger for english (if you license it) is better at pos-tagging than either alone, making it competitive with the best taggers in the world.

Here few command line parameters usage examples of usual edit/compile development phase, running ChatScript from a Linux terminal console (standalone mode):

Rebuild *level0* (compiling system ChatScript files, listed usually in file files0.txt):

BINARIES/LinuxChatScript64 local build0=files0.txt

Rebuild level1, compiling bot Mybot (files listed in file filesMybot.txt), showing build report on screen (stdout):

BINARIES/LinuxChatScript64 local build1=filesMybot.txt

Rebuild and run: If building phase is without building errors, you can run the just built Mybot in local mode (interactive console) with user name Amy:

BINARIES/LinuxChatScript64 local login=Amy

Build bot Mybot and run ChatScript with user Amy:

BINARIES/LinuxChatScript64 local build1=filesMybot.txt && BINARIES/LinuxChatScript64 local

Bot variables (aka Server variables)

You can create predefined bot variables by simply naming permanent variables on the command line, using V to replace \$ (since Linux shell scripts don't like \$). Eg.

ChatScript Vmyvar=fatcat

ChatScript Vmyvar="tony is here"

ChatScript "Vmyvar=tony is here"

Quoted strings will be stored without the quotes. Bot variables are always reset to their original value at each volley, even if you overwrite them during a volley. This can be used to provide server-host specific values into a script. Nor will they be saved in The user's topic file across volleys. This also applies to variables defined during any CS BOOT

No such bot-specific - nosuchbotrestart=true

If the system does not recognize the bot name requested, it can automatically restart a server (on the presumption that something got damaged). If you don't expect no such bot to happen, you can enable this restart using nosuchbotrestart=true. Default is false.

Time options

option	description	
Timer=15000	if a volley lasts more than 15 seconds, abort it and return a	
	timeout message.	
Timer=18000x10same as above, but more roughly, higher number after the x		
	reduces how frequently it samples time, reducing the cost of	
	sampling	
Timelog=5000	if a volley lasts more than 5000 milliseconds, record it in	
	${\rm LOGS/time.txt}$ and for LINUX in /log/cstime.txt .	

:TranslateConcept Google API Key

option	description
apikey=xxxxxx	is how you provide a google translate api key to :translateconcept

Security

Typically security parameters only are used in a server configuration.

option	description
sandbox	If the engine is not allowed to alter the server machine other than through the standard ChatScript directories, you can start it with the parameter sandbox which disables Export and System calls.
nodebug	Users may not issue debug commands (regardless of authorizations). Scripts can still do so.
authorize=""	bunch of authorizations "". The contents of the string are just like the contents of the authorizations file for the server. Each entry separated from the other by a space. This list is checked first. If it fails to authorize AND there is a file, then the file will be checked also. Otherwise authorization is denied.
encrypt=xxxxx	decrypt user data. User data is of two forms, topic data and LTM data. LTM data is intended to be more personalized for a user, so if encrypt is set, LTM will be encrypted. User topic data is often just execution state of the user and potentially big, so by default it is not encrypted. You can request encryption using userencrypt as a command line parameter to encrypt the topic file and ltmdecrypt to encrypt the ltm file.

The JSON data sent to the URL given by the parameters looks like this:

{"datavalues": {"x": "..."}}

where \dots is the text to encrypt or decrypt. Data from CS will be filled into the \dots and are JSON compatible.

Server Parameters

Either Mac/LINUX or Windows versions accept the following command line args:

option	description
port=xxx	This tells the system to be a server and to use the given numeric port. You must do this to tell Windows to run as a server. The standard port is 1024 but you can use any port.
local	The opposite of the port command, this says run the program as a stand-alone system, not as a server.
interface=127.0	.0By default the value is 0.0.0.0 and the system directly uses a port that may be open to the internet. You can set the interface to a different value and it will set the local port of the TCP connection to what you designate. 127 is the classic TCP port.

User Data

Scripts can direct the system to store individualized data for a user in the user's topic file in USERS. It can store user variables (\$xxx) or facts. Since variables hold only a single piece of information a script already controls how many of those there are. But facts can be arbitrarily created by a script and there is no natural limit. As these all take up room in the user's file, affecting how long it takes to process a volley (due to the time it takes to load and write back a topic file), you may want to limit how many facts each user can have written. This is unrelated to universal facts the system has at its permanent disposal as part of the base system.

userfacts=n limits a user file to saving only the n most recently created facts of a user (this does not include facts stored in fact sets). Overridden if the user has \$cs_userfactlimit set to some value

User Caching

Each user is tracked via their topic file in USERS. The system must load it and write it back for each volley and in some cases will become I/O bound as a result (particularly if the filesystem is not local).

You can direct the system to keep a cache in memory of recent users, to reduce the I/O volume. It will still write out data periodically, but not every volley. Of

course if you do this and the server crashes, writebacks may not have happened and some system rememberance of user interaction will be lost.

Of course if the system crashes, user's may not think it unusually that the chatbot forgot some of what happened. By default, the system automatically writes to disk every volley, If you use a different value, a user file will never be more out of date than that.

cache=20 cache=20x1

This specifies how many users can be cached in memory and how big the cache block in kb should be for a user. The default block size is 50 (50,000 bytes). User files typically are under 20,000 bytes.

If a file is too big for the block, it will just have to write directly to and from the filesystem. The default cache count is 1, telling how many users to cache at once, but you can explicitly set how many users get cached with the number after the "x". If the second number is 0, then no caching is done and users have no data saved. They remember nothing from volley to volley.

Do not use caching with fork. The forks will be hiding user data from each other.

save=n

This specifies how many volleys should elapse before a cached user is saved to disk. Default is 1. A value of 0 not only causes a user's data to be written out every volley, but also causes the user record to be dropped from the cache, so it is read back in every time it is needed (handy when running multi-core copies of chatscript off the same port).

Note, if you change the default to a number higher than 1, you should always use :quit to end a server. Merely killing the process may result in loss of the most recent user activity.

Logging or Not

In stand-alone mode the system logs what a user says with a bot in the USERS folder. It can also do this in server mode. It can also log what the server itself does. But logging slows down the system. Particularly if you have an intervening server running and it is logging things, you may have no use whatsoever for ChatScript's logging.

Userlog

Store a user-bot log in USERS directory. Stand-alone default if unspecified. Alternatively you can do userlog=1 to enable.

Nouserlog

Don't store a user-bot log. Server default if unspecified. Alternatively you can do userlog=0 to disable. Alternatively you can do userlogging=none.

Serverlog

Write a server log and a bugs log. Alternatively you can do serverlog=1 to enable to file, 2 to use stdout, 4 to use stderr. You can combine like serverlog=5 Prefer the alternate form of request, serverlogging=none for off and file, stdout, stderr. - you may combine serverlogging=file,stdout Last form scanned (read in order from cs_init.txt and then cs_initmore.txt) wins.

The server log will be put into the LOGS directory under serverlogxxx.txt where xxx is the port.

The bugs log is in the same directory under bugs.txt (all ports).

The server log records all transactions by all users in order of arrival. Whereas the user log records transactions by user/bot.

The server log can be written regardless of whether CS is running in server mode or not.

serverlogauthcode=xxxxx

In addition to permanently turning on server and/or user logging, you can provide a cheat code in your input that, if it matches the serverlogauthcode, will enable server and user logging for that input. This code is hidden from CS processing so it will not impact NL processing.

hidefromlog="label label2 label3"

If there is data you don't want reflected into either server or user log files, this is the parameter. Maybe you don't want an authorization code recorded, or whatever. This presumes the data is part of some JSON object. You name one or more labels and when those are found in data outbound to a log file, the label and its value will be omitted.

Serverctrlz

Have server terminate its output with 0x00 0xfe 0xff as a verification the client received the entire message, since without sending to server, client cannot be positive the connection wasn't broken somewhere and await more input forever.

pseudoserver

This asserts that cs in DLL/sharedobject form is being used as a server (though its caller is doing all the server work). This enables the required authorizations from CS before using debug commands.

Noserverlog

Superceeded by serverloggging=. Don't write a server log or a bugs log. Alternatively you can do serverlog=0 to disable.

Nobuglog

Don't write a bugs log. Same as Buglog=0 or Buglog=none

Buglog

Buglog=n

Buglogging=none,file,stdout,stderr

Write a LOGS/bugs.txt log if n=1. Write nothing if n==0. Alternate form of request, you can use buglogging=none for off and file, stdout, stderr. - you may combine buglogging=file,stderr

DebugLevel=n

Sets debug level of server logging. 0 will remove logging all the startup variables and their values.

Fork=n

If using LINUX EVSERVER, you can request extra copies of ChatScript (to run on each core for example). n specifies how many additional copies of ChatScript to launch.

Serverretry

Allows :retry to work from a server - don't use this except for testing a singleperson on a server as it slows down the server.

servertrace

when present, forces all users to have tracing turned on. Traces go to the user logs.

repeatLimit=n

Servers are subject to malicious inputs, often generated as repeated words over and over. This detects repeated input and if the number of sequential repeats is non-zero and equal or greater to this parameter, such inputs will be truncated to just the initial repeats. All other input in this volley will be discarded.

erasename=myname

reset, when called from running script, is unable to fully reset the system. Facts that have already been created are not destroyed and user variables that have been defined are not erased, only ones in the bot definition are changed back to their default settings. The erasename parameter is used to perform a full reset prior to loading the user topic file. The incoming input is scanned for the text given, and if found the system bypasses loading the topic file and instead just initializes a fresh bot. The actual erasename seen in input will be converted to all blanks, so it will not disturb normal behavior, either in OOB input or user input.

The default value for this is: csuser_erase which you can change to anything else you want.

cs_new_user="text""

The cs_new_user parameter is used to perform a full reset prior to loading the user topic file. The incoming input is scanned for the text given, and if found the system bypasses loading the topic file and instead just initializes a fresh bot. This differs from erasename in that the text is not erased.

No such bot-specific - nosuchbotrestart=true

If the system does not recognize the bot name requested, it can automatically restart a server (on the presumption that something got damaged). If you don't expect no such bot to happen, you can enable this restart using nosuchbotrestart=true. Default is false.

Testing a server

There are various configurations for having an instance be a client to test a server.

client=xxxx:yyyy

This says be a client to test a remote server at IP xxxx and port yyyy. You will be able to "login" to this client and then send and receive messages with a server.

client=localhost:yyyy

This says be a client to test a local server on port yyyy. Similar to above.

Load=1

This creates a localhost client that constantly sends messages to a server. Works its way through REGRESS/bigregress.txt as its input (over 100K messages). Can assign different numbers to create different loading clients (e.g., load=10 creates 10 clients).

Dual

Yet another client. But this one feeds the output of the server back as input for the next round. There are also command line parameters for controlling memory usage which are not specific to being a server.