


Planning / Testing

Objectives

At the end of this module, you will be able to:

- Have a basic sense of capacity planning.
- Load test data into an Aerospike database using the Aerospike Java Benchmark tool.
- Run benchmark tests.
- Understand high level hardware considerations.
- Testing SSDs with the ACT.

These tasks are ones that you can use in your environments. Doing proper benchmarking will not only help to determine what your performance is, but also useful for finding basic connectivity issues.



Capacity Planning

For a exact, detailed planning guide, go to:

http://www.aerospike.com/docs/operations/plan/capacity/

For a quick estimate (no secondary indexes) you will need the following:


- number of records
- replication factor
- size of records
- number of bins
- average set size
- type of storage (RAM or flash/SSD)

The exact method for estimating is often too stringent. To create a simple estimate collect the following.

Area	How stored	Formula	Note
Primary Index	RAM	n * r * 64	The amount of RAM needed for the primary index is fixed at 6-bytes.
Data storage	RAM	n * r * (2 + (17 * b) + v)	Every objects needs 2 bytes for overhead, 17 bytes per bin, and the actual data
Data storage	Flash/SSD	n * r * p Where p is ((64 + (9 + s) + (28 * b) +5 + v) -> round up to nearest 128 bytes	Every object needs to store the index (64 bytes), set overhead (9 +s bytes), general overheac (28 bytes), type info (5 bytes), and the actual data. Because Aerospike stores data in 128 byte blocks, you must round up to the nearest 128 byte amount.
 n = number r = replicatio v = average b = number s = average 	n factor size of reco of bins	rds	

Note that this does not take into account secondary indexes. Aerospike always stores secondary indexes in RAM, so you should plan accordingly.

The size of the index varies on the type of value (string or numeric), but as a quick estimate, you can assume 40 bytes of RAM per string and 64 bytes per integer indexed.



Benchmarking Dos And Don'ts

Do:

- Understand what you are benchmarking. Start with the most simple use case (single server, RAM storage, small objects), to make sure you understand the upper limits of the system. Then change things one at a time to bring it closer to your production configuration.
- Be aware of what you are bottlenecked on.
- Be prepared to have more power on the clients than server.
- Know if you will be impacted by network congestion.

Don't:

- Expect high performance with VMs. You must be very careful when testing in a public cloud such as Amazon.
- Expect realistic number when the client and server are on the same host.

One of the most common problems is finding network congestion. Often this will requires network administrators to help determine if there are network issues causing the problem.

Use standard Linux commands like top to detect your bottlenecks.

The Java Benchmark Tool

- + Multi-platform
- + Portable
- + Easy to use
- + Total throughput easily seen from database nodes
- Poor performance with objects larger than 4 KB
- Must use many processes/servers to get to high throughput

The Java benchmark tool currently generates random text using ineffective methods. So large objects are not created quickly. Be aware of this if you want to test large objects and you will quickly saturate the CPUs on the clients.

If you want to test with large objects and need performance, you may want to use the benchmarking tool built into the C client. This is specific to Linux.

Java Benchmark Syntax > ./run benchmarks [options] Description -b, --bins <arg> The number of bins (like columns) of data. The target total throughput. This will include all operations. -g, --throughput <arg> -h, --host <arg> A seed node (any node in the cluster). The tool will learn about the other nodes from this one. -p, --port <arg> The port on the Aerospike node to connect to (default 3000) This is the number of keys/records to use. If you select a number too small, you will get write contention. Too large and you may run out of memory. -k, --keys <arg> -s, --set <arg> -latency <arg> Produce a table of latencies as measured from the client. This can be compared with the latencies on the server to see where any bottleneck may lie. Recommended value "-latency 7,1" -n, --namespace <arg> The namespace to test against. This is similar to a "database" in a relational database. -o, --objectSpec <arg> The type of object to use: "I" is an integer, "S:<size>" is the size of the object. Is is recommended to start with small objects to remove the network Type of workload: I - Insert only, test stops when the final record is loaded (based on –k above) -w, --workload <arg> RU, <percent> - The read percentage. "90" means a 90% read rate. The number of threads used by the benchmark. For bare metal, 64 is a good value. For VMs, you -z, --threads <arg> should use 4-8 threads/core.


It is very important to use the appropriate parameters with the –latency command. The defaults are often too coarse.

The Java Benchmark Tool

The Aerospike benchmark tool can be found within the full Aerospike Java Client.

Untar, go to the appropriate directory and compile it:

- > cd /home/aerotraining/packages/aerospike
- > tar xvf aerospike-client-java.tgz
- > cd aerospike-client-java-3.1.4/benchmarks
- >mvn package



Loading Data Example

Prior to running any tests, you should load data into the database.


You will want to do tests on reading/writing data. However, it is important to preload data prior to running these tests.

Otherwise, initially, most reads will return not found and will be artificially fast...

```
Loading Data Example Output
$./run_benchmarks -h 127.0.0.1 -p 3000 -n test -s testset -k 100000 -latency "7,1" -S 1 -o S:100 -w I -z 8
Benchmark: 127.0.0.1:3000, namespace: test, set: testset, threads: 8, workload: INITIALIZE
keys: 100000, start key: 1, key length: 10, bins: 1, throughput: unlimited, debug: false
write policy: timeout: 0, maxRetries: 2, sleepBetweenRetries: 500
bin type 1: string[100]
2014-08-27 22:12:52.091 INFO Thread 1 Add node BB9ED14150B0022 127.0.0.1:3000
2014-08-27 22:12:52.137 write(count=0 tps=0 timeouts=0 errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 0% 0% 0% 0% 0% 0%
2014-08-27 22:12:53.141 write(count=2432 tps=2432 timeouts=0 errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 90% 10% 9% 8% 7% 5% 1%
2014-08-27 22:12:54.170 write(count=6492 tps=4060 timeouts=0 errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 92% 8% 7% 6% 5% 3% 1%
2014-08-27 22:12:55.194 write(count=12705 tps=6213 timeouts=0 errors=0)
While this is running, check on the AMC.
```

Notice here that there are latencies given for writes.

The numbers represent the that exceed the timemarks at the top.



Running Balanced Workload

The first test to run is on a balanced workload. This will test database operations that are 50% read/50% write.

```
-h 127.0.0.1 \ # Local DB server
-p 3000 \ # Local port
-n test \ # Namespace "test"
-k 100000 \ # Load 100,000 records
-s testset \ # Use the set "testset"
-latency "7,1" \ # Show latency numbers
-o S:100 \ # Use 100 byte string
-w RU,50 \ # Read at 50%
-z 8 # Use 8 threads
```

This script will continue running until it is stopped.

You can run an intensive test using a balanced workload. These numbers show reading 50% of the time and updating 50% of the time.

When interpreting these remember the following:

- An update on this test is actually a read and a write. This is due to the need to update existing data. While you can replace the data rather than update, the Java benchmark tool currently only does an update.
- Keep in mind that when writing data, you will be writing a number of copies based on the replication factor. For a single node, this will be always be 1.
- You may need to run multiple copies of these scripts to maximize performance.

Running Balanced Load Example Output

```
$./run_benchmarks -h 127.0.0.1 -p 3000 -n test -s testset -k 100000 -latency "7,1" -o S:100 -w RU,50 -z 8
Benchmark: 127.0.0.1:3000, namespace: test, set: testset, threads: 8, workload: READ_UPDATE
read: 50% (all bins: 100%, single bin: 0%), write: 50% (all bins: 100%, single bin: 0%)
keys: 100000, start key: 0, key length: 10, bins: 1, throughput: unlimited, debug: false
read policy: timeout: 0, maxRetries: 2, sleepBetweenRetries: 500, reportNotFound: false
write policy: timeout: 0, maxRetries: 2, sleepBetweenRetries: 500
bin type 1: string[100]
2014-08-27 22:14:56.269 INFO Thread 1 Add node BB9ED14150B0022 127.0.0.1:3000
2014-08-27 \ 22:14:56.329 \ write (tps=2 \ timeouts=0 \ errors=0) \ read (tps=0 \ timeouts=0 \ errors=0) \ total (tps=2 \ timeouts=0 \ errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 89% 11% 11% 11% 5% 2% read 86% 14% 13% 13% 13% 9% 2% 2014-08-27 22:14:57.577 write(tps=1458 timeouts=0 errors=0) read(tps=1402 timeouts=0 errors=0)
total(tps=2860 timeouts=0 errors=0)
      <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 86% 14% 13% 12% 11% 6% 1%
read 89% 11% 10% 9% 8%
                                      5%
                                             2%
2014-08-27 \ 22:14:58.585 \ write (tps=1994 \ timeouts=0 \ errors=0) \ read(tps=1934 \ timeouts=0 \ errors=0) \ total(tps=3928 \ timeouts=0 \ errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 93% 7% 7% 6% 5% 3% 1% read 94% 6% 5% 5% 4% 2% 1%
While this is running, check on the AMC.
```

Running High-read Workload


You can then run a workload based on high read rates. This will test database operations that are 95% read/5% write

This script will continue running until it is stopped.

Running High-read workload Example Output

```
$./run_benchmarks -h 127.0.0.1 -p 3000 -n test -s testset -k 100000 -latency "7,1" -o S:100 -w
RU, 95 -z 8
Benchmark: 127.0.0.1:3000, namespace: test, set: <empty>, threads: 8, workload: READ_UPDATE
read: 95% (all bins: 100%, single bin: 0%), write: 5% (all bins: 100%, single bin: 0%)
keys: 100000, start key: 0, key length: 10, bins: 1, throughput: unlimited, debug: false
read policy: timeout: 0, maxRetries: 2, sleepBetweenRetries: 500, reportNotFound: false
write policy: timeout: 0, maxRetries: 2, sleepBetweenRetries: 500
bin type 1: string[100]
2015-05-28 18:58:09.946 INFO Thread 1 Add node BB94FB6A4647106 127.0.0.1:3000
2015-05-28 18:58:17.356 write(tps=488 timeouts=0 errors=0) read(tps=8374 timeouts=0 errors=0)
total(tps=8862 timeouts=0 errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 96% 4% 3% 2% 2% 1% 1% read 97% 3% 3% 2% 2% 1% 1% 1%
2015-05-28 18:58:18.391 write(tps=468 timeouts=0 errors=0) read(tps=9569 timeouts=0 errors=0)
total(tps=10037 timeouts=0 errors=0)
     <=1ms >1ms >2ms >4ms >8ms >16ms >32ms
write 95% 5% 4% 3% 2% 1% read 97% 3% 2% 2% 2% 1%
```

While this is running, check on the AMC.



Hardware - CPU

Aerospike is **multi-core** and **multi-threaded** and can take advantage of all available cores.

- Minimum: quad-core CPUs.
 - Common: 6 or 8 core CPUs.
- CPU is usually not a bottleneck.

top - if top shows software interrupts (si) >30%,

indicates bound by a single network queue.

There are 2 reasons to choose multiple high-powered CPUs:

- 1) You need to have the extra CPU to be able to access additional RAM
- 2) Your throughput requirements are high (> 80 ktps per node). If so, you should also be aware of your networking equipment

Using NICs that have 8+ network queues is essential to getting the best performance. If you only need < 80ktps per node, this will not likely pose an issue. If you do have high throughput requirements, please contact Aerospike in assistance configuring your hardware.

Hardware RAM

RAM is used for:

- Storage of primary index
- Storage of secondary index (if using)
- Storage of data (if configured RAM storage)

RAM speed **does not** significantly affect performance, unless TPS is **>~1Million** per node.

Hardware - Network

- Many Aerospike customers use 2 NICs: 1 that is forward facing and is used to communicate with the clients. Also a second one that is used for intra-cluster communication. The settings for these can be configured.
- Aerospike can use either unicast (a.k.a mesh) or multicast methods for cluster heartbeats. Most people will use multicast, but you must make sure your network switches can handle this.
- People often underestimate the need for bandwidth. If you have 4 KB objects and need 30 ktps of transactions from a single node, this is 120 MB per second, or 0.96 Gb per second. This will obviously strain a 1 Gbps ethernet connection.
- If your bandwidth requirements are very high > 6Gbps, you can link aggregate multiple connections into a single one. Make sure the bonding method you use actually improves throughput and is not a simple failover.
- Even if your bandwidth requirements are met, it is possible that you will be bottlenecked by pure transactions per second due to software interrupts on a single core. Modern Linux kernels (version > 3.10) have a version of irqbalance that can handle this. Otherwise there are manual methods for doing the same thing. Contact Aerospike, if you wish to do this. There are hardware dependencies.

It is very common for Aerospike hosts to have more than 1 NIC. The details in selecting the best method for how this works depends on the details of the environment and how you wish to connect to them. This topic is covered in the configuration of an Aerospike cluster.

Hardware - RAID


- Direct connect of flash/SSD to the motherboard often works very well.
- For SATA/SAS based flash devices, the choice and configuration of the RAID controller is very important. RAID controllers based on the LSI 2208 (used by many manufacturers) are especially good if you use the LSI Fastpath. The method for turning this on varies depending on the RAID controller manufacturer. In many cases this requires a low-cost software license.
- PCle based flash devices are still new. It is not known how linearly these scale with multiple cards.

Performance of even the best drives can be hurt by using improper connections to the server.

Normally the best performance is to use direct attach to the motherboard.

If this is not possible, you will want to use very good RAID controllers. The lower end ones get very poor performance with multiple drives. Aerospike has found that a single disk on a RAID controller may have very good performance, but as you add more drives, this degrades very rapidly.

In some cases your RAID controller may have settings that are optimal for control of individual disks rather than as a single RAIDed drive. This is common among controllers optimized for hadoop.



SSD Testing

Aerospike has specialized the database to make the most out of SSDs. But not all SSDs have the same performance. Getting the most means being able to test.

Aerospike has open sourced the Aerospike Certification Tool (ACT), which is available at Github (https://github.com/aerospike/act).

What the ACT Does

The ACT is a low level tool used to test the performance of SSDs as Aerospike uses them. The default settings for the tests are:

- Reads are of 1.5 KB objects
- Writes are in large blocks of 128 KB
- Reads and writes are simultaneous
- Simulates Aerospike garbage collection
- Does not use network
- Published results are based on a single drive. Aerospike can use these in parallel, but linearity depends on several factors in the hardware.
- Tests will work on a factor of "x". "1x" was the performance of a good SSD in 2011. This is the equivalent of 2,000 reads/second with 1,000 simultaneous writes/second. "2x" is twice that, "3x" is 3 times, etc. A good SATA drive in 2015 will support 3x speeds.

What Affects ACT Tests

- SSDs are not all alike. Higher model numbers are not always better.
- Changing the object size, read/write ratio, etc... will change the results.
- RAID controller How the drives are connected is extremely important.
 - Low cost controllers will always add a few ms of latency.
 - Even high cost RAID controllers may have issues. If you are using one of these, please see our note at:
 - http://www.aerospike.com/docs/operations/plan/ssd/lsi_megacli.html
- Performance can depend a lot on overprovisioning (OP). Total OP should be between 22%-29%.
- Firmware can also have a big impact. Generally, newer firmware is better.

Running ACT Tests - Preparation

- You will be destroying any data on the drive/partition. Make sure you are not using the drive with the OS or any important data.
- Make sure you know the device IDs of the device(s)/partitions(s) (e.g. / dev/sdb, /dev/xvdb, etc).
- Check the Aerospike Web site for devices that Aerospike have tested, this will form a good basis for your testing.
 http://www.aerospike.com/docs/operations/plan/ssd/ssd_certification.html
- Download and compile the ACT (https://github.com/aerospike/act).
- Prior to running any tests, run the program actprep on each device/ partition you are going to test. This will place random data on the device.
- If necessary OP the drives (instructions are at: http://www.aerospike.com/docs/operations/plan/ssd/ssd_setup.html).

The Importance of Overprovisioning (OP)

Overprovisioning is space on an SSD that is reserved for use by the SSD controller (not the RAID controller).

Total OP (manufacturer + user) for Aerospike use should be at least 29%.

- Consumer drives generally have 6%-8%
- Enterprise SATA vary a lot, but many have up to 30%
- PCIe/NVMe 22%+

This space is not user accessible and user OP will decrease the size of the SSD.

Running ACT Tests – Executing Tests

Create a configuration file for the test by executing:

```
[act-3.0]$ python act_config_helper.py
Enter the number of devices you want to create config for: 1
Enter either raw device if over-provisioned using hdparm or partition if over-provisioned using fdisk:
Enter device name #1 (e.g. /dev/sdb or /dev/sdb1): /dev/sdb
Change test duration default of 24 hours? (y/N): y
Enter the test duration in hours: 3
Use non-standard configuration? (y/N): n
"1x" load is 2000 reads per second and 1000 writes per second.
Enter the load factor (e.g. enter 1 for 1x test): 3
Do you want to save this config to a file? (y/N): y
Config file actconfig_3x_ld.txt successfully created.
```


- Select an appropriate starting point for your drive
 - Consumer SATA/Cloud 3x
 - Enterprise SATA 6x
 - PCIe/NVMe 24x
- Run the ACT test and redirect output to a file:

```
[act-3.0]$ act actconfig_3x_1d.txt > actconfig_3x_1d.log &
```

Change the x factor and retest. The final test should be for 24 hours.

Analyzing the results:

- Passing means:
 - extstyle < 5% of transactions should take longer than 1 ms
 - < 1% of transactions should take longer than 8 ms</p>
 - < 0.1% of transactions should take longer than 64 ms</p>



Summary

What we have covered:

- Have a basic sense of capacity planning.
- Load test data into an Aerospike database using the Aerospike Java Benchmark tool.
- Run benchmark tests.
- Understand high level hardware considerations.
- Testing SSDs with the ACT.

You can use the benchmark tool by simply copying the files and running them from different servers.