QATzip 0.2.5

Generated by Doxygen 1.8.5

Wed Jun 20 2018 14:33:59

Contents

1	Mod	ule Inde	ex		1
	1.1	Module	98		1
2	Clas	s Index			3
	2.1	Class	List		3
3	File	Index			5
	3.1	File Lis	st		5
4	Mod	ule Doc	umentati	ion	7
	4.1	Data C	ompression	on API	7
		4.1.1	Detailed	Description	8
		4.1.2	Macro D	Definition Documentation	8
			4.1.2.1	QZ_OK	8
			4.1.2.2	QZ_SKID_PAD_SZ	8
		4.1.3	Typedef	Documentation	9
			4.1.3.1	QzCrcType_T	9
			4.1.3.2	QzDataFormat_T	9
			4.1.3.3	QzDirection_T	9
			4.1.3.4	QzHuffmanHdr_T	9
			4.1.3.5	QzSession_T	10
			4.1.3.6	QzSessionParams_T	10
			4.1.3.7	QzStatus_T	10
		4.1.4	Enumera	ation Type Documentation	10
			4.1.4.1	PinMem_T	10
			4.1.4.2	QzCrcType_E	10
			4.1.4.3	QzDataFormat_E	11
			4.1.4.4	QzDirection_E	11
			4.1.4.5	QzHuffmanHdr_E	11
		4.1.5	Function	Documentation	12
			4.1.5.1	qzClose	12
			4152	azCompress	13

iv CONTENTS

		4.1.5.3	qzCompressCrc	13
		4.1.5.4	qzDecompress	14
		4.1.5.5	qzFree	15
		4.1.5.6	qzGetDefaults	16
		4.1.5.7	qzGetStatus	16
		4.1.5.8	qzInit	17
		4.1.5.9	qzMalloc	18
		4.1.5.10	qzMemFindAddr	18
		4.1.5.11	qzSetDefaults	19
		4.1.5.12	qzSetupSession	20
		4.1.5.13	qzTeardownSession	20
Class	e Doou	montation		23
				23
5.1		_		
	5.1.2			23
				23
5.2	OzSes			
5.2				
	5.2.2			24
		_	. – .	24
				25
			-	25
			-	25
		5.2.2.8		25
		5.2.2.9		25
		5.2.2.10	-	25
		5.2.2.11		25
		5.2.2.12		25
		5.2.2.13	sw_backup	25
			_ ·	25
5.3	QzStat			
	5.3.1	_		
	5.1	5.1 QzSes 5.1.1 5.1.2 5.2 QzSes 5.2.1 5.2.2	4.1.5.4 4.1.5.5 4.1.5.6 4.1.5.7 4.1.5.8 4.1.5.9 4.1.5.10 4.1.5.11 4.1.5.12 4.1.5.13 Class Documentation 5.1 QzSession_S Str 5.1.1 Detailed 5.1.2 Member 5.1.2.1 5.1.2.2 5.1.2.3 5.1.2.4 5.1.2.5 5.2 QzSessionParam 5.2.1 Detailed 5.2.2 Member 5.2.2.1 5.2.2.2 5.2.2.3 5.2.2.4 5.2.2.5 5.2.2.6 5.2.2.7 5.2.2.8 5.2.2.9 5.2.2.10 5.2.2.10 5.2.2.11 5.2.2.12 5.2.2.13 5.2.2.14 5.3 QzStatus_S Structory 5.2.2.14	4.1.5.4 qzDecompress 4.1.5.5 qzFree 4.1.5.6 qzGetDefaults 4.1.5.7 qzGetSlatus 4.1.5.8 qzInit 4.1.5.9 qzMalloc 4.1.5.10 qzMemFindAddr 4.1.5.11 qzSetDefaults 4.1.5.12 qzSetupSession 4.1.5.13 qzTeardownSession Class Documentation 5.1 QzSession_S Struct Reference 5.1.1 Detailed Description 5.1.2 Member Data Documentation. 5.1.2.1 hw_session_stat 5.1.2.2 internal 5.1.2.3 thd_sess_stat 5.1.2.4 total_in 5.1.2.5 total_out 5.2.1 Detailed Description 5.2.2 Member Data Documentation. 5.2.2.1 comp_algorithm 5.2.2.2 comp_lM 5.2.2.1 comp_algorithm 5.2.2.2 comp_lM 5.2.2.3 data_fmt 5.2.2.4 direction 5.2.2.5 enable_cnv 5.2.2.6 huffman_hdr 5.2.2.7 hw_buff_sz 5.2.2.9 max_lorks 5.2.2.10 poll_sleep 5.2.2.11 req_cnt_thrshold 5.2.2.21 sw_backup 5.2.2.13 sw_backup 5.2.2.14 wait_cnt_thrshold 5.2.2.13 sw_backup 5.2.2.14 wait_cnt_thrshold 5.2.2.1 sruch Reference 5.2.2.1 sw_backup 5.2.2.14 wait_cnt_thrshold 5.2.2.13 sw_backup 5.2.2.14 wait_cnt_thrshold

CONTENTS

		5.3.2	Member I	Data Documentation	26
			5.3.2.1	algo_hw	26
			5.3.2.2	algo_sw	26
			5.3.2.3	hw_session_status	26
			5.3.2.4	memory_alloced	26
			5.3.2.5	qat_hw_count	26
			5.3.2.6	qat_instance_attach	26
			5.3.2.7	qat_mem_drvr	26
			5.3.2.8	qat_service_stated	26
			5.3.2.9	using_huge_pages	27
6	File	Docume	entation		29
	6.1			ile Reference	29
		6.1.1		efinition Documentation	31
			6.1.1.1	MIN	31
			6.1.1.2	QZ BUF ERROR	31
			6.1.1.3	QZ_COMP_ALGOL_DEFAULT	31
			6.1.1.4	QZ COMP LEVEL DEFAULT	31
			6.1.1.5	QZ_COMP_THRESHOLD_DEFAULT	31
			6.1.1.6	QZ_COMP_THRESHOLD_MINIMUM	31
			6.1.1.7	QZ_DATA_ERROR	31
			6.1.1.8	QZ_DATA_FORMAT_DEFAULT	31
			6.1.1.9	QZ_DEFLATE	31
			6.1.1.10	QZ_DIRECTION_DEFAULT	31
			6.1.1.11	QZ_DUPLICATE	31
			6.1.1.12	QZ_FAIL	31
				QZ_FORCE_SW	31
			6.1.1.14	QZ_HUFF_HDR_DEFAULT	31
			6.1.1.15	QZ_HW_BUFF_MAX_SZ	31
			6.1.1.16	QZ_HW_BUFF_MIN_SZ	31
			6.1.1.17	QZ_HW_BUFF_SZ	31
			6.1.1.18	QZ_LOW_MEM	32
			6.1.1.19	QZ_LZ4	32
			6.1.1.20	QZ_MAX_ALGORITHMS	32
			6.1.1.21	QZ_MAX_FORK_DEFAULT	32
			6.1.1.22	QZ_MEMCPY	32
			6.1.1.23	QZ_NO_HW	32
			6.1.1.24	QZ_NO_INST_ATTACH	32
				QZ_NO_MDRV	32
				QZ_NONE	32

vi CONTENTS

Index				34
		6.1.2.1	qzMaxCompressedLength	33
	0.1.2			
	6.1.2		Documentation	
			QZ_WAIT_CNT_THRESHOLD_DEFAULT	
			QZ SW BACKUP DEFAULT	
		6.1.1.40		
		6.1.1.39	QZ_STRM_BUFF_MIN_SZ	
		6.1.1.38	QZ_STRM_BUFF_MAX_SZ	
		6.1.1.37	QZ_SNAPPY	
		6.1.1.36	QZ_REQ_THRESHOLD_MINIMUM	33
		6.1.1.35	QZ_REQ_THRESHOLD_MAXINUM	33
		6.1.1.34	QZ_REQ_THRESHOLD_DEFAULT	33
		6.1.1.33	QZ_REQ_CNV_DEFAULT	33
		6.1.1.32	QZ_POLL_SLEEP_DEFAULT	33
		6.1.1.31	QZ_PARAMS	32
		6.1.1.30	QZ_NOSW_NO_MDRV	32
		6.1.1.29	QZ_NOSW_NO_INST_ATTACH	32
		6.1.1.28	QZ_NOSW_NO_HW	32
		6.1.1.27	QZ_NOSW_LOW_MEM	32

Chapter 1

Module Index

1.1	Modules
Here	is a list of all modules:
Da	ata Compression API

2 **Module Index**

Chapter 2

Class Index

2	4	Class	Lict
7	1	() 22 C	I ISI

Here are the classes	, structs, unions ar	nd interfaces with brief	descriptions:

QzSession_S	23
QzSessionParams_S	24
QzStatus S	25

Class Index

Chapter 3

File Index

3.1	FIIE LIST	
Here i	s a list of all files with brief descriptions:	

6 File Index

Chapter 4

Module Documentation

4.1 Data Compression API

Classes

- struct QzSessionParams_S
- struct QzSession_S
- struct QzStatus_S

Macros

- #define QZ_OK (0)
- #define QZ_SKID_PAD_SZ 48

Typedefs

- typedef enum QzHuffmanHdr_E QzHuffmanHdr_T
- typedef enum QzDirection_E QzDirection_T
- typedef enum QzDataFormat_E QzDataFormat_T
- typedef enum QzCrcType_E QzCrcType_T
- typedef struct QzSessionParams_S QzSessionParams_T
- typedef struct QzSession_S QzSession_T
- typedef struct QzStatus_S QzStatus_T

Enumerations

- enum QzHuffmanHdr_E { QZ_DYNAMIC_HDR = 0, QZ_STATIC_HDR }
- enum PinMem_T { COMMON_MEM = 0, PINNED_MEM }
- enum QzDirection_E { QZ_DIR_COMPRESS = 0, QZ_DIR_DECOMPRESS, QZ_DIR_BOTH }
- enum QzDataFormat_E { QZ_DEFLATE_RAW = 0, QZ_DEFLATE_GZIP, QZ_DEFLATE_GZIP_EXT, QZ_FMT_NUM }
- enum QzCrcType E { QZ CRC32 = 0, QZ CRC64, QZ ADLER, NONE }

Functions

- int qzInit (QzSession T *sess, unsigned char sw backup)
- int qzSetupSession (QzSession_T *sess, QzSessionParams_T *params)

8 Module Documentation

• int qzCompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last)

- int qzCompressCrc (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last, unsigned long *crc)
- int qzDecompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest len)
- int qzTeardownSession (QzSession_T *sess)
- int qzClose (QzSession_T *sess)
- int qzGetStatus (QzSession_T *sess, QzStatus_T *status)
- int qzSetDefaults (QzSessionParams T *defaults)
- int qzGetDefaults (QzSessionParams_T *defaults)
- void * qzMalloc (size_t sz, int numa, int force_pinned)
- void qzFree (void *m)
- int qzMemFindAddr (unsigned char *a)

4.1.1 Detailed Description

These functions specify the API for Data Compression operations.

Remarks

4.1.2 Macro Definition Documentation

4.1.2.1 #define QZ_OK (0)

QATZIP Session Status definitions and function return codes

This list identifies valid values for session status and function return codes. Success

4.1.2.2 #define QZ_SKID_PAD_SZ 48

Get the max compressed output length

Get the max compressed output length

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	src_sz	Input data length in byte.

Return values

dest_sz	Max compressed data output length in byte. When src_sz equal to 0, the return
	value is 0.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.3 Typedef Documentation

4.1.3.1 typedef enum QzCrcType_E QzCrcType_T

Supported checksum type

This enumerated list identifies the checksum type for input/output data. A format can be CRC32, CRC64, Adler or none.

4.1.3.2 typedef enum QzDataFormat E QzDataFormat T

Streaming API input and output format

This enumerated list identifies the data format supported by QATZip streaming API. A format can be raw deflate data block, deflate block wrapped by GZip header and footer, or deflate data block wrapped by GZip extension header and footer.

4.1.3.3 typedef enum QzDirection E QzDirection T

Compress or decompress setting

This enumerated list identifies the session directions supported by QATZip. A session can be compress, decompress or both.

4.1.3.4 typedef enum QzHuffmanHdr E QzHuffmanHdr T

This API provides access to underlying compression functions in QAT hardware. The API supports an implementation that provides compression service in software if not all of the required resources are not available to execute the compression service in hardware.

The API supports threaded applications. Applications can create threads and each of these threads can invoke the API defined herein.

For simplicity, initializations and setup function calls are not required to obtain compression services. If the initialization and setup functions are not called before compression or decompression requests, then they will be called with default arguments from within the compression or decompression functions. This results in several legal calling scenarios, described below.

Scenario 1 - all functions explicitly invoked by caller, with all arguments provided

qzInit(&sess_c, sw_backup); qzSetupSession(&sess_c, ¶ms); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); qzDecompress(&sess, src, &src_len, dest, &dest_len); qzTeardownSession(&sess); qzClose(&sess);

Scenario 2 - initialization function called, setup function not invoked by caller. This scenario can be used to specify the sw backup argument to gzlnit.

qzInit(&sess, sw_backup); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); calls qzSetupSession(sess, NU-LL); qzTeardownSession(&sess); qzClose(&sess);

Scenario 3 - calling application simply invokes the actual qzCompress functions

10 Module Documentation

qzCompress(&sess, src, &src_len, dest, &dest_len, 0); calls qzInit sess, 1); calls qzSetupSession(sess, NULL); qzCompress(&sess, src, &src_len, dest, &dest_len, 1);

Notes: Invoking qzSetupSession with NULL for params sets up a session with default session attributed, detailed in the function description below.

If an application terminates with out invoking tear down and close functions, process termination will invoke memory and hardware instance cleanup.

If a thread terminates without invoking tear down and close functions, memory and hardware are not cleanup until the application exits.

```
Supported Huffman Headers
```

This enumerated list identifies the Huffman header types supported by QATZip

4.1.3.5 typedef struct QzSession_S QzSession_T

QATZIP Session opaque data storage

This structure contains a pointer to a structure with session state

4.1.3.6 typedef struct QzSessionParams_S QzSessionParams_T

QATZIP Session Initialization parameters

This structure contains data for initializing a session

4.1.3.7 typedef struct QzStatus_S QzStatus_T

QATZIP status structure

This structure contains data relating to the stat usof QAT on the platform

4.1.4 Enumeration Type Documentation

4.1.4.1 enum PinMem_T

```
Supported memory types
```

This enumerated list identifies memory types supported by QATZip.

Enumerator

COMMON_MEM Allocate non-continous memory **PINNED_MEM** Allocate continous memory

4.1.4.2 enum QzCrcType_E

```
Supported checksum type
```

This enumerated list identifies the checksum type for input/output data. A format can be CRC32, CRC64, Adler or none.

Enumerator

QZ_CRC32 CRC32 checksum

QZ_CRC64 CRC64 checksum

QZ_ADLER Adler checksum

NONE No checksum

4.1.4.3 enum QzDataFormat E

Streaming API input and output format

This enumerated list identifies the data format supported by QATZip streaming API. A format can be raw deflate data block, deflate block wrapped by GZip header and footer, or deflate data block wrapped by GZip extension header and footer.

Enumerator

QZ_DEFLATE_RAW Data is in raw deflate format
 QZ_DEFLATE_GZIP Data is in deflate wrappped by GZip header and footer
 QZ_DEFLATE_GZIP_EXT Data is in deflate warpped by GZip extension header and footer
 QZ_FMT_NUM

4.1.4.4 enum QzDirection E

Compress or decompress setting

This enumerated list identifies the session directions supported by QATZip. A session can be compress, decompress or both.

Enumerator

QZ_DIR_COMPRESS Session will be used for compression

QZ_DIR_DECOMPRESS Session will be used for decompression

QZ_DIR_BOTH Session will be used for both compression and decompression

4.1.4.5 enum QzHuffmanHdr_E

This API provides access to underlying compression functions in QAT hardware. The API supports an implementation that provides compression service in software if not all of the required resources are not available to execute the compression service in hardware.

The API supports threaded applications. Applications can create threads and each of these threads can invoke the API defined herein.

For simplicity, initializations and setup function calls are not required to obtain compression services. If the initialization and setup functions are not called before compression or decompression requests, then they will be called with default arguments from within the compression or decompression functions. This results in several legal calling scenarios, described below.

Scenario 1 - all functions explicitly invoked by caller, with all arguments provided

qzInit(&sess_c, sw_backup); qzSetupSession(&sess_c, ¶ms); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); qzDecompress(&sess, src, &src_len, dest, &dest_len); qzTeardownSession(&sess); qzClose(&sess);

Scenario 2 - initialization function called, setup function not invoked by caller. This scenario can be used to specify the sw_backup argument to qzInit.

qzInit(&sess, sw_backup); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); calls qzSetupSession(sess, NU-LL); qzTeardownSession(&sess); qzClose(&sess);

12 Module Documentation

Scenario 3 - calling application simply invokes the actual qzCompress functions

qzCompress(&sess, src, &src_len, dest, &dest_len, 0); calls qzInit sess, 1); calls qzSetupSession(sess, NULL); qzCompress(&sess, src, &src_len, dest, &dest_len, 1);

Notes: Invoking qzSetupSession with NULL for params sets up a session with default session attributed, detailed in the function description below.

If an application terminates with out invoking tear down and close functions, process termination will invoke memory and hardware instance cleanup.

If a thread terminates without invoking tear down and close functions, memory and hardware are not cleanup until the application exits.

```
Supported Huffman Headers
```

This enumerated list identifies the Huffman header types supported by QATZip

Enumerator

```
QZ_DYNAMIC_HDR Full Dynamic Huffman Trees
QZ_STATIC_HDR Static Huffman Trees
```

4.1.5 Function Documentation

4.1.5.1 int qzClose (QzSession_T * sess)

```
terminates a QATZip session
```

This function closes the connection with QAT

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	pointer to session data

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.2 int qzCompress (QzSession_T * sess, const unsigned char * src, unsigned int * src_len, unsigned char * dest, unsigned int * dest_len, unsigned int last)

compress a buffer

This function will compress a buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of *sess - then this function will attempt to set up a session using qzInit and qzSetupSession.

The resulting compressed block of data will be composed of one or more gzip blocks per RFC 1952.

This function will place completed compression blocks in the output buffer.

The caller must check the updated src_len. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter dest_len will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	src	point to source buffer
in,out	src_len	length of source buffer. Modified to number of bytes consumed
in	dest	point to destination buffer
in, out	dest_len	length of destination buffer. Modified to length of compressed data when func-
		tion returns
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.3 int qzCompressCrc (QzSession_T * sess, const unsigned char * src, unsigned int * src_len, unsigned char * dest, unsigned int * dest_len, unsigned int last, unsigned long * crc)

compress a buffer and return the CRC checksum

14 Module Documentation

This function will compress a buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of *sess - then this function will attempt to set up a session using qzInit and qzSetupSession.

The resulting compressed block of data will be composed of one or more gzip blocks per RFC 1952.

This function will place completed compression blocks in the output buffer and put CRC32 checksum for compressed input data in user provided bufer *crc.

The caller must check the updated src_len. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter dest_len will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	src	point to source buffer
in,out	src_len	length of source buffer. Modified to number of bytes consumed
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of compressed data when func-
		tion returns
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'
in,out	crc	point to CRC32 checksum buffer

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.4 int qzDecompress (QzSession_T * sess, const unsigned char * src, unsigned int * src_len, unsigned char * dest, unsigned int * dest_len)

```
decompress a buffer
```

This function will decompress a buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of *sess - then this function will attempt to set up a session using qzInit and qzSetupSession.

The input compressed block of data will be composed of one or more gzip blocks per RFC1952.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	src	point to source buffer
in	src_len	length of source buffer. Modified to length of processed compressed data
		when function returns
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of decompressed data when
		function returns

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.5 void qzFree (void *m)

Free allocated memory

Free allocated memory

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	т	Memory address to be freed.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

16 Module Documentation

4.1.5.6 int qzGetDefaults (QzSessionParams_T * defaults)

Get default QzSessionParams_T value

Get default QzSessionParams T value

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	defaults	The pointer to default value.

Return values

QZ_OK	Success on getting default value.
QZ_PARAM	Fail to get default value.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.7 int qzGetStatus (QzSession_T * sess, QzStatus_T * status)

Get current QAT status

This function retrieves the status of QAT in the platform. The status structure will be filled in as follows: qat_hw_count number of discovered QAT devices on PCU bus qat_service_stated 1 if qzInit has been successfully run, 0 otherwise qat_mem_drvr 1 if the QAT memory driver is installed, 0 otherwise qat_instance_attach 1 if session has attached to a hardware instance, 0 otherwise memory_alloced amount of memory, in kilobytes, from kernel or huge pages allocated by this process/thread. using_huge_pages 1 if memory is being allocated from huge pages, 0 if memory is being allocated from standard kernel memory hw_session_stat Hw session status: one of: QZ_OK QZ_FAIL QZ_NO_HW QZ_NO_MDRV QZ_NO_INST_ATTACH QZ_LOW_MEM QZ_NOSW_NO_HW QZ_NOSW_NO_HW QZ_NOSW_NO_HW QZ_NOSW_LOW_MEM

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	pointer to opaque instance and session data.
in	status	pointer to QATZIP status structure.

Return values

......

QZ_OK	Function executed successfully. A hardware based compression session has
	been created.
QZ_PARAMS	*status is NULL

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.8 int qzInit (QzSession_T * sess, unsigned char sw_backup)

Initialize QAT hardware

This function initializes the QAT hardware. This function is optional in the function calling sequence. If desired, this call can be made to avoid latency impact during the first call to qzDecompress or qzCompress, or to set the sw_backup parameter explicitly. The input parameter sw_backup specifies the behavior of the function and that of the functions called with the same session in the event there are insufficient resources to establish a QAT based compression or decompression session.

Required resources include access to the QAT hardware, contiguous pinned memory for mmaping the hardware rings, and contiguous pinned memory for buffers.

This function shall not be called in an interrupt context. None This function will: 1) start the user space driver if necessary 2) allocate all hardware instances available Yes No Yes

Parameters

in	sess	pointer to opaque instance and session data.
in	sw_backup	0 for no sw backup, 1 for sw backup

Return values

QZ_OK	Function executed successfully. A hardware or sw instance has been allocated to
	the calling process/thread.
QZ_DUPLICATE	This process/thread already has a hardware instance
QZ_PARAMS	*sess is NULL
QZ_NOSW_NO_HW	No hardware and no sw session being established
QZ_NOSW_NO_MDRV	No memory driver. No software session established
QZ_NOSW_NO_INST_AT-	No instance avail. No software session established
TACH	
QZ_NOSW_LOW_MEM	Not enough pinned memory available. No software session established

Precondition

None

18 Module Documentation

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.9 void* qzMalloc (size_t sz, int numa, int force_pinned)

Allocate different types of memory

Allocate different types of memory

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	SZ	Memory size to be allocated.
in	numa	NUMA node from which to allocate memory
in	force_pinned	PINNED_MEM allocate continous memory COMMON_MEM allocate non- continous memory

Return values

NULL	Fail to allocate memory
adress	The address to allocated memory

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.10 int qzMemFindAddr (unsigned char * a)

Check whether the address is available

Check whether the address is available

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	а	Address need to be checked
----	---	----------------------------

Return values

1	The Address is available
0	The address is not available

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.11 int qzSetDefaults (QzSessionParams_T * defaults)

Set default QzSessionParams_T value

Set default QzSessionParams_T value

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	defaults	The pointer to value to be set as default.

Return values

QZ_OK	Success on setting default value.
QZ_PARAM	Fail to set default value.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

20 Module Documentation

4.1.5.12 int qzSetupSession (QzSession_T * sess, QzSessionParams_T * params)

```
initialize a QATZip session
```

This function establishes a QAT session. This involves associating a hardware instance to the session, allocating buffers. If all of these activities can not be completed successfully, then this function will set up a software based session of param->sw_backup is set to 1.

Before this function is called, the hardware must have been successfully started via qzInit.

If *sess includes an existing hardware or software session, then this session will be torn down before a new one is attempted.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	params	Parameters for session

Return values

QZ_OK	Function executed successfully. A hardware or sw based compression session
	has been created.
QZ_PARAMS	*sess is NULL or member of params is invalid
QZ_NOSW_NO_HW	No hardware and no sw session being established
QZ_NOSW_NO_MDRV	No memory driver. No software session established
QZ_NOSW_NO_INST_AT-	No instance avail. No software session established
TACH	
QZ_NO_LOW_MEM	Not enough pinned memory available. No software session established

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.13 int qzTeardownSession (QzSession_T * sess)

```
Deinitialize a QATZip session
```

This function disconnects a session from a hardware instance and deallocates buffers. If no session has been initialized, then no action will take place.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
----	------	----------------

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

22 **Module Documentation**

Chapter 5

Class Documentation

5.1 QzSession_S Struct Reference

```
#include <qatzip.h>
```

Public Attributes

- · signed long int hw session stat
- int thd_sess_stat
- void * internal
- unsigned long total_in
- unsigned long total_out

5.1.1 Detailed Description

QATZIP Session opaque data storage

This structure contains a pointer to a structure with session state

5.1.2 Member Data Documentation

5.1.2.1 signed long int QzSession_S::hw_session_stat

filled in during initialization, session startup and decompression

5.1.2.2 void* QzSession_S::internal

session data is opaque to outside world

5.1.2.3 int QzSession_S::thd_sess_stat

note process compression and decompression thread state

5.1.2.4 unsigned long QzSession_S::total_in

Total processed input data length in this session

24 Class Documentation

5.1.2.5 unsigned long QzSession_S::total_out

Total output data length in this session

The documentation for this struct was generated from the following file:

• include/qatzip.h

5.2 QzSessionParams_S Struct Reference

```
#include <qatzip.h>
```

Public Attributes

- QzHuffmanHdr_T huffman_hdr
- · QzDirection T direction
- QzDataFormat_T data_fmt
- unsigned int comp_lvl
- unsigned char comp_algorithm
- unsigned int poll_sleep
- unsigned int max_forks
- unsigned char sw_backup
- unsigned int hw_buff_sz
- unsigned int strm_buff_sz
- unsigned int input_sz_thrshold
- unsigned int req_cnt_thrshold
- unsigned int enable_cnv
- · unsigned int wait_cnt_thrshold

5.2.1 Detailed Description

QATZIP Session Initialization parameters

This structure contains data for initializing a session

5.2.2 Member Data Documentation

5.2.2.1 unsigned char QzSessionParams_S::comp_algorithm

Compress/decompression algorithms

5.2.2.2 unsigned int QzSessionParams_S::comp_lvl

Compression level 1..9

5.2.2.3 QzDataFormat_T QzSessionParams_S::data_fmt

defalte, deflate with GZip or deflate with GZip ext

5.2.2.4 QzDirection T QzSessionParams_S::direction

compress or decompress

5.2.2.5 unsigned int QzSessionParams_S::enable_cnv

1 Compress And Verify enabled, 0 Disable Compress and Verify

5.2.2.6 QzHuffmanHdr_T QzSessionParams_S::huffman_hdr

Dynamic or Static Huffman headers

5.2.2.7 unsigned int QzSessionParams_S::hw_buff_sz

default buffer size, Must be a power of 2 4K,8K,16K,32K,64K,128K

5.2.2.8 unsigned int QzSessionParams_S::input_sz_thrshold

default threshold of compression service's input size for sw failover, if the size of input request less than the threshold, QATZip will route the request to software

5.2.2.9 unsigned int QzSessionParams_S::max_forks

maximum forks permitted in the current thread. 0 means no forking permitted

5.2.2.10 unsigned int QzSessionParams_S::poll_sleep

nanosleep between poll [0..1000] 0 means no sleep

5.2.2.11 unsigned int QzSessionParams_S::req_cnt_thrshold

set between 1 and 4, default 4

5.2.2.12 unsigned int QzSessionParams_S::strm_buff_sz

stream buffer size between [1K .. 2M - 5K] default strm_buf_sz equals to hw_buff_sz

5.2.2.13 unsigned char QzSessionParams_S::sw_backup

0 means no sw backup, 1 means sw backup

5.2.2.14 unsigned int QzSessionParams_S::wait_cnt_thrshold

when previous try failed, wait for specific number of call before retry device open. default threshold is 8 The documentation for this struct was generated from the following file:

· include/qatzip.h

5.3 QzStatus S Struct Reference

#include <qatzip.h>

26 Class Documentation

Public Attributes

- · unsigned short int gat hw count
- unsigned char qat_service_stated
- unsigned char qat_mem_drvr
- unsigned char qat_instance_attach
- · unsigned long int memory_alloced
- unsigned char using_huge_pages
- signed long int hw_session_status
- unsigned char algo_sw [QZ_MAX_ALGORITHMS]
- unsigned char algo hw [QZ MAX ALGORITHMS]

5.3.1 Detailed Description

QATZIP status structure

This structure contains data relating to the stat usof QAT on the platform

5.3.2 Member Data Documentation

5.3.2.1 unsigned char QzStatus_S::algo_hw[QZ_MAX_ALGORITHMS]

count of hardware devices supporting algorithms

5.3.2.2 unsigned char QzStatus_S::algo_sw[QZ_MAX_ALGORITHMS]

support software algorithms

5.3.2.3 signed long int QzStatus S::hw_session_status

One of QATZIP Session Status

5.3.2.4 unsigned long int QzStatus_S::memory_alloced

Amount of memory allocated by this thread/process

5.3.2.5 unsigned short int QzStatus_S::qat_hw_count

from PCI scan

5.3.2.6 unsigned char QzStatus_S::qat_instance_attach

Is this thread/g_process properly attached to an Instance?

5.3.2.7 unsigned char QzStatus_S::qat_mem_drvr

1 if /dev/qat_mem exists 2 if /dev/qat_mem has been opened 0 otherwise

5.3.2.8 unsigned char QzStatus_S::qat_service_stated

Check if the QAT service is properly running on at least one device

5.3.2.9 unsigned char QzStatus_S::using_huge_pages

Are memory slabs coming from huge pages

The documentation for this struct was generated from the following file:

• include/qatzip.h

28 Class Documentation

Chapter 6

File Documentation

6.1 include/qatzip.h File Reference

```
#include <string.h>
```

Classes

- struct QzSessionParams_S
- struct QzSession_S
- struct QzStatus_S

Macros

- #define QZ_OK (0)
- #define QZ_DUPLICATE (1)
- #define QZ_FORCE_SW (2)
- #define QZ_PARAMS (-1)
- #define QZ FAIL (-2)
- #define QZ_BUF_ERROR (-3)
- #define QZ_DATA_ERROR (-4)
- #define QZ_NO_HW (11)
- #define QZ_NO_MDRV (12)
- #define QZ_NO_INST_ATTACH (13)
- #define QZ_LOW_MEM (14)
- #define QZ_NONE (100)
- #define QZ_NOSW_NO_HW (-101)
- #define QZ_NOSW_NO_MDRV (-102)
- #define QZ_NOSW_NO_INST_ATTACH (-103)
- #define QZ_NOSW_LOW_MEM (-104)
- #define QZ_MAX_ALGORITHMS ((int)255)
- #define QZ_DEFLATE ((unsigned char)8)
- #define QZ_SNAPPY ((unsigned char)'S')
- #define QZ_LZ4 ((unsigned char)'4')
- #define MIN(a, b) (((a)<(b))?(a):(b))
- #define QZ_MEMCPY(dest, src, dest_sz, src_sz) memcpy((void *)(dest), (void *) (src), (size_t)MIN(dest_sz, src_sz))
- #define QZ_HUFF_HDR_DEFAULT QZ_DYNAMIC_HDR
- #define QZ_DIRECTION_DEFAULT QZ_DIR_BOTH

30 File Documentation

- #define QZ_DATA_FORMAT_DEFAULT QZ_DEFLATE_GZIP_EXT
- #define QZ_COMP_LEVEL_DEFAULT 1
- #define QZ COMP ALGOL DEFAULT QZ DEFLATE
- #define QZ POLL SLEEP DEFAULT 10
- #define QZ MAX FORK DEFAULT 3
- #define QZ SW BACKUP DEFAULT 1
- #define QZ_HW_BUFF_SZ (64*1024)
- #define QZ_HW_BUFF_MIN_SZ (1*1024)
- #define QZ HW BUFF MAX SZ (512*1024)
- #define QZ_STRM_BUFF_SZ_DEFAULT QZ_HW_BUFF_SZ
- #define QZ_STRM_BUFF_MIN_SZ (1*1024)
- #define QZ_STRM_BUFF_MAX_SZ (2*1024*1024 5*1024)
- #define QZ_COMP_THRESHOLD_DEFAULT 1024
- #define QZ COMP THRESHOLD MINIMUM 128
- #define QZ REQ THRESHOLD MINIMUM 1
- #define QZ_REQ_THRESHOLD_MAXINUM NUM_BUFF
- #define QZ REQ THRESHOLD DEFAULT QZ REQ THRESHOLD MAXINUM
- #define QZ_REQ_CNV_DEFAULT 1
- #define QZ_WAIT_CNT_THRESHOLD_DEFAULT 8
- #define QZ_SKID_PAD_SZ 48

Typedefs

- typedef enum QzHuffmanHdr_E QzHuffmanHdr_T
- typedef enum QzDirection_E QzDirection_T
- typedef enum QzDataFormat_E QzDataFormat_T
- typedef enum QzCrcType E QzCrcType T
- typedef struct QzSessionParams_S QzSessionParams_T
- typedef struct QzSession S QzSession T
- typedef struct QzStatus_S QzStatus_T

Enumerations

- enum QzHuffmanHdr_E { QZ_DYNAMIC_HDR = 0, QZ_STATIC_HDR }
- enum PinMem_T { COMMON_MEM = 0, PINNED_MEM }
- enum QzDirection_E { QZ_DIR_COMPRESS = 0, QZ_DIR_DECOMPRESS, QZ_DIR_BOTH }
- enum QzDataFormat_E { QZ_DEFLATE_RAW = 0, QZ_DEFLATE_GZIP, QZ_DEFLATE_GZIP_EXT, QZ_-FMT_NUM }
- enum QzCrcType_E { QZ_CRC32 = 0, QZ_CRC64, QZ_ADLER, NONE }

Functions

- int qzInit (QzSession_T *sess, unsigned char sw_backup)
- int qzSetupSession (QzSession_T *sess, QzSessionParams_T *params)
- int qzCompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last)
- int qzCompressCrc (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last, unsigned long *crc)
- int qzDecompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len)
- int qzTeardownSession (QzSession_T *sess)
- int qzClose (QzSession_T *sess)
- int qzGetStatus (QzSession_T *sess, QzStatus_T *status)

- unsigned int qzMaxCompressedLength (unsigned int src_sz)
- int qzSetDefaults (QzSessionParams_T *defaults)
- int qzGetDefaults (QzSessionParams_T *defaults)
- void * qzMalloc (size_t sz, int numa, int force_pinned)
- void qzFree (void *m)
- int qzMemFindAddr (unsigned char *a)
- 6.1.1 Macro Definition Documentation
- 6.1.1.1 #define MIN(a, b) (((a)<(b))?(a):(b))
- 6.1.1.2 #define QZ_BUF_ERROR (-3)

Insufficient buffer error

- 6.1.1.3 #define QZ_COMP_ALGOL_DEFAULT QZ_DEFLATE
- 6.1.1.4 #define QZ_COMP_LEVEL_DEFAULT 1
- 6.1.1.5 #define QZ_COMP_THRESHOLD_DEFAULT 1024
- 6.1.1.6 #define QZ_COMP_THRESHOLD_MINIMUM 128
- 6.1.1.7 #define QZ_DATA_ERROR (-4)

Input data was corrupted

- 6.1.1.8 #define QZ_DATA_FORMAT_DEFAULT QZ_DEFLATE_GZIP_EXT
- 6.1.1.9 #define QZ_DEFLATE ((unsigned char)8)
- 6.1.1.10 #define QZ_DIRECTION_DEFAULT QZ_DIR_BOTH
- 6.1.1.11 #define QZ_DUPLICATE (1)

Can not process function again. No failure.

6.1.1.12 #define QZ_FAIL (-2)

Unspecified error

- 6.1.1.13 #define QZ_FORCE_SW (2)
- using SW: Switch to software because of previous block
- $6.1.1.14 \quad \hbox{\#define QZ_HUFF_HDR_DEFAULT QZ_DYNAMIC_HDR}$
- 6.1.1.15 #define QZ_HW_BUFF_MAX_SZ (512*1024)
- 6.1.1.16 #define QZ_HW_BUFF_MIN_SZ (1*1024)
- 6.1.1.17 #define QZ_HW_BUFF_SZ (64*1024)

32 File Documentation

```
6.1.1.18 #define QZ_LOW_MEM (14)
using SW: Not enough pinned memory
6.1.1.19 #define QZ_LZ4 ((unsigned char)'4')
6.1.1.20 #define QZ_MAX_ALGORITHMS ((int)255)
6.1.1.21 #define QZ_MAX_FORK_DEFAULT 3
6.1.1.22 #define QZ_MEMCPY( dest, src, dest_sz, src_sz ) memcpy((void *)(dest), (void *) (src), (size_t)MIN(dest_sz,
        src_sz))
6.1.1.23 #define QZ_NO_HW (11)
using SW: No QAT HW detected
6.1.1.24 #define QZ_NO_INST_ATTACH (13)
using SW: Could not attach to an instance
6.1.1.25 #define QZ_NO_MDRV (12)
using SW: No memory driver detected
6.1.1.26 #define QZ_NONE (100)
device uninitialzied
6.1.1.27 #define QZ_NOSW_LOW_MEM (-104)
not using SW: not enough pinned memory
6.1.1.28 #define QZ_NOSW_NO_HW (-101)
not using SW: No QAT HW detected
6.1.1.29 #define QZ_NOSW_NO_INST_ATTACH (-103)
not using SW: Could not attach to instance
6.1.1.30 #define QZ_NOSW_NO_MDRV (-102)
not using SW: No memory driver detected
6.1.1.31 #define QZ_PARAMS (-1)
invalid parameter in function call
```

6.1.2 Function Documentation

6.1.2.1 unsigned int qzMaxCompressedLength (unsigned int src_sz)

6.1.1.32 #define QZ_POLL_SLEEP_DEFAULT 10
6.1.1.33 #define QZ_REQ_CNV_DEFAULT 1
6.1.1.34 #define QZ_REQ_THRESHOLD_DEFAULT QZ_REQ_THRESHOLD_MAXINUM
6.1.1.35 #define QZ_REQ_THRESHOLD_MAXINUM NUM_BUFF
6.1.1.36 #define QZ_REQ_THRESHOLD_MINIMUM 1
6.1.1.37 #define QZ_SNAPPY ((unsigned char)'S')
6.1.1.38 #define QZ_STRM_BUFF_MAX_SZ (2*1024*1024 - 5*1024)
6.1.1.39 #define QZ_STRM_BUFF_MIN_SZ (1*1024)
6.1.1.40 #define QZ_STRM_BUFF_SZ_DEFAULT QZ_HW_BUFF_SZ
6.1.1.41 #define QZ_SW_BACKUP_DEFAULT 1
6.1.1.42 #define QZ_WAIT_CNT_THRESHOLD_DEFAULT 8

Generated on Wed Jun 20 2018 14:33:59 for QATzip by Doxygen

Index

alaa law	O-Cassian T 10
algo_hw	QzSession_T, 10
QzStatus_S, 26	QzSessionParams_T, 10
algo_sw	qzSetDefaults, 19
QzStatus_S, 26	qzSetupSession, 19
00111011111	QzStatus_T, 10
COMMON_MEM	qzTeardownSession, 20
Data Compression API, 10	data_fmt
comp_algorithm	QzSessionParams_S, 24
QzSessionParams_S, 24	direction
comp_lvl	QzSessionParams_S, 24
QzSessionParams_S, 24	
	enable_cnv
Data Compression API	QzSessionParams_S, 24
COMMON_MEM, 10	
NONE, 11	huffman_hdr
PINNED_MEM, 10	QzSessionParams_S, 25
QZ_ADLER, 11	hw_buff_sz
QZ CRC32, 10	QzSessionParams_S, 25
QZ CRC64, 10	hw_session_stat
QZ_DEFLATE_GZIP, 11	QzSession_S, 23
QZ_DEFLATE_GZIP_EXT, 11	hw_session_status
QZ DEFLATE RAW, 11	QzStatus_S, 26
QZ DIR BOTH, 11	- /
QZ DIR COMPRESS, 11	include/qatzip.h, 29
QZ_DIR_DECOMPRESS, 11	input_sz_thrshold
QZ_DYNAMIC_HDR, 12	QzSessionParams_S, 25
	internal
QZ_FMT_NUM, 11	QzSession_S, 23
QZ_STATIC_HDR, 12	Q2000icii_0, 20
Data Compression API, 7	MIN
PinMem_T, 10	qatzip.h, 31
QZ_OK, 8	max_forks
QZ_SKID_PAD_SZ, 8	QzSessionParams_S, 25
qzClose, 12	memory_alloced
qzCompress, 12	QzStatus_S, 26
qzCompressCrc, 13	Q23iaius_3, 20
QzCrcType_E, 10	NONE
QzCrcType_T, 9	Data Compression API, 11
QzDataFormat_E, 11	Bata Compression 7th 1, 11
QzDataFormat_T, 9	PINNED MEM
gzDecompress, 14	Data Compression API, 10
QzDirection_E, 11	PinMem T
QzDirection_T, 9	Data Compression API, 10
qzFree, 15	•
qzGetDefaults, 15	poll_sleep
qzGetStatus, 16	QzSessionParams_S, 25
QzHuffmanHdr_E, 11	QZ ADLER
QzHuffmanHdr T, 9	Data Compression API, 11
- ·	•
qzInit, 17	QZ_CRC32
qzMalloc, 18	Data Compression API, 10
qzMemFindAddr, 18	QZ_CRC64

INDEX 35

Data Compression API, 10	qatzip.h, 32
QZ_DEFLATE_GZIP	QZ_NOSW_LOW_MEM
Data Compression API, 11	qatzip.h, 32
QZ_DEFLATE_GZIP_EXT	QZ_NOSW_NO_HW
Data Compression API, 11	qatzip.h, 32
QZ_DEFLATE_RAW	QZ_NOSW_NO_MDRV
Data Compression API, 11	qatzip.h, 32
QZ_DIR_BOTH	QZ_OK
Data Compression API, 11	Data Compression API, 8
QZ_DIR_COMPRESS	QZ_PARAMS
Data Compression API, 11 QZ_DIR_DECOMPRESS	qatzip.h, 32
Data Compression API, 11	QZ_REQ_CNV_DEFAULT
QZ_DYNAMIC_HDR	qatzip.h, 33 QZ SKID PAD SZ
Data Compression API, 12	Data Compression API, 8
QZ_FMT_NUM	QZ_SNAPPY
Data Compression API, 11	qatzip.h, 33
QZ_STATIC_HDR	qat_hw_count
Data Compression API, 12	QzStatus_S, 26
QZ_BUF_ERROR	qat_instance_attach
qatzip.h, 31	QzStatus_S, 26
QZ DATA ERROR	qat_mem_drvr
qatzip.h, 31	QzStatus_S, 26
QZ DEFLATE	gat service stated
qatzip.h, 31	QzStatus_S, 26
QZ_DIRECTION_DEFAULT	qatzip.h
qatzip.h, 31	MIN, 31
QZ_DUPLICATE	QZ_BUF_ERROR, 31
qatzip.h, 31	QZ_DATA_ERROR, 31
QZ_FAIL	QZ_DEFLATE, 31
qatzip.h, 31	QZ_DUPLICATE, 31
QZ_FORCE_SW	QZ_FAIL, 31
qatzip.h, 31	QZ_FORCE_SW, 31
QZ_HUFF_HDR_DEFAULT	QZ_HW_BUFF_MAX_SZ, 31
qatzip.h, 31	QZ_HW_BUFF_MIN_SZ, 31
QZ_HW_BUFF_MAX_SZ	QZ_HW_BUFF_SZ, 31
qatzip.h, 31	QZ_LOW_MEM, 31
QZ_HW_BUFF_MIN_SZ	QZ_LZ4, <mark>32</mark>
qatzip.h, 31	QZ_MAX_ALGORITHMS, 32
QZ_HW_BUFF_SZ	QZ_MEMCPY, 32
qatzip.h, 31	QZ_NO_HW, 32
QZ_LOW_MEM	QZ_NO_INST_ATTACH, 32
qatzip.h, 31	QZ_NO_MDRV, 32
QZ_LZ4	QZ_NONE, 32
qatzip.h, 32	QZ_NOSW_LOW_MEM, 32
QZ_MAX_ALGORITHMS	QZ_NOSW_NO_HW, 32
qatzip.h, 32	QZ_NOSW_NO_MDRV, 32
QZ_MAX_FORK_DEFAULT	QZ_PARAMS, 32
qatzip.h, 32	QZ_REQ_CNV_DEFAULT, 33
QZ_MEMCPY	QZ_SNAPPY, 33
qatzip.h, 32	qzMaxCompressedLength, 33
QZ_NO_HW	qzClose
qatzip.h, 32	Data Compression API, 12
QZ_NO_INST_ATTACH	qzCompress
qatzip.h, 32 QZ_NO_MDRV	Data Compression API, 12 qzCompressCrc
qatzip.h, 32	Data Compression API, 13
QZ_NONE	QzCrcType_E
4	azororypo_L

36 INDEX

Data Compression API, 10	qzSetupSession
QzCrcType_T	Data Compression API, 19
Data Compression API, 9	QzStatus_S, 25
QzDataFormat_E	algo_hw, 26
Data Compression API, 11	algo_sw, 26
QzDataFormat_T	hw_session_status, 26
Data Compression API, 9	memory_alloced, 26
qzDecompress	qat_hw_count, 26
Data Compression API, 14	qat_instance_attach, 26
QzDirection E	qat_mem_drvr, 26
Data Compression API, 11	qat_service_stated, 26
QzDirection_T	using_huge_pages, 26
Data Compression API, 9	QzStatus_T
qzFree	Data Compression API, 10
Data Compression API, 15	qzTeardownSession
qzGetDefaults	Data Compression API, 20
Data Compression API, 15	,
qzGetStatus	req_cnt_thrshold
•	QzSessionParams_S, 25
Data Compression API, 16	
QzHuffmanHdr_E	strm_buff_sz
Data Compression API, 11	QzSessionParams_S, 25
QzHuffmanHdr_T	sw_backup
Data Compression API, 9	QzSessionParams_S, 25
qzInit	
Data Compression API, 17	thd_sess_stat
qzMalloc	QzSession_S, 23
Data Compression API, 18	total_in
qzMaxCompressedLength	QzSession_S, 23
qatzip.h, <mark>33</mark>	total_out
qzMemFindAddr	QzSession_S, 23
Data Compression API, 18	
QzSession_S, 23	using_huge_pages
hw_session_stat, 23	QzStatus_S, 26
internal, 23	
thd_sess_stat, 23	wait_cnt_thrshold
total_in, 23	QzSessionParams_S, 25
total_out, 23	
QzSession_T	
Data Compression API, 10	
QzSessionParams_S, 24	
comp_algorithm, 24	
comp_lvl, 24	
data fmt, 24	
direction, 24	
enable_cnv, 24	
huffman_hdr, 25	
hw_buff_sz, 25	
input_sz_thrshold, 25	
max_forks, 25	
poll_sleep, 25	
req_cnt_thrshold, 25	
- -	
strm_buff_sz, 25	
sw_backup, 25	
wait_cnt_thrshold, 25	
QzSessionParams_T	
Data Compression API, 10	
qzSetDefaults	
Data Compression API 19	