QATzip 0.2.5

Generated by Doxygen 1.8.5

Mon Jul 9 2018 14:36:16

# **Contents**

1	Mod	lule Inde	ex		1
	1.1	Module	es		1
2	Clas	s Index	(		3
	2.1	Class	List		3
3	File	Index			5
	3.1	File Lis	st		5
4	Mod	ule Doc	cumentati	ion	7
	4.1	Data C	Compression	on API	7
		4.1.1	Detailed	Description	8
		4.1.2	Macro D	Definition Documentation	8
			4.1.2.1	QZ_OK	8
			4.1.2.2	QZ_SKID_PAD_SZ	8
		4.1.3	Typedef	Documentation	9
			4.1.3.1	QzCrcType_T	9
			4.1.3.2	QzDataFormat_T	9
			4.1.3.3	QzDirection_T	9
			4.1.3.4	QzHuffmanHdr_T	9
			4.1.3.5	QzSession_T	10
			4.1.3.6	QzSessionParams_T	10
			4.1.3.7	QzStatus_T	10
			4.1.3.8	QzStream_T	10
		4.1.4	Enumera	ation Type Documentation	10
			4.1.4.1	PinMem_T	10
			4.1.4.2	QzCrcType_E	11
			4.1.4.3	QzDataFormat_E	11
			4.1.4.4	QzDirection_E	11
			4.1.4.5	QzHuffmanHdr_E	11
		4.1.5		Documentation	
			4151	azClese.	10

iv CONTENTS

			4.1.5.2	qzCompress	13
			4.1.5.3	qzCompressCrc	14
			4.1.5.4	qzCompressStream	14
			4.1.5.5	qzDecompress	15
			4.1.5.6	qzDecompressStream	16
			4.1.5.7	qzEndStream	17
			4.1.5.8	qzFree	18
			4.1.5.9	qzGetDefaults	18
			4.1.5.10	qzGetStatus	19
			4.1.5.11	qzInit	20
			4.1.5.12	qzMalloc	20
			4.1.5.13	qzMemFindAddr	21
			4.1.5.14	qzSetDefaults	22
			4.1.5.15	qzSetupSession	22
			4.1.5.16	qzTeardownSession	23
5	Clas	o Door	mentation		25
3	5.1			ruct Reference	2 <b>5</b>
	0.1	5.1.1	_	Description	25
		5.1.2		Data Documentation	25
		0.1.2	5.1.2.1	hw session stat	25
			5.1.2.2	internal	25
			5.1.2.3	thd_sess_stat	25
			5.1.2.4	total_in	25
			5.1.2.5	total_out	26
	5.2	QzSes		s_S Struct Reference	26
		5.2.1		Description	26
		5.2.2		Data Documentation	26
			5.2.2.1	comp_algorithm	26
			5.2.2.2	comp_lvl	26
			5.2.2.3	data fmt	26
			5.2.2.4	direction	26
			5.2.2.5	huffman_hdr	27
			5.2.2.6	hw_buff_sz	27
			5.2.2.7	input sz thrshold	27
			5.2.2.8	max_forks	27
			5.2.2.9	poll_sleep	27
			5.2.2.10	req_cnt_thrshold	27
			5.2.2.11	strm_buff_sz	27
			5.2.2.12	sw_backup	27

CONTENTS

			5.2.2.13	wait_cnt_thrshold	27
	5.3	QzStat	us_S Struc	ct Reference	27
		5.3.1	Detailed	Description	28
		5.3.2	Member	Data Documentation	28
			5.3.2.1	algo_hw	28
			5.3.2.2	algo_sw	28
			5.3.2.3	hw_session_status	28
			5.3.2.4	memory_alloced	28
			5.3.2.5	qat_hw_count	28
			5.3.2.6	qat_instance_attach	28
			5.3.2.7	qat_mem_drvr	28
			5.3.2.8	qat_service_stated	28
			5.3.2.9	using_huge_pages	29
	5.4	QzStre	am_S Stru	ıct Reference	29
		5.4.1	Detailed	Description	29
		5.4.2	Member	Data Documentation	29
			5.4.2.1	crc_32	29
			5.4.2.2	crc_64	29
			5.4.2.3	crc_type	29
			5.4.2.4	in	29
			5.4.2.5	in_sz	30
			5.4.2.6	opaque	30
			5.4.2.7	out	30
			5.4.2.8	out_sz	30
			5.4.2.9	pending_in	30
			5.4.2.10	pending_out	30
			5.4.2.11	reserved	30
					0.4
6			entation		31
	6.1			file Reference	31
		6.1.1		efinition Documentation	33
			6.1.1.1	MIN	33
			6.1.1.2	QZ_BUF_ERROR	33
			6.1.1.3	QZ_COMP_ALGOL_DEFAULT	33
			6.1.1.4	QZ_COMP_LEVEL_DEFAULT	33
			6.1.1.5	QZ_COMP_THRESHOLD_DEFAULT	33
			6.1.1.6	QZ_COMP_THRESHOLD_MINIMUM	33
			6.1.1.7	QZ_DATA_ERROR	33
			6.1.1.8	QZ_DATA_FORMAT_DEFAULT	33
			6.1.1.9	QZ_DEFLATE	33

vi CONTENTS

	6.1.1.10	QZ_DIRECTION_DEFAULT	33
	6.1.1.11	QZ_DUPLICATE	33
	6.1.1.12	QZ_FAIL	33
	6.1.1.13	QZ_FORCE_SW	33
	6.1.1.14	QZ_HUFF_HDR_DEFAULT	34
	6.1.1.15	QZ_HW_BUFF_MAX_SZ	34
	6.1.1.16	QZ_HW_BUFF_MIN_SZ	34
	6.1.1.17	QZ_HW_BUFF_SZ	34
	6.1.1.18	QZ_LOW_MEM	34
	6.1.1.19	QZ_LZ4	34
	6.1.1.20	QZ_MAX_ALGORITHMS	34
	6.1.1.21	QZ_MAX_FORK_DEFAULT	34
	6.1.1.22	QZ_MEMCPY	34
	6.1.1.23	QZ_NO_HW	34
	6.1.1.24	QZ_NO_INST_ATTACH	34
	6.1.1.25	QZ_NO_MDRV	34
	6.1.1.26	QZ_NONE	34
	6.1.1.27	QZ_NOSW_LOW_MEM	34
	6.1.1.28	QZ_NOSW_NO_HW	34
	6.1.1.29	QZ_NOSW_NO_INST_ATTACH	34
	6.1.1.30	QZ_NOSW_NO_MDRV	34
	6.1.1.31	QZ_PARAMS	35
	6.1.1.32	QZ_POLL_SLEEP_DEFAULT	35
	6.1.1.33	QZ_REQ_THRESHOLD_DEFAULT	35
	6.1.1.34	QZ_REQ_THRESHOLD_MAXINUM	35
	6.1.1.35	QZ_REQ_THRESHOLD_MINIMUM	35
	6.1.1.36	QZ_SNAPPY	35
	6.1.1.37	QZ_STRM_BUFF_MAX_SZ	35
	6.1.1.38	QZ_STRM_BUFF_MIN_SZ	35
	6.1.1.39	QZ_STRM_BUFF_SZ_DEFAULT	35
	6.1.1.40	QZ_SW_BACKUP_DEFAULT	35
	6.1.1.41	QZ_WAIT_CNT_THRESHOLD_DEFAULT	35
6.1.2	Function	Documentation	35
	6.1.2.1	qzMaxCompressedLength	35

Index 36

# Chapter 1

# **Module Index**

1.1	Modules
Here	is a list of all modules:
Da	ata Compression API

2 **Module Index** 

# Chapter 2

# **Class Index**

## 2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:

QzSession_S	25
QzSessionParams_S	26
QzStatus_S	27
QzStream_S	29

Class Index

# **Chapter 3**

# File Index

3.1	File List	
Here i	is a list of all files with brief descriptions:	

 $include/qatzip.h \\ \ \ldots \\ \ \ldots$ 

6 File Index

## Chapter 4

## **Module Documentation**

## 4.1 Data Compression API

## Classes

- struct QzSessionParams\_S
- struct QzSession\_S
- struct QzStatus\_S
- struct QzStream S

#### **Macros**

- #define QZ OK (0)
- #define QZ\_SKID\_PAD\_SZ 48

## **Typedefs**

- typedef enum QzHuffmanHdr\_E QzHuffmanHdr\_T
- typedef enum QzDirection\_E QzDirection\_T
- typedef enum QzDataFormat\_E QzDataFormat\_T
- typedef enum QzCrcType\_E QzCrcType\_T
- typedef struct QzSessionParams\_S QzSessionParams\_T
- typedef struct QzSession\_S QzSession\_T
- typedef struct QzStatus\_S QzStatus\_T
- typedef struct QzStream\_S QzStream\_T

## **Enumerations**

- enum QzHuffmanHdr\_E { QZ\_DYNAMIC\_HDR = 0, QZ\_STATIC\_HDR }
- enum PinMem T { COMMON MEM = 0, PINNED MEM }
- enum QzDirection\_E { QZ\_DIR\_COMPRESS = 0, QZ\_DIR\_DECOMPRESS, QZ\_DIR\_BOTH }
- enum QzDataFormat\_E { QZ\_DEFLATE\_RAW = 0, QZ\_DEFLATE\_GZIP, QZ\_DEFLATE\_GZIP\_EXT, QZ\_FMT\_NUM }
- enum QzCrcType\_E { QZ\_CRC32 = 0, QZ\_CRC64, QZ\_ADLER, NONE }

#### **Functions**

- int qzInit (QzSession T \*sess, unsigned char sw backup)
- int qzSetupSession (QzSession\_T \*sess, QzSessionParams\_T \*params)
- int qzCompress (QzSession\_T \*sess, const unsigned char \*src, unsigned int \*src\_len, unsigned char \*dest, unsigned int \*dest\_len, unsigned int last)
- int qzCompressCrc (QzSession\_T \*sess, const unsigned char \*src, unsigned int \*src\_len, unsigned char \*dest, unsigned int \*dest\_len, unsigned int last, unsigned long \*crc)
- int qzDecompress (QzSession\_T \*sess, const unsigned char \*src, unsigned int \*src\_len, unsigned char \*dest, unsigned int \*dest\_len)
- int qzTeardownSession (QzSession T \*sess)
- int qzClose (QzSession T \*sess)
- int qzGetStatus (QzSession T \*sess, QzStatus T \*status)
- int qzSetDefaults (QzSessionParams\_T \*defaults)
- int gzGetDefaults (QzSessionParams T \*defaults)
- void \* qzMalloc (size\_t sz, int numa, int force\_pinned)
- void qzFree (void \*m)
- int qzMemFindAddr (unsigned char \*a)
- int qzCompressStream (QzSession T \*sess, QzStream T \*strm, unsigned int last)
- int gzDecompressStream (QzSession T \*sess, QzStream T \*strm, unsigned int last)
- int qzEndStream (QzSession\_T \*sess, QzStream\_T \*strm)

## 4.1.1 Detailed Description

These functions specify the API for Data Compression operations.

Remarks

## 4.1.2 Macro Definition Documentation

4.1.2.1 #define QZ\_OK (0)

QATZIP Session Status definitions and function return codes

This list identifies valid values for session status and function return codes. Success

## 4.1.2.2 #define QZ\_SKID\_PAD\_SZ 48

Get the max compressed output length

Get the max compressed output length

This function shall not be called in an interrupt context. None None Yes No Yes

## **Parameters**

in	src_sz	Input data length in byte.

## Return values

dest_sz	Max compressed data output length in byte. When src_sz equal to 0, the return
	value is 0.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

## 4.1.3 Typedef Documentation

## 4.1.3.1 typedef enum QzCrcType\_E QzCrcType\_T

Supported checksum type

This enumerated list identifies the checksum type for input/output data. A format can be CRC32, CRC64, Adler or none.

## 4.1.3.2 typedef enum QzDataFormat\_E QzDataFormat\_T

Streaming API input and output format

This enumerated list identifies the data format supported by QATZip streaming API. A format can be raw deflate data block, deflate block wrapped by GZip header and footer, or deflate data block wrapped by GZip extension header and footer.

## 4.1.3.3 typedef enum QzDirection\_E QzDirection\_T

Compress or decompress setting

This enumerated list identifies the session directions supported by QATZip. A session can be compress, decompress or both.

#### 4.1.3.4 typedef enum QzHuffmanHdr E QzHuffmanHdr T

This API provides access to underlying compression functions in QAT hardware. The API supports an implementation that provides compression service in software if not all of the required resources are not available to execute the compression service in hardware.

The API supports threaded applications. Applications can create threads and each of these threads can invoke the API defined herein.

For simplicity, initializations and setup function calls are not required to obtain compression services. If the initialization and setup functions are not called before compression or decompression requests, then they will be called with default arguments from within the compression or decompression functions. This results in several legal calling scenarios, described below.

Scenario 1 - all functions explicitly invoked by caller, with all arguments provided

qzInit(&sess\_c, sw\_backup); qzSetupSession(&sess\_c, &params); qzCompress(&sess, src, &src\_len, dest, &dest\_len, 1); qzDecompress(&sess, src, &src\_len, dest, &dest\_len); qzTeardownSession(&sess); qzClose(&sess);

Scenario 2 - initialization function called, setup function not invoked by caller. This scenario can be used to specify the sw\_backup argument to qzInit.

qzInit(&sess, sw\_backup); qzCompress(&sess, src, &src\_len, dest, &dest\_len, 1); calls qzSetupSession(sess, NU-LL); qzTeardownSession(&sess); qzClose(&sess);

Scenario 3 - calling application simply invokes the actual qzCompress functions

qzCompress(&sess, src, &src\_len, dest, &dest\_len, 0); calls qzInit sess, 1); calls qzSetupSession(sess, NULL); qzCompress(&sess, src, &src\_len, dest, &dest\_len, 1);

Notes: Invoking qzSetupSession with NULL for params sets up a session with default session attributed, detailed in the function description below.

If an application terminates with out invoking tear down and close functions, process termination will invoke memory and hardware instance cleanup.

If a thread terminates without invoking tear down and close functions, memory and hardware are not cleanup until the application exits.

```
Supported Huffman Headers
```

This enumerated list identifies the Huffman header types supported by QATZip

4.1.3.5 typedef struct QzSession\_S QzSession\_T

QATZIP Session opaque data storage

This structure contains a pointer to a structure with session state

4.1.3.6 typedef struct QzSessionParams\_S QzSessionParams\_T

**QATZIP** Session Initialization parameters

This structure contains data for initializing a session

4.1.3.7 typedef struct QzStatus\_S QzStatus\_T

QATZIP status structure

This structure contains data relating to the stat usof QAT on the platform

4.1.3.8 typedef struct QzStream\_S QzStream\_T

QATZIP Stream data storage

This structure contains metadata needed for stream operation

4.1.4 Enumeration Type Documentation

4.1.4.1 enum PinMem\_T

Supported memory types

This enumerated list identifies memory types supported by QATZip.

**Enumerator** 

**COMMON\_MEM** Allocate non-continous memory **PINNED\_MEM** Allocate continous memory

## 4.1.4.2 enum QzCrcType\_E

Supported checksum type

This enumerated list identifies the checksum type for input/output data. A format can be CRC32, CRC64, Adler or none.

#### **Enumerator**

QZ\_CRC32 CRC32 checksumQZ\_CRC64 CRC64 checksumQZ\_ADLER Adler checksumNONE No checksum

## 4.1.4.3 enum QzDataFormat\_E

Streaming API input and output format

This enumerated list identifies the data format supported by QATZip streaming API. A format can be raw deflate data block, deflate block wrapped by GZip header and footer, or deflate data block wrapped by GZip extension header and footer.

#### Enumerator

```
    QZ_DEFLATE_RAW Data is in raw deflate format
    QZ_DEFLATE_GZIP Data is in deflate wrappped by GZip header and footer
    QZ_DEFLATE_GZIP_EXT Data is in deflate warpped by GZip extension header and footer
    QZ_FMT_NUM
```

## 4.1.4.4 enum QzDirection\_E

Compress or decompress setting

This enumerated list identifies the session directions supported by QATZip. A session can be compress, decompress or both.

#### Enumerator

```
    QZ_DIR_COMPRESS Session will be used for compression
    QZ_DIR_DECOMPRESS Session will be used for decompression
    QZ_DIR_BOTH Session will be used for both compression and decompression
```

## 4.1.4.5 enum QzHuffmanHdr\_E

This API provides access to underlying compression functions in QAT hardware. The API supports an implementation that provides compression service in software if not all of the required resources are not available to execute the compression service in hardware.

The API supports threaded applications. Applications can create threads and each of these threads can invoke the API defined herein.

For simplicity, initializations and setup function calls are not required to obtain compression services. If the initialization and setup functions are not called before compression or decompression requests, then they will be called with default arguments from within the compression or decompression functions. This results in several legal calling scenarios, described below.

Scenario 1 - all functions explicitly invoked by caller, with all arguments provided

qzInit(&sess\_c, sw\_backup); qzSetupSession(&sess\_c, &params); qzCompress(&sess, src, &src\_len, dest, &dest\_len, 1); qzDecompress(&sess, src, &src\_len, dest, &dest\_len); qzTeardownSession(&sess); qzClose(&sess);

Scenario 2 - initialization function called, setup function not invoked by caller. This scenario can be used to specify the sw\_backup argument to qzInit.

qzInit(&sess, sw\_backup); qzCompress(&sess, src, &src\_len, dest, &dest\_len, 1); calls qzSetupSession(sess, NU-LL); qzTeardownSession(&sess); qzClose(&sess);

Scenario 3 - calling application simply invokes the actual qzCompress functions

qzCompress(&sess, src, &src\_len, dest, &dest\_len, 0); calls qzInit sess, 1); calls qzSetupSession(sess, NULL); qzCompress(&sess, src, &src\_len, dest, &dest\_len, 1);

Notes: Invoking qzSetupSession with NULL for params sets up a session with default session attributed, detailed in the function description below.

If an application terminates with out invoking tear down and close functions, process termination will invoke memory and hardware instance cleanup.

If a thread terminates without invoking tear down and close functions, memory and hardware are not cleanup until the application exits.

```
Supported Huffman Headers
```

This enumerated list identifies the Huffman header types supported by QATZip

#### Enumerator

**QZ\_DYNAMIC\_HDR** Full Dynamic Huffman Trees **QZ\_STATIC\_HDR** Static Huffman Trees

## 4.1.5 Function Documentation

4.1.5.1 int qzClose ( QzSession\_T \* sess )

```
terminates a QATZip session
```

This function closes the connection with QAT

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	sess	pointer to session data

## Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

#### See Also

None

4.1.5.2 int qzCompress ( QzSession\_T \* sess, const unsigned char \* src, unsigned int \* src\_len, unsigned char \* dest, unsigned int \* dest\_len, unsigned int last )

compress a buffer

This function will compress a buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of \*sess - then this function will attempt to set up a session using qzInit and qzSetupSession.

The resulting compressed block of data will be composed of one or more gzip blocks per RFC 1952.

This function will place completed compression blocks in the output buffer.

The caller must check the updated src\_len. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter dest\_len will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	sess	Session handle
in	src	point to source buffer
in,out	src_len	length of source buffer. Modified to number of bytes consumed
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of compressed data when func-
		tion returns
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'

## Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.3 int qzCompressCrc ( QzSession\_T \* sess, const unsigned char \* src, unsigned int \* src\_len, unsigned char \* dest, unsigned int \* dest\_len, unsigned int last, unsigned long \* crc )

```
compress a buffer and return the CRC checksum
```

This function will compress a buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of \*sess - then this function will attempt to set up a session using qzInit and qzSetupSession.

The resulting compressed block of data will be composed of one or more gzip blocks per RFC 1952.

This function will place completed compression blocks in the output buffer and put CRC32 checksum for compressed input data in user provided bufer \*crc.

The caller must check the updated src\_len. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter dest\_len will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	sess	Session handle
in	src	point to source buffer
in,out	src_len	length of source buffer. Modified to number of bytes consumed
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of compressed data when func-
		tion returns
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'
in,out	crc	point to CRC32 checksum buffer

### Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.4 int qzCompressStream ( QzSession\_T \* sess, QzStream\_T \* strm, unsigned int last )

compress data in stream and return checksum

This function will compress data in stream buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of \*sess - then this function will attempt to set up a session using qzInit and qzSetupSession. The function will start to compress the data when receiving sufficient number of bytes - as defined by hw\_buf\_sz in QzSessionParams\_T - or reaching the end of input data - as indicated by last parameter.

The resulting compressed block of data will be composed of one or more gzip blocks per RFC 1952 or deflate blocks per RFC 1951.

This function will place completed compression blocks in the \*out of QzStream\_T structure and put checksum for compressed input data in crc32/crc64 of QzStream\_T structure.

The caller must check the updated in\_sz of QzStream\_T. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter out\_sz in QzStream\_T will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

The caller must check the updated pending\_in of QzStream\_T. This value will be the number of unprocessed bytes held in QATZip. The calling API may have to feed more input data or indicate reaching the end of input and call again.

The caller must check the updated pending\_out of QzStream\_T. This value will be the number of processed bytes held in QATZip. The calling API may have to process the destination buffer and call again.

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	sess	Session handle
in,out	strm	Stream handle
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'

### Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.5 int qzDecompress ( QzSession\_T \* sess, const unsigned char \* src, unsigned int \* src\_len, unsigned char \* dest, unsigned int \* dest\_len )

decompress a buffer

This function will decompress a buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of \*sess - then this function will attempt to set up a session using qzInit and qzSetupSession.

The input compressed block of data will be composed of one or more gzip blocks per RFC1952.

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	sess	Session handle
in	src	point to source buffer
in	src_len	length of source buffer. Modified to length of processed compressed data
		when function returns
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of decompressed data when
		function returns

#### Return values

G	Z_OK	Function executed successfully.
QZ	_FAIL	Function did not succeed.
QZ_PA	RAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.6 int qzDecompressStream ( QzSession\_T \* sess, QzStream\_T \* strm, unsigned int last )

decompress data in stream and return checksum

This function will decompress data in stream buffer if either a hardware based session or a software based session is available. If no session has been established - as indicated by the contents of \*sess - then this function will attempt to set up a session using qzInit and qzSetupSession. The function will start to decompress the data when receiving sufficient number of bytes - as defined by hw\_buf\_sz in QzSessionParams\_T - or reaching the end of input data - as indicated by last parameter.

The input compressed block of data will be composed of one or more gzip blocks per RFC 1952 or deflate blocks per RFC 1951.

This function will place completed uncompression blocks in the \*out of QzStream\_T structure and put checksum for uncompressed data in crc32/crc64 of QzStream\_T structure.

The caller must check the updated in\_sz of QzStream\_T. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter out\_sz in QzStream\_T will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

The caller must check the updated pending\_in of QzStream\_T. This value will be the number of unprocessed bytes held in QATZip. The calling API may have to feed more input data or indicate reaching the end of input and call again.

The caller must check the updated pending\_out of QzStream\_T. This value will be the number of processed bytes held in QATZip. The calling API may have to process the destination buffer and call again.

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	sess	Session handle
in,out	strm	Stream handle
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'

#### Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid
QZ_NEED_MORE	*last is set but end of block is absent

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.7 int qzEndStream ( QzSession\_T \* sess, QzStream\_T \* strm )

terminates a QATZip stream

This function disconnect stream handle from session handle then reset stream flag and release stream memory.

This function shall not be called in an interrupt context. None None Yes No Yes

## **Parameters**

in	sess	pointer to session data

## **Return values**

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ PARAMS	*sess is NULL or member of params is invalid

## Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.8 void qzFree (void \*m)

Free allocated memory

Free allocated memory

This function shall not be called in an interrupt context. None None Yes No Yes

**Parameters** 

in	m	Memory address to be freed.
----	---	-----------------------------

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.9 int qzGetDefaults ( QzSessionParams\_T \* defaults )

Get default QzSessionParams\_T value

Get default QzSessionParams\_T value

This function shall not be called in an interrupt context. None None Yes No Yes

**Parameters** 

in	defaults	The pointer to default value.

#### Return values

QZ_OK	Success on getting default value.
QZ_PARAM	Fail to get default value.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.10 int qzGetStatus ( QzSession\_T \* sess, QzStatus\_T \* status )

Get current QAT status

This function retrieves the status of QAT in the platform. The status structure will be filled in as follows: qat\_hw\_count number of discovered QAT devices on PCU bus qat\_service\_stated 1 if qzInit has been successfully run, 0 otherwise qat\_mem\_drvr 1 if the QAT memory driver is installed, 0 otherwise qat\_instance\_attach 1 if session has attached to a hardware instance, 0 otherwise memory\_alloced amount of memory, in kilobytes, from kernel or huge pages allocated by this process/thread. using\_huge\_pages 1 if memory is being allocated from huge pages, 0 if memory is being allocated from standard kernel memory hw\_session\_stat Hw session status: one of: QZ\_OK QZ\_FAIL QZ\_NO\_HW QZ\_NO\_MDRV QZ\_NO\_INST\_ATTACH QZ\_LOW\_MEM QZ\_NOSW\_NO\_HW QZ\_NOSW\_NO\_HW QZ\_NOSW\_NO\_HW QZ\_NOSW\_LOW\_MEM

This function shall not be called in an interrupt context. None None Yes No Yes

## **Parameters**

in	sess	pointer to opaque instance and session data.
in	status	pointer to QATZIP status structure.

## Return values

QZ_OK	Function executed successfully. A hardware based compression session has
	been created.
QZ_PARAMS	*status is NULL

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

## 4.1.5.11 int qzInit ( QzSession\_T \* sess, unsigned char sw\_backup )

Initialize QAT hardware

This function initializes the QAT hardware. This function is optional in the function calling sequence. If desired, this call can be made to avoid latency impact during the first call to qzDecompress or qzCompress, or to set the sw\_backup parameter explicitly. The input parameter sw\_backup specifies the behavior of the function and that of the functions called with the same session in the event there are insufficient resources to establish a QAT based compression or decompression session.

Required resources include access to the QAT hardware, contiguous pinned memory for mmaping the hardware rings, and contiguous pinned memory for buffers.

This function shall not be called in an interrupt context. None This function will: 1) start the user space driver if necessary 2) allocate all hardware instances available Yes No Yes

#### **Parameters**

in	sess	pointer to opaque instance and session data.
in	sw_backup	0 for no sw backup, 1 for sw backup

#### Return values

QZ_OK	Function executed successfully. A hardware or sw instance has been allocated to
	the calling process/thread.
QZ_DUPLICATE	This process/thread already has a hardware instance
QZ_PARAMS	*sess is NULL
QZ_NOSW_NO_HW	No hardware and no sw session being established
QZ_NOSW_NO_MDRV	No memory driver. No software session established
QZ_NOSW_NO_INST_AT-	No instance avail. No software session established
TACH	
QZ_NOSW_LOW_MEM	Not enough pinned memory available. No software session established

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.12 void\* qzMalloc ( size\_t sz, int numa, int force\_pinned )

Allocate different types of memory

Allocate different types of memory

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	SZ	Memory size to be allocated.
in	numa	NUMA node from which to allocate memory
in	force_pinned	PINNED_MEM allocate continous memory COMMON_MEM allocate non-
		continous memory

## Return values

NULL	Fail to allocate memory
adress	The address to allocated memory

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.13 int qzMemFindAddr ( unsigned char \* a )

Check whether the address is available

Check whether the address is available

This function shall not be called in an interrupt context. None None Yes No Yes

## **Parameters**

	in	а	Address need to be checked
--	----	---	----------------------------

## Return values

1	The Address is available
0	The address is not available

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

## 4.1.5.14 int qzSetDefaults ( QzSessionParams\_T \* defaults )

Set default QzSessionParams\_T value

Set default QzSessionParams\_T value

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in	defaults	The pointer to value to be set as default.

#### Return values

QZ_OK	Success on setting default value.
QZ_PARAM	Fail to set default value.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

## 4.1.5.15 int qzSetupSession ( QzSession\_T \* sess, QzSessionParams\_T \* params )

```
initialize a QATZip session
```

This function establishes a QAT session. This involves associating a hardware instance to the session, allocating buffers. If all of these activities can not be completed successfully, then this function will set up a software based session of param->sw\_backup is set to 1.

Before this function is called, the hardware must have been successfully started via qzInit.

If \*sess includes an existing hardware or software session, then this session will be torn down before a new one is attempted.

This function shall not be called in an interrupt context. None None Yes No Yes

## **Parameters**

in	sess	Session handle
in	params	Parameters for session

## Return values

QZ_OK	Function executed successfully. A hardware or sw based compression session
	has been created.

QZ_PARAMS	*sess is NULL or member of params is invalid
QZ_NOSW_NO_HW	No hardware and no sw session being established
QZ_NOSW_NO_MDRV	No memory driver. No software session established
QZ_NOSW_NO_INST_AT-	No instance avail. No software session established
TACH	
QZ_NO_LOW_MEM	Not enough pinned memory available. No software session established

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.16 int qzTeardownSession ( QzSession\_T \* sess )

Deinitialize a QATZip session

This function disconnects a session from a hardware instance and deallocates buffers. If no session has been initialized, then no action will take place.

This function shall not be called in an interrupt context. None None Yes No Yes

#### **Parameters**

in sess Session handle
------------------------

## Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

## **Chapter 5**

## **Class Documentation**

## 5.1 QzSession\_S Struct Reference

```
#include <qatzip.h>
```

## **Public Attributes**

- · signed long int hw session stat
- int thd\_sess\_stat
- void \* internal
- unsigned long total\_in
- unsigned long total\_out

## 5.1.1 Detailed Description

QATZIP Session opaque data storage

This structure contains a pointer to a structure with session state

## 5.1.2 Member Data Documentation

5.1.2.1 signed long int QzSession\_S::hw\_session\_stat

filled in during initialization, session startup and decompression

5.1.2.2 void\* QzSession\_S::internal

session data is opaque to outside world

5.1.2.3 int QzSession\_S::thd\_sess\_stat

note process compression and decompression thread state

5.1.2.4 unsigned long QzSession\_S::total\_in

Total processed input data length in this session

26 Class Documentation

## 5.1.2.5 unsigned long QzSession\_S::total\_out

Total output data length in this session

The documentation for this struct was generated from the following file:

include/qatzip.h

## 5.2 QzSessionParams\_S Struct Reference

```
#include <qatzip.h>
```

## **Public Attributes**

- QzHuffmanHdr\_T huffman\_hdr
- QzDirection\_T direction
- QzDataFormat\_T data\_fmt
- unsigned int comp\_lvl
- unsigned char comp\_algorithm
- · unsigned int poll sleep
- unsigned int max\_forks
- unsigned char sw\_backup
- · unsigned int hw buff sz
- unsigned int strm\_buff\_sz
- unsigned int input\_sz\_thrshold
- unsigned int req\_cnt\_thrshold
- · unsigned int wait\_cnt\_thrshold

## 5.2.1 Detailed Description

**QATZIP** Session Initialization parameters

This structure contains data for initializing a session

## 5.2.2 Member Data Documentation

5.2.2.1 unsigned char QzSessionParams\_S::comp\_algorithm

Compress/decompression algorithms

5.2.2.2 unsigned int QzSessionParams\_S::comp\_lvl

Compression level 1..9

5.2.2.3 QzDataFormat T QzSessionParams\_S::data\_fmt

defalte, deflate with GZip or deflate with GZip ext

5.2.2.4 QzDirection T QzSessionParams\_S::direction

compress or decompress

5.2.2.5 QzHuffmanHdr\_T QzSessionParams\_S::huffman\_hdr

Dynamic or Static Huffman headers

5.2.2.6 unsigned int QzSessionParams\_S::hw\_buff\_sz

default buffer size, Must be a power of 2 4K,8K,16K,32K,64K,128K

5.2.2.7 unsigned int QzSessionParams\_S::input\_sz\_thrshold

default threshold of compression service's input size for sw failover, if the size of input request less than the threshold, QATZip will route the request to software

5.2.2.8 unsigned int QzSessionParams\_S::max\_forks

maximum forks permitted in the current thread. 0 means no forking permitted

5.2.2.9 unsigned int QzSessionParams\_S::poll\_sleep

nanosleep between poll [0..1000] 0 means no sleep

5.2.2.10 unsigned int QzSessionParams\_S::req\_cnt\_thrshold

set between 1 and 4, default 4

5.2.2.11 unsigned int QzSessionParams\_S::strm\_buff\_sz

stream buffer size between [1K .. 2M - 5K] default strm\_buf\_sz equals to hw\_buff\_sz

5.2.2.12 unsigned char QzSessionParams\_S::sw\_backup

0 means no sw backup, 1 means sw backup

5.2.2.13 unsigned int QzSessionParams\_S::wait\_cnt\_thrshold

when previous try failed, wait for specific number of call before retry device open. default threshold is 8 The documentation for this struct was generated from the following file:

• include/qatzip.h

## 5.3 QzStatus\_S Struct Reference

#include <qatzip.h>

### **Public Attributes**

- unsigned short int qat\_hw\_count
- · unsigned char gat service stated
- unsigned char qat\_mem\_drvr

28 Class Documentation

- · unsigned char qat\_instance\_attach
- · unsigned long int memory\_alloced
- unsigned char using\_huge\_pages
- signed long int hw\_session\_status
- unsigned char algo sw [QZ MAX ALGORITHMS]
- unsigned char algo\_hw [QZ\_MAX\_ALGORITHMS]

## 5.3.1 Detailed Description

QATZIP status structure

This structure contains data relating to the stat usof QAT on the platform

- 5.3.2 Member Data Documentation
- 5.3.2.1 unsigned char QzStatus\_S::algo\_hw[QZ\_MAX\_ALGORITHMS]

count of hardware devices supporting algorithms

5.3.2.2 unsigned char QzStatus\_S::algo\_sw[QZ\_MAX\_ALGORITHMS]

support software algorithms

5.3.2.3 signed long int QzStatus\_S::hw\_session\_status

One of QATZIP Session Status

5.3.2.4 unsigned long int QzStatus\_S::memory\_alloced

Amount of memory allocated by this thread/process

5.3.2.5 unsigned short int QzStatus\_S::qat\_hw\_count

from PCI scan

5.3.2.6 unsigned char QzStatus\_S::qat\_instance\_attach

Is this thread/g\_process properly attached to an Instance?

- 5.3.2.7 unsigned char QzStatus\_S::qat\_mem\_drvr
- 1 if /dev/qat\_mem exists 2 if /dev/qat\_mem has been opened 0 otherwise
- 5.3.2.8 unsigned char QzStatus\_S::qat\_service\_stated

Check if the QAT service is properly running on at least one device

## 5.3.2.9 unsigned char QzStatus\_S::using\_huge\_pages

Are memory slabs coming from huge pages

The documentation for this struct was generated from the following file:

• include/qatzip.h

## 5.4 QzStream\_S Struct Reference

```
#include <qatzip.h>
```

## **Public Attributes**

- · unsigned int in sz
- unsigned int out\_sz
- unsigned char \* in
- unsigned char \* out
- unsigned int pending\_in
- unsigned int pending\_out
- QzCrcType\_T crc\_type
- unsigned int crc\_32
- unsigned long long crc\_64
- · unsigned long long reserved
- void \* opaque

## 5.4.1 Detailed Description

QATZIP Stream data storage

This structure contains metadata needed for stream operation

## 5.4.2 Member Data Documentation

5.4.2.1 unsigned int QzStream\_S::crc\_32

Checksum value

5.4.2.2 unsigned long long QzStream\_S::crc\_64

Checksum value for 64bit CRC

5.4.2.3 QzCrcType\_T QzStream\_S::crc\_type

Checksum type in Adler, CRC32, CRC64 or none

5.4.2.4 unsigned char\* QzStream\_S::in

Input data pointer set by application

30 Class Documentation

5.4.2.5 unsigned int QzStream\_S::in\_sz

Set by application, reset by QATZip to indicate consumed data

5.4.2.6 void\* QzStream\_S::opaque

Internal storage managed by QATZip

5.4.2.7 unsigned char\* QzStream\_S::out

Output data pointer set by application

5.4.2.8 unsigned int QzStream\_S::out\_sz

Set by application, reset by QATZip to indicate processed data

5.4.2.9 unsigned int QzStream\_S::pending\_in

Unprocessed bytes held in QATZip

5.4.2.10 unsigned int QzStream\_S::pending\_out

Processed bytes held in QATZip

5.4.2.11 unsigned long long QzStream\_S::reserved

CRC64 polynomial

The documentation for this struct was generated from the following file:

· include/qatzip.h

## **Chapter 6**

## **File Documentation**

## 6.1 include/qatzip.h File Reference

```
#include <string.h>
```

## Classes

- struct QzSessionParams\_S
- struct QzSession\_S
- struct QzStatus S
- struct QzStream\_S

#### **Macros**

- #define QZ\_OK (0)
- #define QZ\_DUPLICATE (1)
- #define QZ\_FORCE\_SW (2)
- #define QZ PARAMS (-1)
- #define QZ FAIL (-2)
- #define QZ\_BUF\_ERROR (-3)
- #define QZ\_DATA\_ERROR (-4)
- #define QZ\_NO\_HW (11)
- #define QZ\_NO\_MDRV (12)
- #define QZ\_NO\_INST\_ATTACH (13)
- #define QZ\_LOW\_MEM (14)
- #define QZ\_NONE (100)
- #define QZ\_NOSW\_NO\_HW (-101)
- #define QZ\_NOSW\_NO\_MDRV (-102)
- #define QZ\_NOSW\_NO\_INST\_ATTACH (-103)
- #define QZ\_NOSW\_LOW\_MEM (-104)
- #define QZ\_MAX\_ALGORITHMS ((int)255)
- #define QZ\_DEFLATE ((unsigned char)8)
- #define QZ\_SNAPPY ((unsigned char)'S')
- #define QZ\_LZ4 ((unsigned char)'4')
- #define MIN(a, b) (((a)<(b))?(a):(b))
- #define QZ\_MEMCPY(dest, src, dest\_sz, src\_sz) memcpy((void \*)(dest), (void \*) (src), (size\_t)MIN(dest\_sz, src\_sz))
- #define QZ\_HUFF\_HDR\_DEFAULT QZ\_DYNAMIC\_HDR

32 File Documentation

- #define QZ\_DIRECTION\_DEFAULT QZ\_DIR\_BOTH
- #define QZ\_DATA\_FORMAT\_DEFAULT QZ\_DEFLATE\_GZIP\_EXT
- #define QZ COMP LEVEL DEFAULT 1
- #define QZ COMP ALGOL DEFAULT QZ DEFLATE
- #define QZ\_POLL\_SLEEP\_DEFAULT 10
- #define QZ MAX FORK DEFAULT 3
- #define QZ\_SW\_BACKUP\_DEFAULT 1
- #define QZ\_HW\_BUFF\_SZ (64\*1024)
- #define QZ HW BUFF MIN SZ (1\*1024)
- #define QZ\_HW\_BUFF\_MAX\_SZ (512\*1024)
- #define QZ\_STRM\_BUFF\_SZ\_DEFAULT QZ\_HW\_BUFF\_SZ
- #define QZ\_STRM\_BUFF\_MIN\_SZ (1\*1024)
- #define QZ\_STRM\_BUFF\_MAX\_SZ (2\*1024\*1024 5\*1024)
- #define QZ COMP THRESHOLD DEFAULT 1024
- #define QZ COMP THRESHOLD MINIMUM 128
- #define QZ\_REQ\_THRESHOLD\_MINIMUM 1
- #define QZ\_REQ\_THRESHOLD\_MAXINUM NUM\_BUFF
- #define QZ\_REQ\_THRESHOLD\_DEFAULT QZ\_REQ\_THRESHOLD\_MAXINUM
- #define QZ\_WAIT\_CNT\_THRESHOLD\_DEFAULT 8
- #define QZ SKID PAD SZ 48

## **Typedefs**

- typedef enum QzHuffmanHdr\_E QzHuffmanHdr\_T
- typedef enum QzDirection\_E QzDirection\_T
- typedef enum QzDataFormat\_E QzDataFormat\_T
- typedef enum QzCrcType E QzCrcType T
- typedef struct QzSessionParams\_S QzSessionParams\_T
- typedef struct QzSession S QzSession T
- typedef struct QzStatus\_S QzStatus\_T
- typedef struct QzStream S QzStream T

## **Enumerations**

- enum QzHuffmanHdr E { QZ DYNAMIC HDR = 0, QZ STATIC HDR }
- enum PinMem\_T { COMMON\_MEM = 0, PINNED\_MEM }
- enum QzDirection E { QZ DIR COMPRESS = 0, QZ DIR DECOMPRESS, QZ DIR BOTH }
- enum QzDataFormat\_E { QZ\_DEFLATE\_RAW = 0, QZ\_DEFLATE\_GZIP, QZ\_DEFLATE\_GZIP\_EXT, QZ\_FMT\_NUM }
- enum QzCrcType\_E { QZ\_CRC32 = 0, QZ\_CRC64, QZ\_ADLER, NONE }

## **Functions**

- int qzInit (QzSession\_T \*sess, unsigned char sw\_backup)
- int qzSetupSession (QzSession\_T \*sess, QzSessionParams\_T \*params)
- int qzCompress (QzSession\_T \*sess, const unsigned char \*src, unsigned int \*src\_len, unsigned char \*dest, unsigned int \*dest\_len, unsigned int last)
- int qzCompressCrc (QzSession\_T \*sess, const unsigned char \*src, unsigned int \*src\_len, unsigned char \*dest, unsigned int \*dest len, unsigned int last, unsigned long \*crc)
- int qzDecompress (QzSession\_T \*sess, const unsigned char \*src, unsigned int \*src\_len, unsigned char \*dest, unsigned int \*dest\_len)
- int gzTeardownSession (QzSession T \*sess)
- int qzClose (QzSession\_T \*sess)

- int qzGetStatus (QzSession\_T \*sess, QzStatus\_T \*status)
- unsigned int qzMaxCompressedLength (unsigned int src\_sz)
- int qzSetDefaults (QzSessionParams\_T \*defaults)
- int qzGetDefaults (QzSessionParams\_T \*defaults)
- void \* qzMalloc (size\_t sz, int numa, int force\_pinned)
- void qzFree (void \*m)
- int qzMemFindAddr (unsigned char \*a)
- int qzCompressStream (QzSession\_T \*sess, QzStream\_T \*strm, unsigned int last)
- int qzDecompressStream (QzSession\_T \*sess, QzStream\_T \*strm, unsigned int last)
- int qzEndStream (QzSession\_T \*sess, QzStream\_T \*strm)

## 6.1.1 Macro Definition Documentation

- 6.1.1.1 #define MIN( a, b) (((a)<(b))?(a):(b))
- 6.1.1.2 #define QZ\_BUF\_ERROR (-3)

Insufficient buffer error

- 6.1.1.3 #define QZ\_COMP\_ALGOL\_DEFAULT QZ\_DEFLATE
- 6.1.1.4 #define QZ\_COMP\_LEVEL\_DEFAULT 1
- 6.1.1.5 #define QZ\_COMP\_THRESHOLD\_DEFAULT 1024
- 6.1.1.6 #define QZ\_COMP\_THRESHOLD\_MINIMUM 128
- 6.1.1.7 #define QZ\_DATA\_ERROR (-4)

Input data was corrupted

- 6.1.1.8 #define QZ\_DATA\_FORMAT\_DEFAULT QZ\_DEFLATE\_GZIP\_EXT
- 6.1.1.9 #define QZ\_DEFLATE ((unsigned char)8)
- 6.1.1.10 #define QZ\_DIRECTION\_DEFAULT QZ\_DIR\_BOTH
- 6.1.1.11 #define QZ\_DUPLICATE (1)

Can not process function again. No failure.

6.1.1.12 #define QZ\_FAIL (-2)

Unspecified error

6.1.1.13 #define QZ\_FORCE\_SW (2)

using SW: Switch to software because of previous block

34 File Documentation

```
6.1.1.14 #define QZ_HUFF_HDR_DEFAULT QZ_DYNAMIC_HDR
6.1.1.15 #define QZ_HW_BUFF_MAX_SZ (512*1024)
6.1.1.16 #define QZ_HW_BUFF_MIN_SZ (1*1024)
6.1.1.17 #define QZ_HW_BUFF_SZ (64*1024)
6.1.1.18 #define QZ_LOW_MEM (14)
using SW: Not enough pinned memory
6.1.1.19 #define QZ_LZ4 ((unsigned char)'4')
6.1.1.20 #define QZ_MAX_ALGORITHMS ((int)255)
6.1.1.21 #define QZ_MAX_FORK_DEFAULT 3
6.1.1.22 #define QZ_MEMCPY( dest, src, dest_sz, src_sz ) memcpy((void *)(dest), (void *) (src), (size_t)MIN(dest_sz,
        src_sz))
6.1.1.23 #define QZ_NO_HW (11)
using SW: No QAT HW detected
6.1.1.24 #define QZ_NO_INST_ATTACH (13)
using SW: Could not attach to an instance
6.1.1.25 #define QZ_NO_MDRV (12)
using SW: No memory driver detected
6.1.1.26 #define QZ_NONE (100)
device uninitialzied
6.1.1.27 #define QZ_NOSW_LOW_MEM (-104)
not using SW: not enough pinned memory
6.1.1.28 #define QZ_NOSW_NO_HW (-101)
not using SW: No QAT HW detected
6.1.1.29 #define QZ_NOSW_NO_INST_ATTACH (-103)
not using SW: Could not attach to instance
6.1.1.30 #define QZ_NOSW_NO_MDRV (-102)
not using SW: No memory driver detected
```

- 6.1.1.31 #define QZ\_PARAMS (-1)
- invalid parameter in function call
- 6.1.1.32 #define QZ\_POLL\_SLEEP\_DEFAULT 10
- 6.1.1.33 #define QZ\_REQ\_THRESHOLD\_DEFAULT QZ\_REQ\_THRESHOLD\_MAXINUM
- 6.1.1.34 #define QZ\_REQ\_THRESHOLD\_MAXINUM NUM\_BUFF
- 6.1.1.35 #define QZ\_REQ\_THRESHOLD\_MINIMUM 1
- 6.1.1.36 #define QZ\_SNAPPY ((unsigned char)'S')
- 6.1.1.37 #define QZ\_STRM\_BUFF\_MAX\_SZ (2\*1024\*1024 5\*1024)
- 6.1.1.38 #define QZ\_STRM\_BUFF\_MIN\_SZ (1\*1024)
- 6.1.1.39 #define QZ\_STRM\_BUFF\_SZ\_DEFAULT QZ\_HW\_BUFF\_SZ
- 6.1.1.40 #define QZ\_SW\_BACKUP\_DEFAULT 1
- 6.1.1.41 #define QZ\_WAIT\_CNT\_THRESHOLD\_DEFAULT 8
- **6.1.2 Function Documentation**
- 6.1.2.1 unsigned int qzMaxCompressedLength ( unsigned int src\_sz )

# Index

algo_hw	qzEndStream, 17
QzStatus_S, 28	qzFree, 18
algo_sw	qzGetDefaults, 18
QzStatus_S, 28	qzGetStatus, 19
	QzHuffmanHdr_E, 11
COMMON MEM	QzHuffmanHdr T, 9
Data Compression API, 10	qzInit, 19
comp_algorithm	•
QzSessionParams_S, 26	qzMalloc, 20
	qzMemFindAddr, 21
comp_lvl	QzSession_T, 10
QzSessionParams_S, 26	QzSessionParams_T, 10
crc_32	qzSetDefaults, 21
QzStream_S, 29	qzSetupSession, 22
crc_64	QzStatus_T, 10
QzStream_S, 29	QzStream_T, 10
crc_type	qzTeardownSession, 23
QzStream_S, 29	data_fmt
	QzSessionParams S, 26
Data Compression API	direction
COMMON_MEM, 10	QzSessionParams_S, 26
NONE, 11	Q2003310111 drd1113_0, 20
PINNED_MEM, 10	huffman hdr
QZ_ADLER, 11	QzSessionParams_S, 26
QZ_RC32, 11	hw buff sz
QZ_CRC64, 11	QzSessionParams_S, 27
QZ_DEFLATE_GZIP, 11	hw_session_stat
	QzSession_S, 25
QZ_DEFLATE_GZIP_EXT, 11	
QZ_DEFLATE_RAW, 11	hw_session_status
QZ_DIR_BOTH, 11	QzStatus_S, 28
QZ_DIR_COMPRESS, 11	in
QZ_DIR_DECOMPRESS, 11	
QZ_DYNAMIC_HDR, 12	QzStream_S, 29
QZ_FMT_NUM, 11	in_sz
QZ_STATIC_HDR, 12	QzStream_S, 29
Data Compression API, 7	include/qatzip.h, 31
PinMem_T, 10	input_sz_thrshold
QZ_OK, 8	QzSessionParams_S, 27
QZ_SKID_PAD_SZ, 8	internal
qzClose, 12	QzSession_S, 25
qzCompress, 13	
qzCompressCrc, 13	MIN
qzCompressStream, 14	qatzip.h, <mark>33</mark>
QzCrcType_E, 10	max_forks
• • —	QzSessionParams_S, 27
QzCrcType_T, 9	memory_alloced
QzDataFormat_E, 11	QzStatus_S, 28
QzDataFormat_T, 9	<u> </u>
qzDecompress, 15	NONE
qzDecompressStream, 16	Data Compression API, 11
QzDirection_E, 11	
QzDirection_T, 9	opaque

INDEX 37

QzStream_S, 30	QZ_HW_BUFF_MIN_SZ
out	qatzip.h, 34
QzStream_S, 30	QZ_HW_BUFF_SZ
out_sz	qatzip.h, 34
QzStream_S, 30	QZ_LOW_MEM
PINNED MEM	qatzip.h, 34
Data Compression API, 10	QZ_LZ4
pending in	qatzip.h, 34
QzStream_S, 30	QZ_MAX_ALGORITHMS
pending_out	qatzip.h, 34
QzStream_S, 30	QZ_MAX_FORK_DEFAULT
PinMem_T	qatzip.h, 34
Data Compression API, 10	QZ_MEMCPY
poll_sleep	qatzip.h, 34
QzSessionParams_S, 27	QZ_NO_HW
<u> </u>	qatzip.h, 34
QZ_ADLER	QZ_NO_INST_ATTACH
Data Compression API, 11	qatzip.h, 34
QZ_CRC32	QZ_NO_MDRV
Data Compression API, 11	qatzip.h, 34
QZ_CRC64	QZ_NONE
Data Compression API, 11	qatzip.h, 34
QZ_DEFLATE_GZIP	QZ_NOSW_LOW_MEM
Data Compression API, 11	qatzip.h, 34
QZ_DEFLATE_GZIP_EXT	QZ_NOSW_NO_HW
Data Compression API, 11	qatzip.h, 34
QZ_DEFLATE_RAW	QZ_NOSW_NO_MDRV
Data Compression API, 11	qatzip.h, 34
QZ_DIR_BOTH	QZ_OK
Data Compression API, 11	Data Compression API, 8
QZ_DIR_COMPRESS	QZ_PARAMS
Data Compression API, 11	qatzip.h, 34
QZ_DIR_DECOMPRESS	QZ_SKID_PAD_SZ
Data Compression API, 11	Data Compression API, 8
QZ_DYNAMIC_HDR	QZ_SNAPPY
Data Compression API, 12	qatzip.h, 35
QZ_FMT_NUM	qat_hw_count
Data Compression API, 11	QzStatus_S, 28
QZ_STATIC_HDR	qat_instance_attach
Data Compression API, 12	QzStatus_S, 28
QZ_BUF_ERROR	qat_mem_drvr
qatzip.h, 33	QzStatus_S, 28
QZ_DATA_ERROR	qat_service_stated
qatzip.h, 33	QzStatus_S, 28
QZ_DEFLATE	qatzip.h
qatzip.h, 33	MIN, 33
QZ_DIRECTION_DEFAULT	QZ_BUF_ERROR, 33
qatzip.h, 33	QZ_DATA_ERROR, 33
QZ_DUPLICATE	QZ_DEFLATE, 33
qatzip.h, 33	QZ_DUPLICATE, 33
QZ_FAIL	QZ_FAIL, 33
qatzip.h, 33	QZ_FORCE_SW, 33
QZ_FORCE_SW	QZ_HW_BUFF_MAX_SZ, 34
qatzip.h, 33	QZ_HW_BUFF_MIN_SZ, 34
QZ_HUFF_HDR_DEFAULT	QZ_HW_BUFF_SZ, 34
qatzip.h, 33	QZ_LOW_MEM, 34
QZ_HW_BUFF_MAX_SZ	QZ_LZ4, 34
qatzip.h, 34	QZ_MAX_ALGORITHMS, 34

38 INDEX

QZ_MEMCPY, 34	thd_sess_stat, 25
QZ_NO_HW, 34	total_in, 25
QZ_NO_INST_ATTACH, 34	total_out, 25
QZ_NO_MDRV, 34	QzSession T
QZ_NONE, 34	Data Compression API, 10
QZ_NOSW_LOW_MEM, 34	QzSessionParams_S, 26
QZ_NOSW_NO_HW, 34	comp_algorithm, 26
QZ_NOSW_NO_MDRV, 34	comp_lvl, 26
QZ_PARAMS, 34	data_fmt, 26
QZ_SNAPPY, 35	direction, 26
qzMaxCompressedLength, 35	huffman_hdr, 26
qzClose	hw_buff_sz, 27
•	input_sz_thrshold, 27
Data Compression API, 12	max_forks, 27
qzCompress	
Data Compression API, 13	poll_sleep, 27
qzCompressCrc	req_cnt_thrshold, 27
Data Compression API, 13	strm_buff_sz, 27
qzCompressStream	sw_backup, 27
Data Compression API, 14	wait_cnt_thrshold, 27
QzCrcType_E	QzSessionParams_T
Data Compression API, 10	Data Compression API, 10
QzCrcType_T	qzSetDefaults
Data Compression API, 9	Data Compression API, 21
QzDataFormat_E	qzSetupSession
Data Compression API, 11	Data Compression API, 22
QzDataFormat_T	QzStatus_S, 27
Data Compression API, 9	algo_hw, 28
qzDecompress	algo_sw, 28
Data Compression API, 15	hw_session_status, 28
qzDecompressStream	memory_alloced, 28
Data Compression API, 16	qat_hw_count, 28
QzDirection_E	qat_instance_attach, 28
Data Compression API, 11	qat_mem_drvr, 28
QzDirection_T	qat_service_stated, 28
Data Compression API, 9	using_huge_pages, 28
qzEndStream	QzStatus T
•	<del>_</del>
Data Compression API, 17	Data Compression API, 10
qzFree	QzStream_S, 29
Data Compression API, 18	crc_32, 29
qzGetDefaults	crc_64, 29
Data Compression API, 18	crc_type, 29
qzGetStatus	in, 29
Data Compression API, 19	in_sz, <mark>29</mark>
QzHuffmanHdr_E	opaque, 30
Data Compression API, 11	out, 30
QzHuffmanHdr_T	out_sz, <mark>30</mark>
Data Compression API, 9	pending_in, 30
qzInit	pending_out, 30
Data Compression API, 19	reserved, 30
qzMalloc	QzStream_T
Data Compression API, 20	Data Compression API, 10
qzMaxCompressedLength	qzTeardownSession
qatzip.h, 35	Data Compression API, 23
qzMemFindAddr	,
Data Compression API, 21	req_cnt_thrshold
QzSession_S, 25	QzSessionParams_S, 27
hw_session_stat, 25	reserved
internal, 25	QzStream_S, 30
mornar, Lo	@20110a111_0, 00

INDEX 39