QATzip

Generated by Doxygen 1.8.5

Tue Nov 28 2017 11:26:47

Contents

1	Mod	lule Inde	ex		1
	1.1	Module	es		 1
2	Clas	s Index	[3
	2.1	Class	List		 3
3	File	Index			5
	3.1	File Lis	st		 5
4	Mod	lule Doc	cumentati	ion	7
	4.1	Data C	Compression	ion API	 7
		4.1.1	Detailed	Description	 8
		4.1.2	Macro D	Definition Documentation	 8
			4.1.2.1	QZ_OK	 8
			4.1.2.2	QZ_SKID_PAD_SZ	 8
		4.1.3	Typedef	Documentation	 9
			4.1.3.1	QzDirection_T	 9
			4.1.3.2	QzHuffmanHdr_T	 9
			4.1.3.3	QzSession_T	 9
			4.1.3.4	QzSessionParams_T	 9
			4.1.3.5	QzStatus_T	 10
		4.1.4	Enumera	ation Type Documentation	 10
			4.1.4.1	QzDirection_E	 10
			4.1.4.2	QzHuffmanHdr_E	 10
		4.1.5	Function	Documentation	 11
			4.1.5.1	qzClose	 11
			4.1.5.2	qzCompress	 11
			4.1.5.3	qzCompressCrc	 12
			4.1.5.4	qzDecompress	 13
			4.1.5.5	qzFree	 14
			4.1.5.6	qzGetDefaults	 14
			1157	ar Cot Status	15

iv CONTENTS

			4.1.5.8	qzInit	16
			4.1.5.9	qzMalloc	17
			4.1.5.10	qzMemFindAddr	18
			4.1.5.11	qzSetDefaults	19
			4.1.5.12	qzSetupSession	19
			4.1.5.13	qzTeardownSession	20
5	Clas	s Docu	mentation	1	21
	5.1	QzSes	sion_S Str	ruct Reference	21
		5.1.1	Detailed	Description	21
		5.1.2	Member	Data Documentation	21
			5.1.2.1	hw_session_stat	21
			5.1.2.2	internal	21
			5.1.2.3	thd_sess_stat	21
			5.1.2.4	total_in	21
			5.1.2.5	total_out	22
	5.2	QzSes	sionParam	ns_S Struct Reference	22
		5.2.1	Detailed	Description	22
		5.2.2	Member	Data Documentation	22
			5.2.2.1	comp_algorithm	22
			5.2.2.2	comp_lvl	22
			5.2.2.3	direction	22
			5.2.2.4	huffman_hdr	22
			5.2.2.5	hw_buff_sz	22
			5.2.2.6	input_sz_thrshold	23
			5.2.2.7	max_forks	23
			5.2.2.8	poll_sleep	23
			5.2.2.9	req_cnt_thrshold	23
			5.2.2.10	sw_backup	23
	5.3	QzStat	us_S Stru	ct Reference	23
		5.3.1	Detailed	Description	23
		5.3.2	Member	Data Documentation	23
			5.3.2.1	algo_hw	23
			5.3.2.2	algo_sw	24
			5.3.2.3	hw_session_status	24
			5.3.2.4	memory_alloced	24
			5.3.2.5	qat_hw_count	24
			5.3.2.6	qat_instance_attach	24
			5.3.2.7	qat_mem_drvr	24
			5.3.2.8	qat_service_stated	24

CONTENTS

			5.3.2.9	using_huge_pages	24
6	File	Docume	entation		25
	6.1	include	e/qatzip.h F	ile Reference	25
		6.1.1	Macro De	efinition Documentation	26
			6.1.1.1	MIN	26
			6.1.1.2	QZ_BUF_ERROR	26
			6.1.1.3	QZ_COMP_ALGOL_DEFAULT	27
			6.1.1.4	QZ_COMP_LEVEL_DEFAULT	27
			6.1.1.5	QZ_COMP_THRESHOLD_DEFAULT	27
			6.1.1.6	QZ_COMP_THRESHOLD_MINIMUM	27
			6.1.1.7	QZ_DATA_ERROR	27
			6.1.1.8	QZ_DEFLATE	27
			6.1.1.9	QZ_DIRECTION_DEFAULT	27
			6.1.1.10	QZ_DUPLICATE	27
			6.1.1.11	QZ_FAIL	27
			6.1.1.12	QZ_FORCE_SW	27
			6.1.1.13	QZ_HUFF_HDR_DEFAULT	27
			6.1.1.14	QZ_HW_BUFF_MAX_SZ	27
			6.1.1.15	QZ_HW_BUFF_MIN_SZ	27
			6.1.1.16	QZ_HW_BUFF_SZ	27
			6.1.1.17	QZ_LOW_MEM	27
			6.1.1.18	QZ_LZ4	27
			6.1.1.19	QZ_MAX_ALGORITHMS	27
			6.1.1.20	QZ_MAX_FORK_DEFAULT	27
			6.1.1.21	QZ_MEMCPY	27
			6.1.1.22	QZ_NO_HW	27
			6.1.1.23	QZ_NO_INST_ATTACH	28
			6.1.1.24	QZ_NO_MDRV	28
			6.1.1.25	QZ_NOSW_LOW_MEM	28
			6.1.1.26	QZ_NOSW_NO_HW	28
			6.1.1.27	QZ_NOSW_NO_INST_ATTACH	28
			6.1.1.28	QZ_NOSW_NO_MDRV	28
			6.1.1.29	QZ_PARAMS	28
			6.1.1.30	QZ_POLL_SLEEP_DEFAULT	28
			6.1.1.31	QZ_REQ_THRESHOLD_DEFAULT	28
			6.1.1.32	QZ_REQ_THRESHOLD_MAXINUM	28
			6.1.1.33	QZ_REQ_THRESHOLD_MINIMUM	28
			6.1.1.34	QZ_SNAPPY	28
			6.1.1.35	QZ_SW_BACKUP_DEFAULT	28

vi							 CONT	TENTS
	6.1.2	Function	Documentation	 	 	 	 	. 28
		6.1.2.1	qzMaxCompressedLength	 	 	 	 	. 28
Index								29

Chapter 1

Module Index

1.1	Modules
Here	is a list of all modules:
Da	ata Compression API

2 **Module Index**

Chapter 2

Class Index

2.1 Class List

Here are the classes, structs, unions and interfaces with brief descriptions:						
QzSession S						

21

22

Class Index

Chapter 3

File Index

3.1	File List	
Here	is a list of all files with brief descriptions:	
ind	clude/qatzip.h	25

6 File Index

Chapter 4

Module Documentation

4.1 Data Compression API

Classes

- struct QzSessionParams_S
- struct QzSession_S
- struct QzStatus S

Macros

- #define QZ OK (0)
- #define QZ_SKID_PAD_SZ 48

Typedefs

- typedef enum QzHuffmanHdr_E QzHuffmanHdr_T
- typedef enum QzDirection E QzDirection T
- typedef struct QzSessionParams_S QzSessionParams_T
- typedef struct QzSession_S QzSession_T
- typedef struct QzStatus_S QzStatus_T

Enumerations

- enum QzHuffmanHdr_E { QZ_DYNAMIC_HDR = 0, QZ_STATIC_HDR }
- enum QzDirection E { QZ DIR COMPRESS = 0, QZ DIR DECOMPRESS, QZ DIR BOTH }

Functions

- int qzInit (QzSession_T *sess, unsigned char sw_backup)
- int qzSetupSession (QzSession_T *sess, QzSessionParams_T *params)
- int qzCompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last)
- int qzCompressCrc (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last, unsigned long *crc)
- int qzDecompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len)
- int qzTeardownSession (QzSession_T *sess)

- int qzClose (QzSession_T *sess)
- int qzGetStatus (QzSession_T *sess, QzStatus_T *status)
- int qzSetDefaults (QzSessionParams_T *defaults)
- int qzGetDefaults (QzSessionParams_T *defaults)
- void * qzMalloc (size_t sz, int numa, int force_pinned)
- void qzFree (void *m)
- int qzMemFindAddr (unsigned char *a)

4.1.1 Detailed Description

These functions specify the API for Data Compression operations.

Remarks

4.1.2 Macro Definition Documentation

4.1.2.1 #define QZ_OK (0)

QATZIP Session Status definitions and function return codes

This list identifies valid values for session status and function return codes. Success

4.1.2.2 #define QZ_SKID_PAD_SZ 48

Get the max compressed output length

Get the max compressed output length

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in src_sz Input data length in byte.

Return values

dest_sz	Max compressed data output length in byte. When src_sz equal to 0, the return
	value is 0.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.3 Typedef Documentation

4.1.3.1 typedef enum QzDirection_E QzDirection_T

Compress or decompress setting

This enumerated list identifies the session directions supported by QATZip. A session can be compress, decompress or both.

4.1.3.2 typedef enum QzHuffmanHdr_E QzHuffmanHdr_T

This API provides access to underlying compression functions in QAT hardware The API supports an implementation that provides compression service in software if not all of the required resources are not available to execute the compression service in hardware.

The API supports threaded applications. Applications can create threads and each of these threads can invoke the API defined herein.

For simplicity, initializations and setup function calls are not required to obtain compression services. If the initialization and setup functions are not called before compression or decompression requests, then they will be called with default arguments from within the compression or decompression functions. This results in several legal calling scenarios, described below.

Scenario 1 - all functions explicitly invoked by caller, with all arguments provided

qzInit(&sess_c, sw_backup); qzSetupSession(&sess_c, ¶ms); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); qzDecompress(&sess, src, &src_len, dest, &dest_len); qzTeardownSession(&sess); qzClose(&sess);

Scenario 2 - initialization function called, setup function not invoked by caller. This scenario can be used to specify the sw_backup argument to qzInit.

qzInit(&sess, sw_backup); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); calls qzSetupSession(sess, NU-LL); qzTeardownSession(&sess); qzClose(&sess);

Scenario 3 - calling application simply invokes the actual qzCompress functions

qzCompress(&sess, src, &src_len, dest, &dest_len, 0); calls qzInit sess, 1); calls qzSetupSession(sess, NULL); qzCompress(&sess, src, &src_len, dest, &dest_len, 1);

Notes: Invoking qzSetupSession with NULL for params sets up a session with default session attributed, detailed in the function description below.

If an application terminates with out invoking tear down and close functions, process termination will invoke memory and hardware instance cleanup.

If a thread terminates without invoking tear down and close functions, memory and hardware are not cleanup until the application exits.

Supported Huffman Headers

This enumerated list identifies the Huffman header types supported by QATZip

4.1.3.3 typedef struct QzSession_S QzSession_T

QATZIP Session opaque data storage

This structure contains a pointer to a structure with session state

4.1.3.4 typedef struct QzSessionParams_S QzSessionParams_T

QATZIP Session Initialization parameters

This structure contains data for initializing a session

4.1.3.5 typedef struct QzStatus_S QzStatus_T

QATZIP status structure

This structure contains data relating to the stat usof QAT on the platform

4.1.4 Enumeration Type Documentation

4.1.4.1 enum QzDirection_E

Compress or decompress setting

This enumerated list identifies the session directions supported by QATZip. A session can be compress, decompress or both.

Enumerator

QZ_DIR_COMPRESS Session will be used for compression

QZ_DIR_DECOMPRESS Session will be used for decompression

QZ_DIR_BOTH Session will be used for both compression and decompression

4.1.4.2 enum QzHuffmanHdr E

This API provides access to underlying compression functions in QAT hardware The API supports an implementation that provides compression service in software if not all of the required resources are not available to execute the compression service in hardware.

The API supports threaded applications. Applications can create threads and each of these threads can invoke the API defined herein.

For simplicity, initializations and setup function calls are not required to obtain compression services. If the initialization and setup functions are not called before compression or decompression requests, then they will be called with default arguments from within the compression or decompression functions. This results in several legal calling scenarios, described below.

Scenario 1 - all functions explicitly invoked by caller, with all arguments provided

qzInit(&sess_c, sw_backup); qzSetupSession(&sess_c, ¶ms); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); qzDecompress(&sess, src, &src_len, dest, &dest_len); qzTeardownSession(&sess); qzClose(&sess);

Scenario 2 - initialization function called, setup function not invoked by caller. This scenario can be used to specify the sw_backup argument to qzInit.

qzInit(&sess, sw_backup); qzCompress(&sess, src, &src_len, dest, &dest_len, 1); calls qzSetupSession(sess, NU-LL); qzTeardownSession(&sess); qzClose(&sess);

Scenario 3 - calling application simply invokes the actual qzCompress functions

qzCompress(&sess, src, &src_len, dest, &dest_len, 0); calls qzInit sess, 1); calls qzSetupSession(sess, NULL); qzCompress(&sess, src, &src_len, dest, &dest_len, 1);

Notes: Invoking qzSetupSession with NULL for params sets up a session with default session attributed, detailed in the function description below.

If an application terminates with out invoking tear down and close functions, process termination will invoke memory and hardware instance cleanup.

If a thread terminates without invoking tear down and close functions, memory and hardware are not cleanup until the application exits.

Supported Huffman Headers

This enumerated list identifies the Huffman header types supported by QATZip

Enumerator

QZ_DYNAMIC_HDR Full Dynamic Huffman Trees
QZ_STATIC_HDR Static Huffman Trees

4.1.5 Function Documentation

4.1.5.1 int qzClose (QzSession_T * sess)

terminates a QATZip session

This function closes the connection with QAT

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	pointer to session data

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.2 int qzCompress (QzSession_T * sess, const unsigned char * src, unsigned int * src_len, unsigned char * dest, unsigned int * dest_len, unsigned int last)

```
compress a buffer
```

This function will compress a buffer if either a hw based session or a software based session is available. If no session has been established - as indicated by the contents of *sess - then this app will attempt to set up a session using gzinit and qzSetupSession.

This function will place completed compression blocks in the output buffer.

The caller must check the updated src_len. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter dest_len will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	src	point to source buffer
in,out	src_len	length of source buffer. Modified to number of bytes consumed
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of compressed data when func-
		tion returns
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.3 int qzCompressCrc (QzSession_T * sess, const unsigned char * src, unsigned int * src_len, unsigned char * dest, unsigned int * dest_len, unsigned int last, unsigned long * crc)

compress a buffer and return the CRC check sum

This function will compress a buffer if either a hw based session or a software based session is available. If no session has been established - as indicated by the contents of *sess - then this app will attempt to set up a session using gzinit and qzSetupSession.

This function will place completed compression blocks in the output buffer and put CRC32 checksum for compressed input data in user provided bufer *crc.

The caller must check the updated src_len. This value will be the number of consumed bytes on exit. The calling API may have to process the destination buffer and call again.

The parameter dest_len will be set to the number of bytes produced in the destination buffer. This value may be zero if no data was produced which may occur if the consumed data is retained internally. A possible reason for this may be small amounts of data in the src buffer.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	src	point to source buffer
in,out	src_len	length of source buffer. Modified to number of bytes consumed
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of compressed data when func-
		tion returns
in	last	1 for 'No more data to be compressed' 0 for 'More data to be compressed'
in,out	crc	point to CRC32 checksum buffer

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.4 int qzDecompress (QzSession_T * sess, const unsigned char * src, unsigned int * src_len, unsigned char * dest, unsigned int * dest_len)

decompress a buffer

This function will decompress a buffer if either a hw based session or a software based session is available. If no session has been established - as indicated by the contents of *sess - then this app will attempt to set up a session using qzinit and qzSetupSession.

The resulting compressed block of data will be composed of one or more gzip blocks per RFC1952.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
in	src	point to source buffer
in	src_len	length of source buffer. Modified to length of processed compressed data
		when function returns
in	dest	point to destination buffer
in,out	dest_len	length of destination buffer. Modified to length of decompressed data when
		function returns

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.5 void qzFree (void *m)

Free allocated memory

Free allocated memory

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in m Memory address to be freed.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.6 int qzGetDefaults (QzSessionParams_T * defaults)

Get default QzSessionParams_T value

Get default QzSessionParams_T value

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	defaults	The pointer to default value.
----	----------	-------------------------------

Return values

QZ_OK	Success on getting default value.
QZ_PARAM	Fail to get default value.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.7 int qzGetStatus (QzSession_T * sess, QzStatus_T * status)

Get current QAT status

This function retrieves the status of QAT in the platform. The status structure will be filled in as follows: qat_hw_count number of discovered QAT devices on PCU bus qat_service_stated 1 if qzInit has been successfully run, 0 otherwise qat_mem_drvr 1 if the QAT memory driver is installed, 0 otherwise qat_instance_attach 1 if session has attached to a hw instance, 0 otherwise memory_alloced amount of memory, in kilobytes, from kernel or huge pages allocated by this process/thread. using_huge_pages 1 if memory is being allocated from huge pages, 0 if memory is being allocated from standard kernel memory hw_session_stat Hw session status: one of: QZ_OK QZ_FAIL QZ_NO_HW QZ_NO_MDRV QZ_NO_INST_ATTACH QZ_LOW_MEM QZ_NOSW_NO_HW QZ_NOSW_MDRV QZ_NOSW_NO_HW QZ_NOSW_LOW MEM

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	dcInstance	Instance handle derived from discovery functions
----	------------	--

Return values

QZ_OK	Function executed successfully. A hw based compression session has been cre-
	ated.
QZ PARAMS	*status is NULL

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.8 int qzlnit (QzSession_T * sess, unsigned char sw_backup)

Initialize QAT hardware

This function initializes the QAT hardware. This function is optional in the function calling sequence. If desired, this call can be made to avoid latency impact during the first call to qzDecompress or qzCompress, or to set the sw_backup parameter explicitly. The input parameter sw_backup specifies the behavior of the function and that of the functions called with the same session in the event there are insufficient resources to establish a QAT based compression or decompression session.

Required resources include access to the QAT hardware, contiguous pinned memory for mmaping the hardware rings, and contiguous pinned memory for buffers.

This function shall not be called in an interrupt context. None This function will: 1) start the user space driver if necessary 2) allocate all hw instances available Yes No Yes

Parameters

in	sess	pointer to opaque instance and session data.
in	sw_backup	0 for no sw backup, 1 for sw backup

Return values

QZ_OK	Function executed successfully. A hw or sw instance has been allocated to the
	calling process/thread.
QZ_DUPLICATE	This process/thread already has a hw instance
QZ_PARAMS	*sess is NULL
QZ_NOSW_NO_HW	No hardware and no sw session being established
QZ_NOSW_NO_MDRV	No memory driver. No software session established
QZ_NOSW_NO_INST_AT-	No instance avail. No software session established
TACH	
QZ_NOSW_LOW_MEM	Not enough pinned memory available. No software session established

Pre			

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.9 void* qzMalloc (size_t sz, int numa, int force_pinned)

Allocate different types of memory

Allocate different types of memory

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	SZ	Memory size to be allocated.
in	numa	NUMA node from which to allocate memory
in	force_pinned	PINNED_MEM allocate continous memory COMMON_MEM allocate non-
		continous memory

Return values

NULL	Fail to allocate memory
adress The address to allocated memory	

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.10 int qzMemFindAddr (unsigned char * a)

Check whether the address is available

Check whether the address is available

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

a Address need to be checked

Return values

1	The Address is available
0	The address is not available

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.11 int qzSetDefaults (QzSessionParams_T * defaults)

Set default QzSessionParams_T value

Set default QzSessionParams_T value

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	defaults	The pointer to value to be set as default.

Return values

QZ_OK	Success on setting default value.
QZ_PARAM	Fail to set default value.

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.12 int qzSetupSession (QzSession_T * sess, QzSessionParams_T * params)

```
initialize a QATZip session
```

This function establishes a QAT session. This involves associating a hardware instance to the session, allocating buffers. If all of these activities can not be completed successfully, then this function will set up a software based session of param->sw_backup is set to 1.

Before this function is called, the hardware must have been successfully started via qzlnit.

If *sess includes an existing hardware or software session, then this session will be torn down before a new one is attempted.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle	
in	params	Parameters for session	

Return values

QZ_OK	Function executed successfully. A hw or sw based compression session has been
	created.

QZ_PARAMS	*sess is NULL or member of params is invalid
QZ_NOSW_NO_HW	No hardware and no sw session being established
QZ_NOSW_NO_MDRV	No memory driver. No software session established
QZ_NOSW_NO_INST_AT- No instance avail. No software session established	
TACH	
QZ_NO_LOW_MEM	Not enough pinned memory available. No software session established

					•••	
u	r۵	\boldsymbol{r}	۱n	М	ITI	on
	10	\cdot	,,,	ч	ıu	vii

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

4.1.5.13 int qzTeardownSession (QzSession_T * sess)

Deinitialize a QATZip session

This function disconnects a session from a hardware instance and deallocates buffers. If no session has been initialized, then no action will take place.

This function shall not be called in an interrupt context. None None Yes No Yes

Parameters

in	sess	Session handle
----	------	----------------

Return values

QZ_OK	Function executed successfully.
QZ_FAIL	Function did not succeed.
QZ_PARAMS	*sess is NULL or member of params is invalid

Precondition

None

Postcondition

None

Note

Only a synchronous version of this function is provided.

See Also

None

Chapter 5

Class Documentation

5.1 QzSession_S Struct Reference

```
#include <qatzip.h>
```

Public Attributes

- · signed long int hw session stat
- int thd_sess_stat
- void * internal
- unsigned long total_in
- unsigned long total_out

5.1.1 Detailed Description

QATZIP Session opaque data storage

This structure contains a pointer to a structure with session state

5.1.2 Member Data Documentation

5.1.2.1 signed long int QzSession_S::hw_session_stat

filled in during initialization, session startup and decompression

5.1.2.2 void* QzSession_S::internal

session data is opaque to outside world

5.1.2.3 int QzSession_S::thd_sess_stat

note process compression and decompression thread state

5.1.2.4 unsigned long QzSession_S::total_in

Total processed input data length in this session

22 Class Documentation

5.1.2.5 unsigned long QzSession_S::total_out

Total output data length in this session

The documentation for this struct was generated from the following file:

· include/qatzip.h

5.2 QzSessionParams_S Struct Reference

```
#include <qatzip.h>
```

Public Attributes

- QzHuffmanHdr_T huffman_hdr
- QzDirection_T direction
- · unsigned int comp_lvl
- unsigned char comp_algorithm
- unsigned int poll_sleep
- · unsigned int max forks
- · unsigned char sw backup
- unsigned int hw_buff_sz
- unsigned int input_sz_thrshold
- unsigned int req_cnt_thrshold

5.2.1 Detailed Description

QATZIP Session Initialization parameters

This structure contains data for initializing a session

5.2.2 Member Data Documentation

5.2.2.1 unsigned char QzSessionParams_S::comp_algorithm

5.2.2.2 unsigned int QzSessionParams_S::comp_lvl

Compression level 1..9

5.2.2.3 QzDirection_T QzSessionParams_S::direction

compress or decompress

5.2.2.4 QzHuffmanHdr_T QzSessionParams_S::huffman_hdr

Dynamic or Static Huffman headers

5.2.2.5 unsigned int QzSessionParams_S::hw_buff_sz

default buffer size, Must be a power of 2 4K,8K,16K,32K,64K,128K

5.2.2.6 unsigned int QzSessionParams_S::input_sz_thrshold

default threshold of compression service's input size for sw failover, if the size of input request less than the threshold, QATzip will route the request to software

5.2.2.7 unsigned int QzSessionParams_S::max_forks

maximum forks permitted in the current thread. 0 means no forking permitted

5.2.2.8 unsigned int QzSessionParams_S::poll_sleep

< Compress/decompression algorithms nanosleep between poll [0..1000] 0 means no sleep

5.2.2.9 unsigned int QzSessionParams_S::req_cnt_thrshold

5.2.2.10 unsigned char QzSessionParams_S::sw_backup

0 means no sw backup, 1 means sw backup

The documentation for this struct was generated from the following file:

· include/qatzip.h

5.3 QzStatus S Struct Reference

#include <qatzip.h>

Public Attributes

- · unsigned short int qat_hw_count
- unsigned char qat_service_stated
- · unsigned char gat mem drvr
- unsigned char qat_instance_attach
- unsigned long int memory_alloced
- unsigned char using_huge_pages
- signed long int hw_session_status
- unsigned char algo sw [QZ MAX ALGORITHMS]
- unsigned char algo_hw [QZ_MAX_ALGORITHMS]

5.3.1 Detailed Description

QATZIP status structure

This structure contains data relating to the stat usof QAT on the platform

5.3.2 Member Data Documentation

5.3.2.1 unsigned char QzStatus_S::algo_hw[QZ_MAX_ALGORITHMS]

count of hw devices supporting algorithms

24 Class Documentation

5.3.2.2 unsigned char QzStatus_S::algo_sw[QZ_MAX_ALGORITHMS]

support software algorithms

5.3.2.3 signed long int QzStatus_S::hw_session_status

One of QATZIP Session Status

5.3.2.4 unsigned long int QzStatus_S::memory_alloced

Amount of memory allocated by this thread/process

5.3.2.5 unsigned short int QzStatus_S::qat_hw_count

from PCI scan

5.3.2.6 unsigned char QzStatus_S::qat_instance_attach

Is this thread/g_process properly attached to an Instance?

5.3.2.7 unsigned char QzStatus_S::qat_mem_drvr

1 if /dev/qat mem exists 2 if /dev/qat mem has been opened 0 otherwise

5.3.2.8 unsigned char QzStatus_S::qat_service_stated

Check if the QAT service is properly running on at least one device

5.3.2.9 unsigned char QzStatus_S::using_huge_pages

Are memory slabs coming from huge pages

The documentation for this struct was generated from the following file:

• include/qatzip.h

Chapter 6

File Documentation

6.1 include/qatzip.h File Reference

```
#include <string.h>
```

Classes

- struct QzSessionParams_S
- struct QzSession_S
- struct QzStatus_S

Macros

- #define QZ_OK (0)
- #define QZ_DUPLICATE (1)
- #define QZ_FORCE_SW (2)
- #define QZ_PARAMS (-1)
- #define QZ FAIL (-2)
- #define QZ_BUF_ERROR (-3)
- #define QZ_DATA_ERROR (-4)
- #define QZ_NO_HW (11)
- #define QZ_NO_MDRV (12)
- #define QZ_NO_INST_ATTACH (13)
- #define QZ_LOW_MEM (14)
- #define QZ_NOSW_NO_HW (-101)
- #define QZ_NOSW_NO_MDRV (-102)
- #define QZ_NOSW_NO_INST_ATTACH (-103)
- #define QZ_NOSW_LOW_MEM (-104)
- #define QZ_MAX_ALGORITHMS ((int)255)
- #define QZ_DEFLATE ((unsigned char)8)
- #define QZ_SNAPPY ((unsigned char)'S')
- #define QZ_LZ4 ((unsigned char)'4')
- #define MIN(a, b) (((a)<(b))?(a):(b))
- #define QZ_MEMCPY(dest, src, dest_sz, src_sz) memcpy((void *)(dest), (void *) (src), (size_t)MIN(dest_sz, src_sz))
- #define QZ_HUFF_HDR_DEFAULT QZ_DYNAMIC_HDR
- #define QZ DIRECTION DEFAULT QZ DIR BOTH
- #define QZ_COMP_LEVEL_DEFAULT 1

26 File Documentation

- #define QZ_COMP_ALGOL_DEFAULT QZ_DEFLATE
- #define QZ_POLL_SLEEP_DEFAULT 10
- #define QZ_MAX_FORK_DEFAULT 3
- #define QZ SW BACKUP DEFAULT 1
- #define QZ_HW_BUFF_SZ (64*1024)
- #define QZ HW BUFF MIN SZ (1*1024)
- #define QZ_HW_BUFF_MAX_SZ (512*1024)
- #define QZ COMP THRESHOLD DEFAULT 1024
- #define QZ_COMP_THRESHOLD_MINIMUM 128
- #define QZ_REQ_THRESHOLD_MINIMUM 1
- #define QZ_REQ_THRESHOLD_MAXINUM 4
- #define QZ REQ THRESHOLD DEFAULT 4
- #define QZ SKID PAD SZ 48

Typedefs

- typedef enum QzHuffmanHdr_E QzHuffmanHdr_T
- typedef enum QzDirection E QzDirection T
- typedef struct QzSessionParams_S QzSessionParams_T
- typedef struct QzSession_S QzSession_T
- typedef struct QzStatus_S QzStatus_T

Enumerations

- enum QzHuffmanHdr E { QZ DYNAMIC HDR = 0, QZ STATIC HDR }
- enum QzDirection_E { QZ_DIR_COMPRESS = 0, QZ_DIR_DECOMPRESS, QZ_DIR_BOTH }

Functions

- int qzInit (QzSession_T *sess, unsigned char sw_backup)
- int qzSetupSession (QzSession_T *sess, QzSessionParams_T *params)
- int qzCompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len, unsigned int last)
- int qzCompressCrc (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest len, unsigned int last, unsigned long *crc)
- int qzDecompress (QzSession_T *sess, const unsigned char *src, unsigned int *src_len, unsigned char *dest, unsigned int *dest_len)
- int qzTeardownSession (QzSession_T *sess)
- int qzClose (QzSession_T *sess)
- int qzGetStatus (QzSession_T *sess, QzStatus_T *status)
- unsigned int qzMaxCompressedLength (unsigned int src_sz)
- int gzSetDefaults (QzSessionParams T *defaults)
- int qzGetDefaults (QzSessionParams_T *defaults)
- void * qzMalloc (size_t sz, int numa, int force_pinned)
- void qzFree (void *m)
- int qzMemFindAddr (unsigned char *a)

6.1.1 Macro Definition Documentation

- 6.1.1.1 #define MIN(a, b) (((a)<(b))?(a):(b))
- 6.1.1.2 #define QZ_BUF_ERROR (-3)

Insufficient buffer error

```
6.1.1.3 #define QZ_COMP_ALGOL_DEFAULT QZ_DEFLATE
6.1.1.4 #define QZ_COMP_LEVEL_DEFAULT 1
6.1.1.5 #define QZ_COMP_THRESHOLD_DEFAULT 1024
6.1.1.6 #define QZ_COMP_THRESHOLD_MINIMUM 128
6.1.1.7 #define QZ_DATA_ERROR (-4)
Input data was corrupted
6.1.1.8 #define QZ_DEFLATE ((unsigned char)8)
6.1.1.9 #define QZ_DIRECTION_DEFAULT QZ_DIR_BOTH
6.1.1.10 #define QZ_DUPLICATE (1)
Can not process function again. No failure.
6.1.1.11 #define QZ_FAIL (-2)
Unspecified error
6.1.1.12 #define QZ_FORCE_SW (2)
using SW: Switch to software because of previous block
6.1.1.13 #define QZ_HUFF_HDR_DEFAULT QZ_DYNAMIC_HDR
6.1.1.14 #define QZ_HW_BUFF_MAX_SZ (512*1024)
6.1.1.15 #define QZ_HW_BUFF_MIN_SZ (1*1024)
6.1.1.16 #define QZ_HW_BUFF_SZ (64*1024)
6.1.1.17 #define QZ_LOW_MEM (14)
using SW: Not enough pinned memory
6.1.1.18 #define QZ_LZ4 ((unsigned char)'4')
6.1.1.19 #define QZ_MAX_ALGORITHMS ((int)255)
6.1.1.20 #define QZ_MAX_FORK_DEFAULT 3
6.1.1.21 #define QZ_MEMCPY( dest, src, dest_sz, src_sz ) memcpy((void *)(dest), (void *) (src), (size_t)MIN(dest_sz,
        src_sz))
6.1.1.22 #define QZ_NO_HW (11)
using SW: No QAT HW detected
```

28 File Documentation

6.1.1.23 #define QZ_NO_INST_ATTACH (13)

using SW: Could not attach to an instance

6.1.1.24 #define QZ_NO_MDRV (12)

using SW: No memory driver detected

6.1.1.25 #define QZ_NOSW_LOW_MEM (-104)

not using SW: not enough pinned memory

6.1.1.26 #define QZ_NOSW_NO_HW (-101)

not using SW: No QAT HW detected

6.1.1.27 #define QZ_NOSW_NO_INST_ATTACH (-103)

not using SW: Could not attach to instance

6.1.1.28 #define QZ_NOSW_NO_MDRV (-102)

not using SW: No memory driver detected

6.1.1.29 #define QZ_PARAMS (-1)

invalid parameter in function call

6.1.1.30 #define QZ_POLL_SLEEP_DEFAULT 10

6.1.1.31 #define QZ_REQ_THRESHOLD_DEFAULT 4

6.1.1.32 #define QZ_REQ_THRESHOLD_MAXINUM 4

6.1.1.33 #define QZ_REQ_THRESHOLD_MINIMUM 1

6.1.1.34 #define QZ_SNAPPY ((unsigned char)'S')

6.1.1.35 #define QZ_SW_BACKUP_DEFAULT 1

6.1.2 Function Documentation

6.1.2.1 unsigned int qzMaxCompressedLength (unsigned int src_sz)

Index

algo_hw	include/qatzip.h, 25
QzStatus_S, 23	input_sz_thrshold
algo_sw	QzSessionParams_S, 22
QzStatus_S, 23	internal
Q2010105_0, 20	QzSession S, 21
comp_algorithm	<u> </u>
QzSessionParams_S, 22	MIN
comp_lvl	qatzip.h, 26
QzSessionParams_S, 22	max forks
- '	QzSessionParams S, 23
Data Compression API	memory_alloced
QZ_DIR_BOTH, 10	QzStatus_S, 24
QZ_DIR_COMPRESS, 10	
QZ_DIR_DECOMPRESS, 10	poll_sleep
QZ_DYNAMIC_HDR, 11	QzSessionParams_S, 23
QZ_STATIC_HDR, 11	
Data Compression API, 7	QZ_DIR_BOTH
QZ_OK, 8	Data Compression API, 1
QZ_SKID_PAD_SZ, 8	QZ_DIR_COMPRESS
qzClose, 11	Data Compression API, 1
qzCompress, 11	QZ_DIR_DECOMPRESS
qzCompressCrc, 12	Data Compression API, 1
qzDecompress, 13	QZ_DYNAMIC_HDR
QzDirection_E, 10	Data Compression API, 1
QzDirection_T, 9	QZ_STATIC_HDR
qzFree, 14	Data Compression API, 1
qzGetDefaults, 14	QZ_BUF_ERROR
qzGetStatus, 15	qatzip.h, <mark>26</mark>
QzHuffmanHdr_E, 10	QZ_DATA_ERROR
QzHuffmanHdr_T, 9	qatzip.h, <mark>27</mark>
qzInit, 16	QZ_DEFLATE
qzMalloc, 16	qatzip.h, <mark>27</mark>
qzMemFindAddr, 18	QZ_DIRECTION_DEFAULT
QzSession_T, 9	qatzip.h, <mark>27</mark>
QzSessionParams_T, 9	QZ_DUPLICATE
qzSetDefaults, 18	qatzip.h, <mark>27</mark>
qzSetupSession, 19	QZ_FAIL
QzStatus_T, 9	qatzip.h, <mark>27</mark>
qzTeardownSession, 20	QZ_FORCE_SW
direction	qatzip.h, 27
QzSessionParams_S, 22	QZ_HUFF_HDR_DEFAULT
	qatzip.h, 27
huffman_hdr	QZ_HW_BUFF_MAX_SZ
QzSessionParams_S, 22	qatzip.h, <mark>27</mark>
hw_buff_sz	QZ_HW_BUFF_MIN_SZ
QzSessionParams_S, 22	qatzip.h, 27
hw_session_stat	QZ_HW_BUFF_SZ
QzSession_S, 21	qatzip.h, 27
hw_session_status	QZ_LOW_MEM
QzStatus_S, 24	qatzip.h, <mark>27</mark>

30 INDEX

QZ_LZ4 qatzip.h, 27	QZ_SNAPPY, 28 qzMaxCompressedLength, 28
QZ_MAX_ALGORITHMS	qzClose
qatzip.h, 27	Data Compression API, 11
QZ_MAX_FORK_DEFAULT	qzCompress
qatzip.h, 27	Data Compression API, 11
QZ_MEMCPY	qzCompressCrc
qatzip.h, 27	Data Compression API, 12
QZ_NO_HW	qzDecompress
qatzip.h, 27	Data Compression API, 13
QZ_NO_INST_ATTACH	QzDirection_E
qatzip.h, 27	Data Compression API, 10
QZ_NO_MDRV	QzDirection_T
qatzip.h, 28	Data Compression API, 9
QZ_NOSW_LOW_MEM	qzFree
qatzip.h, <mark>28</mark>	Data Compression API, 14
QZ_NOSW_NO_HW	qzGetDefaults
qatzip.h, 28	Data Compression API, 14
QZ_NOSW_NO_MDRV	qzGetStatus
qatzip.h, <mark>28</mark>	Data Compression API, 15
QZ_OK	QzHuffmanHdr_E
Data Compression API, 8	Data Compression API, 10
QZ_PARAMS	QzHuffmanHdr_T
qatzip.h, 28	Data Compression API, 9
QZ_SKID_PAD_SZ	qzInit
Data Compression API, 8	Data Compression API, 16
QZ_SNAPPY	qzMalloc
qatzip.h, 28	Data Compression API, 16
qat_hw_count	qzMaxCompressedLength
QzStatus_S, 24	qatzip.h, 28
qat_instance_attach	qzMemFindAddr
QzStatus_S, 24	Data Compression API, 18
qat_mem_drvr	QzSession_S, 21
QzStatus_S, 24	hw_session_stat, 21
qat_service_stated	internal, 21
QzStatus_S, 24	thd_sess_stat, 21
qatzip.h	total_in, 21
MIN, 26	total_out, 21
QZ_BUF_ERROR, 26	QzSession_T
QZ_DATA_ERROR, 27	Data Compression API, 9
QZ_DEFLATE, 27	QzSessionParams_S, 22
QZ_DUPLICATE, 27	comp_algorithm, 22
QZ_FAIL, 27	comp_lvl, 22
QZ_FORCE_SW, 27	direction, 22
QZ_HW_BUFF_MAX_SZ, 27	huffman_hdr, 22
QZ_HW_BUFF_MIN_SZ, 27	hw_buff_sz, 22
QZ_HW_BUFF_SZ, 27	input_sz_thrshold, 22
QZ_LOW_MEM, 27	max_forks, 23
QZ_LZ4, 27	poll_sleep, 23
QZ_MAX_ALGORITHMS, 27	req_cnt_thrshold, 23
QZ_MEMCPY, 27	sw_backup, 23
QZ_NO_HW, 27 QZ_NO_INST_ATTACH, 27	QzSessionParams_T Data Compression API, 9
QZ_NO_INST_ATTACH, 27 QZ_NO_MDRV, 28	qzSetDefaults
QZ_NOSW_LOW_MEM, 28	Data Compression API, 18
QZ_NOSW_NO_HW, 28	qzSetupSession
QZ_NOSW_NO_MDRV, 28	Data Compression API, 19
QZ_PARAMS, 28	QzStatus_S, 23
32_1 / 11 / 11 / 10 O , 20	32010105_0, 20

INDEX 31

```
algo_hw, 23
    algo_sw, 23
    hw_session_status, 24
    memory_alloced, 24
    qat_hw_count, 24
    qat_instance_attach, 24
    qat_mem_drvr, 24
    qat_service_stated, 24
    using_huge_pages, 24
QzStatus_T
    Data Compression API, 9
qzTeardownSession
    Data Compression API, 20
req_cnt_thrshold
    QzSessionParams_S, 23
sw_backup
    QzSessionParams_S, 23
thd_sess_stat
    QzSession_S, 21
total_in
    QzSession_S, 21
total out
    QzSession_S, 21
using_huge_pages
    QzStatus_S, 24
```