

Lecture 20 -Low-Level Programming

Meng-Hsun Tsai CSIE, NCKU




Introduction

- Some kinds of programs need to perform operations at the bit level:
 - Systems programs (including compilers and operating systems)
 - Encryption programs
 - Graphics programs
 - Programs for which fast execution and/or efficient use of space is critical



Bitwise Operators

- C provides six bitwise operators, which operate on integer data at the bit level.
- Two of these operators perform shift operations.
- The other four perform bitwise complement, bitwise and, bitwise exclusive or, and bitwise inclusive or operations.





Bitwise Shift Operators

- The bitwise shift operators shift the bits in an integer to the left or right:
 - << left shift
 - >> right shift
- The operands for << and >> may be of any integer type (including char).
- The integer promotions are performed on both operands; the result has the type of the left operand after promotion.



Bitwise Shift Operators (cont.)

- The value of i << j is the result when the bits in i are shifted left by j places.
 - For each bit that is "shifted off" the left end of i, a zero bit enters at the right.
- The value of i >> j is the result when i is shifted right by j places.
 - If i is of an unsigned type or if the value of i is nonnegative, zeros are added at the left as needed.
 - If i is negative, the result is implementation-defined.



Bitwise Shift Operators (cont.)

 Examples illustrating the effect of applying the shift operators to the number 13:

```
unsigned short i, j;
i = 13;
  /* i is now 13 (binary 000000000001101) */
j = i << 2;
  /* j is now 52 (binary 0000000000110100) */
j = i >> 2;
  /* j is now 3 (binary 00000000000011) */
```



Bitwise Shift Operators (cont.)

 To modify a variable by shifting its bits, use the compound assignment operators <<= and >>=:

```
i = 13;
  /* i is now 13 (binary 0000000000001101) */
i <<= 2;
  /* i is now 52 (binary 000000000110100) */
i >>= 2;
  /* i is now 13 (binary 000000000001101) */
```

• The bitwise shift operators have lower precedence than the arithmetic operators, which can cause surprises:

```
i << 2 + 1 not (i << 2) + 1

means i << (2 + 1),
```

- There are four additional bitwise operators:
 - bitwise complement
 - & bitwise and
 - bitwise exclusive or
 - bitwise inclusive or

X	у	x y	x&y	х^у
0	0	0	0	0
0	1	1	0	1
1	0	1	0	1
1	1	1	1	0

The ~ operator is unary; the other operators are binary.



Examples of the ~, &, ^, and | operators:

```
unsigned short i, j, k;
i = 21;
 /* i is now 21 (binary 000000000010101) */
j = 56;
/* j is now 56 (binary 000000000111000) */
k = \sim i:
  /* k is now 65514 (binary 1111111111101010) */
k = i \& j;
/* k is now 16 (binary 000000000010000) */
k = i ^ j;
 /* k is now 45 (binary 00000000101101) */
k = i \mid j;
             61 (binary 000000000111101) */
 /* k is now
```

- The ~ operator can be used to help make low-level programs more portable.
 - An integer whose bits are all 1: ~0
 - An integer whose bits are all 1 except for the last five: $\sim 0 \times 1 \, \mathrm{f}$

```
0 00000000 0000000 0x1f 00000000 00011111
~0 1111111 1111111  ~0x1f 1111111 11100000
```



 Each of the ~, &, ^, and | operators has a different precedence:

```
Highest: ~ & .
```

Lowest:

Examples:

1111 Since 2010

Using parentheses helps avoid confusion.

The compound assignment operators &=, ^=, and
 |= correspond to the bitwise operators &, ^, and |:

```
i = 21;
  /* i is now 21 (binary 000000000010101) */
j = 56;
  /* j is now 56 (binary 00000000111000) */
i &= j;
  /* i is now 16 (binary 000000000010000) */
i ^= j;
  /* i is now 40 (binary 00000000101000) */
i \mid = j;
/* i is now 56 (binary 000000000111000) */
```

- The bitwise operators can be used to extract or modify data stored in a small number of bits.
- Common single-bit operations:
 - Setting a bit
 - Clearing a bit
 - Testing a bit

00000000 00111000 15 0

- Assumptions:
 - i is a 16-bit unsigned short variable.
- The leftmost—or **most significant**—bit is numbered 15 and the least significant is numbered 0.

 Setting a bit. The easiest way to set bit 4 of i is to or the value of i with the constant 0x0010:

```
i = 0x0000;
  /* i is now 000000000000000000 */
i |= 0x0010;
  /* i is now 000000000010000 */
```

• If the position of the bit is stored in the variable j, a shift operator can be used to create the mask:

```
i |= 1 << j; /* sets bit j */
```

• Example: If j has the value 3, then 1 << j is 0x0008.



 Clearing a bit. Clearing bit 4 of i requires a mask with a 0 bit in position 4 and 1 bits everywhere else:

```
i = 0x00ff;
  /* i is now 0000000111111111 */
i &= ~0x0010;
  /* i is now 000000011101111 */
```

 A statement that clears a bit whose position is stored in a variable:

 Testing a bit. An if statement that tests whether bit 4 of i is set:

```
if (i & 0 \times 0010) ... /* tests bit 4 */
```

A statement that tests whether bit j is set:

```
if (i & 1 << j) ... /* tests bit j */
```

```
00000000 00001000
j 0
```



- Working with bits is easier if they are given names.
- Suppose that bits 0, 1, and 2 of a number correspond to the colors blue, green, and red, respectively.
- Names that represent the three bit positions:

Examples of setting, clearing, and testing the BLUE bit:

MSLAD since 2010

It's also easy to set, clear, or test several bits at a time:

```
i |= BLUE | GREEN;
  /* sets BLUE and GREEN bits */

i &= ~(BLUE | GREEN);
  /* clears BLUE and GREEN bits */

if (i & (BLUE | GREEN)) ...
  /* tests BLUE and GREEN bits */
```

 The if statement tests whether either the BLUE bit or the GREEN bit is set.



Using the Bitwise Operators to Access Bit-Fields

- Dealing with a group of several consecutive bits (a bitfield) is slightly more complicated than working with single bits.
- Common bit-field operations:
 - Modifying a bit-field
 - Retrieving a bit-field



- Modifying a bit-field. Modifying a bit-field requires two operations:
 - A bitwise and (to clear the bit-field)
 - A bitwise or (to store new bits in the bit-field)
- The & operator clears bits 4-6 of i; the | operator then sets bits 6 and 4.



- To generalize the example, assume that j contains the value to be stored in bits 4–6 of i.
- j will need to be shifted into position before the bitwise or is performed:

```
i = (i \& \sim 0 \times 0070) | (j << 4);
/* stores j in bits 4-6 */ j << 4 00000000 010100000
```



 Retrieving a bit-field. Fetching a bit-field at the right end of a number (in the least significant bits) is easy:

```
j = i \& 0x0007;
/* retrieves bits 0-2 */

0x0007 00000000 00000111
```

 If the bit-field isn't at the right end of i, we can first shift the bit-field to the end before extracting the field using the & operator:

```
j = (i >> 4) & 0x0007;
   /* retrieves bits 4-6 */
   i >> 4 ???????? ?xxx????
```



Program: XOR Encryption

- One of the simplest ways to encrypt data is to exclusive-or (XOR) each character with a secret key.
- Suppose that the key is the & character.
- XORing this key with the character z yields the \ character:

```
XOR 01111010 (ASCII code for &) 01111010 (ASCII code for z) 01011100 (ASCII code for \)
```



 Decrypting a message is done by applying the same algorithm:

```
XOR 0100110 (ASCII code for &) 01011100 (ASCII code for \) 01111010 (ASCII code for z)
```



- The xor.c program encrypts a message by XORing each character with the & character.
- The original message can be entered by the user or read from a file using input redirection.
- The encrypted message can be viewed on the screen or saved in a file using output redirection.
- A sample file named msg:

Trust not him with your secrets, who, when left alone in your room, turns over your papers.

--Johann Kaspar Lavater (1741-1801)



 A command that encrypts msg, saving the encrypted message in newmsg:

```
xor <msg >newmsg
```

Contents of newmsg:

```
rTSUR HIR NOK QORN _IST UCETCRU, QNI, QNCH JC@R GJIHC OH _IST TIIK, RSTHU IPCT _IST VGVCTU.
--linghh mguvgt jgpgrct (1741-1801)
```

 A command that recovers the original message and displays it on the screen:

```
xor < newmsg
```



- The xor.c program won't change some characters, including digits.
- XORing these characters with & would produce invisible control characters, which could cause problems with some operating systems.
- The program checks whether both the original character and the new (encrypted) character are printing characters.
- If not, the program will write the original character instead of the new character.



```
xor.c
#include <ctype.h>
#include <stdio.h>
#define KEY '&'
int main (void)
  int orig char, new char;
 while ((orig_char = getchar()) != EOF) {
    new char = orig char ^ KEY;
    if (isprint(orig char) && isprint(new_char))
      putchar(new char);
    else
      putchar(orig char);
  return 0;
```