# **Install Milvus from Source Code**

# **Install Milvus from Source Code**

# Requirements

- Operating system
  - Ubuntu 18.04 or higher
  - CentOS 7
- GCC 7.0 or higher to support C++ 17
- CMake 3.14 or higher
- Git

For GPU-enabled version, you will also need:

- CUDA 10.0 or higher
- NVIDIA driver 418 or higher

## **Download milvus source from GitHub**

```
1 git clone https://github.com/milvus-io/milvus
```

# **Install dependencies**

#### **Install in Ubuntu**

```
1 $ cd [Milvus root path]/core
2 $ ./ubuntu_build_deps.sh
```

#### **Install in CentOS**

```
1 $ cd [Milvus root path]/core
2 $ ./centos7_build_deps.sh
```

## **Build from source**

```
1 $ cd [Milvus root path]/core
2 $ ./build.sh -t Debug
```

or

```
1 $ ./build.sh -t Release
```

By default, it will build CPU-only version. To build GPU version, add –g option.

```
1 $ ./build.sh -g
```

If you want to know the complete build options, run the following command.

```
1 $./build.sh -h
```

When the build is completed, everything that you need in order to run Milvus will be installed under [Milvus root path]/core/milvus.

#### **Launch Milvus server**

```
1 $ cd [Milvus root path]/core/milvus
```

Add lib/directory to LD\_LIBRARY\_PATH

```
1 $ export LD_LIBRARY_PATH=$LD_LIBRARY_PATH:[Milvus root path]/core/
milvus/lib
```

Then start Milvus server:

```
1 $ cd scripts
2 $ ./start_server.sh
```

To stop Milvus server, run:

```
1 $ ./stop_server.sh
```

## **Troubleshooting**

**Error message: protocol https not supported or disabled in libcurl** Follow the steps below to solve this problem:

- 1. Make sure you have libcurl4-openssl-dev installed in your system.
- 2. Try reinstalling the latest CMake from source with --system-curl option:

```
1 $ ./bootstrap --system-curl
2 $ make
3 $ sudo make install
```

If the --system-curl command doesn't work, you can also reinstall CMake in **Ubuntu Software** on your local computer.

**Error message: internal compiler error** Try increasing the memory allocated to Docker. If this doesn't work, you can reduce the number of threads in CMake build in [Milvus root path]/core/build.sh.

```
1 make -j 8 install || exit 1 # The default number of threads is 8.
```

Note: You might also need to configure CMake build for faiss in [Milvus root path]/core/src/index/thirdparty/faiss.

**Error message: error while loading shared libraries: libmysqlpp.so.3** Follow the steps below to solve this problem:

- 1. Check whether libmysqlpp.so.3 is correctly installed.
- 2. If libmysqlpp.so.3 is installed, check whether it is added to LD\_LIBRARY\_PATH.

**CMake version is not supported** Follow the steps below to install a supported version of CMake:

- 1. Remove the unsupported version of CMake.
- 2. Get CMake 3.14 or higher. Here we get CMake 3.14.

```
1 $ wget https://cmake.org/files/v3.14/cmake-3.14.7-Linux-x86_64.tar
```

3. Extract the file and install CMake.

```
1  $ tar zxvf cmake-3.14.7-Linux-x86_64.tar.gz
2  $ mv cmake-3.14.7-Linux-x86_64 /opt/cmake-3.14.7
3  $ ln -sf /opt/cmake-3.14.7/bin/* /usr/bin/
```