Component description: *.wbp-component.xml
 Table 1.1 – tags in *.wbp-component.xml

Tag	Description
<component></component>	The root element in a component description.
<pre><description>A component that allows the user to select one or more objects from a list.</description></pre>	Sets the description of the component to display on the palette.
<model class=""></model>	Sets the class of the model – a subclass of JavaInfo.
<order>last</order>	The following component order parameters are supported:
CREATION <creation></creation>	Specifies source code and method invocations that should be used to create this component using the constructor creation support (it is expected that the code in <source/> is an object created using the constructor). Optional <invocation> tags allow method invocations to be added directly after the component has been added. This is useful when setting the default text, selection, etc. The «id» attribute can be used with the «creationId» attribute of the <component>, in the <palette> in plugin.xml to specify several variants of creating components with the same type. For example, a SWT Button can be a push/check/radio button, but the only difference is the style specified in the constructor.</palette></component></invocation>

<standard-bean-properties></standard-bean-properties>	Adds standard bean properties with getters and setters.
	Property, is created only if Designer has an editor for this property type. For example, String, Icon, int, etc.
	Each «standard» property has an id «signatureOfSetterMethod».
	In the following tags, use the «name» attribute to specify property - rules of matching are following: • «m:nameOfMethod» - specifies that only the setter should be considered, and the name of the method is given; • «f:fieldName» - specifies the exact name of the field; • «setText(java.lang.String[])» - specifies the exact signature for setter; • «nameOfMethodOrField» - it first tries to find the setter with the given name, then tries to find a field with the given name.
<pre><public-field-properties></public-field-properties></pre>	Adds field based properties.
	Property is created only if Designer has an editor for this property type, for example String, Icon, int, etc.
	Each «field» property has id «property:field: nameOfField».
<pre><pre><pre><pre>cproperties-preferred names="text icon"/></pre></pre></pre></pre>	Specifies that the listed properties are preferred, i.e. properties often used with this component. For example text and image on a button. These properties are highlighted in the properties table (by default the bold font is used).
<pre><pre><pre>cproperties-normal names="align valign"/></pre></pre></pre>	Specifies that the listed properties are normal, so undo any special category settings specified in descriptions for superclass.
<pre><pre><pre><pre><pre><pre><pre>properties-advanced names="bounds location size maximumSize minimumSize preferredSize"/></pre></pre></pre></pre></pre></pre></pre>	Specifies that the listed properties are advanced. Advanced properties are not displayed by default in the properties table. They are also painted with a different font and color (defaults to italic font and gray color). Specifying advanced properties reduces the number of properties listed in the properties table, and also speeds up searching.
<pre><pre><pre><pre>properties-hidden names="Ul label"/></pre></pre></pre></pre>	Specifies that listed properties should not be used at design time. These can cause some bad effects, so we don't want to show them to the user. There is no way for the user to make them visible.
<pre><pre><pre>cproperties-noDefaultValue names="pageLeft pageTop right bottom"/></pre></pre></pre>	Specifies that there is no default value for these properties. This feature is used in GWT libraries, such as GWT-Ext and SmartGWT. These libraries have specific quirks - they create JavaScript object for reading value, and at the same time they don't allow

	to set many properties after creating object.
<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Sets some tag for standard property. Designer uses these tags to interpret properties in some special way. For example <code>«isText == true»</code> means that this property is displayed as text for this component, so when the user requests direct edit, property <code>«title»</code> should be edited.
	See other tag in table below.
<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Specifies the editor for the property.
<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Specifies category for the property. Possible values are: preferred, normal, advanced, hidden.
<pre><pre><pre><pre><pre><pre><pre>< defaultValue value="false"/></pre></pre></pre></pre></pre></pre></pre>	Specifies the default value for the property. This is useful, for example, when some «standard bean property» has only a «set» method, but not a «get» method, so we can not get the default value from the component instance. Any MVEL expression/script can be used, editor ClassLoader is set as context ClassLoader, so classes from the project can be referenced directly.
<pre><pre><pre><pre><pre><pre><</pre></pre></pre></pre></pre></pre>	Specifies the alternative «getter» method. Sometimes a «normal» setter method does not have a corresponding getter method. For example, for «setFoo» we expect «getFoo» as the getter method. To use a different getter method, specify <getter and="" getter="" give="" method.<="" name="" of="" td="" the=""></getter>
<methods-include signature="/set\w+\([^,]+\)/"></methods-include> <methods-exclude signature="setVisible(boolean)"></methods-exclude>	Specifies that methods with given signature should be included/excluded in the set of

<method name="setLocation" order="beforeAssociation"></method>	executable methods. Designer executes only the methods included in the executable set, invocations of other methods that are present in the source code are ignored. If the signature starts with «/» then it is handled as a regular expression. Specifies executable method with parameters of the given type. See the description for the «parameter» tag below: «order» - specifies the location for invoking this method. See the «method-order» for a full description. «tag» element provides a way to set some tag for a method. Known tags are: 1. «noFactory» used to indicate that this method should not be marked as "extracted" by default, when we open the «Extract Factory» dialog.
<pre><parameter [child="true/false" [child2="true/false" [defaultsource="" [name="" [parent="true/false" [parent2="true/false" [property="id"]="" type=""></parameter></pre>	 2. and much more no description yet Describes the parameters for the method or constructor. «type» – the fully qualified type of the parameter, for example «int» or «java.lang.String»; «parent» - is «true» if the parameter is a parent of the component, for example in SWT, the parent is passed in the constructor; «child» - is «true» if parameter is child of this component, for example in Swing the method «add(java.awt.Component)» receives the child. «parent2»/«child2» - if a pair of parameters is defined, the invocation of the method creates a parent/child link. For example, it is possible to create a method like «addInGrid(x, y, parent, child)» that adds the given child on the given parent in the specified grid cell. «property» specifies the id of property to which this parameter is bound. It is usually used in the constructor description. Oftentimes, in Swing, there are several constructors with text/image/etc properties. «defaultSource» - another attribute that is useful mainly for constructors. When the user asks for «cleaning» property, we use this source (because we can not remove the argument of the constructor). If there is no «defaultSource», «cleaning» will do nothing. «editor» tag that allows to specify the editor for this parameter, usually in the constructor. If there is no «editor» attribute defined, type based editor will be used.
<method-order></method-order>	The following order parameters are supported: • «last» - after any related statement and any child.

- «afterCreation» directly after the creation statement. This order is used by default.
- «beforeAssociation» before the statement that associates this component with its parent, for example before panel.add(component) invocation.
- «afterAssociation» after the statement that associates this component with its parent. In GWT libraries some properties should be set before, and some – after association.
- «after methodSignature» after invocation of a method with the specified signature. If no invocation with such signature, the default association will be used, and when «methodSignature» will be added, it will be added before the method is marked so.
- «afterLastStatement» after any related statement, but before any child.

Tags:

- «default» specifies default position for any method invocation of this component and its subclasses. Only the following orders can be used as default: afterCreation, beforeAssociation, afterAssociation, afterLastStatement.
- «method» specifies the method order for a single method.
- «methods» and «s» (signature) convenient way to specify the same order for multiple methods.

```
<method-property title="text"
method="setText(java.lang.String,boolean,boolean)"/>
cproperty id="setText(java.lang.String,boolean,boolean)">
      <category value="advanced"/>
</property>
<methods>
<method name="setAlignment">
   <parameter type="int">
    <editor id="staticField">
     <parameter name="class">org.eclipse.swt.SWT</parameter>
     <parameter name="fields">LEFT CENTER RIGHT</parameter>
    </editor>
   </parameter>
   <parameter type="int">
    <editor id="staticField">
     <parameter name="class">org.eclipse.swt.SWT</parameter>
     <parameter name="fields">TOP CENTER BOTTOM</parameter>
```

Specifies that complex property for some method with several parameters should be created. The ID for such property is the same as signature of the method (i.e. practically the same as value of the «method» attribute). This property will have a sub-property for each parameter. Title of the sub-property is the same as the name of the corresponding parameter. The ID for the parameter property is «methodSignature parameterIndex».

You can specify the name, default source and editor in the corresponding method parameter description.

<method-property method="setAlignment(int,int)" title="alignment"></method-property> <method-single-property method="foo(int)" title="myFoo"></method-single-property>	Specifies that a property with the title myFoo » should be created. This is the same as the property created by standard-bean-properties , but the method is not a setter, therefore we need to specify it directly. Id of such property is soo(int) ».
<pre><constructors></constructors></pre>	Describes one or more constructors, similar to methods with a <constructor> tag and one or more <pre></pre></constructor>
<exposing-rules></exposing-rules>	Describes the rules for exposing children components (similar to getXXX() methods). You can include or exclude a set of methods. Note, that rules are executed in reverse order, so if you later have some rules that includes (enables) using some method, it will be used for exposing, even if previous rules exclude it. • «package» accepts any method of classes exactly in the same package, without sub-packages; • «method» accepts method with exactly the same name, without parameters in any package. Of course, all these filters will work only for components that correspond to this description or its subclasses.

Table 1.2 component parameters.

<pre><parameters></parameters></pre>	Specifies that description for this component should not be cached even if the package has «.wbp-cache-descriptions» file, so it requires caching by default.
<pre><parameters></parameters></pre>	Parameter «layout.has» specifies if this component has layout manager (supported by Swing anf eSWT).
<pre><parameters></parameters></pre>	Parameters «variable.name» and «variable.acronym» specify default variable name and acronym for this component. So, component developer can tweak code generation. For example for javax.swing.JTree we can specify that acronym «tree» should be used, not auto generated «tr».
<pre><parameter name="variable.validateID"><![CDATA[</td><td>Parameter "variable.validateID" is script that can validate that given variable «id» can be used for this component, and return alternative variable.</td></tr><tr><td><pre><parameter name='visible.inTree'>false</parameter> <parameter name='visible.inGraphical'>false</parameter></pre></td><td>These parameters specify if component should be visible in components tree and design canvas.</td></tr><tr><td><pre><parameter name="objectReadyValidator">component.parent != null</parameter></pre></td><td>ExpressionAccessor's get default values from component object, but sometimes just fact that component has object is not enough to allow invocation of getters and reading from fields. For example GWT-Ext requires that component should be bound to parent (so its DOM Element rendered) before we can invoke most of its methods. So, we need some way to allow component specify that it is ready.</td></tr></tbody></table>]]></parameter></pre>	

	Following variables are defined for script: • «component» - the toolkit object.
<pre><parameters></parameters></pre>	In grid-based layouts (such as SWT GridLayout, Swing GridBagLayout and Jgoodies FormLayout), components may be automatically aligned when dropped into layout. • «gridLayout.grabHorizontal» means that component's column will grab excess space, and component fills the column horizontally. • «gridLayout.grabVertical» means that component's row will grab excess space, and component fills the row vertically. • «gridLayout.rightAlignment.isLabel» means that this component is «label» like component (Label in SWT, Jlabel in Swing), so when it is on the same row as «text» like component, and directly on left of it, then «label» should be aligned right. • «gridLayout.rightAlignment.isTarget» means that this component is «text» like component, for example Text in SWT, JtextField in Swing.
<pre><parameters></parameters></pre>	Mark components that does not accept focus using this parameter, so they will be excluded from setting the tab order.
<pre><parameter name="tabOrder.disable">true</parameter></pre>	Disables displaying «tab order» property for this component.
<pre><parameter name="databinding.disable">true</parameter></pre>	Disables displaying «bindings» property for this component.
<pre><parameters></parameters></pre>	Specifies that on double click on component, event listener with name «action» and its method «performed» will be opened. So, you can easily configure your custom components to generate/open often used event listener using double click.
<pre><parameter name="events: no listeners of class">javax.swing.JPanel</parameter></pre>	WindowBuilder automatically discovers methods «addXListener» and «addXHandler» using reflection and shows them as event listeners. Using this parameter you specify that you don't want to show user listeners declared in specified class and any of its superclasses. This is useful if you build specialized component and don't want to overload user with bunch of listeners inherited from Swing (for example).
<pre><parameters></parameters></pre>	For JFace Viewer, specifies name of method (without arguments) that returns Control.
<pre><parameters></parameters></pre>	For SWT «layout data» objects, we may exclude some properties, because they don't add any new information. For example «class» is not needed for LayoutData, it is already displayed as text. Also for RowData all constructor properties are mapped to fields, so no need to show «Constructor» property. So, we can perform

	some «fine tuning». It's not important, just nice to have.
<pre><parameters></parameters></pre>	For SWT Layout, specifies that this layout has LayoutData, and its type.
<pre><parameters></parameters></pre>	Parameters for direct edit. • «directEdit.location.insets» insets for component bounds; • «directEdit.location.horizontalAlignment» horizontal alignment of text widget, possible values: «center» (or empty, i.e. no alignment specified), «left». • «directEdit.location.verticalAlignment» vertical alignment of text widget, possible values: «center» (or empty, i.e. no alignment specified), «top». For buttons, labels, texts - «center» is good default. For JFrame, Shell and other windows - «left» and «top» alignments with reasonable insets can be used.
flip expanded <parameter name="double-click.flipBooleanProperty">expanded</parameter>	Flips given boolean property between true/false values when user double clicks component on design canvas. If no such property, double click is ignored. If property value is not boolean, double click is ignored. Note that you can specify «/» separated path, not just title of property.
select it on double click <parameter name="double-click.runScript">doSelect()</parameter>	Runs specified MVEL script with model as context.
flow container (canvas and tree) <parameter name="flowContainer">true</parameter> <parameter name="flowContainer.horizontal">true</parameter> <parameter name="flowContainer.association">%parameter> <parameter name="flowContainer.association">%parameter> %)</parameter></parameter>	WindowBuilder supports declarative flow based containers, i.e. containers where children components can be placed before/after each other. Flow containers may be horizontal or vertical, accept some type of components, user same or different type of existing children components as references to add/move before them. When just «flowContainer» is specified, then flow container for both design canvas and components tree is declared. When «flowContainer.canvas» and
flowContainer for design canvas <parameter name="flowContainer.canvas">true</parameter> <parameter name="flowContainer.horizontal">true</parameter> <parameter name="flowContainer.canvas.association">%parentAccess %add(%child%)</parameter>	«flowContainer.tree» you can specify separate settings for design canvas and components tree. You can use «.number» prefix to specify up to 10 separate flow containers with different types or components and references. For example for SWT Table you need to use two – for TableColumn and TableItem.

```
<!-- two containers - for TableColumn and TableItem -->
<parameter name="flowContainer.1">true</parameter>
<parameter name="flowContainer.1.horizontal">true</parameter>
<parameter name="flowContainer.1.component">TableColumn/parameter>
<parameter name="flowContainer.1.reference">TableColumn/parameter>
<parameter name="flowContainer.2">true</parameter>
<parameter name="flowContainer.2.horizontal">false</parameter>
<parameter name="flowContainer.2.component">TableItem</parameter>
<parameter name="flowContainer.2.reference">TableItem</parameter>
<!-- flowContainer for tree -->
<parameter name="flowContainer.tree">true</parameter>
<parameter name="flowContainer.tree.association">%parentAccess
%add(%child%)</parameter>
<!-- flowContainer defaults -->
parameter
name="flowContainer.defaultComponent">com.google.gwt.user.client.ui.Widget
</parameter>
<parameter</pre>
name="flowContainer.defaultReference">com.google.gwt.user.client.ui.Widget< | «com.google.gwt.user.client.ui.Widget» in GWT. So, it is convenient to use
/parameter>
<!-- list of types -->
<parameter</pre>
name="flowContainer.component">org.eclipse.nebula.widgets.grid.GridColumn
org.eclipse.nebula.widgets.grid.GridColumnGroup</parameter>
<!-- MVEL script as validator -->
<parameter name="flowContainer.component-validator"><![CDATA]</pre>
      isComponentType('org.eclipse.nebula.widgets.grid.GridColumn') ||
      isComponentType('org.eclipse.nebula.widgets.grid.GridColumnGroup')
]]></parameter>
<parameter name="flowContainer.reference-validator"><![CDATA]</pre>
      isReferenceType('org.eclipse.nebula.widgets.grid.GridColumn') ||
      isReferenceType('org.eclipse.nebula.widgets.grid.GridColumnGroup')
```

Parameter «flowContainer.horizontal» specifies if container is horizontal on design canvas. In components tree, items are always layed out vertically, so «flowContainer,horizontal» is ignored for the tree. You can use not only static values «true» or «false», but also MVEL expressions, such as «isHorizontal()» that will be evaluated using JavaInfo model for container as context.

Parameters «flowContainer.component» or «flowContainer.reference» specify what kind of components can be dropped on this container and can be used as reference to drop before. You can use single name of type or space separated list of them. When only «flowContainer.component» is specified, the same validator is used for references.

If you need to perform more complex check for component/reference, you can specify «flowContainer.component-validator» and «flowContainer.reference-validator». In these scripts you can use variables «container», «component» and «reference». Also, you can use methods «isComponentType()» and «isReferenceType()» to check that component or reference are subclasses of given one. You can also call any methods of «container», «component» and «reference».

Often all containers in the same toolkit accept same type of components and references, for example «org.eclipse.swt.widgets.Control» is SWT or «flowContainer.defaultComponent» and «flowContainer.defaultReference» for superclass of all containers and don't specify them separately in each place (but you may if you want). Note, that defaults are used only when you don't specify both – component and reference validators.

Parameter «flowContainer.association» specifies the child component's association with this flow container. It is required for add/move operations in JavaInfoUtils. The following types of associations are supported:

• «invocationChild» - usual association in Swing and GWT, when a child is passed into the «add» method, it requires exact specification of method after the space «%parentAccess%add(%child%)». Since this type of association is often used, it does not require a separate «invocationChild» prefix, you can just write the invocation itself.

```
]]></parameter>
<!-- simple container -->
                                                                                       WindowBuilder supports declarative «simple» containers, i.e. containers that
<parameter name="simpleContainer">true</parameter>
                                                                                       accept only one component.
<parameter name="simpleContainer.association">%parentAccess
%setWidget(%child%)</parameter>
                                                                                       When «simpleContainer» (without specifying canvas or tree) is specified, then
                                                                                       simple container for both the design canvas and components tree is declared.
                                                                                       When «simpleContainer.canvas» and «simpleContainer.tree» you can
                                                                                       specify separate settings for design canvas and components tree.
                                                                                       Parameter «simpleContainer.component» specifies what kind of components
                                                                                       can be dropped on this container. You can use a single name of type or a space-
                                                                                       separated list of types.
                                                                                       Oftentimes, all containers in the same toolkit accepts the same type of
                                                                                       components and references, for example «org.eclipse.swt.widgets.Control» in
                                                                                       SWT or «com.google.gwt.user.client.ui.Widget» in GWT. So, it is convenient to use
                                                                                       «simpleContainer.defaultComponent» for superclass of all containers and
                                                                                       don't specify it separately in each place (but you may if you want).
                                                                                       Parameter «simpleContainer.association» specifies the child component's
                                                                                       association with this flow container. It is required for add/move operations in
                                                                                       JavaInfoUtils. The following types of associations are supported:
                                                                                           • «invocationChild» - the usual association in Swing and GWT, when a
                                                                                              child is passed into the «add» method. It requires an exact specification of
                                                                                              the method after a space «%parentAccess%add(%child%)». Since this
                                                                                              type of association is often used, it does not require any separate
                                                                                              «invocationChild» prefix, you can just write the invocation itself.
<!-- bounds for DialogBox -->
                                                                                       For some components in GWT you can not set the size directly. See
<parameter name="applyTopBoundsScript"><![CDATA]</pre>
                                                                                       http://code.google.com/p/google-web-toolkit/issues/detail?id=2595, on how to
                                                                                       write a script to do this. The following variables are defined in the script:
       widget.getWidget().setSize(size.width, size.height);

    «DOM» - the GWT DOM class:

       widget.show();

    «rootPanel» - the instance of RootPanel;

11></parameter>
                                                                                           • «widget» - the instance of the top level widget:
<!-- bounds for Composite -->
                                                                                           • «size» - the size of the widget requested by the user; has properties
<parameter name="applyTopBoundsScript"><![CDATA]</pre>
                                                                                               «width» and «height»;
       rootPanel.add(widget);
       widget.setSize(size.width, size.height);
11></parameter>
```

<pre><parameter name="setTopBoundsScript"><![CDATA[</td><td>Allows some operations to be performed when user resizes this top level component. The following variables are defined in the script: • «DOM» - the GWT DOM class; • «rootPanel» - the instance of RootPanel; • «widget» - the instance of the top level widget; • «size» - the size of the widget requested by the user; has properties «width» and «height»;</td></tr><tr><td><pre><parameter name="copyChildPropertyTop from=Association/direction to=Direction category=system(7)"/> <parameter name="copyPropertyTop from=Constructor/columnWidth to=width category=normal"/></pre></td><td>Adds copying of given property (usually part of some complex property) as the top level. The following attributes are supported: • «from» - the «/» separated path to the source property; • «to» - the name of the top level target property; • «category» - the category of the target property, may be «preferred», «normal», «advanced», «hidden» or «system(int)»;</td></tr><tr><td><pre><parameter name="modelMethodProperty getter=getAnchor setter=setAnchor type=java.lang.String title=anchor"/> <parameter name="modelMethodChildProperty getter=getWidth setter=setWidth title=Width category=system(7) type=java.lang.String child=com.instantiations.designer.gwt.model.widgets.Widget_Info"/></pre></td><td>Adds a new property to component/its_child that is bound to getter/setter method in JavaInfo model.</td></tr><tr><td><pre><parameter name="GEF.requestValidator.parent">true</parameter> <parameter name="GEF.requestValidator.child"><![CDATA[isComponentType(parent, 'org.eclipse.swt.widgets.Table') && parent.object.itemCount <= 2]]></parameter></pre>	Sometimes, you need to add limitations on what children can be dropped on a parent (during create/paste/move/add operations). So, you can specify two MVEL scripts: • «GEF.requestValidator.parent» - for parent, to check all possible children. If no such script, then «true». • «GEF.requestValidator.child» - for child, to check that this child can be dropped only on some specific parents. For example, here we check that «parent» is a SWT Table that has no more than 2 items. If no such script,

	then «true». Following variables and functions can be used:
	 «parent» - the parent where we are going to drop the child; «child» - the child to drop; «isComponentType(javaInfo, componentClassName)» - checks that given object is JavaInfo and its component type is instance of given one. «ReflectionUtils» - class with many Class/Method/Field utils.
	In addition, WindowBuilder, always checks that constructor/factory of the child is compatible with the parent (i.e. you can pass the parent as a parameter into the constructor/factory, if needed).
	If one of the conditions (compatibility or parent/child scripts) is false, then parent becomes «transparent» for this child, so request will be passed to the parent.
<pre><parameter name="GEF.transparentOnBorders.always">true</parameter></pre>	Specifies that EditPart for this model is «transparent» on borders, in 3 pixels. This is useful when we know that the container places these children without a gap between them, so to hit container between children we need to make them transparent.
	NOTE: may be we should replace this with some parameter for container, because container knows how it lays out its children.
<pre><parameter name="refresh_afterCreate"><![CDATA[import com.google.gwt.user.client.ui.*; if (object.getItemCount() == 0) { object.addItem("Empty Tree."); object.addItem("Drop items in structure."); }]]></parameter></pre>	Script «refresh_afterCreate» allows you to tweak created component object, for example show some message if the component can accept some children or some properties should be set.
<pre><parameter name="parser.preferredRoot">true</parameter></pre>	Sometimes after parsing we have more than one possible root JavaInfo. Usually we select the root that has the biggest hierarchy. However, sometimes we know that there is a better choice. For example, GWT 1.6 examples use RootPanel and also create DialogBox. We want to show the RootPanel, because it is the entry point, and DialogBox is something dynamic. So, we mark the RootPanel with this tag and it is always selected as the preferred root. Note, that if there are more than one preferred roots, the actual root will be selected by size of hierarchy.

<pre><parameter name="GEF.clickToParent">true</parameter></pre>	If some model is marked with this parameter, then clicking on it on the design canvas will move the selection request to the parent. In most cases, this will cause parent selection instead of this model selection. This is used for example in ApplicationWindow, where, because of binary execution flow we have several model for the same Shell object – window itself, «parent» parameter for method «createContents()». Without this parameter, clicking on window header will cause a «parent» selection. But the user expects the ApplicationWindow to be selected (for example to resize it).
<pre><parameter name="topBounds.pack">true</parameter></pre>	Specifies that the superclass of this Swing Window has pack() invocation which means the default size (450x300) should not be applied to this Window.
<pre><parameter name="Wrapper.method">getControl</parameter></pre>	Specifies the method used to access wrapped component of the viewer.
<pre><parameter name="Wrapper.noWrapped.inConstructors">true</parameter></pre>	Specifies that this viewer (and its subclasses) has no constructors that accept wrapped component (for example CellEditor-s have no such constructors, but Jface Viewer-s have them). Or you can use "Wrapper.notWrapped" tag for single constructor or factory parameter.
<pre><parameter name="liveComponent.forcedSize.use"><![CDATA[</td><td>WindowBuilder needs to create «live component image» when you drop component on absolute based containers/layouts. However, some components don't have reasonable preferred size, so user have to force it in description. In GWT, size can be any string that is a valid CSS size. Other toolkits support only integer. Also in GWT, you can use a script «liveComponent.forcedSize.use» to check if size should be applied, if problem happens only with specific OS/Browser.</td></tr><tr><td></td><td></td></tr></tbody></table>]]></parameter></pre>	

Table 1.3 method tags.

<method name="getDocument"> <tag name="exposeDisconnectedComponent" value="true"></tag> </method>	Specifies that method "getDocument()" should be used to expose the component, even if it is not connected to the host component. For example JTextComponent (such as JTextField) has a method, getDocument(), that returns a non-visual object Document, that can not be a child of a visual component. But we still want to show it as a child, so force this.

Table 1.4 standard property tags.

<pre><pre><pre><pre><pre><pre><pre><pre></pre></pre></pre></pre></pre></pre></pre></pre>	Tag «isText == true» means that this property is displayed as text for this component, so when user requests direct edit, the property «title» should be edited.
	Tag «isText == true» means that this property contains displayed image, so when (on absolute layout) the user changes one of these properties, component will be resized to its (new) preferred size.

Table 1.5 property editors with id's.

editor id	example	description
staticField	<editor id="staticField"></editor>	Editor that allows the selection of one static field from a given class.
style	<editor id="style"></editor>	Complex editor for «int» property that supports two sets of sub-properties – set properties (zero or more can be selected) and select properties (only one can be selected). For «select» properties, name should start with the word «select» and then some unique string, in «values» first word is title, second — default field name, rest of the words – names of static fields from class.
innerClass	<editor id="innerClass"></editor>	Editor that allows the selection of existing class that extends type with «class» parameter (class or interface), or create new inner class using configured code. Other parameters: • name — default name of created class; • class — the type to find subclasses;

	<pre>public int compare(org.eclipse.jface.viewers.Viewer viewer, Object e1, Object e2) { Object item1 = e1; Object item2 = e2; return 0; } }]]> </pre>	source — the source for creating new class.
displayExpression	<constructor> <parameter parent="true" type="org.eclipse.swt.widgets.Table"></parameter> <parameter type="int"> <editor id="displayExpression"></editor> </parameter> </constructor>	Editor that shows expression of property as it is written in source, but does not allow editing it.
stringList	<pre><editor id="stringList"></editor></pre>	Editor that allows user to choose from a list of strings.

```
2. Static/instance factory description: *.wbp-factory.xml
<?xml version='1.0' encoding='UTF-8'?>
<factory>
       <method name='createButton_xmlDesc' factory='true'>
              <parameter type='java.lang.String' property='setText(java.lang.String)'/>
       </method>
      <method name='createButton2' factory='true'>
              <parameter type='java.lang.String'/>
              <parameter type='java.lang.String'/>
              <parameter type='java.lang.String' defaultSource='"222"'/>
              <parameter type='java.lang.String'/>
      </method>
      <method name='createButton_factoryFalseOverride' factory='true'>
              <parameter type='java.lang.String' property='setText(java.lang.String)'/>
      </method>
</factory>
<?xml version='1.0' encoding='UTF-8'?>
<factory>
       <method name="createLabel">
              <parameter type="org.eclipse.swt.widgets.Composite" parent="true"/>
              <parameter type="java.lang.String" defaultSource="&quot;New Label&quot;" property="property.setter: setText(java.lang.String)"/>
              <parameter type="int" defaultSource="org.eclipse.swt.SWT.NONE">
                     <editor id="style">
                           <parameter name="class">org.eclipse.swt.SWT</parameter>
                           <parameter name="set">BORDER SEPARATOR WRAP</parameter>
                           <parameter name="select0">dir VERTICAL HORIZONTAL VERTICAL</parameter>
                           <parameter name="select1">shadow SHADOW_OUT SHADOW_IN SHADOW_OUT SHADOW_NONE
                           <parameter name="select2">align LEFT LEFT CENTER RIGHT/parameter>
                     </editor>
              </parameter>
              <description>Creates a label as a part of the form.</description>
              <name>Some name for palette entry.</name>
       </method>
</factory>
```

Table 2.1 – tags in *.wbp-factory.xml

Tag	description
	Describes the method with the given name, parameters (see below) and flag «factory» that specifies if this method is a factory.
<pre><parameter></parameter></pre>	See description for <parameter> in *.wbp-component.xml</parameter>

<description>Creates a label as a part of the form.</description>	The description text to use for palette entry (may be overridden in it).
<name>Some name for palette entry.</name>	The name to use for palette entry (may be overridden in it). If name is not specified, then the signature of the method is used.

You can also specify descriptions for factory methods directly in source:

```
public final class StaticFactory {
    /**
    * @wbp.factory
    * @wbp.factory.parameter.source text "new JButton"
    * @wbp.factory.parameter.property text text
    */
    public static JButton createButton(String text, Icon icon) {
        return new JButton(text, icon);
    }
    /**
    * @wbp.factory
    * @wbp.factory.parameters.noBinding
    */
    public static JTextField createTextField(int columns) {
        return new JTextField(10);
    }
}
```

Table 2.2 – tags source for factory

Tag	description
@wbp.factory	Specifies if method is a factory method.
	If this tag is used on a class, then all methods of this class are considered as factories.
	Designer will automatically exclude methods that return «null» (such as setters) and getters, i.e. methods that starts with «set» and have no parameters.
@wbp.factory.parameter.source parameterName expressionSource	Sets the default source for parameter. This source will also be used when adding component using this factory method. If no such source is specified, the default value for this type will be used – zero for numerics and «null» for objects.
@wbp.factory.parameter.property parameterName propertyTitle	Specifies that the parameter with given name is bound to some component property. This is useful for example if you want to set the text of a button directly in

	a factory method, without additional setText() invocation.
@wbp.factory.parameters.noBinding	Specifies that Designer should not bind parameters to properties by names.
	Usually parameters are bound to corresponding properties, but if there are many methods and parameters, it is tedious to describe each binding. Instead, you can just name the parameters with the same name as the title of the components property. For example, if you name the parameter «text», it will be bound to a property with title «text». Note that title is used, not id of the property (because id is a complex string).
	One special name of parameter is reserved for SWT support, parameter with name «parent» is considered as parent parameter (i.e. in same way if it would be marked as parent in *.wbp-factory.xml).

Table 3.1 – other source tags

Tag	description
/** * @wbp.parser.entryPoint */ public void someMethod(Composite parent) { Composite composite = new Composite(parent, SWT.NONE); }	If you want to edit a GUI in a standalone class, which is not a subclass of a known component, such as Swing JPanel or SWT Composite, then you should tell WindowBuilder which method to use as the entry point for execution flow. In this case WindowBuilder will not look in the constructor and superclass, it will design only this specific method.
mainPanel = new JPanel(); // @wbp.parser.preferredRoot	Specifies that marked component should be used as root component, even when there are other possible roots, may be with bigger hierarchy (by default WindowBuilder chooses root component with biggest hierarchy).
@wbp.parser.constructor	If «this» component has only one constructor, then Designer will select it as entry point for execution flow. If «this» container has several constructors and one of them marked with this tag, then it will be used. If no tag and container has a default constructor (without parameters), then it will be used implicitly. If all constructors are non-default, error will be generated.
@wbp.eval.method.parameter parameterName expressionSource /**", * @wbp.eval.method.parameter _int 1 + 2 * @wbp.eval.method.parameter _true true * @wbp.eval.method.parameter _false false * @wbp.eval.method.parameter _string "ab" + "c" * @wbp.eval.method.parameter _null null */ public Test(int _int, boolean _true, boolean _false, String _string, Object _null) { super(_int, _true, _false, _string, _null); }	If the constructor, (or other entry method), has a parameter whose value is used for creating some component or as part of some property (method invocation or field assignment), then Designer requires hint about value that will be passed with this parameter. This tag can be used to specify any statically evaluable expression.
<pre>@wbp.eval.method.return parameterName public int root() { return instancePublicMethod(5); } /** * @wbp.eval.method.return value</pre>	Sometimes code may use some instance methods declared in the same class. Designer can not evaluate these methods (at least in current implementation), so it requires some hint. In our experience, the value of one of the parameters (usually even single parameter) is enough.

Parameters for GridLayout.

parameter	description	
GridLayout.grabHorizontal	Specifies that when this component is added to a GridLayout, it should grab horizontally and use FILL as the alignment.	
GridLayout.grabVertical	Specifies that when this component added to a GridLayout, it should grab vertically and use FILL as the alignment.	
GridLayout.rightAlignment.isLabel GridLayout.rightAlignment.isTarget	If one component is marked as «isLabel» and other as «isTarget», and «target» is in the next column of the same row as «label», then «label» should be aligned right.	

Tags for **«<method>»** elements.

parameter	description
<tag name="binaryExecutionFlow.dontVisit" value="true"></tag>	Specifies that this method should not be visited when called from binary execution flow.