

ClamAV Bytecode Compiler

User Manual

Contents

1	Inst	allation
	1.1	Requirements
	1.2	Obtaining the ClamAV Bytecode Compiler
	1.3	Building
	1.0	1.3.1 Disk space
		1.3.2 Create build directory
	1.4	Testing
	$1.4 \\ 1.5$	Installing
	1.0	
		1.5.1 Structure of installed files
2	Tut	orial
_	2.1	Short introduction to the bytecode language
		2.1.1 Types, variables and constants
		2.1.2 Arrays and pointers
		2.1.3 Arithmetics
		2.1.4 Functions
		2.1.5 Control flow
		2.1.6 Common functions
	0.0	
	2.2	Writing logical signatures
		2.2.1 Structure of a bytecode for algorithmic detection
		2.2.2 Virusnames
		2.2.3 Patterns
		2.2.4 Single subsignature
		2.2.5 Multiple subsignatures
		2.2.6 W32.Polipos.A detector rewritten as bytecode
		2.2.7 Virut detector in bytecode
	2.3	Writing regular expressions in bytecode
		2.3.1 A very simple regular expression
		2.3.2 Named regular expressions
	2.4	Writing unpackers
		2.4.1 Structure of a bytecode for unpacking (and other hooks)
		2.4.2 Detecting clam.exe via bytecode
		2.4.3 Detecting clam.exe via bytecode (disasm)
		2.4.4 A simple unpacker
		2.4.5 Matching PDF javascript
		2.4.6 YC unpacker rewritten as bytecode
3	Usa	-
	3.1	Invoking the compiler
		3.1.1 Compiling C++ files
	3.2	Running compiled bytecode
		3.2.1 ClamBC
		3.2.2 clamscan, clamd
	3.3	Debugging bytecode
		3.3.1 "printf" style debugging
		3.3.2 Single-stepping

ii	Cont	ents
4	ClamAV bytecode language	17
4	4.1 Differences from C99 and GNU C	
	4.2 Limitations	
	4.3 Logical signatures	19
	4.4 Headers and runtime environment	20
5	Bytecode security & portability	21
6	Reporting bugs	23
7	Bytecode API	25
•	7.1 API groups	25
	7.1.1 Bytecode Configuration	$\frac{25}{25}$
	7.1.1 Bytecode Configuration	
	* -	
		37
	7.1.4 Disassembly	
	7.1.5 Engine Queries	38
	7.1.6 Environment	40
	7.1.7 File Operations	44
	7.1.8 JavaScript Normalization	47
	7.1.9 Icon Matcher	48
	7.1.10 Math Operation	49
	7.1.11 PDF Handling	51
	7.1.12 PE Operations	
	7.1.13 Scan Control	
	7.1.14 String Operations	64
8	Copyright and License	67
G	8.1 The ClamAV Bytecode Compiler	
	8.2 Bytecode	
	J.Z. By occode	00
\mathbf{A}	Low-Level API Globals	71
	A.0.1 Global Variables	71
В	Low-Level API Structures	73
	B.0.2 cli_exe_info Struct Reference	73
	B.0.3 DIS_fixed Struct Reference	73
	B.0.4 pe_image_data_dir Struct Reference	74
	B.0.5 DIS_arg Struct Reference	74
	B.0.6 pe_image_optional_hdr64 Struct Reference	74
	B.0.7 cli_exe_info Struct Reference	75
	B.0.8 pe_image_section_hdr Struct Reference	76
	B.0.9 cli_pe_hook_data Struct Reference	77
	B.0.10 cli exe section Struct Reference	77
	B.0.11 pe_image_file_hdr Struct Reference	78
	B.0.12 pe_image_optional_hdr32 Struct Reference	79
	B.0.13 DIS_mem_arg Struct Reference	80
	B.0.14 DISASM RESULT Struct Reference	80
	D.O.14 DIDADIVI_ICEDOLI DICUCC RETERICE	80
\mathbf{C}	API Headers	81
_	C.0.15 File List	81
	C.0.16 bytecode_api.h File Reference	81
	C.0.17 bytecode_disasm.h File Reference	84
	C.0.17 bytecode_disasin.n File Reference	92
	· ·	
	C.0.19 bytecode_local.h File Reference	93
	C.0.20 bytecode_pe.h File Reference	90

Contents

97

D Predefined API Macros

ClamAV Bytecode Compiler - Internals Manual,

 $\ \, \odot \, 2009\text{-}2013$ Sourcefire, Inc.

© 2014 Cisco Systems, Inc. and/or its affiliates.

All rights reserved.

Authors: Török Edvin, Kevin Lin

This document is distributed under the terms of the GNU General Public License v2.

Clam AntiVirus is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

ClamAV and Clam AntiVirus are trademarks of Cisco Systems, Inc. and/or its affiliates.

iv Contents

CHAPTER 1 Installation

1.1. Requirements

The ClamAV Bytecode Compiler uses the LLVM compiler framework, thus requires an Operating System where building LLVM is supported:

- FreeBSD/x86
- $Linux/\{x86,x86_64,ppc\}$
- Mac OS $X/\{x86,ppc\}$
- Solaris/sparcv9
- Windows/x86 using mingw32 or Visual Studio

The following packages are required to compile the ClamAV Bytecode Compiler:

- GCC C and C++ compilers (minimum 4.1.3, recommended: 4.3.4 or newer) ¹.
- Perl (version 5.6.0+)
- GNU make (version 3.79+, recommended 3.81)

The following packages are optional, but highly recommended:

• Python (version 2.5.4+?) - for running the tests

1.2. Obtaining the ClamAV Bytecode Compiler

You can obtain the source code in one of the following ways ²

- Check out the source code using git native protocol: git clone git://git.clamav.net/git/clamav-bytecode-compiler
- Check out the source code using HTTP:

```
git clone http://git.clamav.net/git/clamav-bytecode-compiler.git
```

You can keep the source code updated using: git pull

¹Note that several versions of GCC have bugs when compiling LLVM, see http://llvm.org/docs/GettingStarted.html#brokengcc for a full list. Also LLVM requires support for atomic builtins for multithreaded mode, which gcc 3.4.x doesn't have

²For now the use the internal clamtools repository: git clone username@git.clam.sourcefire.com:/var/lib/git/clamtools.git

2 1.3. Building

1.3. Building

1.3.1. Disk space

A minimalistic release build requires 100M of disk space.

Testing the compiler requires a full build, 320M of disk space. A debug build requires significantly more disk space (1.4G for a minimalistic debug build).

Note that this only needed during the build process, once installed only 12M is needed.

1.3.2. Create build directory

Building requires a separate object directory, building in the source directory is not supported. Create a build directory:

```
$ cd clamav-bytecode-compiler && mkdir obj
Run configure (you can use any prefix you want, this example uses /usr/local/clamav):
$ cd obj && ../llvm/configure --enable-optimized \
    --enable-targets=host-only --disable-bindings \
    --prefix=/usr/local/clamav
Run the build under ulimit 1:
```

1.4. Testing

```
$ (ulimit -t 3600 v 512000 && make -j4)
$ make check-all
```

\$ (ulimit -t 3600 -v 512000 && make clambc-only -j4)

If make check reports errors, check that your compiler is NOT on this list: http://llvm.org/docs/GettingStarted.html#brokengcc.

If it is, then your compiler is buggy, and you need to do one of the following: upgrade your compiler to a non-buggy version, upgrade the OS to one that has a non-buggy compiler, compile with export OPTMIZE_OPTION=-02, or export OPTIMIZE_OPTION=-01, or export OPTIMIZE_OPTION=\-01.

If not you probably found a bug, report it at http://bugs.clamav.net

1.5. Installing

Install it:

```
$ make install-clambc -j8
```

1.5.1. Structure of installed files

- 1. The ClamAV Bytecode compiler driver: \$PREFIX/bin/clambc-compiler
- 2. ClamAV bytecode header files:

```
$PREFIX/lib/clang/1.1/include:
bcfeatures.h
bytecode_{api_decl.c,api,disasm,execs,features}.h
bytecode.h
bytecode_{local,pe,types}.h
```

3. clang compiler (with ClamAV bytecode backend) compiler include files:

¹compiling some files can be very memory intensive, especially with older compilers

Chapter 1. Installation

```
$PREFIX/lib/clang/1.1/include:
emmintrin.h
float.h
iso646.h
limits.h
{,p,t,x}mmintrin.h
mm_malloc.h
std{arg,bool,def,int}.h
tgmath.h
```

4. User manual

\$PREFIX/docs/clamav/clambc-user.pdf

4 1.5. Installing

CHAPTER 2 Tutorial

2.1. Short introduction to the bytecode language

- 2.1.1. Types, variables and constants
- 2.1.2. Arrays and pointers
- 2.1.3. Arithmetics
- 2.1.4. Functions
- **2.1.5.** Control flow
- **2.1.6.** Common functions

2.2. Writing logical signature bytecodes

A bytecode triggered by a logical signature is much more powerful than a logical signature itself: you can write complex algorithmic detections, and use the logical signature as a *filter* (to speed up matching). Thus another name for "logical signature bytecodes" is "algorithmic detection bytecodes". The detection you write in bytecode has read-only access to the file being scanned and its metadata (PE sections, EP, etc.).

2.2.1. Structure of a bytecode for algorithmic detection

Algorithmic detection bytecodes are triggered when a logical signature matches. They can execute an algorithm that determines whether the file is infected and with which virus.

A bytecode can be either algorithmic or an unpacker (or other hook), but not both. It consists of:

- Definition of virusnames used in the bytecode
- Pattern definitions (for logical subexpressions)
- The logical signature as C function: bool logical_trigger(void)
- The int entrypoint(void) function which gets executed when the logical signature matches
- (Optional) Other functions and global constants used in entrypoint

The syntax for defining logical signatures, and an example is described in Section 2.2.4.

The function entrypoint must report the detected virus by calling foundVirus and returning 0. It is recommended that you always return 0, otherwise a warning is shown and the file is considered clean. If foundVirus is not called, then ClamAV also assumes the file is clean.

¹ Logical signatures can be used as triggers for executing bytecode. However, instead of describing a logical signature as a .ldb pattern, you use (simple) C code which is later translated to a .ldb-style logical signature by the ClamAV Bytecode Compiler.

¹See Section 4.3 for more details about logical signatures in bytecode.

2.2.2. Virusnames

Each logical signature bytecode must have a virusname prefix, and one or more virusnames. The virusname prefix is used by the SI to ensure unique virusnames (a unique number is appended for duplicate prefixes).

Program 1 Declaring virusnames

```
1 /* Prefix, used for duplicate detection and fixing */
VIRUSNAME_PREFIX("Trojan.Foo")
3 /* You are only allowed to set these virusnames as found */
VIRUSNAMES("A", "B")
5 /* File type */
TARGET(2)
```

In Program 1 3 predefied macros are used:

- VIRUSNAME_PREFIX which must have exactly one string argument
- VIRUSNAMES which must have one or more string arguments
- TARGET which must have exactly one integer argument

In this example, the bytecode could generate one of these virusnames: Trojan.Foo.A, or Trojan.Foo.B, by calling foundVirus("A") or foundVirus("B") respectively (notice that the prefix is not part of these calls).

2.2.3. Patterns

Logical signatures use .ndb style patterns, an example on how to define these is shown in Program 2.

Program 2 Declaring patterns

```
SIGNATURES_DECL_BEGIN

DECLARE_SIGNATURE(magic)
DECLARE_SIGNATURE(check)

DECLARE_SIGNATURE(zero)
SIGNATURES_DECL_END

SIGNATURES_DEF_BEGIN
DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(check, "f00d")

DEFINE_SIGNATURE(zero, "fffff")
SIGNATURES_END
```

Each pattern has a name (like a variable), and a string that is the hex pattern itself. The declarations are delimited by the macros SIGNATURES_DECL_BEGIN, and SIGNATURES_DECL_END. The definitions are delimited by the macros SIGNATURES_DEF_BEGIN, and SIGNATURES_END. Declarations must always come before definitions, and you can have only one declaration and declaration section! (think of declaration like variable declarations, and definitions as variable assignments, since that what they are under the hood). The order in which you declare the signatures is the order in which they appear in the generated logical signature.

You can use any name for the patterns that is a valid record field name in C, and doesn't conflict with anything else declared.

After using the above macros, the global variable Signatures will have two new fields: magic, and zero. These can be used as arguments to the functions count_match(), and matches() anywhere in the program as shown in Program 3:

- matches (Signatures.match) will return true when the match signature matches (at least once)
- count_match(Signatures.zero) will return the number of times the zero signature matched
- count_match(Signatures.check) will return the number of times the check signature matched

The condition in the if can be interpreted as: if the match signature has matched at least once, and the number of times the zero signature matched is higher than the number of times the check signature matched, then we have found a virus A, otherwise the file is clean.

Chapter 2. Tutorial

Program 3 Using patterns

```
int entrypoint(void)
{
   if (matches(Signatures.match) && count_match(Signatures.zero) >
        count_match(Signatures.check))
      foundVirus("A");
   return 0;
}
```

2.2.4. Single subsignature

The simplest logical signature is like a .ndb signature: a virus name, signature target, 0 as logical expression ¹, and a ndb-style pattern.

The code for this is shown in Program 4

Program 4 Single subsignature example

```
/* Declare the prefix of the virusname */
vIRUSNAME_PREFIX("Trojan.Foo")
  /* Declare the suffix of the virusname */
4 VIRUSNAMES ("A")
  /* Declare the signature target type (1 = PE) */
6 TARGET (1)
  /* Declare the name of all subsignatures used */
  SIGNATURES_DECL_BEGIN
10 DECLARE_SIGNATURE(magic)
  SIGNATURES_DECL_END
/* Define the pattern for each subsignature */ ^{\rm 14} SIGNATURES_DEF_BEGIN
  DEFINE_SIGNATURE(magic, "aabb")
16 SIGNATURES_END
18 /* All bytecode triggered by logical signatures must have this
     function */
  bool logical_trigger(void)
    /* return true if the magic subsignature matched,
22
     * its pattern is defined above to "aabb" */
    return count_match(Signatures.magic) != 2;
24
  }
26
  /* This is the bytecode function that is actually executed when the logical
   * signature matched */
  int entrypoint(void)
30 {
    /* call this function to set the suffix of the virus found */
    foundVirus("A");
32
    /* success, return 0 */
    return 0;
34
```

The logical signature (created by the compiler) looks like this: Trojan.Foo.{A}; Target:2;0; aabb Of course you should use a .ldb signature in this case when all the processing in entrypoint is only setting a virusname and returning. However, you can do more complex checks in entrypoint, once the bytecode was triggered by the logical_trigger

In the example in Program 4 the pattern was used without an anchor; such a pattern matches at any offset. You can use offsets though, the same way as in .ndb signatures, see Program 5 for an example.

¹meaning that subexpression 0 must match

2.2.5. Multiple subsignatures

An example for this is shown in Program 5. Here you see the following new features used: 1

- Multiple virusnames returned from a single bytecode (with common prefix)
- Multiple subsignatures, each with a name of your choice
- A pattern with an anchor (EP+0:aabb)
- More subsignatures defined than used in the logical expression

The logical signature looks like this:

 $Trojan.Foo.\{A,B\}; Target:2; (((0|1|2)=42,2)|(3=10)); EP+0:aabb; ffff; aaccee; f00d; dead$

Notice how the subsignature that is not used in the logical expression (number 4, dead) is used in entrypoint to decide the virus name. This works because ClamAV does collect the match counts for all subsignatures (regardless if they are used or not in a signature). The count_match(Signatures.check2) call is thus a simple memory read of the count already determined by ClamAV.

Also notice that comments can be used freely: they are ignored by the compiler. You can use either C-style multiline comments (start comment with /*, end with */), or C++-style single-line comments (start comment with //, automatically ended by newline).

2.2.6. W32.Polipos.A detector rewritten as bytecode

2.2.7. Virut detector in bytecode

2.3. Writing regular expressions in bytecode

ClamAV only supports a limited set of regular expressions in .ndb format : wildcards. The bytecode compiler allows you to compile fully generic regular expressions to bytecode directly. When libclamav loads the bytecode, it will compile to native code (if using the JIT), so it should offer quite good performance.

The compiler currently uses re2c to compile regular expressions to C code, and then compile that to bytecode. The internal workings are all transparent to the user: the compiler automatically uses re2c when needed, and re2c is embedded in the compiler, so you don't need to install it.

The syntax of regular expressions are similar to the one used by POSIX regular expressions, except you have to quote literals, since unquoted they are interpreted as regular expression names.

2.3.1. A very simple regular expression

Lets start with a simple example, to match this POSIX regular expression: eval($[a-zA-Z_]$ [$a-zA-Z0-9_]*\.$ unescape. See Program 6 ².

There are several new features introduced here, here is a step by step breakdown:

REGEX_SCANNER this declares the data structures needed by the regular expression matcher

- seek(0, SEEK_SET) this sets the current file offset to position 0, matching will start at this position. For offset 0 it is not strictly necessary to do this, but it serves as a reminder that you might want to start matching somewhere, that is not necessarily 0.
- for(;;) { REGEX_LOOP_BEGIN this creates the regular expression matcher main loop. It takes the current file byte-by-byte ³ and tries to match one of the regular expressions.
- /*!re2c This mark the beginning of the regular expression description. The entire regular expression block is a C comment, starting with !re2c
- ANY = [^]; This declares a regular expression named ANY that matches any byte.
- "eval("[a-zA-Z_] [a-zA-Z_0-9]*".unescape" { This is the actual regular expression.

¹In case of a duplicate virusname the prefix is appended a unique number by the SI

²This omits the virusname, and logical signature declarations

³it is not really reading byte-by-byte, it is using a buffer to speed things up

g

Program 5 Multiple subsignatures

```
/* You are only allowed to set these virusnames as found */
  VIRUSNAME_PREFIX("Test")
3 VIRUSNAMES("A", "B")
  TARGET (1)
  SIGNATURES_DECL_BEGIN
7 DECLARE_SIGNATURE(magic)
  DECLARE_SIGNATURE(zero)
9 DECLARE_SIGNATURE(check)
  DECLARE_SIGNATURE(fivetoten)
11 DECLARE_SIGNATURE (check2)
  SIGNATURES_DECL_END
13
  SIGNATURES_DEF_BEGIN
15 DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(zero, "fffff")
17 DEFINE_SIGNATURE(fivetoten, "aaccee")
DEFINE_SIGNATURE(check, "f00d")
19 DEFINE_SIGNATURE(check2, "dead")
  SIGNATURES_END
21
  bool logical_trigger(void)
23 {
       unsigned sum_matches = count_match(Signatures.magic)+
           count_match(Signatures.zero) + count_match(Signatures.fivetoten);
25
       unsigned unique_matches = matches(Signatures.magic)+
                matches(Signatures.zero)+ matches(Signatures.fivetoten);
       if (sum_matches == 42 && unique_matches == 2) {
           // The above 3 signatures have matched a total of 42 times, and at least // 2 of them have matched
29
           return true;
31
       // If the check signature matches 10 times we still have a match
33
       if (count_match(Signatures.check) == 10)
35
           return true;
       // No match
       return false;
37
  }
39
  int entrypoint(void)
41 {
       unsigned count = count_match(Signatures.check2);
       if (count >= 2)
43
           foundVirus(count = 2 ? "A" : "B");
         if (count == 2)
45
           foundVirus("A");
         else
47
           foundVirus("B");
       return 0;
49
```

10 2.4. Writing unpackers

Program 6 Simple regular expression example

```
int entrypoint(void)
  {
2
       REGEX_SCANNER;
       seek(0, SEEK_SET);
       for (;;) {
           REGEX_LOOP_BEGIN
6
             /* !re2c
                ANY = [^];
                 "eval("[a-zA-Z_][a-zA-Z_0-9]*".unescape" {
                    long pos = REGEX_POS;
12
                    if (pos < 0)
                      continue;
14
                    debug("unescape found at:");
                    debug (pos);
16
                ANY { continue; }
20
       return 0;
22 }
```

"eval(" This matches the literal string eval(. Literals have to be placed in double quotes " here, unlike in POSIX regular expressions or PCRE. If you want case-insensitive matching, you can use '.

[a-zA-Z_] This is a character class, it matches any lowercase, uppercase or _ characters.

[a-zA-Z_0-9]*" Same as before, but with repetition. * means match zero or more times, + means match one or more times, just like in POSIX regular expressions.

".unescape" A literal string again

{ start of the action block for this regular expression. Whenever the regular expression matches, the attached C code is executed.

long pos = REGEX_POS; this determines the absolute file offset where the regular expression has matched.
Note that because the regular expression matcher uses a buffer, using just seek(0, SEEK_CUR)
would give the current position of the end of that buffer, and not the current position during regular
expression matching. You have to use the REGEX_POS macro to get the correct position.

debug(...) Shows a debug message about what was found and where. This is extremely helpful when you start writing regular expressions, and nothing works: you can determine whether your regular expression matched at all, and if it matched where you thought it would. There is also a DEBUG_PRINT_MATCH that prints the entire matched string to the debug output. Of course before publishing the bytecode you might want to turn off these debug messages.

} closes the action block for this regular expression

ANY { continue; } If none of the regular expressions matched so far, just keep running the matcher, at the next byte

*/ closes the regular expression description block

} closes the for() loop

You may have multiple regular expressions, or declare multiple regular expressions with a name, and use those names to build more complex regular expressions.

2.3.2. Named regular expressions

2.4. Writing unpackers

2.4.1. Structure of a bytecode for unpacking (and other hooks)

When writing an unpacker, the bytecode should consist of:

Chapter 2. Tutorial 11

- Define which hook you use (for example PE_UNPACKER_DECLARE for a PE hook)
- An int entrypoint(void) function that reads the current file and unpacks it to a new file
- Return 0 from entrypoint if you want the unpacked file to be scanned
- (Optional) Other functions and global constants used by entrypoint

2.4.2. Detecting clam.exe via bytecode

Example provided by aCaB:

2.4.3. Detecting clam.exe via bytecode (disasm)

Example provided by aCaB:

2.4.4. A simple unpacker

2.4.5. Matching PDF javascript

2.4.6. YC unpacker rewritten as bytecode

12 2.4. Writing unpackers

CHAPTER 3 Usage

3.1. Invoking the compiler

Compiling is similar to gcc ¹:

\$ /usr/local/clamav/bin/clambc-compiler foo.c -o foo.cbc -02

This will compile the file foo.c into a file called foo.cbc, that can be loaded by ClamAV, and packed inside a .cvd file.

The compiler by default has all warnings turned on.

Supported optimization levels: -00, -01, -02, -03. It is recommended that you always compile with at least -01.

Warning options: -Werror (transforms all warnings into errors).

Preprocessor flags:

- -I <directory> Searches in the given directory when it encounters a #include "headerfile" directive in the source code, in addition to the system defined header search directories.
- -D <MACRONAME>=<VALUE> Predefine given <MACRONAME> to be equal to <VALUE>.
- -U <MACRONAME> Undefine a predefined macro

The compiler also supports some other commandline options (see clambc-compiler --help for a full list), however some of them have no effect when using the ClamAV bytecode backend (such as the X86 backend options). You shouldn't need to use any flags not documented above.

3.1.1. Compiling C++ files

Filenames with a .cpp extension are compiled as C++ files, however clang++ is not yet ready for production use, so this is EXPERIMENTAL currently. For now write bytecodes in C.

3.2. Running compiled bytecode

After compiling a C source file to bytecode, you can load it in ClamAV:

3.2.1. ClamBC

ClamBC is a tool you can use to test whether the bytecode loads, compiles, and can execute its entrypoint successfully. Usage:

```
clambc <file> [function] [param1 ...]
```

For example loading a simple bytecode with 2 functions is done like this:

¹Note that the ClamAV bytecode compiler will refuse to compile code it considers insecure

 $^{^2}$ Currently -O0 doesn't work

3.3. Debugging bytecode

```
$ clambc foo.cbc
LibClamAV debug: searching for unrar, user-searchpath: /usr/local/lib
LibClamAV debug: unrar support loaded from libclamunrar_iface.so.6.0.4 libclamunrar_iface_so_6_0
LibClamAV debug: bytecode: Parsed 0 APIcalls, maxapi 0
LibClamAV debug: Parsed 1 BBs, 2 instructions
LibClamAV debug: Parsed 1 BBs, 2 instructions
LibClamAV debug: Parsed 2 functions
Bytecode loaded
Running bytecode function :0
Bytecode run finished
Bytecode returned: 0x8
Exiting
```

3.2.2. clamscan, clamd

You can tell clamscan to load the bytecode as a database directly:

```
$ clamscan -dfoo.cbc
```

Or you can instruct it to load all databases from a directory, then clamscan will load all supported formats, including files with bytecode, which have the .cbc extension.

```
$ clamscan -ddirectory
```

You can also put the bytecode files into the default database directory of ClamAV (usually /usr/local/share/clamav) to have it loaded automatically from there. Of course, the bytecode can be stored inside CVD files, too.

3.3. Debugging bytecode

3.3.1. "printf" style debugging

Printf, and printf-like format specifiers are not supported in the bytecode. You can use these functions instead of printf to print strings and integer to clamscan's —debug output:

```
debug_print_str, debug_print_uint, debug_print_str_start, debug_print_str_nonl.
```

You can also use the debug convenience wrapper that automatically prints as string or integer depending on parameter type: debug, debug, debug.

See Program 7 for an example.

3.3.2. Single-stepping

If you have GDB 7.0 (or newer) you can single-step ^{1 2} during the execution of the bytecode.

• Run clambc or clamscan under gdb:

```
$ ./libtool --mode=execute gdb clamscan/clamscan
...
(gdb) b cli_vm_execute_jit
Are you sure ....? y
(gdb) run -dfoo.cbc
...
Breakpoint ....
(gdb) step
(gdb) next
```

You can single-step through the execution of the bytecode, however you can't (yet) print values of individual variables, you'll need to add debug statements in the bytecode to print interesting values.

¹not yet implemented in libclamav

²assuming you have JIT support

Chapter 3. Usage

Program 7 Example of using debug APIs

```
/* test debug APIs */
2 int entrypoint(void)
    /* print a debug message, followed by newline */
    debug_print_str("bytecode started", 16);
    /* start a new debug message, don't end with newline yet */
    debug_print_str_start("Engine functionality level: ", 28);
    /* print an integer, no newline */
    debug_print_uint(engine_functionality_level());
10
    /\ast print a string without starting a new debug message, and without
     * terminating with newline */
    debug_print_str_nonl(", dconf functionality level: ", 28);
    debug_print_uint(engine_dconf_level());
    debug_print_str_nonl("\n", 1);
    debug_print_str_start("Engine scan options: ", 21);
    debug_print_uint(engine_scan_options());
    debug_print_str_nonl(", db options: ", 13);
18
    debug_print_uint(engine_db_options());
    debug_print_str_nonl("\n", 1);
    /* convenience wrapper to just print a string */
    debug("just print a string");
    /* convenience wrapper to just print an integer */
24
    debug(4);
    return OxfOOd;
26
```

16 3.3. Debugging bytecode

CHAPTER 4

ClamAV bytecode language

The bytecode that ClamAV loads is a simplified form of the LLVM Intermediate Representation, and as such it is language-independent.

However currently the only supported language from which such by tecode can be generated is a simplified form of C $^{\rm 1}$

The language supported by the ClamAV bytecode compiler is a restricted set of C99 with some GNU extensions.

4.1. Differences from C99 and GNU C

These restrictions are enforced at compile time:

- No standard include files. ²
- The ClamAV API header files are preincluded.
- No external function calls, except to the ClamAV API ³
- No inline assembly ⁴
- Globals can only be readonly constants ⁵
- inline is C99 inline (equivalent to GNU C89 extern inline), thus it cannot be used outside of the definition of the ClamAV API, you should use static inline
- sizeof(int) == 4 always
- sizeof(long) == sizeof(long long) == 8 always
- ptr_diff_t = int, intptr_t = int, intmax_t = long, uintmax_t = unsigned long 6
- No pointer to integer casts and integer to pointer casts (pointer arithmetic is allowed though)
- No __thread support
- Size of memory region associated with each pointer must be known in each function, thus if you pass a pointer to a function, you must also pass its allocated size as a parameter.
- Endianness must be handled via the __is_bigendian() API function call, or via the cli_{read,write}int{16,32} wrappers, and not by casting pointers
- Predefines __CLAMBC__
- All integer types have fixed width

¹In the future more languages could be supported, see the Internals Manual on language frontends

²For portability reasons: preprocessed C code is not portable

 $^{^3}$ For safety reasons we can't allow the bytecode to call arbitrary system functions

⁴This is both for safety and portability reasons

⁵For thread safety reasons

 $^{^6}$ Note that a pointer's size of is runtime-platform dependent, although at compile time size of(void*) == 4, at runtime it can be something else. Thus you should avoid using size of(pointer)

4.2. Limitations

• main or entrypoint must have the following prototype: int main(void), the prototype int main(int argc, char is not accepted

They are meant to ensure the following:

- Thread safe execution of multiple different bytecodes, and multiple instances of the same bytecode
- Portability to multiple CPU architectures and OSes: the bytecode must execute on both the libclamav/LLVM JIT where that is supported (x86, x86_64, ppc, arm?), and on the libclamav interpreter where that is not supported.
- No external runtime dependency: libclamav should have everything needed to run the bytecode, thus no external calls are allowed, not even to libc!
- Same behaviour on all platforms: fixed size integers.

These restrictions are checked at runtime (checks are inserted at compile time):

- Accessing an out-of-bounds pointer will result in a call to abort()
- Calling abort() interrupts the execution of the bytecode in a thread safe manner, and doesn't halt ClamAV ¹.

The ClamAV API header has further restriction, see the Internals manual.

Although the bytecode undergoes a series of automated tests (see Publishing chapter in Internals manual), the above restrictions don't guarantee that the resulting bytecode will execute correctly! You must still test the code yourself, these restrictions only avoid the most common errors. Although the compiler and verifier aims to accept only code that won't crash ClamAV, no code is 100% perfect, and a bug in the verifier could allow unsafe code be executed by ClamAV.

4.2. Limitations

The bytecode format has the following limitations:

- At most 64k bytecode kinds (hooks)
- At most 64k types (including pointers, and all nested types)
- At most 16 parameters to functions, no vararg functions
- At most 64-bit integers
- No vector types or vector operations
- No opaque types
- No floating point
- Global variable initializer must be compile-time computable
- At most 32k global variables (and at most 32k API globals)
- Pointer indexing at most 15 levels deep (can be worked around if needed by using temporaries)
- No struct return or byval parameters
- At most 32k instructions in a single function
- No Variable Length Arrays

¹in fact it calls a ClamAV API function, and not the libc abort function.

4.3. Logical signatures

Logical signatures can be used as triggers for executing a bytecode. Instead of describing a logical signatures as a .ldb pattern, you use C code which is then translated to a .ldb-style logical signature. Logical signatures in ClamAV support the following operations:

- Sum the count of logical subsignatures that matched inside a subexpression
- Sum the number of different subsignatures that matched inside a subexpression
- Compare the above counts using the >, =, < relation operators
- Perform logical &&, || operations on above boolean values
- Nest subexpressions
- Maximum 64 subexpressions

Out of the above operations the ClamAV Bytecode Compiler doesn't support computing sums of nested subexpressions, (it does support nesting though).

The C code that can be converted into a logical signature must obey these restrictions:

- a function named logical_trigger with the following prototype: bool logical_trigger(void)
- no function calls, except for count_match and matches
- no global variable access (except as done by the above 2 functions internally)
- return true when signature should trigger, false otherwise
- use only integer compare instructions, branches, integer add, logical and, logical or, logical xor, zero extension, store/load from local variables
- the final boolean expression must be convertible to disjunctive normal form without negation
- the final logical expression must not have more than 64 subexpressions
- it can have early returns (all true returns are unified using $\mid\mid)$
- you can freely use comments, they are ignored
- the final boolean expression cannot be a true or false constant

The compiler does the following transformations (not necessarily in this order):

- convert shortcircuit boolean operations into non-shortcircuit ones (since all operands are boolean expressions or local variables, it is safe to execute these unconditionally)
- propagate constants
- simplify control flow graph
- (sparse) conditional constant propagation
- dead store elimination
- dead code elimination
- instruction combining (arithmetic simplifications)
- jump threading

If after this transformation the program meets the requirements outlined above, then it is converted to a logical signature. The resulting logical signature is simplified using basic properties of boolean operations, such as associativity, distributivity, De Morgan's law.

The final logical signature is not unique (there might be another logical signature with identical behavior), however the boolean part is in a canonical form: it is in disjunctive normal form, with operands sorted in ascending order.

For best results the C code should consist of:

- local variables declaring the sums you want to use
- a series of if branches that return true, where the if's condition is a single comparison or a logical and of comparisons
- a final return false

You can use || in the if condition too, but be careful that after expanding to disjunctive normal form, the number of subexpressions doesn't exceed 64.

Note that you do not have to use all the subsignatures you declared in logical_trigger, you can do more complicated checks (that wouldn't obey the above restrictions) in the bytecode itself at runtime. The logical_trigger function is fully compiled into a logical signature, it won't be a runtime executed function (hence the restrictions).

4.4. Headers and runtime environment

When compiling a bytecode program, bytecode.h is automatically included, so you don't need to explicitly include it. These headers (and the compiler itself) predefine certain macros, see Appendix D for a full list. In addition the following types are defined:

```
typedef unsigned char uint8_t;
typedef char int8_t;
typedef unsigned short uint16_t;

4 typedef short int16_t;
typedef unsigned int uint32_t;
6 typedef int int32_t;
typedef unsigned long uint64_t;
8 typedef long int64_t;
typedef unsigned int size_t;
10 typedef int off_t;
typedef struct signature { unsigned id } __Signature;
```

As described in Section 4.1 the width of integer types are fixed, the above typedefs show that.

A bytecode's entrypoint is the function entrypoint and it's required by ClamAV to load the bytecode. Bytecode that is triggered by a logical signature must have a list of virusnames and patterns defined. Bytecodes triggered via hooks can optionally have them, but for example a PE unpacker doesn't need virus names as it only processes the data.

CHAPTER 5 Bytecode security & portability

CHAPTER 6 Reporting bugs

CHAPTER 7 Bytecode API

7.1. API groups

7.1.1. Bytecode Configuration

Macros

```
• #define VIRUSNAME_PREFIX(name) const char ___clambc_virusname_prefix[] = name;
```

- #define VIRUSNAMES(...) const char *const ___clambc_virusnames[] = {___VA_ARGS___};
- #define PE_UNPACKER_DECLARE const uint16_t __clambc_kind = BC_PE_UNPACKER;
- #define PDF_HOOK_DECLARE const uint16_t __clambc_kind = BC_PDF;
- #define PE_HOOK_DECLARE const uint16_t __clambc_kind = BC_PE_ALL;
- #define SIGNATURES_DECL_BEGIN struct ___Signatures {
- #define DECLARE_SIGNATURE(name)
- #define SIGNATURES_DECL_END };
- #define TARGET(tgt) const unsigned short ___Target = (tgt);
- #define COPYRIGHT(c) const char *const ___Copyright = (c);
- #define ICONGROUP1(group) const char *const ___IconGroup1 = (group);
- $\bullet \ \ \# define \ ICONGROUP2 (group) \ const \ char \ *const \ __IconGroup2 = (group);$
- #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m);
- #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m);
- #define SIGNATURES DEF BEGIN
- #define SIGNATURES DEF END };

Enumerations

```
enum BytecodeKind {
    BC_GENERIC =0, BC_STARTUP =1 , BC_LOGICAL =256, BC_PE_UNPACKER,
    BC_PDF, BC_PE_ALL }
enum FunctionalityLevels {
    FUNC_LEVEL_096 = 51 , FUNC_LEVEL_096_1 = 53 , FUNC_LEVEL_096_2 = 54 , FUNC_LEVEL_096_3 = 55,
    FUNC_LEVEL_096_4 = 56, FUNC_LEVEL_096_5 = 58, FUNC_LEVEL_097 = 60, FUNC_LEVEL_097_1 = 61,
    FUNC_LEVEL_097_2 = 62, FUNC_LEVEL_097_3 = 63, FUNC_LEVEL_097_4 = 64, FUNC_LEVEL_097_5 = 65,
    FUNC_LEVEL_097_6 = 67, FUNC_LEVEL_097_7 = 68, FUNC_LEVEL_097_8 = 69, FUNC_LEVEL_098_1 = 76,
    FUNC_LEVEL_098_1 = 76,
    FUNC_LEVEL_098_2 = 77, FUNC_LEVEL_098_3 = 77, FUNC_LEVEL_098_4 = 78 }
```

7.1. API groups

Detailed Description

Macro Definition Documentation

#define COPYRIGHT(c) const char *const ___Copyright = (c); Defines an alternative copyright for this bytecode.

This will also prevent the sourcecode from being embedded into the bytecode.

#define DECLARE_SIGNATURE(name) Value:

```
const char *name##_sig;\
    __Signature name;
```

Declares a name for a subsignature.

#define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m); Define the maximum engine functionality level required for this bytecode/logical signature. Engines newer than this will skip loading the bytecode. You can use the FunctionalityLevels enumeration here.

#define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m); Define the minimum engine functionality level required for this bytecode/logical signature. Engines older than this will skip loading the bytecode. You can use the FunctionalityLevels enumeration here.

See logical signature documentation for what it is.

#define ICONGROUP2(group) const char *const ___IconGroup2 = (group); Define IconGroup2 for logical signature.

See logical signature documentation for what it is.

#define PDF_HOOK_DECLARE const uint16_t ___clambc_kind = BC_PDF; Make the current bytecode a PDF hook.

Having a logical signature doesn't make sense here, since the logical signature is evaluated AFTER these hooks run.

This hook is called several times, use pdf get phase() to find out in which phase you got called.

#define PE_HOOK_DECLARE const uint16_t ___clambc_kind = BC_PE_ALL; Make the current bytecode a PE hook.

Bytecode will be called once the logical signature trigger matches (or always if there is none), and if you have access to all the PE information. By default you only have access to execs.h information, and not to PE field information (even for PE files).

#define PE_UNPACKER_DECLARE const uint16_t __clambc_kind = BC_PE_UN-PACKER; Like PE_HOOK_DECLARE, but it is not run for packed files that pe.c can unpack (only on the unpacked file).

#define SIGNATURES_DECL_BEGIN struct ___Signatures { Marks the beginning of the subsignature name declaration section.

Chapter 7. Bytecode API

define SIGNATURES_DECL_END $\}$; Marks the end of the subsignature name declaration section.

#define SIGNATURES_DEF_BEGIN Value:

```
static const unsigned __signature_bias = __COUNTER__+1;\ const struct __Signatures Signatures = {\
```

Marks the beginning of subsignature pattern definitions.

See Also

SIGNATURES DECL BEGIN

#define SIGNATURES_DEF_END }; Marks the end of the subsignature pattern definitions. Alternative: SIGNATURES_END

#define TARGET(tgt) const unsigned short ___Target = (tgt); Defines the ClamAV file target.

Parameters

in $tgt \mid \text{ClamAV signature type } (0 - \text{raw}, 1 - \text{PE}, \text{etc.})$
--

#define VIRUSNAME_PREFIX(name) const char ___clambc_virusname_prefix[] = name; Declares the virusname prefix.

Parameters

in	name	the prefix common to all viruses reported by this bytecode
----	------	--

 $\# define \ VIRUSNAMES(\ \dots \) \ const \ char * const __clambc_virusnames[] = \{ __VA_-ARGS__ \}; \ \ Declares \ all \ the \ virusnames \ that \ this \ bytecode \ can \ report.$

Parameters

in	 a comma-separated list of strings interpreted as virusnames

Enumeration Type Documentation

enum BytecodeKind Specifies the bytecode type and how ClamAV executes it

Enumerator

 $BC_GENERIC$ generic bytecode, not tied a specific hook

BC_STARTUP triggered at startup, only one is allowed per ClamAV startup

 $BC_LOGICAL$ executed on a logical trigger

BC_PE_UNPACKER specifies a PE unpacker, executed on PE files on a logical trigger

BC_PDF specifies a PDF hook, executes at a predetermined point of PDF parsing for PDF files

 BC_PE_ALL specifies a PE hook, executes at a predetermined point in PE parsing for PE files, both packed and unpacked files

enum FunctionalityLevels LibClamAV functionality level constants

Enumerator

 $FUNC_LEVEL_096$ LibClamAV release 0.96.0: bytecode engine released

FUNC_LEVEL_096_1 LibClamAV release 0.96.1: logical signature use of VI/macros requires this minimum functionality level

FUNC_LEVEL_096_2 LibClamAV release 0.96.2: PDF Hooks require this minimum level

FUNC_LEVEL_096_3 LibClamAV release 0.96.3: BC_PE_ALL bytecodes require this minimum level

7.1. API groups

 $FUNC_LEVEL_096_4$ LibClamAV release 0.96.4: minimum recommended engine version, older versions have quadratic load time

- $FUNC_LEVEL_096_5$ LibClamAV release 0.96.5
- FUNC_LEVEL_097 LibClamAV release 0.97.0: older bytecodes may incorrectly use 57
- $FUNC_LEVEL_097_1$ LibClamAV release 0.97.1
- FUNC_LEVEL_097_2 LibClamAV release 0.97.2
- FUNC_LEVEL_097_3 LibClamAV release 0.97.3
- FUNC_LEVEL_097_4 LibClamAV release 0.97.4
- FUNC_LEVEL_097_5 LibClamAV release 0.97.5
- FUNC_LEVEL_097_6 LibClamAV release 0.97.6
- FUNC_LEVEL_097_7 LibClamAV release 0.97.7
- $FUNC_LEVEL_097_8$ LibClamAV release 0.97.8
- FUNC_LEVEL_098_1 LibClamAV release 0.98.2
- FUNC_LEVEL_098_2 LibClamAV release 0.98.2
- $FUNC_LEVEL_098_3$ LibClamAV release 0.98.3
- FUNC_LEVEL_098_4 LibClamAV release 0.98.4: JSON reading API requires this minimum level

Chapter 7. Bytecode API 29

7.1.2. Abstract Data Types

Functions

- void * malloc (uint32_t size)
- int32_t hashset_new (void)
- int32_t hashset_add (int32_t hs, uint32_t key)
- int32 t hashset remove (int32 t hs, uint32 t key)
- int32_t hashset_contains (int32_t hs, uint32_t key)
- int32_t hashset_done (int32_t id)
- int32 t hashset empty (int32 t id)
- int32_t buffer_pipe_new (uint32_t size)
- int32_t buffer_pipe_new_fromfile (uint32_t pos)
- uint32 t buffer pipe read avail (int32 t id)
- const uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)
- int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)
- uint32_t buffer_pipe_write_avail (int32_t id)
- uint8_t * buffer_pipe_write_get (int32_t id, uint32_t size)
- int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)
- int32_t buffer_pipe_done (int32_t id)
- int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
- int32 t inflate process (int32 t id)
- int32_t inflate_done (int32_t id)
- int32_t map_new (int32_t keysize, int32_t valuesize)
- int32_t map_addkey (const uint8_t *key, int32_t ksize, int32_t id)
- int32_t map_setvalue (const uint8_t *value, int32_t vsize, int32_t id)
- int32 t map remove (const uint8 t *key, int32 t ksize, int32 t id)
- int32 t map find (const uint8 t *key, int32 t ksize, int32 t id)
- int32 t map getvaluesize (int32 t id)
- uint8_t * map_getvalue (int32_t id, int32_t size)
- int32_t map_done (int32_t id)

Detailed Description

Function Documentation

 $int32_t$ buffer_pipe_done ($int32_t$ id) Deallocate memory used by buffer. After this all attempts to use this buffer will result in error. All buffer_pipes are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of buffer_pipe
----	----	-------------------

Returns

0 on success

 $int32_t \ buffer_pipe_new$ ($uint32_t \ size$) Creates a new pipe with the specified buffer size Parameters

in	size	size of buffer

Returns

ID of newly created buffer_pipe

7.1. API groups

int32_t buffer_pipe_new_fromfile (uint32_t pos) Creates a new pipe with the specified buffer size w/ tied input to the current file, at the specified position. Parameters

in	pos	starting position of pipe input in current file

Returns

ID of newly created buffer pipe

in	id	ID of buffer_pipe

Returns

amount of bytes available to read

const uint8_t* buffer_pipe_read_get (int32_t id, uint32_t amount) Returns a pointer to the buffer for reading. The 'amount' parameter should be obtained by a call to buffer_pipe_read_avail().

Parameters

in	id	ID of buffer_pipe
in	amount	to read

Returns

pointer to buffer, or NULL if buffer has less than specified amount

int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount) Updates read cursor in buffer_pipe.

Parameters

in	id	ID of buffer_pipe
in	amount	amount of bytes to move read cursor

Returns

0 on success

 ${\tt uint32_t\ buffer_pipe_write_avail}$ (${\tt int32_t\ id}$) Returns the amount of bytes available for writing.

Parameters

in	id	ID of buffer_pipe

Returns

amount of bytes available for writing

uint8_t* buffer_pipe_write_get (int32_t id, uint32_t size) Returns pointer to writable buffer. The 'size' parameter should be obtained by a call to buffer_pipe_write_avail(). Parameters

in	id	ID of buffer_pipe

in	size	amount of bytes to write

Returns

pointer to write buffer, or NULL if requested amount is more than what is available in the buffer

 $int32_t\ buffer_pipe_write_stopped\ (\ int32_t\ id,\ uint32_t\ amount\)$ Updates the write cursor in buffer_pipe.

Parameters

in	id	ID of buffer_pipe
in	amount	amount of bytes to move write cursor

Returns

0 on success

 $int32_t\ hashset_add\ (\ int32_t\ hs,\ uint32_t\ key\)$ Add a new 32-bit key to the hashset. Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to add

Returns

0 on success

 $int32_t\ hashset_contains$ ($int32_t\ hs$, $uint32_t\ key$) Returns whether the hashset contains the specified key.

Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to lookup

Returns

1 if found

0 if not found

<0 on invalid hashset ID

 $int32_t$ hashset_done ($int32_t$ id) Deallocates the memory used by the specified hashset. Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of hashset (from hashset_new)
----	------	----------------------------------

Returns

0 on success

int32_t hashset_empty (int32_t id) Returns whether the hashset is empty.

Parameters

in	id	of hashset (from hashset_new)

Returns

0 on success

int32_t hashset_new (void) Creates a new hashset and returns its id.

Returns

ID for new hashset

 $int32_t\ hashset_remove\ (int32_t\ hs,\ uint32_t\ key\)$ Remove a 32-bit key from the hashset. Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to add

Returns

0 on success

int32_t inflate_done (int32_t id) Deallocates inflate data structure. Using the inflate data structure after this will result in an error. All inflate data structures are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of inflate data structure

Returns

0 on success.

int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits) Initializes inflate data structures for decompressing data 'from_buffer' and writing uncompressed uncompressed data 'to_buffer'.

Parameters

in	from_buffer	ID of buffer_pipe to read compressed data from
in	to_buffer	ID of buffer_pipe to write decompressed data to
in	window Bits	(see zlib documentation)

Returns

ID of newly created inflate data structure, <0 on failure

int32_t inflate_process (int32_t id) Inflate all available data in the input buffer, and write to output buffer. Stops when the input buffer becomes empty, or write buffer becomes full. Also attempts to recover from corrupted inflate stream (via inflateSync). This function can be called repeatedly on success after filling the input buffer, and flushing the output buffer. The inflate stream is done processing when 0 bytes are available from output buffer, and input buffer is not empty.

Parameters

in	id	ID of inflate data structure
----	----	------------------------------

Returns

0 on success, zlib error code otherwise

void* malloc (uint32_t size) Allocates memory. Currently this memory is freed automatically on exit from the bytecode, and there is no way to free it sooner.
Parameters

in	size	amount of memory to allocate in bytes

Returns

pointer to allocated memory

int32_t map_addkey (const uint8_t * key, int32_t ksize, int32_t id) Inserts the specified key/value pair into the map.

Parameters

in	id	id of table
in	key	key
in	ksize	size of key

Returns

- 0 if key existed before
- 1 if key didn't exist before
- < 0 if ksize doesn't match keysize specified at table creation

 $int32_t$ map_done ($int32_t$ id) Deallocates the memory used by the specified map. Trying to use the map after this will result in an error. All maps are automatically deallocated when the bytecode finishes execution.

Parameters

in	id	id of map
----	----	-----------

Returns

- 0 success
- -1 invalid map

 $int32_t map_find$ ($const uint8_t * key$, $int32_t ksize$, $int32_t id$) Looks up key in map. The map remember the last looked up key (so you can retrieve the value).

Parameters

in	id	id of map
in	key	key
in	ksize	size of key

Returns

- 0 if not found
- 1 if found
- $<\!0$ if k size doesn't match the size specified at table creation

 $wint8_t* map_getvalue (int32_t id, int32_t size)$ Returns the value obtained during last map_find.

Parameters

in	id	id of map.
in	size	size of value (obtained from map_getvaluesize)

Returns

value

 $int32_t\ map_getvaluesize\ (\ int32_t\ id\)$ Returns the size of value obtained during last map_find. Parameters

in	id	id of map.
		1

Returns

size of value

 $int32_t\ map_new\ (\ int32_t\ keysize,\ int32_t\ valuesize\)$ Creates a new map and returns its id.

Parameters

in	keysize	size of key
in	valuesize	size of value, if 0 then value is allocated separately

Returns

ID of new map

 $int 32_t \ map_remove \ (\ const \ uint 8_t * \textit{key}, \ int 32_t \ \textit{ksize}, \ int 32_t \ \textit{id} \) \ \ \text{Remove an element from the map}.$

Parameters

in	id	id of map
in	key	key
in	ksize	size of key

Returns

0 on success, key was present

1 if key was not present

<0 if ksize doesn't match key size specified at table creation

 $int 32_t \ map_set value \ (\ const \ uint 8_t * value, \ int 32_t \ vsize, \ int 32_t \ id \) \ \ Sets \ the \ value \ for \ the \ last \ inserted \ key \ with \ map_add key.$

Parameters

in	id	id of table
in	value	value
in	vsize	size of value

Returns

0 - if update was successful

<0 - if there is no last key

Chapter 7. Bytecode API 35

7.1.3. Debugging

Functions

```
• uint32_t debug_print_str (const uint8_t *str, uint32_t len)
```

- uint32_t debug_print_uint (uint32_t a)
- uint32_t debug_print_str_start (const uint8_t *str, uint32_t len)
- uint32_t debug_print_str_nonl (const uint8_t *str, uint32_t len)
- void debug (...) __attribute__((overloadable
- static force_inline void overloadable_func debug (const char *str)
- static force_inline void overloadable_func debug (const uint8_t *str)
- static force_inline void overloadable_func debug (uint32_t a)

Detailed Description

Function Documentation

debug (const char * <math>str) [static] Prints str to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in	str	null terminated string
----	-----	------------------------

debug (const uint8_t * str **) [static]** Prints str to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in	str	null terminated string

debug (uint32_t a) [static] Prints a integer to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

```
in a integer
```

 ${f void\ debug\ (}$...) debug is an overloaded function (yes clang supports that in C!), but it only works on strings, and integers. Give an error on any other type.

See Also

```
debug(const char * str),
debug(const uint8_t* str),
debug(uint32_t a)
```

 ${\tt uint32_t\ debug_print_str}$ (${\tt const\ uint8_t*str},\ {\tt uint32_t\ len}$) Prints a debug message string.

Parameters

in	str	Message to print
in	len	length of message to print

Returns

0

in	str	the string
in	len	length of str

Returns

0

in	str	the string
in	len	length of str

Returns

0

 ${\tt uint32_t\ debug_print_uint}$ (${\tt uint32_t\ a}$) Prints a number as a debug message. This is similar to debug_print_str_nonl.

Parameters

		1 ,
ın	a	number to print

Returns

0

7.1.4. Disassembly

Data Structures

- struct DIS_mem_arg
- struct DIS arg
- struct DIS_fixed

Functions

- uint32_t disasm_x86 (struct DISASM_RESULT *result, uint32_t len)
- static force_inline uint32_t DisassembleAt (struct DIS_fixed *result, uint32_t offset, uint32_t len)

Detailed Description

Function Documentation

out	result	pointer to struct holding result
in	len	how many bytes to disassemble

Returns

0 for success

You can use lseek to disassemble starting from a different location. This is a low-level API, the result is in ClamAV type-8 signature format (64 bytes/instruction).

See Also

DisassembleAt

static force_inline uint32_t DisassembleAt (struct DIS_fixed * result, uint32_t offset, uint32_t len) [static] Disassembles one X86 instruction starting at the specified offset.

Parameters

out	result	disassembly result
in	offset	start disassembling from this offset, in the current file
in	len	max amount of bytes to disassemble

Returns

offset where disassembly ended

7.1.5. Engine Queries

Functions

- uint32_t engine_functionality_level (void)
- uint32_t engine_dconf_level (void)
- uint32_t engine_scan_options (void)
- uint32_t engine_db_options (void)
- int32_t running_on_jit (void)
- static force_inline uint32_t count_match (___Signature sig)
- static force inline uint32 t matches (Signature sig)
- static force_inline uint32_t match_location (___Signature sig, uint32_t goback)
- static force_inline int32_t match_location_check (__Signature sig, uint32_t goback, const char *static_start, uint32_t static_len)

Detailed Description

Function Documentation

static force_inline uint32_t count_match (___Signature sig) [static] Returns how many times the specified signature matched.

Parameters

in sig name of subsignature queried	
-------------------------------------	--

Returns

number of times this subsignature matched in the entire file

This is a constant-time operation, the counts for all subsignatures are already computed.

uint32_t engine_db_options (void) Returns the current engine's db options.

Returns

CL DB * flags

 $\label{lem:cond_level} \begin{tabular}{ll} \bf uint 32_t \ engine_dconf_level \ (\ void\) \ \ Returns the current engine (dconf) functionality level. \\ Usually identical to engine_functionality_level(), unless distro backported patches. Compare with FunctionalityLevels. \\ \end{tabular}$

Returns

an integer representing the DCONF (security fixes) level.

 $\label{lem:condity_level} \begin{tabular}{ll} \bf uint 32_t \ engine_functionality_level \ (\ void\) \ \ Returns the current engine (feature) functionality level. To map these to ClamAV releases, compare it with FunctionalityLevels. \\ \end{tabular}$

Returns

an integer representing current engine functionality level.

uint32_t engine_scan_options (void) Returns the current engine's scan options.

Returns

 CL_SCAN* flags

static force_inline uint32_t match_location (___Signature sig, uint32_t goback) [static] Returns the offset of the match.

Parameters

in	sig	- Signature
in	goback	- max length of signature

Returns

offset of match

static force_inline int32_t match_location_check (___Signature sig, uint32_t goback, const char * $static_start$, uint32_t $static_len$) [static] Like match_location(), but also checks that the match starts with the specified hex string.

It is recommended to use this for safety and compatibility with 0.96.1

Parameters

in	sig	- signature
in	goback	- maximum length of signature (till start of last subsig)
in	$static_start$	- static string that sig must begin with
in	$static_len$	- static string that sig must begin with - length

Returns

>=0 - offset of match

-1 - no match

static force_inline uint32_t matches (___Signature sig) [static] Returns whether the specified subsignature has matched at least once. Parameters

in

Returns

1 if subsignature one or more times, 0 otherwise

int32_t running_on_jit (void) Returns whether running on JIT. As side-effect it disables interp / JIT comparisons in test mode (errors are still checked)

Returns

- 1 running on JIT
- 0 running on ClamAV interpreter

7.1.6. Environment

Functions

- uint32_t get_environment (struct cli_environment *env, uint32_t len)
- uint32_t disable_bytecode_if (const int8_t *reason, uint32_t len, uint32_t cond)
- uint32_t disable_jit_if (const int8_t *reason, uint32_t len, uint32_t cond)
- int32_t version_compare (const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_t rhs_len)
- uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c)
- bool __is_bigendian (void) __attribute__((const)) __attribute__((nothrow))
- static uint32 t force inline le32 to host (uint32 t v)
- static uint32_t force_inline be32_to_host (uint32_t v)
- static uint64_t force_inline le64_to_host (uint64_t v)
- static uint64_t force_inline be64_to_host (uint64_t v)
- static uint16 t force inline le16 to host (uint16 t v)
- static uint16 t force inline be16 to host (uint16 t v)
- static uint32 t force inline cli readint32 (const void *buff)
- static uint16 t force inline cli readint16 (const void *buff)
- static void force_inline cli_writeint32 (void *offset, uint32_t v)

Detailed Description

Function Documentation

bool ___is_bigendian (void) const Returns true if the bytecode is executing on a big-endian CPU.

Returns

true if executing on bigendian CPU, false otherwise

This will be optimized away in libclamav, but it must be used when dealing with endianess for portability reasons

For example whenever you read a 32-bit integer from a file, it can be written in little-endian convention (x86 CPU for example), or big-endian convention (PowerPC CPU for example).

If the file always contains little-endian integers, then conversion might be needed.

ClamAV bytecodes by their nature must only handle known-endian integers, if endianness can change, then both situations must be taken into account (based on a 1-byte field for example).

static uint16_t force_inline be16_to_host (uint16_t v) [static] Converts the specified value if needed, knowing it is in big endian order. Parameters

in $v \mid 16$ -bit integer as read from a file

Returns

integer converted to host's endianess

static uint32_t force_inline be32_to_host (uint32_t v) [static] Converts the specified value if needed, knowing it is in big endian order. Parameters

in $v \mid 32$ -bit integer as read from a file

Returns

integer converted to host's endianess

Parameters

in	v	64-bit integer as read from a file

Returns

integer converted to host's endianess

Parameters

in	a	- os_category $<<$ 24 arch $<<$ 20 compiler $<<$ 16 flevel $<<$ 8
		dconf
in	b	- big_endian $<<$ 28 sizeof_ptr $<<$ 24 cpp_version
in	c	- os_features << 24 c_version

Returns

0 - no match

1 - match

Parameters

in	buff	pointer to buffer
----	-----------------	-------------------

Returns

16-bit little-endian integer converted to host endianness

static uint 32_t force_inline cli_readint 32 (const void * buff) [static] Reads from the specified buffer a 32-bit of little-endian integer.

Parameters

in oug pointer to burier	in	buff	pointer to buffer
--------------------------	----	------	-------------------

Returns

32-bit little-endian integer converted to host endianness

static void force_inline cli_writeint32 (void * offset, uint32_t v) [static] Writes the specified value into the specified buffer in little-endian order Parameters

out	offset	pointer to buffer to write to
in	v	value to write

 $\label{lem:cond} \begin{tabular}{ll} uint 32_t & disable_bytecode_if (const int 8_t * reason, uint 32_t len, uint 32_t cond) \\ Disables & the bytecode completely if condition is true. Can only be called from the BC_STARTUP bytecode. \\ \end{tabular}$

Parameters

in	reason	- why the bytecode had to be disabled
in	len	- length of reason
in	cond	- condition

Returns

- 0 auto mode
- 1 JIT disabled
- 2 fully disabled

in	reason	- why the JIT had to be disabled
in	len	- length of reason
in	cond	- condition

Returns

- 0 auto mode
- 1 JIT disabled
- 2 fully disabled

uint32_t get_environment (struct cli_environment * env, uint32_t len) Queries the environment this bytecode runs in. Used by BC_STARTUP to disable bytecode when bugs are known for the current platform.

Parameters

out	env	- the full environment
in	len	- size of env

Returns

0

static uint16_t force_inline le16_to_host (uint16_t v) [static] Converts the specified value if needed, knowing it is in little endian order. Parameters

in	v	16-bit integer as read from a file

Returns

integer converted to host's endianess

static uint32_t force_inline le32_to_host (uint32_t v) [static] Converts the specified value if needed, knowing it is in little endian order. Parameters

in	v	32-bit integer as read from a file

Returns

integer converted to host's endianess

static uint64_t force_inline le64_to_host (uint64_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Chapter 7. Bytecode API

//3

Parameters

in	v	64-bit integer as read from a file

Returns

integer converted to host's endianess

Parameters

in	lhs	- left hand side of comparison
in	lhs_len	- length of lhs
in	rhs	- right hand side of comparison
in	rhs_len	- length of rhs

Returns

-1 - lhs < rhs

0 - lhs == rhs

1 - lhs > rhs

7.1.7. File Operations

Enumerations

• enum { SEEK_SET =0, SEEK_CUR, SEEK_END }

Functions

- int32 t read (uint8 t *data, int32 t size)
- int32 t write (uint8 t *data, int32 t size)
- int32_t seek (int32_t pos, uint32_t whence)
- int32_t file_find (const uint8_t *data, uint32_t len)
- int32_t file_byteat (uint32_t offset)
- $\bullet \ \ int 32_t \ fill_buffer \ (uint 8_t \ *buffer, \ uint 32_t \ len, \ uint 32_t \ filled, \ uint 32_t \ cursor, \ uint 32_t \ fill)$
- int32 t read number (uint32 t radix)
- int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)
- int32_t get_file_reliability (void)
- static force_inline uint32_t getFilesize (void)

Detailed Description

Enumeration Type Documentation

anonymous enum

Enumerator

 $SEEK_SET$ set file position to specified absolute position

SEEK_CUR set file position relative to current position

SEEK END set file position relative to file end

Function Documentation

 $int32_t$ file_byteat ($uint32_t$ offset) Read a single byte from current file

Parameters

in	offset	file offset

Returns

byte at offset off in the current file, or -1 if offset is invalid

int32_t file_find (const uint8_t * data, uint32_t len) Looks for the specified sequence of bytes in the current file.

Parameters

in	data	the sequence of bytes to look for
in	len	length of data, cannot be more than 1024

Returns

offset in the current file if match is found, -1 otherwise

int32_t file_find_limit (const uint8_t * data, uint32_t len, int32_t maxpos) Looks for the specified sequence of bytes in the current file, up to the specified position. Parameters

in	data	the sequence of bytes to look for
in	len	length of data, cannot be more than 1024
in	maxpos	maximum position to look for a match, note that this is 1 byte after
		the end of last possible match: $match_pos + len < maxpos$

Returns

offset in the current file if match is found, -1 otherwise

int32_t fill_buffer (uint8_t * buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill) Fills the specified buffer with at least fill bytes.

Parameters

out	buffer	the buffer to fill
in	len	length of buffer
in	filled	how much of the buffer is currently filled
in	cursor	position of cursor in buffer
in	fill	amount of bytes to fill in (0 is valid)

Returns

<0 on error

0 on EOF

number bytes available in buffer (starting from 0)

The character at the cursor will be at position 0 after this call.

 $int32_t$ get_file_reliability (void) Get file reliability flag, higher value means less reliable. When >0 import tables and such are not reliable

Returns

0 - normal

1 - embedded PE

2 - unpacker created file (not impl. yet)

static force_inline uint32_t getFilesize (void) [static] Returns the currently scanned file's size.

Returns

file size as 32-bit unsigned integer

 $int32_t\ read\ (\ uint8_t*data,\ int32_t\ size\)$ Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

Parameters

in	size	amount of bytes to read
out	data	pointer to buffer where data is read into

Returns

amount read.

 $int32_t\ read_number\ (\ uint32_t\ radix\)$ Reads a number in the specified radix starting from the current position. Non-numeric characters are ignored.

Parameters

in	radix	10 or 16

Returns

the number read

 $int32_t$ seek ($int32_t$ pos, $uint32_t$ whence) Changes the current file position to the specified one.

See Also

SEEK_SET, SEEK_CUR, SEEK_END

Parameters

in	pos	offset (absolute or relative depending on whence param)
in	whence	one of SEEK_SET, SEEK_CUR, SEEK_END

Returns

absolute position in file

 $\label{lem:continuity} \textbf{int32_t write (uint8_t*data, int32_t\ size)} \quad \text{Writes the specified amount of bytes from a buffer to the current temporary file.}$

Parameters

in	data	pointer to buffer of data to write
in	size	amount of bytes to write size bytes to temporary file, from the buffer
		pointed to byte

Returns

amount of bytes successfully written

7.1.8. JavaScript Normalization

Functions

- int32_t jsnorm_init (int32_t from_buffer)
- int32_t jsnorm_process (int32_t id)
- int32_t jsnorm_done (int32_t id)

Detailed Description

Function Documentation

int32_t jsnorm_done (int32_t id) Flushes JS normalizer.

Parameters

in	id	ID of js normalizer to flush

Returns

0 on success, <0 on failure

int32_t jsnorm_init (int32_t from_buffer) Initializes JS normalizer for reading 'from_buffer'. Normalized JS will be written to a single tempfile, one normalized JS per line, and automatically scanned when the bytecode finishes execution.

Parameters

in	from_buffer	ID of buffer_pipe to read javascript from
----	-------------	---

Returns

ID of JS normalizer, <0 on failure

int32_t jsnorm_process (int32_t id) Normalize all javascript from the input buffer, and write to tempfile. You can call this function repeatedly on success, if you (re)fill the input buffer. Parameters

in	id	ID of JS normalizer

Returns

0 on success, <0 on failure

7.1.9. Icon Matcher

Functions

- int 32_t matchicon (const uint 8_t *group1, int 32_t group1_len, const uint 8_t *group2, int 32_t group2_len)

Detailed Description

Function Documentation

in	group1	- same as GROUP1 in LDB signatures
in	$group1_len$	- length of group1
in	group2	- same as GROUP2 in LDB signatures
in	$group2_len$	- length of group2

${\rm Returns}$

- -1 invalid call, or sizes (only valid for PE hooks)
- 0 not a match
- 1 match

7.1.10. Math Operation

Functions

- int32_t ilog2 (uint32_t a, uint32_t b)
- int32_t ipow (int32_t a, int32_t b, int32_t c)
- uint32_t iexp (int32_t a, int32_t b, int32_t c)
- int32_t isin (int32_t a, int32_t b, int32_t c)
- int32_t icos (int32_t a, int32_t b, int32_t c)

Detailed Description

Function Documentation

 $\mathbf{int32_t\ icos}\ (\ \mathbf{int32_t}\ a,\ \mathbf{int32_t}\ b,\ \mathbf{int32_t}\ c\)\ \mathrm{Returns}\ \mathbf{c}*\mathbf{cos}(\mathbf{a/b}).$

Parameters

in	a	integer
in	b	integer
in	c	integer

Returns

c*sin(a/b)

uint32_t iexp (int32_t a, int32_t b, int32_t c) Returns exp(a/b)*c

Parameters

in	a	integer
in	b	integer
in	c	integer

Returns

c*exp(a/b)

int32_t ilog2 (uint32_t a, uint32_t b) Returns $2^26*\log 2(a/b)$

Parameters

in	a	input
in	b	input

Returns

 2^{2} 4 * log2(a/b)

int32_t ipow (int32_t a, int32_t b, int32_t c) Returns c*a^b.

Parameters

in	a	integer
in	b	integer
in	c	integer

Returns

c*pow(a,b)

 $\mathbf{int32_t} \ \mathbf{isin} \ (\ \mathbf{int32_t} \ a, \ \mathbf{int32_t} \ b, \ \mathbf{int32_t} \ c \) \ \ \mathbf{Returns} \ \mathbf{c*sin}(\mathbf{a/b}).$

Parameters

in	a	integer
in	b	integer
in	c	integer

${\rm Returns}$

c*sin(a/b)

Chapter 7. Bytecode API 51

7.1.11. PDF Handling

Enumerations

- enum pdf_phase { , PDF_PHASE_PARSED, PDF_PHASE_POSTDUMP, PDF_PHASE_END, PDF_PHASE_PRE }
- enum pdf_flag
- enum pdf_objflags

Functions

- int32_t pdf_get_obj_num (void)
- int32_t pdf_get_flags (void)
- int32_t pdf_set_flags (int32_t flags)
- int32 t pdf lookupobj (uint32 t id)
- uint32 t pdf getobjsize (int32 t objidx)
- const uint8_t * pdf_getobj (int32_t objidx, uint32_t amount)
- int32_t pdf_getobjid (int32_t objidx)
- int32 t pdf getobjflags (int32 t objidx)
- int32 t pdf setobjflags (int32 t objidx, int32 t flags)
- int32_t pdf_get_offset (int32_t objidx)
- int32_t pdf_get_phase (void)
- int32_t pdf_get_dumpedobjid (void)

Detailed Description

```
Enumeration Type Documentation
```

```
enum pdf_flag PDF flags
```

enum pdf_objflags PDF obj flags

enum pdf_phase Phase of PDF parsing used for PDF Hooks

Enumerator

```
PDF_PHASE_PARSED after parsing a PDF, object flags can be set etc.
```

PDF_PHASE_POSTDUMP after an obj was dumped and scanned

 PDF_PHASE_END after the pdf scan finished

PDF_PHASE_PRE before pdf is parsed at all

Function Documentation

 $int32_t\ pdf_get_dumpedobjid$ (void) Return the currently dumped obj index. Valid only in PDF_PHASE_POSTDUMP.

Returns

- >=0 object index
- -1 invalid phase

int32_t pdf_get_flags (void) Return the flags for the entire PDF (as set so far).

Returns

- -1 if not called from PDF hook
- >=0 pdf flags

int32_t pdf_get_obj_num (void) Return number of pdf objects

Returns

-1 - if not called from PDF hook

>=0 - number of PDF objects

int32_t pdf_get_offset (int32_t objidx) Return the object's offset in the PDF.

Parameters

in	objidx	- object index (from 0)
----	--------	-------------------------

Returns

-1 - object index invalid

>=0 - offset

int32_t pdf_get_phase (void) Return an 'enum pdf_phase'. Identifies at which phase this bytecode was called.

Returns

the current pdf_phase

in	objidx	- object index (from 0), not object id!
in	amount	- size returned by pdf_getobjsize (or smaller)

Returns

NULL - invalid objidx/amount

pointer - pointer to original object

 $int32_t\ pdf_getobjflags$ ($int32_t\ objidx$) Return the object flags for the specified object index. Parameters

in	objidx	- object index (from 0)

Returns

-1 - object index invalid

>=0 - object flags

 $int32_t\ pdf_getobjid$ ($int32_t\ objidx$) Return the object id for the specified object index. Parameters

in |objidx| - object index (from 0)

Returns

-1 - object index invalid

>=0 - object id (obj id << 8 | generation id)

uint32_t pdf_getobjsize (int32_t objidx) Return the size of the specified PDF obj.

53

Parameters

in	objidx	- object index (from 0), not object id!	

Returns

0 - if not called from PDF hook, or invalid objnum

>=0 - size of object

int32_t pdf_lookupobj (uint32_t id) Lookup pdf object with specified id.

Parameters

in	id	- pdf id (objnumber << 8 generationid)

Returns

-1 - if object id doesn't exist

>=0 - object index

 $int32_t\ pdf_set_flags$ ($int32_t\ flags$) Sets the flags for the entire PDF. It is recommended that you retrieve old flags, and just add new ones.

Parameters

in	flags	- flags to set.
----	-------	-----------------

Returns

0 - success -1 - invalid phase

 $int32_t\ pdf_setobjflags$ ($int32_t\ objidx$, $int32_t\ flags$) Sets the object flags for the specified object index. This can be used to force dumping of a certain obj, by setting the OBJ_FORCEDUMP flag for example.

Parameters

in	objidx	- object index (from 0)
in	flags	- value to set flags

Returns

-1 - object index invalid

>=0 - flags set

7.1.12. PE Operations

Data Structures

- struct cli_exe_section
- struct cli_exe_info
- struct pe_image_file_hdr
- struct pe image data dir
- struct pe_image_optional_hdr32
- struct pe image optional hdr64
- struct pe_image_section_hdr
- struct cli_pe_hook_data

Functions

- uint32_t pe_rawaddr (uint32_t rva)
- int32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
- static force inline bool hasExeInfo (void)
- static force_inline bool hasPEInfo (void)
- static force_inline bool isPE64 (void)
- static force inline uint8 t getPEMajorLinkerVersion (void)
- static force inline uint8 t getPEMinorLinkerVersion (void)
- static force inline uint32 t getPESizeOfCode (void)
- static force_inline uint32_t getPESizeOfInitializedData (void)
- static force_inline uint32_t getPESizeOfUninitializedData (void)
- static force_inline uint32_t getPEBaseOfCode (void)
- static force inline uint32 t getPEBaseOfData (void)
- static force_inline uint64_t getPEImageBase (void)
- static force_inline uint32_t getPESectionAlignment (void)
- static force_inline uint32_t getPEFileAlignment (void)
- static force_inline uint16_t getPEMajorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMajorImageVersion (void)
- static force inline uint16 t getPEMinorImageVersion (void)
- static force_inline uint16_t getPEMajorSubsystemVersion (void)
- static force_inline uint16_t getPEMinorSubsystemVersion (void)
- static force_inline uint32_t getPEWin32VersionValue (void)
- static force inline uint32 t getPESizeOfImage (void)
- static force_inline uint32_t getPESizeOfHeaders (void)
- static force_inline uint32_t getPECheckSum (void)
- static force_inline uint16_t getPESubsystem (void)
- static force_inline uint16_t getPEDllCharacteristics (void)
 static force_inline uint32_t getPESizeOfStackReserve (void)
- static force inline uint32 t getPESizeOfStackCommit (void)
- static force inline uint32 t getPESizeOfHeapReserve (void)
- static force inline uint32 t getPESizeOfHeapCommit (void)
- static force_inline uint32_t getPELoaderFlags (void)
- static force_inline uint16_t getPEMachine ()
- static force_inline uint32_t getPETimeDateStamp ()
- static force_inline uint32_t getPEPointerToSymbolTable ()
- static force_inline uint32_t getPENumberOfSymbols ()
- static force_inline uint16_t getPESizeOfOptionalHeader ()
- static force_inline uint16_t getPECharacteristics ()
- static force_inline bool getPEisDLL ()
- static force inline uint32 t getPEDataDirRVA (unsigned n)
- static force inline uint32 t getPEDataDirSize (unsigned n)

Chapter 7. Bytecode API 55

- static force_inline uint16_t getNumberOfSections (void)
- static uint32 t getPELFANew (void)
- static force inline int readPESectionName (unsigned char name[8], unsigned n)
- static force_inline uint32_t getEntryPoint (void)
- static force_inline uint32_t getExeOffset (void)
- static force inline uint32 t getImageBase (void)
- static uint32 t getVirtualEntryPoint (void)
- static uint32_t getSectionRVA (unsigned i)
- static uint32_t getSectionVirtualSize (unsigned i)
- static force_inline bool readRVA (uint32_t rva, void *buf, size_t bufsize)

Detailed Description

Function Documentation

int32_t get_pe_section (struct cli_exe_section * section, uint32_t num) Gets information about the specified PE section.

Parameters

out	section	PE section information will be stored here
in	num	PE section number

Returns

0 - success

-1 - failure

static force_inline uint32_t getEntryPoint (void) [static] Returns the offset of the EntryPoint in the executable file.

Returns

offset of EP as 32-bit unsigned integer

 $static\ force_inline\ uint32_t\ getExeOffset\ (void)\ [static]$ Returns the offset of the executable in the file.

Returns

offset of embedded executable inside file

static force_inline uint32_t getImageBase (void) [static] Returns the ImageBase with the correct endian conversion.

Only works if the bytecode is a PE hook (i.e. you invoked PE_UNPACKER_DECLARE).

Returns

ImageBase of PE file, 0 - for non-PE hook

static force_inline uint16_t getNumberOfSections (void) [static] Returns the number of sections in this executable file.

Returns

number of sections as 16-bit unsigned integer

static force_inline uint32_t getPEBaseOfCode (void) [static] Return the PE BaseOfCode.

Returns

PE BaseOfCode, or 0 if not in PE hook

static force_inline uint32_t getPEBaseOfData (void) [static] Return the PE BaseOfData.

Returns

PE BaseOfData, or 0 if not in PE hook

static force_inline uint16_t getPECharacteristics () [static] Returns PE characteristics. For example you can use this to check whether it is a DLL (0x2000).

Returns

characteristic of PE file, or 0 if not in PE hook

static force_inline uint32_t getPECheckSum (void) [static] Return the PE CheckSum.

Returns

PE CheckSum, or 0 if not in PE hook

static force_inline uint32_t getPEDataDirRVA (unsigned n) [static] Gets the virtual address of specified image data directory.

Parameters

in $n \mid \text{im}$	nage directory requested
-----------------------	--------------------------

Returns

Virtual Address of requested image directory

static force_inline uint32_t getPEDataDirSize (unsigned n) [static] Gets the size of the specified image data directory.

Parameters

in	n	image directory requested

Returns

Size of requested image directory

static force_inline uint16_t getPEDllCharacteristics (void) [static] Return the PE DllCharacteristics.

Returns

PE DllCharacteristics, or 0 if not in PE hook

static force_inline uint32_t getPEFileAlignment (void) [static] Return the PE File-Alignment.

Returns

PE File Alignment, or 0 if not in PE hook

static force_inline uint64_t getPEImageBase (void) [static] Return the PE ImageBase as 64-bit integer.

Returns

PE ImageBase as 64-bit int, or 0 if not in PE hook

static force_inline bool getPEisDLL () [static] Returns whether this is a DLL. Use this only in a PE hook!

Returns

true - the file is a DLL false - file is not a DLL

static uint32_t getPELFANew (void) [static] Gets the offset to the PE header.

Returns

offset to the PE header, or 0 if not in PE hook

 ${\bf static\ force_inline\ uint 32_t\ get PELoader Flags\ (\ void\ \)} \quad {\bf [static]} \quad {\bf Return\ the\ PE\ Loader Flags.}$

Returns

PE LoaderFlags or 0 if not in PE hook

static force_inline uint16_t getPEMachine () [static] Returns the CPU this executable runs on, see libclamav/pe.c for possible values.

Returns

PE Machine or 0 if not in PE hook

static force_inline uint16_t getPEMajorImageVersion (void) [static] Return the PE MajorImageVersion.

Returns

PE MajorImageVersion, or 0 if not in PE hook

static force_inline uint8_t getPEMajorLinkerVersion (void) [static] Returns MajorLinkerVersion for this PE file.

Returns

PE MajorLinkerVersion or 0 if not in PE hook

 $static\ force_inline\ uint 16_t\ get PEMajor Operating System Version\ (\ void\)\ [static]\ Return\ the\ PE\ Major Operating System Version.$

Returns

PE MajorOperatingSystemVersion, or 0 if not in PE hook

static force_inline uint16_t getPEMajorSubsystemVersion (void) [static] Return the PE MajorSubsystemVersion.

Returns

PE Major Subsystem
Version or 0 if not in PE hook

static force_inline uint16_t getPEMinorImageVersion (void) [static] Return the PE MinorImageVersion.

Returns

PE MinorrImageVersion, or 0 if not in PE hook

static force_inline uint8_t getPEMinorLinkerVersion (void) [static] Returns MinorLinkerVersion for this PE file.

Returns

PE MinorLinkerVersion or 0 if not in PE hook

 $static\ force_inline\ uint 16_t\ get PEM in or Operating System Version\ (\ void\)\ [static] \ Return\ the\ PE\ Min or Operating System Version.$

Returns

PE MinorOperatingSystemVersion, or 0 if not in PE hook

static force_inline uint16_t getPEMinorSubsystemVersion (void) [static] Return the PE MinorSubsystemVersion.

Returns

PE MinorSubsystemVersion, or 0 if not in PE hook

static force_inline uint32_t getPENumberOfSymbols () [static] Returns the PE number of debug symbols

Returns

PE NumberOfSymbols or 0 if not in PE hook

static force_inline uint32_t getPEPointerToSymbolTable () [static] Returns pointer to the PE debug symbol table

Returns

PE PointerToSymbolTable or 0 if not in PE hook

static force_inline uint32_t getPESectionAlignment (void) [static] Return the PE SectionAlignment.

Returns

PE SectionAlignment, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfCode (void) [static] Return the PE SizeOfCode.

Returns

PE SizeOfCode or 0 if not in PE hook

static force_inline uint32_t getPESizeOfHeaders (void) [static] Return the PE Size-OfHeaders.

Returns

PE SizeOfHeaders, or 0 if not in PE hook

Returns

PE SizeOfHeapCommit, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfHeapReserve (void) [static] Return the PE SizeOfHeapReserve.

Returns

PE SizeOfHeapReserve, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfImage (void) [static] Return the PE SizeOfImage.

Returns

PE SizeOfImage, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfInitializedData (void) [static] Return the PE SizeofInitializedData.

Returns

PE SizeOfInitializeData or 0 if not in PE hook

static force_inline uint16_t getPESizeOfOptionalHeader () [static] Returns the size of PE optional header.

Returns

size of PE optional header, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfStackCommit (void) [static] Return the PE SizeOfStackCommit.

Returns

PE SizeOfStackCommit, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfStackReserve (void) [static] Return the PE SizeOfStackReserve.

Returns

PE SizeOfStackReserver, or 0 if not in PE hook

static force_inline uint32_t getPESizeOfUninitializedData (void) [static] Return the PE SizeofUninitializedData.

Returns

PE SizeofUninitializedData or 0 if not in PE hook

 $\mathbf{static} \ \mathbf{force_inline} \ \mathbf{uint16_t} \ \mathbf{getPESubsystem} \ (\ \mathbf{void} \ \) \ \ [\mathbf{static}] \ \ \mathbf{Return} \ \mathbf{the} \ \mathbf{PE} \ \mathbf{Subsystem}.$

Returns

PE subsystem, or 0 if not in PE hook

static force_inline uint32_t getPETimeDateStamp () [static] Returns the PE Time-DateStamp from headers

Returns

PE TimeDateStamp or 0 if not in PE hook

static force_inline uint32_t getPEWin32VersionValue (void) [static] Return the PE Win32VersionValue.

Returns

PE Win32VersionValue, or 0 if not in PE hook

static uint32_t getSectionRVA (unsigned i) [static] Return the RVA of the specified section.

Parameters

 $i \mid \text{section index (from 0)}$

Returns

RVA of section, or -1 if invalid

static uint32_t getSectionVirtualSize (unsigned i) [static] Return the virtual size of the specified section.

Parameters

 $i \mid \text{section index (from 0)}$

Returns

VSZ of section, or -1 if invalid

static uint32_t getVirtualEntryPoint (void) [static] The address of the EntryPoint. Use this for matching EP against sections.

Returns

virtual address of EntryPoint, or 0 if not in PE hook

static force_inline bool has ExeInfo (void) [static] Returns whether the current file has executable information.

Returns

true if the file has exe info, false otherwise

static force_inline bool hasPEInfo (void) [static] Returns whether PE information is available

Returns

true if PE information is available (in PE hooks)

static force_inline bool isPE64 (void) [static] Returns whether this is a PE32+ executable.

Returns

true if this is a PE32+ executable

uint32_t pe_rawaddr (uint32_t rva) Converts a RVA (Relative Virtual Address) to an absolute PE file offset.

Parameters

in rva a rva address from the PE file

Returns

absolute file offset mapped to the rva, or PE_INVALID_RVA if the rva is invalid.

static force_inline int read PESectionName (unsigned char name[8], unsigned n) [static] Read name of requested PE section.

Parameters

out	name	name of PE section
in	n	PE section requested

Returns

0 if successful,

<0 otherwise

static force_inline bool readRVA (uint32_t rva, void * buf, size_t bufsize) [static] read the specified amount of bytes from the PE file, starting at the address specified by RVA. Parameters

in	rva	the Relative Virtual Address you want to read from (will be converted
		to file offset)
out	buf	destination buffer
in	bufsize	size of buffer

Returns

true on success (full read) false on any failure

7.1.13. Scan Control

Functions

- uint32_t setvirusname (const uint8_t *name, uint32_t len)
- int32 t extract new (int32 t id)
- int32_t bytecode_rt_error (int32_t locationid)
- int32_t extract_set_container (uint32_t container)
- int32_t input_switch (int32_t extracted_file)
- static force_inline overloadable_func void foundVirus (const char *virusname)

Detailed Description

Function Documentation

int32_t bytecode_rt_error (int32_t locationid) Report a runtime error at the specified locationID.

Parameters

in	$locationid \mid (line << 8) \mid (column \& 0xff)$	
----	---	--

Returns

0

 ${\bf int32_t~extract_new}$ (${\bf int32_t~id}$) Prepares for extracting a new file, if we've already extracted one it scans it.

Parameters

in	id an id for the new file (for example position in container)	
----	---	--

Returns

1 if previous extracted file was infected

 $int32_t\ extract_set_container\ (\ uint32_t\ container\)$ Sets the container type for the currently extracted file.

Parameters

in container container type (CL_TYPE_*)

Returns

current setting for container (CL_TYPE_ANY default)

static force_inline overloadable_func void found Virus (const char * virus name) [static] Sets the specified virus name as the virus detected by this bytecode. Parameters

in	virusname	the name of the virus, excluding the prefix, must be one of the virus-
		names declared in VIRUSNAMES.

See Also

VIRUSNAMES

<code>int32_t input_switch</code> (<code>int32_t extracted_file</code>) Toggles the read/seek API to read from the currently extracted file, and back. You must call seek after switching inputs to position the cursor to a valid position.

Chapter 7. Bytecode API	6
Chapter 7. Bytecode AF1	

Parameters

in	$extracted_file$	1 - switch to reading from extracted file
		0 - switch back to original input

Returns

-1 on error (if no extracted file exists)

0 on success

$uint32_t \ setvirusname \ (\ const \ uint8_t * name, \ uint32_t \ len \)$ Sets the name of the virus found. Parameters

in	name	the name of the virus
in	len	length of the virusname

Returns

0

7.1.14. String Operations

Functions

- int32_t memstr (const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needle-size)
- int32 t hex2ui (uint32 t hex1, uint32 t hex2)
- int32 t atoi (const uint8 t *str, int32 t size)
- uint32_t entropy_buffer (uint8_t *buffer, int32_t size)
- static force_inline void * memchr (const void *s, int c, size_t n)
- void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__((__-nonnull__((1))))
- void * memmove (void *dst, const void *src, uintptr_t n) __attribute__((__nothrow__)) __attribute__((__nonnull__(1
- void void * memcpy (void *restrict dst, const void *restrict src, uintptr_t n) __attribute__((__-nothrow__)) __attribute__((__nonnull__(1
- void void int memcmp (const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow__)) __attribute__((_nonnull__(1

Detailed Description

Function Documentation

 $int32_t$ atoi (const uint8 $_t*str$, $int32_t$ size) Converts string to positive number. Parameters

in	str	buffer
in	size	size of str

Returns

>0 string converted to number if possible, -1 on error

 ${\tt uint32_t\ entropy_buffer}$ (${\tt uint8_t\ *\ buffer}, {\tt int32_t\ size}$) Returns an approximation for the entropy of buffer.

Parameters

in	buffer	input buffer
in	size	size of buffer

Returns

entropy estimation * 2^26

 $int32_t\ hex2ui\ (\ uint32_t\ hex1,\ uint32_t\ hex2\)$ Returns hexadecimal characters hex1 and hex2 converted to 8-bit number.

Parameters

in	hex1	hexadecimal character
in	hex2	hexadecimal character

Returns

hex1 hex2 converted to 8-bit integer, -1 on error

static force_inline void* memchr (const void * s, int c, size_t n) [static] Scan the first n bytes of the buffer s, for the character c.

Parameters

in	s	buffer to scan
in	c	character to look for
in	n	size of buffer

Returns

a pointer to the first byte to match, or NULL if not found.

void void int memcmp (const void * s1, const void * s2, uint32_t n) [LLVM Intrinsic] Compares two memory buffers, s1 and s2 to length n.

Parameters

in	s1	buffer one
in	s2	buffer two
in	n	amount of bytes to copy

Returns

an integer less than, equal to, or greater than zero if the first n bytes of s1 are found, respectively, to be less than, to match, or be greater than the first n bytes of s2.

void void* memcpy (void *restrict dst, const void *restrict src, uintptr_t n) [LLVM Intrinsic] Copies data between two non-overlapping buffers, from src to dst to length n. Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

Returns

dst

Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

Returns

dst

Parameters

out	src	pointer to buffer
in	c	character to fill buffer with
in	n	length of buffer

Returns

src

Parameters

in	haystack	buffer to search
in	hay size	size of haystack
in	needle	substring to search
in	needle size	size of needle

Returns

location of match, -1 otherwise

CHAPTER 8

Copyright and License

8.1. The ClamAV Bytecode Compiler

The ClamAV Bytecode Compiler is released under the GNU General Public License version 2.

The following directories are under the GNU General Public License version 2: ClamBC, docs, driver, editor, examples, ifacegen.

Copyright (C) 2009 Sourcefire, Inc.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License version 2 as published by the Free Software Foundation.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

It uses the LLVM compiler framework, contained in the following directories: llvm, clang. They have this copyright:

LLVM Release License

University of Illinois/NCSA Open Source License

Copyright (c) 2003-2009 University of Illinois at Urbana-Champaign. All rights reserved.

Developed by:

LLVM Team

University of Illinois at Urbana-Champaign

http://llvm.org

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal with the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimers.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimers in the documentation and/or other materials provided with the distribution.

* Neither the names of the LLVM Team, University of Illinois at Urbana-Champaign, nor the names of its contributors may be used to endorse or promote products derived from this Software without specific prior written permission.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

Copyrights and Licenses for Third Party Software Distributed with LLVM:

The LLVM software contains code written by third parties. Such software will have its own individual LICENSE.TXT file in the directory in which it appears.

This file will describe the copyrights, license, and restrictions which apply to that code.

The disclaimer of warranty in the University of Illinois Open Source License applies to all code in the LLVM Distribution, and nothing in any of the other licenses gives permission to use the names of the LLVM Team or the University of Illinois to endorse or promote products derived from this Software.

The following pieces of software have additional or alternate copyrights, licenses, and/or restrictions:

 Program
 Directory

 ---- -----

 Autoconf
 11vm/autoconf

llvm/projects/ModuleMaker/autoconf
llvm/projects/sample/autoconf
llvm/lib/Target/CellSPU/README.txt

CellSPU backend llvm/lib/Target/CellSPU/README.tr
Google Test llvm/utils/unittest/googletest

OpenBSD regex llvm/lib/Support/{reg*, COPYRIGHT.regex}

It also uses re2c, contained in driver/clamdriver/re2c. This code is public domain:

Originally written by Peter Bumbulis (peter@csg.uwaterloo.ca)

Currently maintained by:

- * Dan Nuffer <nuffer@users.sourceforge.net>
- * Marcus Boerger <helly@users.sourceforge.net>
- * Hartmut Kaiser <hkaiser@users.sourceforge.net>

The re2c distribution can be found at:

http://sourceforge.net/projects/re2c/

re2c is distributed with no warranty whatever. The code is certain to contain errors. Neither the author nor any contributor takes responsibility for any consequences of its use.

re2c is in the public domain. The data structures and algorithms used in re2c are all either taken from documents available to the general public or are inventions of the author. Programs generated by re2c may be distributed freely. re2c itself may be distributed freely, in source or binary, unchanged or modified. Distributors may charge whatever fees they can obtain for re2c.

If you do make use of re2c, or incorporate it into a larger project an acknowledgement somewhere (documentation, research report, etc.) would be appreciated.

8.2. Bytecode

The headers used when compiling bytecode have these license (clang/lib/Headers/{bcfeatures,bytecode*}.h):

Copyright (C) 2009 Sourcefire, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The other header files in clang/lib/Headers/ are from clang with this license (see individual files for copyright owner):

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

When using the ClamAV bytecode compiler to compile your own bytecode programs, you can release it under the license of your choice, provided that you comply with the license of the above header files.

70 8.2. Bytecode

APPENDIX A

Low-Level API Globals

A.0.1. Global Variables

Variables

```
• const uint32_t __clambc_match_counts [64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.
```

• const uint32_t __clambc_match_offsets [64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

- const struct cli_pe_hook_data ___clambc_pedata
- \bullet const uint32_t __clambc_filesize [1]
- \bullet const uint16_t __clambc_kind

Detailed Description

Variable Documentation

```
\mathbf{const}\ \mathbf{uint32\_t}\ \underline{\hspace{1.5cm}}\mathbf{clambc\_filesize[1]}\quad \mathrm{File}\ \mathrm{size}\ (\mathrm{max}\ 4\mathrm{G}).
```

const uint16_t ___clambc_kind Kind of the bytecode, affects LibClamAV usage

 ${\color{blue} const\ uint 32_t\ __clambc_match_counts} [64] \quad {\color{blue} This\ is\ a\ low-level\ variable,\ use\ the\ Macros\ in\ bytecode_local.h\ instead\ to\ access\ it.}$

Logical signature match counts

 $const\ uint32_t\ __clambc_match_offsets[64]$ This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Logical signature match offsets

const struct cli_pe_hook_data ___clambc_pedata PE data, if this is a PE hook.

APPENDIX B

Low-Level API Structures

B.0.2. cli_exe_info Struct Reference

Data Fields

- struct cli $_$ exe $_$ section * section
- uint32 t offset
- $uint32_t ep$
- uint16_t nsections
- uint32_t res_addr
- uint32_t hdr_size

Detailed Description

Executable file information

Field Documentation

```
uint32_t ep Entrypoint of executable
```

```
uint32_t hdr_size Address size - PE ONLY
```

uint16_t nsections Number of sections

uint32_t offset Offset where this executable start in file (nonzero if embedded)

uint32_t res_addr Resrources RVA - PE ONLY

struct cli_exe_section* section Information about all the sections of this file. This array has nsection elements

B.0.3. DIS fixed Struct Reference

- enum X86OPS x86_opcode
- enum DIS_SIZE operation_size
- enum DIS_SIZE address_size
- uint8_t segment
- struct DIS_arg arg [3]

Disassembled instruction.

Field Documentation

enum DIS_SIZE address_size size of address

struct DIS_arg arg[3] arguments

enum DIS_SIZE operation_size size of operation

uint8_t segment segment

enum X86OPS x86_opcode opcode of X86 instruction

B.0.4. pe_image_data_dir Struct Reference

Detailed Description

PE data directory header

B.0.5. DIS_arg Struct Reference

Data Fields

- enum DIS_ACCESS access_type
- $\bullet \;\; {\rm enum} \; {\rm DIS_SIZE} \; {\rm access_size}$
- struct DIS_mem_arg mem
- enum X86REGS reg
- uint64_t other

Detailed Description

Disassembled operand.

Field Documentation

 $\mathbf{enum\ DIS_SIZE\ access_size}\quad \mathrm{size\ of\ access}$

enum DIS_ACCESS access_type type of access

 $\mathbf{struct}\ \mathbf{DIS_mem_arg}\ \mathbf{mem}\quad \mathbf{memory}\ \mathbf{operand}$

uint64_t other operand

enum X86REGS reg register operand

B.0.6. pe_image_optional_hdr64 Struct Reference

- $\bullet \quad uint8_t \ {\rm MajorLinkerVersion}$
- uint8 t MinorLinkerVersion
- uint32 t SizeOfCode
- uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- uint64 t ImageBase
- $\bullet \ \ uint 32_t \ Section Alignment$

- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32 t CheckSum
- uint32 t NumberOfRvaAndSizes

PE 64-bit optional header

Field Documentation

uint32_t CheckSum NT drivers only

uint32_t FileAlignment usually 32 or 512

uint64_t ImageBase multiple of 64 KB

uint16_t MajorImageVersion unreliable

 ${\bf uint 8_t\ Major Linker Version}\quad {\bf unreliable}$

uint16_t MajorOperatingSystemVersion not used

uint16_t MinorImageVersion unreliable

uint8_t MinorLinkerVersion unreliable

uint16_t MinorOperatingSystemVersion not used

 $uint 32_t\ Number Of Rva And Sizes \quad unreliable$

uint32_t SectionAlignment usually 32 or 4096

uint32_t SizeOfCode unreliable

 ${\bf uint 32_t~Size Of Initialized Data} \quad {\bf unreliable}$

 $uint32_t$ SizeOfUninitializedData unreliable

B.0.7. cli_exe_info Struct Reference

- $\bullet \ \ struct \ cli_exe_section * section$
- $\bullet \ \ uint 32_t \ offset$
- uint32_t ep
- uint16_t nsections
- $uint32_t res_addr$
- uint32 t hdr size

Executable file information

Field Documentation

uint32_t ep Entrypoint of executable

uint32_t hdr_size Address size - PE ONLY

uint16_t nsections Number of sections

uint32_t offset Offset where this executable start in file (nonzero if embedded)

uint32_t res_addr Resrources RVA - PE ONLY

struct cli_exe_section* section Information about all the sections of this file. This array has nsection elements

B.0.8. pe_image_section_hdr Struct Reference

Data Fields

- uint8_t Name [8]
- uint32 t SizeOfRawData
- uint32_t PointerToRawData
- uint32 t PointerToRelocations
- uint32_t PointerToLinenumbers
- uint16 t NumberOfRelocations
- uint16 t NumberOfLinenumbers

Detailed Description

PE section header

Field Documentation

uint8_t Name[8] may not end with NULL

uint16_t NumberOfLinenumbers object files only

uint16_t NumberOfRelocations object files only

uint32_t PointerToLinenumbers object files only

uint32_t PointerToRawData offset to the section's data

 ${\bf uint 32_t\ Pointer To Relocations}\quad {\bf object\ files\ only}$

${\bf uint 32_t~Size Of Raw Data} \quad {\bf multiple~of~File Alignment}$

B.0.9. cli_pe_hook_data Struct Reference

Data Fields

- uint32_t ep
- uint16_t nsections
- struct pe_image_file_hdr file_hdr
- struct pe_image_optional_hdr32 opt32
- $\bullet \ \ \mathbf{struct} \ \ \mathbf{pe_image_optional_hdr} \mathbf{64} \ \ \mathbf{opt} \mathbf{64}$
- struct pe_image_data_dir dirs [16]
- uint32_t e_lfanew
- uint32 t overlays
- int32_t overlays_sz
- uint32 t hdr size

Detailed Description

Data for the bytecode PE hook

Field Documentation

```
struct pe_image_data_dir dirs[16] PE data directory header
uint32_t e_lfanew address of new exe header
uint32_t ep EntryPoint as file offset
```

struct pe_image_file_hdr file_hdr Header for this PE file

uint32_t hdr_size internally needed by rawaddr

uint16_t nsections Number of sections

struct pe_image_optional_hdr32 opt32 32-bit PE optional header

struct pe_image_optional_hdr64 opt64 64-bit PE optional header

uint32_t overlays number of overlays

int32_t overlays_sz size of overlays

B.0.10. cli_exe_section Struct Reference

- uint32 t rva
- $uint32_t vsz$
- uint32 t raw
- uint32_t rsz
- $uint32_t chr$
- uint32_t urva
- \bullet uint32_t uvsz
- uint32 t uraw
- uint32_t ursz

Section of executable file.

Field Documentation

```
uint32_t chr Section characteristics
```

uint32_t raw Raw offset (in file)

uint32_t rsz Raw size (in file)

uint32_t rva Relative VirtualAddress

uint32_t uraw PE - unaligned PointerToRawData

uint32_t ursz PE - unaligned SizeOfRawData

uint32_t urva PE - unaligned VirtualAddress

uint32_t uvsz PE - unaligned VirtualSize

 $uint32_t vsz$ VirtualSize

B.0.11. pe_image_file_hdr Struct Reference

Data Fields

- uint32 t Magic
- $uint16_t$ Machine
- uint16 t NumberOfSections
- uint32_t TimeDateStamp
- uint32_t PointerToSymbolTable
- uint32 t NumberOfSymbols
- uint16_t SizeOfOptionalHeader

Detailed Description

Header for this PE file

Field Documentation

uint16_t Machine CPU this executable runs on, see libclamav/pe.c for possible values

uint32_t Magic PE magic header: $PE \setminus 0 \setminus 0$

uint16_t NumberOfSections Number of sections in this executable

uint32_t NumberOfSymbols debug

 $uint32_t$ PointerToSymbolTable debug

uint16_t SizeOfOptionalHeader == 224

uint32_t TimeDateStamp Unreliable

B.0.12. pe_image_optional_hdr32 Struct Reference

Data Fields

- uint8 t MajorLinkerVersion
- uint8_t MinorLinkerVersion
- uint32_t SizeOfCode
- uint32 t SizeOfInitializedData
- \bullet uint32_t SizeOfUninitializedData
- uint32 t ImageBase
- uint32_t SectionAlignment
- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- $\bullet \ \ uint16_t \ Minor Operating System Version$
- uint16 t MajorImageVersion
- uint16 t MinorImageVersion
- uint32_t CheckSum
- uint32 t NumberOfRvaAndSizes

Detailed Description

32-bit PE optional header

Field Documentation

uint32_t CheckSum NT drivers only

uint32_t FileAlignment usually 32 or 512

uint32_t ImageBase multiple of 64 KB

uint16_t MajorImageVersion unreliable

uint8_t MajorLinkerVersion unreliable

uint16_t MajorOperatingSystemVersion not used

 $uint16_t\ MinorImageVersion$ unreliable

uint8_t MinorLinkerVersion unreliable

 ${\bf uint 16_t\ Minor Operating System Version}\quad {\bf not\ used}$

 $uint32_t NumberOfRvaAndSizes$ unreliable

uint32_t SectionAlignment usually 32 or 4096

 $uint32_t$ SizeOfCode unreliable

uint32_t SizeOfInitializedData unreliable

 $uint32_t$ SizeOfUninitializedData unreliable

B.0.13. DIS_mem_arg Struct Reference

Data Fields

- enum DIS_SIZE access_size
- enum X86REGS scale reg
- enum X86REGS add_reg
- $uint8_t$ scale
- int32_t displacement

Detailed Description

Disassembled memory operand: scale_reg*scale + add_reg + displacement.

Field Documentation

enum DIS_SIZE access_size size of access

enum X86REGS add_reg register used as displacemenet

int32_t displacement displacement as immediate number

 $uint8_t$ scale as immediate number

enum X86REGS scale_reg register used as scale

B.0.14. DISASM_RESULT Struct Reference

Detailed Description

disassembly result, 64-byte, matched by type-8 signatures

API Headers

C.0.15. File List
Here is a list of all documented files with brief descriptions: bytecode_api.h bytecode_disasm.h bytecode_execs.h bytecode_local.h bytecode_pe.h
C.0.16. bytecode_api.h File Reference
Enumerations
 enum BytecodeKind { BC_GENERIC =0, BC_STARTUP =1, BC_LOGICAL =256, BC_PE_UNPACKER, BC_PDF, BC_PE_ALL } enum { PE_INVALID_RVA = 0xFFFFFFFF } enum FunctionalityLevels { FUNC_LEVEL_096 = 51, FUNC_LEVEL_096_1 = 53, FUNC_LEVEL_096_2 = 54, FUNC_LEVEL_096_3 = 55, FUNC_LEVEL_096_4 = 56, FUNC_LEVEL_096_5 = 58, FUNC_LEVEL_097 = 60, FUNC_LEVEL_097_1 = 61, FUNC_LEVEL_097_2 = 62, FUNC_LEVEL_097_3 = 63, FUNC_LEVEL_097_4 = 64, FUNC_LEVEL_097_5 = 65, FUNC_LEVEL_097_6 = 67, FUNC_LEVEL_097_7 = 68, FUNC_LEVEL_097_8 = 69, FUNC_LEVEL_098_1 = 76, FUNC_LEVEL_098_2 = 77, FUNC_LEVEL_098_3 = 77, FUNC_LEVEL_098_4 = 78 } enum pdf_phase { , PDF_PHASE_PARSED, PDF_PHASE_POSTDUMP, PDF_PHASE_EN_PDF_PHASE_PRE } enum pdf_dag enum pdf_objflags enum bc_json_type enum { SEEK_SET =0, SEEK_CUR, SEEK_END }
Functions
 uint32_t test1 (uint32_t a, uint32_t b) int32_t read (uint8_t *data, int32_t size) int32_t write (uint8_t *data, int32_t size) int32_t seek (int32_t pos, uint32_t whence) uint32_t setvirusname (const uint8_t *name, uint32_t len) uint32_t debug_print_str (const uint8_t *str, uint32_t len) uint32_t debug_print_uint (uint32_t a) uint32_t disasm_x86 (struct DISASM_RESULT *result, uint32_t len) uint32_t pe_rawaddr (uint32_t rva)

```
• int32 t file find (const uint8 t *data, uint32 t len)
• int32 t file byteat (uint32 t offset)
• void * malloc (uint32 t size)
• uint32_t test2 (uint32_t a)
• int32 t get pe section (struct cli exe section *section, uint32 t num)
• int32 t fill buffer (uint8 t *buffer, uint32 t len, uint32 t filled, uint32 t cursor, uint32 t fill)
• int32_t extract_new (int32_t id)
• int32 t read number (uint32 t radix)
• int32_t hashset_new (void)
• int32_t hashset_add (int32_t hs, uint32_t key)
• int32 t hashset remove (int32 t hs, uint32 t key)
• int32_t hashset_contains (int32_t hs, uint32_t key)
• int32 t hashset done (int32 t id)
• int32 t hashset empty (int32 t id)
• int32_t buffer_pipe_new (uint32_t size)
• int32 t buffer pipe new fromfile (uint32 t pos)
• uint32 t buffer pipe read avail (int32 t id)
• const uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)
• int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)
• uint32_t buffer_pipe_write_avail (int32_t id)
• uint8 t * buffer pipe write get (int32 t id, uint32 t size)
• int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)
• int32 t buffer pipe done (int32 t id)
• int32 t inflate init (int32 t from buffer, int32 t to buffer, int32 t windowBits)
• int32_t inflate_process (int32_t id)
• int32_t inflate_done (int32_t id)
• int32 t bytecode rt error (int32 t locationid)
• int32_t jsnorm_init (int32_t from_buffer)
• int32 t jsnorm process (int32 t id)
• int32_t jsnorm_done (int32_t id)
• int32_t ilog2 (uint32_t a, uint32_t b)
• int32 t ipow (int32 t a, int32 t b, int32 t c)
• uint32_t iexp (int32_t a, int32_t b, int32_t c)
• int32_t isin (int32_t a, int32_t b, int32_t c)
• int32 t icos (int32 t a, int32 t b, int32 t c)
• int32_t memstr (const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needle-
• int32_t hex2ui (uint32_t hex1, uint32_t hex2)
• int32 t atoi (const uint8 t *str, int32 t size)
• uint32_t debug_print_str_start (const uint8_t *str, uint32_t len)
• uint32_t debug_print_str_nonl (const uint8_t *str, uint32_t len)
• uint32 t entropy buffer (uint8 t *buffer, int32 t size)
• int32 t map new (int32 t keysize, int32 t valuesize)
• int32 t map addkey (const uint8 t *key, int32 t ksize, int32 t id)
• int32_t map_setvalue (const uint8_t *value, int32_t vsize, int32_t id)
• int32_t map_remove (const uint8_t *key, int32_t ksize, int32_t id)
• int32_t map_find (const uint8_t *key, int32_t ksize, int32_t id)
• int32 t map getvaluesize (int32 t id)
• uint8_t * map_getvalue (int32_t id, int32_t size)
• int32 t map done (int32 t id)
• int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)
• uint32_t engine_functionality_level (void)
• uint32 t engine dconf level (void)
```

• uint32_t engine_scan_options (void)

Appendix C. API Headers

```
• uint32_t engine_db_options (void)
```

- int32 t extract set container (uint32 t container)
- int32 t input switch (int32 t extracted file)
- uint32_t get_environment (struct cli_environment *env, uint32_t len)
- uint32_t disable_bytecode_if (const int8_t *reason, uint32_t len, uint32_t cond)
- uint32_t disable_jit_if (const int8_t *reason, uint32_t len, uint32_t cond)
- int32_t version_compare (const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_t rhs_len)
- uint32 t check platform (uint32 t a, uint32 t b, uint32 t c)
- int32_t pdf_get_obj_num (void)
- int32_t pdf_get_flags (void)
- int32_t pdf_set_flags (int32_t flags)
- int32_t pdf_lookupobj (uint32_t id)
- uint32_t pdf_getobjsize (int32_t objidx)
- const uint8_t * pdf_getobj (int32_t objidx, uint32_t amount)
- int32_t pdf_getobjid (int32_t objidx)
- int32 t pdf getobjflags (int32 t objidx)
- int32 t pdf setobjflags (int32 t objidx, int32 t flags)
- int32_t pdf_get_offset (int32_t objidx)
- int32_t pdf_get_phase (void)
- int32_t pdf_get_dumpedobjid (void)
- int32_t matchicon (const uint8_t *group1, int32_t group1_len, const uint8_t *group2, int32_t group2 len)
- int32_t running_on_jit (void)
- int32_t get_file_reliability (void)
- int32_t json_is_active (void)
- int32_t json_get_object (const int8_t *name, int32_t name_len, int32_t objid)
- int32_t json_get_type (int32_t objid)
- int32 t json get array length (int32 t objid)
- int32_t json_get_array_idx (int32_t idx, int32_t objid)
- int32_t json_get_string_length (int32_t objid)
- int32_t json_get_string (int8_t *str, int32_t str_len, int32_t objid)
- int32_t json_get_boolean (int32_t objid)
- int32 t json get int (int32 t objid)

Variables

- const uint32_t __clambc_match_counts [64]
 - This is a low-level variable, use the Macros in bytecode_local.h instead to access it.
- const uint32_t __clambc_match_offsets [64]
 - This is a low-level variable, use the Macros in bytecode_local.h instead to access it.
- const struct cli_pe_hook_data ___clambc_pedata
- const uint32_t ___clambc_filesize [1]
- const uint16 t clambc kind

Enumeration Type Documentation

anonymous enum

Enumerator

 $PE_INVALID_RVA$ Invalid RVA specified

Function Documentation

 ${\tt uint32_t\ test1\ (\ uint32_t\ a,\ uint32_t\ b\)} \ \ {\tt Test\ api}.$

Parameters

in	a	0xf00dbeef
in	b	0xbeeff00d

Returns

0x12345678 if parameters match, 0x55 otherwise

 $uint32_t test2$ ($uint32_t a$) Test api2.

Parameters

|--|

Returns

0xd00f if parameter matches, 0x5555 otherwise

C.0.17. bytecode_disasm.h File Reference

Data Structures

• struct DISASM_RESULT

Enumerations

```
• enum X86OPS {,
 OP_AAA, OP_AAD, OP_AAM, OP_AAS,
 OP ADD, OP ADC, OP AND, OP ARPL.
 OP BOUND, OP BSF, OP BSR, OP BSWAP,
 OP_BT, OP_BTC, OP_BTR, OP_BTS,
 OP_CALL, OP_CDQ, OP_CWDE, OP_CBW,
 OP_CLC, OP_CLD, OP_CLI, OP_CLTS,
 OP_CMC, OP_CMOVO, OP_CMOVNO, OP_CMOVC,
 OP CMOVNC, OP CMOVZ, OP CMOVNZ, OP CMOVBE,
 OP_CMOVA, OP_CMOVS, OP_CMOVNS, OP_CMOVP,
 OP_CMOVNP, OP_CMOVL, OP_CMOVGE, OP_CMOVLE,
 OP_CMOVG, OP_CMP, OP_CMPSD, OP_CMPSW,
 OP_CMPSB, OP_CMPXCHG, OP_CMPXCHG8B, OP_CPUID,
 OP_DAA, OP_DAS, OP_DEC, OP_DIV,
 OP ENTER, OP_FWAIT, OP_HLT, OP_IDIV,
 OP IMUL, OP INC, OP IN, OP INSD,
 OP INSW, OP INSB, OP INT, OP INT3,
 OP_INTO, OP_INVD, OP_INVLPG, OP_IRET,
 OP_JO, OP_JNO, OP_JC, OP_JNC,
 OP_JZ, OP_JNZ, OP_JBE, OP_JA,
 OP_JS, OP_JNS, OP_JP, OP_JNP,
 OP_JL, OP_JGE, OP_JLE, OP_JG,
 OP JMP, OP LAHF, OP LAR, OP LDS,
 OP LES, OP LFS, OP LGS, OP LEA,
 OP LEAVE, OP LGDT, OP LIDT, OP LLDT,
 OP_PREFIX_LOCK, OP_LODSD, OP_LODSW, OP_LODSB,
 OP_LOOP, OP_LOOPE, OP_LOOPNE, OP_JECXZ,
 OP LSL, OP_LSS, OP_LTR, OP_MOV,
 OP_MOVSD, OP_MOVSW, OP_MOVSB, OP_MOVSX,
 OP_MOVZX, OP_MUL, OP_NEG, OP_NOP,
 OP_NOT, OP_OR, OP_OUT, OP_OUTSD,
 OP_OUTSW, OP_OUTSB, OP_PUSH, OP_PUSHAD,
 OP_PUSHFD, OP_POP, OP_POPAD, OP_POPFD,
 OP_RCL, OP_RCR, OP_RDMSR, OP_RDPMC,
 OP_RDTSC, OP_PREFIX_REPE, OP_PREFIX_REPNE, OP_RETF,
 OP_RETN, OP_ROL, OP_ROR, OP_RSM,
 OP_SAHF, OP_SAR, OP_SBB, OP_SCASD,
 OP SCASW, OP SCASB, OP SETO, OP SETNO,
 OP SETC, OP SETNC, OP SETZ, OP SETNZ,
 OP SETBE, OP SETA, OP SETS, OP SETNS,
 OP_SETP, OP_SETNP, OP_SETL, OP_SETGE,
 OP_SETLE, OP_SETG, OP_SGDT, OP_SIDT,
 OP_SHL, OP_SHLD, OP_SHR, OP_SHRD,
 OP_SLDT, OP_STOSD, OP_STOSW, OP_STOSB,
 OP_STR, OP_STC, OP_STD, OP_STI,
 OP_SUB, OP_SYSCALL, OP_SYSENTER, OP_SYSEXIT,
 OP SYSRET, OP TEST, OP UD2, OP VERR,
 OP VERRW, OP_WBINVD, OP_WRMSR, OP_XADD,
 OP_XCHG, OP_XLAT, OP_XOR, OP_FPU,
 OP_F2XM1, OP_FABS, OP_FADD, OP_FADDP,
 OP_FBLD, OP_FBSTP, OP_FCHS, OP_FCLEX,
 OP_FCMOVB, OP_FCMOVBE, OP_FCMOVE, OP_FCMOVNB,
 OP_FCMOVNBE, OP_FCMOVNE, OP_FCMOVNU, OP_FCMOVU,
 OP_FCOM, OP_FCOMI, OP_FCOMIP, OP_FCOMP,
 OP FCOMPP, OP FCOS, OP FDECSTP, OP FDIV,
 OP FDIVP, OP FDIVR, OP FDIVRP, OP FFREE,
 OP FIADD, OP FICOM, OP FICOMP, OP FIDIV,
    FIDIVR, OP FILD, OP FIMUL, OP FINCSTP,
 OP_FINIT, OP_FIST, OP_FISTP, OP_FISTTP,
 OP_FISUB, OP_FISUBR, OP_FLD, OP_FLD1,
```

OP_FLDCW, OP_FLDENV, OP_FLDL2E, OP_FLDL2T, OP_FLDLG2, OP_FLDLN2, OP_FLDPI, OP_FLDZ,

```
OP_FYL2XP1 }
   • enum DIS ACCESS {
     ACCESS_NOARG, ACCESS_IMM, ACCESS_REL, ACCESS_REG,
     ACCESS_MEM }
   • enum DIS_SIZE {
     SIZEB, SIZEW, SIZED, SIZEF,
     SIZEQ, SIZET, SIZEPTR }
   • enum X86REGS
Enumeration Type Documentation
enum DIS_ACCESS Access type
Enumerator
    ACCESS_NOARG arg not present
    ACCESS_IMM immediate
    ACCESS\_REL +/-immediate
    ACCESS_REG register
    ACCESS_MEM [memory]
enum DIS_SIZE for mem access, immediate and relative
Enumerator
    SIZEB Byte size access
    SIZEW Word size access
    SIZED Doubleword size access
    SIZEF 6-byte access (seg+reg pair)
    SIZEQ Quadword access
    SIZET 10-byte access
    SIZEPTR ptr
enum X86OPS X86 opcode
Enumerator
    OP\_AAA Ascii Adjust after Addition
    OP_AAD Ascii Adjust AX before Division
    OP_AAM Ascii Adjust AX after Multiply
    OP\_AAS Ascii Adjust AL after Subtraction
    OP ADD Add
    OP_ADC Add with Carry
    OP\_AND Logical And
    OP_ARPL Adjust Requested Privilege Level
    OP_BOUND Check Array Index Against Bounds
    OP\_BSF Bit Scan Forward
    OP\_BSR Bit Scan Reverse
    OP\_BSWAP Byte Swap
    OP\_BT Bit Test
    OP\_BTC Bit Test and Complement
    OP_BTR Bit Test and Reset
```

 OP_BTS Bit Test and Set

- OP CALL Call
- OP CDQ Convert DoubleWord to QuadWord
- OP CWDE Convert Word to DoubleWord
- OP_CBW Convert Byte to Word
- OP_CLC Clear Carry Flag
- OP_CLD Clear Direction Flag
- OP_CLI Clear Interrupt Flag
- OP_CLTS Clear Task-Switched Flag in CR0
- OP_CMC Complement Carry Flag
- OP_CMOVO Conditional Move if Overflow
- *OP_CMOVNO* Conditional Move if Not Overflow
- OP_CMOVC Conditional Move if Carry
- OP_CMOVNC Conditional Move if Not Carry
- OP_CMOVZ Conditional Move if Zero
- OP CMOVNZ Conditional Move if Non-Zero
- OP CMOVBE Conditional Move if Below or Equal
- OP_CMOVA Conditional Move if Above
- OP_CMOVS Conditional Move if Sign
- OP_CMOVNS Conditional Move if Not Sign
- OP_CMOVP Conditional Move if Parity
- OP_CMOVNP Conditional Move if Not Parity
- OP CMOVL Conditional Move if Less
- *OP_CMOVGE* Conditional Move if Greater or Equal
- OP_CMOVLE Conditional Move if Less than or Equal
- *OP_CMOVG* Conditional Move if Greater
- **OP_CMP** Compare
- *OP_CMPSD* Compare String DoubleWord
- OP_CMPSW Compare String Word
- OP_CMPSB Compare String Byte
- *OP_CMPXCHG* Compare and Exchange
- $OP_CMPXCHG8B$ Compare and Exchange Bytes
- OP_CPUID CPU Identification
- OP_DAA Decimal Adjust AL after Addition
- OP_DAS Decimal Adjust AL after Subtraction
- OP_DEC Decrement by 1
- OP_DIV Unsigned Divide
- *OP ENTER* Make Stack Frame for Procedure Parameters
- OP_FWAIT Wait
- OP_HLT Halt
- OP_IDIV Signed Divide
- **OP_IMUL** Signed Multiply
- **OP_INC** Increment by 1
- **OP_IN** INput from port
- OP_INSD INput from port to String Doubleword
- OP_INSW INput from port to String Word

- *OP_INSB* INput from port to String Byte
- OP_INT INTerrupt
- OP_INT3 INTerrupt 3 (breakpoint)
- **OP_INTO** INTerrupt 4 if Overflow
- OP_INVD Invalidate Internal Caches
- OP_INVLPG Invalidate TLB Entry
- OP_IRET Interrupt Return
- **OP_JO** Jump if Overflow
- **OP JNO** Jump if Not Overflow
- **OP_JC** Jump if Carry
- **OP_JNC** Jump if Not Carry
- OP_JZ Jump if Zero
- OP_JNZ Jump if Not Zero
- OP_JBE Jump if Below or Equal
- OP_JA Jump if Above
- OP_JS Jump if Sign
- OP_JNS Jump if Not Sign
- **OP_JP** Jump if Parity
- **OP_JNP** Jump if Not Parity
- OP_JL Jump if Less
- **OP_JGE** Jump if Greater or Equal
- OP_JLE Jump if Less or Equal
- **OP JG** Jump if Greater
- **OP_JMP** Jump (unconditional)
- OP_LAHF Load Status Flags into AH Register
- OP_LAR load Access Rights Byte
- OP_LDS Load Far Pointer into DS
- OP_LES Load Far Pointer into ES
- OP_LFS Load Far Pointer into FS
- *OP_LGS* Load Far Pointer into GS
- OP_LEA Load Effective Address
- **OP_LEAVE** High Level Procedure Exit
- OP_LGDT Load Global Descript Table Register
- OP_LIDT Load Interrupt Descriptor Table Register
- OP_LLDT Load Local Descriptor Table Register
- OP_PREFIX_LOCK Assert LOCK# Signal Prefix
- OP_LODSD Load String Dword
- OP_LODSW Load String Word
- OP_LODSB Load String Byte
- OP_LOOP Loop According to ECX Counter
- *OP_LOOPE* Loop According to ECX Counter and ZF=1
- *OP_LOOPNE* Looop According to ECX Counter and ZF=0
- OP_JECXZ Jump if ECX is Zero
- *OP_LSL* Load Segment Limit
- OP_LSS Load Far Pointer into SS

- OP_LTR Load Task Register
- **OP MOV** Move
- OP_MOVSD Move Data from String to String Doubleword
- OP_MOVSW Move Data from String to String Word
- OP_MOVSB Move Data from String to String Byte
- *OP_MOVSX* Move with Sign-Extension
- OP_MOVZX Move with Zero-Extension
- **OP_MUL** Unsigned Multiply
- **OP NEG** Two's Complement Negation
- OP_NOP No Operation
- **OP_NOT** One's Complement Negation
- OP_OR Logical Inclusive OR
- OP_OUT Output to Port
- OP_OUTSD Output String to Port Doubleword
- OP_OUTSW Output String to Port Word
- OP_OUTSB Output String to Port Bytes
- OP_PUSH Push Onto the Stack
- OP_PUSHAD Push All Double General Purpose Registers
- OP_PUSHFD Push EFLAGS Register onto the Stack
- **OP_POP** Pop a Value from the Stack
- *OP_POPAD* Pop All Double General Purpose Registers from the Stack
- OP_POPFD Pop Stack into EFLAGS Register
- OP RCL Rotate Carry Left
- OP_RCR Rotate Carry Right
- *OP_RDMSR* Read from Model Specific Register
- OP_RDPMC Read Performance Monitoring Counters
- OP_RDTSC Read Time-Stamp Coutner
- OP_PREFIX_REPE Repeat String Operation Prefix while Equal
- OP_PREFIX_REPNE Repeat String Operation Prefix while Not Equal
- **OP_RETF** Return from Far Procedure
- OP RETN Return from Near Procedure
- OP_ROL Rotate Left
- OP_ROR Rotate Right
- OP_RSM Resumse from System Management Mode
- OP_SAHF Store AH into Flags
- OP SAR Shift Arithmetic Right
- OP SBB Subtract with Borrow
- OP_SCASD Scan String Doubleword
- OP_SCASW Scan String Word
- OP_SCASB Scan String Byte
- **OP_SETO** Set Byte on Overflow
- **OP_SETNO** Set Byte on Not Overflow
- OP_SETC Set Byte on Carry
- OP_SETNC Set Byte on Not Carry
- OP_SETZ Set Byte on Zero

- OP_SETNZ Set Byte on Not Zero
- **OP_SETBE** Set Byte on Below or Equal
- **OP_SETA** Set Byte on Above
- **OP_SETS** Set Byte on Sign
- OP_SETNS Set Byte on Not Sign
- **OP_SETP** Set Byte on Parity
- OP_SETNP Set Byte on Not Parity
- OP_SETL Set Byte on Less
- OP SETGE Set Byte on Greater or Equal
- OP_SETLE Set Byte on Less or Equal
- **OP_SETG** Set Byte on Greater
- OP_SGDT Store Global Descriptor Table Register
- OP_SIDT Store Interrupt Descriptor Table Register
- OP_SHL Shift Left
- OP SHLD Double Precision Shift Left
- OP SHR Shift Right
- OP_SHRD Double Precision Shift Right
- OP_SLDT Store Local Descriptor Table Register
- OP_STOSD Store String Doubleword
- OP_STOSW Store String Word
- OP_STOSB Store String Byte
- OP_STR Store Task Register
- OP STC Set Carry Flag
- OP_STD Set Direction Flag
- *OP_STI* Set Interrupt Flag
- OP_SUB Subtract
- OP_SYSCALL Fast System Call
- OP_SYSENTER Fast System Call
- OP_SYSEXIT Fast Return from Fast System Call
- OP_SYSRET Return from Fast System Call
- OP_TEST Logical Compare
- OP_UD2 Undefined Instruction
- *OP_VERR* Verify a Segment for Reading
- OP_VERRW Verify a Segment for Writing
- OP_WRMSR Write to Model Specific Register
- **OP_XADD** Exchange and Add
- *OP_XCHG* Exchange Register/Memory with Register
- OP_XLAT Table Look-up Translation
- OP_XOR Logical Exclusive OR
- OP_FPU FPU operation
- OP_F2XM1 Compute 2x-1
- OP_FABS Absolute Value
- OP_FADD Floating Point Add
- OP_FADDP Floating Point Add, Pop

- OP_FBLD Load Binary Coded Decimal
- *OP_FBSTP* Store BCD Integer and Pop
- **OP_FCHS** Change Sign
- OP_FCLEX Clear Exceptions
- *OP_FCMOVB* Floating Point Move on Below
- OP_FCMOVBE Floating Point Move on Below or Equal
- OP_FCMOVE Floating Point Move on Equal
- OP_FCMOVNB Floating Point Move on Not Below
- OP_FCMOVNBE Floating Point Move on Not Below or Equal
- OP_FCMOVNE Floating Point Move on Not Equal
- $OP_FCMOVNU$ Floating Point Move on Not Unordered
- OP_FCMOVU Floating Point Move on Unordered
- **OP_FCOM** Compare Floating Pointer Values and Set FPU Flags
- *OP_FCOMI* Compare Floating Pointer Values and Set EFLAGS
- OP_FCOMIP Compare Floating Pointer Values and Set EFLAGS, Pop
- OP FCOMP Compare Floating Pointer Values and Set FPU Flags, Pop
- OP_FCOMPP Compare Floating Pointer Values and Set FPU Flags, Pop Twice
- OP_FCOS Cosine
- OP_FDECSTP Decrement Stack Top Pointer
- **OP_FDIV** Floating Point Divide
- OP_FDIVP Floating Point Divide, Pop
- OP_FDIVR Floating Point Reverse Divide
- *OP_FDIVRP* Floating Point Reverse Divide, Pop
- OP_FFREE Free Floating Point Register
- **OP_FIADD** Floating Point Add
- OP_FICOM Compare Integer
- *OP_FICOMP* Compare Integer, Pop
- OP_FIDIV Floating Point Divide by Integer
- OP_FIDIVR Floating Point Reverse Divide by Integer
- *OP_FILD* Load Integer
- OP_FIMUL Floating Point Multiply with Integer
- OP_FINCSTP Increment Stack-Top Pointer
- **OP_FINIT** Initialize Floating-Point Unit
- OP_FIST Store Integer
- OP_FISTP Store Integer, Pop
- OP_FISTTP Store Integer with Truncation
- *OP_FISUB* Floating Point Integer Subtract
- OP_FISUBR Floating Point Reverse Integer Subtract
- OP_FLD Load Floating Point Value
- OP_FLD1 Load Constant 1
- OP_FLDCW Load x87 FPU Control Word
- OP_FLDENV Load x87 FPU Environment
- OP_FLDL2E Load Constant log_2(e)
- OP_FLDL2T Load Constant log_2(10)
- OP_FLDLG2 Load Constant log 10(2)

```
OP_FLDLN2 Load Constant log_e(2)OP_FLDPI Load Constant PI
```

OP_FLDZ Load Constant Zero

OI_IBBZ Load Constant Zero

OP_FMUL Floating Point MultiplyOP FMULP Floating Point Multiply, Pop

OP_FNOP No Operation

OP_FPATAN Partial Arctangent

 OP_FPREM Partial Remainder

 OP_FPREM1 Partial Remainder

 OP_FPTAN Partial Tangent

OP_FRNDINT Round to Integer

OP_FRSTOR Restore x86 FPU State

OP_FSCALE Scale

 $OP_FSINCOS$ Sine and Cosine

 OP_FSQRT Square Root

 OP_FSAVE Store x87 FPU State

 OP_FST Store Floating Point Value

OP_FSTCW Store x87 FPU Control Word

OP FSTENV Store x87 FPU Environment

 OP_FSTP Store Floating Point Value, Pop

 OP_FSTSW Store x87 FPU Status Word

OP_FSUB Floating Point Subtract

 OP_FSUBP Floating Point Subtract, Pop

OP_FSUBR Floating Point Reverse Subtract

OP_FSUBRP Floating Point Reverse Subtract, Pop

 OP_FTST Floating Point Test

OP_FUCOM Floating Point Unordered Compare

 OP_FUCOMI Floating Point Unordered Compare with Integer

 $OP_FUCOMIP$ Floating Point Unorder Compare with Integer, Pop

 OP_FUCOMP Floating Point Unorder Compare, Pop

OP_FUCOMPP Floating Point Unorder Compare, Pop Twice

 OP_FXAM Examine ModR/M

OP_FXCH Exchange Register Contents

OP_FXTRACT Extract Exponent and Significand

 OP_FYL2X Compute y*log2x

 $OP_FYL2XP1$ Compute y*log2(x+1)

enum X86REGS X86 registers

C.0.18. bytecode execs.h File Reference

Data Structures

- struct cli_exe_section
- struct cli_exe_info

C.0.19. bytecode_local.h File Reference

Data Structures

```
• struct DIS mem arg
```

- struct DIS arg
- struct DIS fixed

Macros

```
• #define VIRUSNAME_PREFIX(name) const char ___clambc_virusname_prefix[] = name;
```

- #define VIRUSNAMES(...) const char *const ___clambc_virusnames[] = {___VA_ARGS___};
- #define PE_UNPACKER_DECLARE const uint16_t ___clambc_kind = BC_PE_UNPACKER;
- #define PDF_HOOK_DECLARE const uint16_t ___clambc_kind = BC_PDF;
- #define BYTECODE ABORT HOOK 0xcea5e
- #define PE HOOK DECLARE const uint16 t clambc kind = BC PE ALL;
- #define SIGNATURES_DECL_BEGIN struct ___Signatures {
- #define DECLARE_SIGNATURE(name)
- #define SIGNATURES_DECL_END };
- #define TARGET(tgt) const unsigned short ___Target = (tgt);
- #define COPYRIGHT(c) const char *const Copyright = (c);
- #define ICONGROUP1(group) const char *const ___IconGroup1 = (group);
- #define ICONGROUP2(group) const char *const ___IconGroup2 = (group);
- #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m);
- #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m);
- #define SIGNATURES_DEF_BEGIN
- #define SIGNATURES END };
- #define SIGNATURES_DEF_END };

Functions

- static force_inline void overloadable func debug (const char *str)
- static force_inline void
 - overloadable_func debug (const uint8_t *str)
- static force_inline void overloadable_func debug (uint32_t a)
- void debug (...) attribute ((overloadable
- static force_inline uint32_t count_match (___Signature sig)
- static force inline uint32 t matches (Signature sig)
- static force_inline uint32_t match_location (___Signature sig, uint32_t goback)
- static_force_inline int32_t match_location_check (__Signature sig, uint32_t goback, const char *static_start, uint32_t static_len)
- static force inline
 - overloadable_func void foundVirus (const char *virusname)
- static force_inline void
- overloadable func foundVirus (void)
- static force_inline uint32_t getFilesize (void)
- bool <u>is bigendian (void)</u> <u>attribute</u> ((const)) <u>attribute</u> ((nothrow))
- static uint32_t force_inline le32_to_host (uint32_t v)
- static uint32_t force_inline be32_to_host (uint32_t v)
- static uint64_t force_inline le64_to_host (uint64_t v)
- static uint64_t force_inline be64_to_host (uint64_t v)
- static uint16_t force_inline le16_to_host (uint16_t v)
 static uint16_t force_inline be16_to_host (uint16_t v)
- static uint32 t force inline cli readint32 (const void *buff)
- static uint16 t force inline cli readint16 (const void *buff)

```
• static void force inline cli writeint32 (void *offset, uint32 t v)
 static force inline bool has ExeInfo (void)
  static force inline bool hasPEInfo (void)
  static force_inline bool isPE64 (void)
  static force inline uint8 t getPEMajorLinkerVersion (void)
 static force inline uint8 t getPEMinorLinkerVersion (void)
  static force_inline uint32_t getPESizeOfCode (void)
  static force_inline uint32_t getPESizeOfInitializedData (void)
  static force inline uint32 t getPESizeOfUninitializedData (void)
 static force inline uint32 t getPEBaseOfCode (void)
  static force_inline uint32_t getPEBaseOfData (void)
  static force_inline uint64_t getPEImageBase (void)
• static force_inline uint32_t getPESectionAlignment (void)
  static force_inline uint32_t getPEFileAlignment (void)
  static force inline uint16 t getPEMajorOperatingSystemVersion (void)
  static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
  static force inline uint16 t getPEMajorImageVersion (void)
  static force_inline uint16_t getPEMinorImageVersion (void)
  static force inline uint16 t getPEMajorSubsystemVersion (void)
  static force inline uint16 t getPEMinorSubsystemVersion (void)
 static force inline uint32 t getPEWin32VersionValue (void)
  static force inline uint32 t getPESizeOfImage (void)
  static force_inline uint32_t getPESizeOfHeaders (void)
• static force inline uint32 t getPECheckSum (void)
  static force inline uint16 t getPESubsystem (void)
  static force_inline uint16_t getPEDllCharacteristics (void)
  static force_inline uint32_t getPESizeOfStackReserve (void)
  static force inline uint32 t getPESizeOfStackCommit (void)
  static force inline uint32 t getPESizeOfHeapReserve (void)
  static force_inline uint32_t getPESizeOfHeapCommit (void)
  static force inline uint32 t getPELoaderFlags (void)
  static force_inline uint16_t getPEMachine ()
  static force inline uint32 t getPETimeDateStamp ()
  static force inline uint32 t getPEPointerToSymbolTable ()
• static force inline uint32 t getPENumberOfSymbols ()
  static force_inline uint16_t getPESizeOfOptionalHeader ()
  static force_inline uint16_t getPECharacteristics ()
 static force inline bool getPEisDLL ()
  static force inline uint32 t getPEDataDirRVA (unsigned n)
  static force inline uint32 t getPEDataDirSize (unsigned n)
  static force_inline uint16_t getNumberOfSections (void)
  static uint32 t getPELFANew (void)
  static force inline int readPESectionName (unsigned char name[8], unsigned n)
  static force inline uint32 t getEntryPoint (void)
 static force_inline uint32_t getExeOffset (void)
• static force inline uint32 t getImageBase (void)
  static uint32_t getVirtualEntryPoint (void)
  static uint32_t getSectionRVA (unsigned i)
• static uint32 t getSectionVirtualSize (unsigned i)
  static force inline bool readRVA (uint32 t rva, void *buf, size t bufsize)
  static force_inline void * memchr (const void *s, int c, size_t n)
```

 $\operatorname{nonnull}_{--}((1)))$

void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__((__-

- void * memmove (void *dst, const void *src, uintptr_t n) __attribute__((__nothrow__)) __attribute__((__nonnull__(1
- void void int memcmp (const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow__)) __attribute__((__nonnull__(1
- static force_inline uint32_t DisassembleAt (struct DIS_fixed *result, uint32_t offset, uint32_t len)
- static int32 t ilog2 compat (uint32 t a, uint32 t b)

Macro Definition Documentation

#define BYTECODE_ABORT_HOOK 0xcea5e entrypoint() return code that tells hook invoker that it should skip executing, probably because it'd trigger a bug in it

#define SIGNATURES_END }; Old macro used to mark the end of the subsignature pattern definitions.

Function Documentation

 $\begin{tabular}{ll} static force_inline\ void\ overloadable_func\ foundVirus\ (\ void\)\ [static] \ Like\ foundVirus\ ()\ but\ just\ use\ the\ prefix\ as\ virusname \end{tabular}$

static int32_t ilog2_compat (uint32_t a, uint32_t b) [inline], [static] ilog2_compat for 0.96 compatibility, you should use ilog2() 0.96.1 API instead of this one!

Parameters

a	input
b	input

Returns

 2^{2} $4 \cdot \log 2(a/b)$

C.0.20. bytecode_pe.h File Reference

Data Structures

- struct pe_image_file_hdr
- struct pe_image_data_dir
- struct pe_image_optional_hdr32
- $struct pe_image_optional_hdr64$
- struct pe_image_section_hdr
- struct cli_pe_hook_data

APPENDIX D

Predefined API Macros

```
### DECAL DE
```