

Clam
AV Bytecode Compiler $User\ Manual$

Contents

1	Inst	stallation 1				
	1.1	Requirements	1			
	1.2	Obtaining the ClamAV Bytecode Compiler	2			
	1.3	Building	2			
		1.3.1 Disk space	2			
		1.3.2 Create build directory	2			
	1.4	Testing	3			
	1.5	Installing	3			
		1.5.1 Structure of installed files	3			
2	Tut	orial	5			
	2.1	Short introduction to the bytecode language	5			
			5			
			5			
		2.1.3 Arithmetics	5			
		2.1.4 Functions	5			
		2.1.5 Control flow	5			
		2.1.6 Common functions	5			
	2.2	Writing logical signatures	5			
			6			
		2.2.2 Virusnames	6			
		2.2.3 Patterns	7			
			8			
			0			
		1 0	0			
			0			
	2.3		0			
			2			
		v 1 c 1	4			
	2.4		4			
		9 1	4			
		v 1 0 \				

ii				Conte	nts
		2.4.2 2.4.3 2.4.4 2.4.5 2.4.6	Detecting clam.exe via bytecode		14 15 15 15 15
3	Usa	ge			17
	3.1		ng the compiler		17
	2.2	3.1.1	Compiling C++ files		18
	3.2		ng compiled bytecode		18
		3.2.1	ClamBC		18
		3.2.2	clamscan, clamd		18
	3.3	_	gging bytecode		19
		3.3.1	"printf" style debugging		19
		3.3.2	Single-stepping		19
4	Cla	m 11/ k	oytecode language		21
4	4.1		ences from C99 and GNU C		21
					23
	4.2 Limitations				$\frac{23}{24}$
	4.4	_	<u> </u>		26
	4.4 Headers and runtime environment				20
5	Byt	ecode	security & portability		27
6	Rep	\mathbf{orting}	bugs		29
7	Byt	ecode	АРІ		31
•	7.1		ure types		31
	•	7.1.1	cli_exe_info Struct Reference		31
			7.1.1.1 Detailed Description		31
			7.1.1.2 Member Function Documentation		31
			7.1.1.3 Field Documentation		32
		7.1.2	cli exe section Struct Reference		32
			7.1.2.1 Detailed Description		32
			7.1.2.2 Field Documentation		32
		7.1.3	cli_pe_hook_data Struct Reference		33
			7.1.3.1 Detailed Description		33
			7.1.3.2 Field Documentation		34
		7.1.4	DIS_arg Struct Reference		34
			7.1.4.1 Detailed Description		35
			7 1 4 2 Field Documentation	-	35

Contents			iii
7	1.5	DIS_fixed Struct Reference	35
	1.0	7.1.5.1 Detailed Description	35
		7.1.5.2 Field Documentation	35
7	1.6	DIS_mem_arg Struct Reference	36
	1.0	7.1.6.1 Detailed Description	36
		7.1.6.2 Field Documentation	36
7	1.7	DISASM RESULT Struct Reference	36
	1.,	7.1.7.1 Detailed Description	36
7	1.8	pe_image_data_dir Struct Reference	37
	1.0	7.1.8.1 Detailed Description	37
7	1.9	pe_image_file_hdr Struct Reference	37
• • • • • • • • • • • • • • • • • • • •	1.0	7.1.9.1 Detailed Description	37
		7.1.9.2 Field Documentation	37
7	1.10	pe_image_optional_hdr32 Struct Reference	38
	1.10	7.1.10.1 Detailed Description	38
		7.1.10.2 Field Documentation	38
7	1.11	pe_image_optional_hdr64 Struct Reference	39
	1.11	7.1.11.1 Detailed Description	40
		7.1.11.2 Field Documentation	40
7	1.12	pe_image_section_hdr Struct Reference	41
• • • • • • • • • • • • • • • • • • • •	<u>-</u>	7.1.12.1 Detailed Description	41
		7.1.12.2 Field Documentation	41
7.2 Lo	ow le	evel API	42
	2.1	bytecode_api.h File Reference	42
,,		7.2.1.1 Detailed Description	44
		7.2.1.2 Enumeration Type Documentation	44
		7.2.1.3 Function Documentation	45
		7.2.1.4 Variable Documentation	62
7.	2.2	bytecode_disasm.h File Reference	62
		7.2.2.1 Detailed Description	65
		7.2.2.2 Enumeration Type Documentation	65
7.	2.3	bytecode_execs.h File Reference	75
		7.2.3.1 Detailed Description	75
7.	2.4	bytecode_pe.h File Reference	75
		7.2.4.1 Detailed Description	75
7.3 H	igh le	evel API	75
	3.1	bytecode_local.h File Reference	75
		7.3.1.1 Detailed Description	78
		7.3.1.2 Define Documentation	78
		7.3.1.3 Function Documentation	80

IV	Co	ntents
8	Copyright and License 8.1 The ClamAV Bytecode Compiler	
${f A}$	Predefined macros	95

ClamAV Bytecode Compiler - Internals Manual,

© 2009 Sourcefire, Inc.

Authors: Török Edvin

This document is distributed under the terms of the GNU General Public License v2.

Clam AntiVirus is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

ClamAV and Clam AntiVirus are trademarks of Sourcefire, Inc.

CHAPTER 1 Installation

1.1. Requirements

The ClamAV Bytecode Compiler uses the LLVM compiler framework, thus requires an Operating System where building LLVM is supported:

- FreeBSD/x86
- $Linux/\{x86,x86_64,ppc\}$
- Mac OS $X/\{x86,ppc\}$
- Solaris/sparcv9
- Windows/x86 using mingw32 or Visual Studio

The following packages are required to compile the ClamAV Bytecode Compiler:

- GCC C and C++ compilers (minimum 4.1.3, recommended: 4.3.4 or newer) ¹.
- Perl (version 5.6.0+)
- GNU make (version 3.79+, recommended 3.81)

The following packages are optional, but highly recommended:

• Python (version 2.5.4+?) - for running the tests

¹Note that several versions of GCC have bugs when compiling LLVM, see http://llvm.org/docs/GettingStarted.html#brokengcc for a full list. Also LLVM requires support for atomic builtins for multithreaded mode, which gcc 3.4.x doesn't have

1.2. Obtaining the ClamAV Bytecode Compiler

You can obtain the source code in one of the following ways ¹

- Check out the source code using git native protocol:
 git clone git://git.clamav.net/git/clamav-bytecode-compiler
- Check out the source code using HTTP:
 git clone http://git.clamav.net/git/clamav-bytecode-compiler.git
 You can keep the source code updated using:
 git pull

1.3. Building

1.3.1. Disk space

A minimalistic release build requires 100M of disk space.

Testing the compiler requires a full build, 320M of disk space. A debug build requires significantly more disk space (1.4G for a minimalistic debug build).

Note that this only needed during the build process, once installed only 12M is needed.

1.3.2. Create build directory

Building requires a separate object directory, building in the source directory is not supported. Create a build directory:

```
$ cd clamav-bytecode-compiler && mkdir obj
```

Run configure (you can use any prefix you want, this example uses /usr/local/clamav):

```
$ cd obj && ../llvm/configure --enable-optimized \
   --enable-targets=host-only --disable-bindings \
   --prefix=/usr/local/clamav
```

Run the build under ulimit ²:

\$ (ulimit -t 3600 -v 512000 && make clambc-only -j4)

¹For now the use the internal clamtools repository:

git clone username@git.clam.sourcefire.com:/var/lib/git/clamtools.git

²compiling some files can be very memory intensive, especially with older compilers

1.4. Testing

```
$ (ulimit -t 3600 v 512000 && make -j4)
$ make check-all
```

If make check reports errors, check that your compiler is NOT on this list: http://llvm.org/docs/GettingStarted.html#brokengcc.

If it is, then your compiler is buggy, and you need to do one of the following: upgrade your compiler to a non-buggy version, upgrade the OS to one that has a non-buggy compiler, compile with export OPTMIZE_OPTION=-02, or export OPTIMIZE OPTION=-01, or export OPTIMIZE OPTION=\-01.

If not you probably found a bug, report it at http://bugs.clamav.net

1.5. Installing

Install it:

\$ make install-clambc -j8

1.5.1. Structure of installed files

- 1. The ClamAV Bytecode compiler driver: \$PREFIX/bin/clambc-compiler
- 2. ClamAV bytecode header files:

```
$PREFIX/lib/clang/1.1/include:
bcfeatures.h
bytecode_{api_decl.c,api,disasm,execs,features}.h
bytecode.h
bytecode_{local,pe,types}.h
```

3. clang compiler (with ClamAV bytecode backend) compiler include files:

```
$PREFIX/lib/clang/1.1/include:
emmintrin.h
float.h
iso646.h
limits.h
{,p,t,x}mmintrin.h
mm_malloc.h
std{arg,bool,def,int}.h
```

tgmath.h

4 1.5. Installing

4. User manual

\$PREFIX/docs/clamav/clambc-user.pdf

CHAPTER 2 Tutorial

2.1. Short introduction to the bytecode language

2.	.1.	1.	Types.	variables	and	constants
			- ,, P = >,	TOTAL TOTAL		COLLOCALIO

- 2.1.2. Arrays and pointers
- 2.1.3. Arithmetics
- 2.1.4. Functions
- 2.1.5. Control flow
- **2.1.6.** Common functions

2.2. Writing logical signature bytecodes

A bytecode triggered by a logical signature is much more powerful than a logical signature itself: you can write complex algorithmic detections, and use the logical signature as a *filter* (to speed up matching). Thus another name for "logical signature bytecodes" is "algorithmic detection bytecodes". The detection you write in bytecode has read-only access to the file being scanned and its metadata (PE sections, EP, etc.).

¹ Logical signatures can be used as triggers for executing bytecode. However, instead of describing a logical signature as a .ldb pattern, you use (simple) C code which is later translated to a .ldb-style logical signature by the ClamAV Bytecode Compiler.

¹See Section 4.3 for more details about logical signatures in bytecode.

2.2.1. Structure of a bytecode for algorithmic detection

Algorithmic detection bytecodes are triggered when a logical signature matches. They can execute an algorithm that determines whether the file is infected and with which virus.

A bytecode can be either algorithmic or an unpacker (or other hook), but not both.

It consists of:

- Definition of virusnames used in the bytecode
- Pattern definitions (for logical subexpressions)
- The logical signature as C function: bool logical_trigger(void)
- The int entrypoint(void) function which gets executed when the logical signature matches
- (Optional) Other functions and global constants used in entrypoint

The syntax for defining logical signatures, and an example is described in Section 2.2.4.

The function entrypoint must report the detected virus by calling foundVirus and returning 0. It is recommended that you always return 0, otherwise a warning is shown and the file is considered clean. If foundVirus is not called, then ClamAV also assumes the file is clean.

2.2.2. Virusnames

Each logical signature bytecode must have a virusname prefix, and one or more virusnames. The virusname prefix is used by the SI to ensure unique virusnames (a unique number is appended for duplicate prefixes).

Program 1 Declaring virusnames

```
1 /* Prefix, used for duplicate detection and fixing */
VIRUSNAME_PREFIX("Trojan.Foo")
3 /* You are only allowed to set these virusnames as found */
VIRUSNAMES("A", "B")
5 /* File type */
TARGET(2)
```

In Program 1 3 predefied macros are used:

• VIRUSNAME PREFIX which must have exactly one string argument

- VIRUSNAMES which must have one or more string arguments
- TARGET which must have exactly one integer argument

In this example, the bytecode could generate one of these virus-names: Trojan.Foo.A, or Trojan.Foo.B, by calling foundVirus("A") or foundVirus("B") respectively (notice that the prefix is not part of these calls).

2.2.3. Patterns

Logical signatures use .ndb style patterns, an example on how to define these is shown in Program 2.

Program 2 Declaring patterns

```
SIGNATURES_DECL_BEGIN

DECLARE_SIGNATURE(magic)
DECLARE_SIGNATURE(check)

DECLARE_SIGNATURE(zero)
SIGNATURES_DECL_END

SIGNATURES_DEF_BEGIN
DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(check, "f00d")
DEFINE_SIGNATURE(zero, "fffff")
SIGNATURES_END
```

Each pattern has a name (like a variable), and a string that is the hex pattern itself. The declarations are delimited by the macros SIGNATURES_DECL_BEGIN, and SIGNATURES_DECL_END. The definitions are delimited by the macros SIGNATURES_DEF_BEGIN, and SIGNATURES_END. Declarations must always come before definitions, and you can have only one declaration and declaration section! (think of declaration like variable declarations, and definitions as variable assignments, since that what they are under the hood). The order in which you declare the signatures is the order in which they appear in the generated logical signature.

You can use any name for the patterns that is a valid record field name in C, and doesn't conflict with anything else declared.

After using the above macros, the global variable Signatures will have two new fields: magic, and zero. These can be used as arguments to the functions count_match(), and matches() anywhere in the program as shown in Program 3:

- matches(Signatures.match) will return true when the match signature matches (at least once)
- count_match(Signatures.zero) will return the number of times the zero signature matched
- count_match(Signatures.check) will return the number of times the check signature matched

The condition in the if can be interpreted as: if the match signature has matched at least once, and the number of times the zero signature matched is higher than the number of times the check signature matched, then we have found a virus A, otherwise the file is clean.

Program 3 Using patterns

2.2.4. Single subsignature

The simplest logical signature is like a .ndb signature: a virus name, signature target, 0 as logical expression ¹, and a ndb-style pattern.

The code for this is shown in Program 4

The logical signature (created by the compiler) looks like this: Trojan.Foo.{A}; Target:2;0; aabb

Of course you should use a .ldb signature in this case when all the processing in entrypoint is only setting a virusname and returning. However, you can do more complex checks in entrypoint, once the bytecode was triggered by the logical_trigger

In the example in Program 4 the pattern was used without an anchor; such a pattern matches at any offset. You can use offsets though, the same way as in .ndb signatures, see Program 5 for an example.

¹meaning that subexpression 0 must match

Program 4 Single subsignature example

```
/* Declare the prefix of the virusname */
2 VIRUSNAME_PREFIX("Trojan.Foo")
  /* Declare the suffix of the virusname */
4 VIRUSNAMES ("A")
  /* Declare the signature target type (1 = PE) */
6 TARGET (1)
8 /* Declare the name of all subsignatures used */
  SIGNATURES_DECL_BEGIN
10 DECLARE_SIGNATURE(magic)
  SIGNATURES_DECL_END
  /* Define the pattern for each subsignature */
14 SIGNATURES_DEF_BEGIN
  DEFINE_SIGNATURE(magic, "aabb")
16 SIGNATURES_END
18 /* All bytecode triggered by logical signatures must have
     this
     function */
20 bool logical_trigger(void)
    /* return true if the magic subsignature matched,
    * its pattern is defined above to "aabb" */
   return count_match(Signatures.magic) != 2;
  }
26
  /* This is the bytecode function that is actually executed
     when the logical
  * signature matched */
  int entrypoint(void)
30 {
    /* call this function to set the suffix of the virus found
       */
    foundVirus("A");
    /* success, return 0 */
    return 0;
  }
```

2.2.5. Multiple subsignatures

An example for this is shown in Program 5. Here you see the following new features used: ¹

- Multiple virusnames returned from a single bytecode (with common prefix)
- Multiple subsignatures, each with a name of your choice
- A pattern with an anchor (EP+0:aabb)
- More subsignatures defined than used in the logical expression

The logical signature looks like this:

Trojan.Foo. $\{A,B\}$; Target:2; (((0|1|2)=42,2)|(3=10)); EP+0:aabb; fffff; aaccee; f00d; dead

Notice how the subsignature that is not used in the logical expression (number 4, dead) is used in entrypoint to decide the virus name. This works because ClamAV does collect the match counts for all subsignatures (regardless if they are used or not in a signature). The count_match(Signatures.check2) call is thus a simple memory read of the count already determined by ClamAV.

Also notice that comments can be used freely: they are ignored by the compiler. You can use either C-style multiline comments (start comment with /*, end with */), or C++-style single-line comments (start comment with //, automatically ended by newline).

2.2.6. W32.Polipos.A detector rewritten as bytecode

2.2.7. Virut detector in bytecode

2.3. Writing regular expressions in bytecode

ClamAV only supports a limited set of regular expressions in .ndb format: wildcards. The bytecode compiler allows you to compile fully generic regular expressions to bytecode directly. When libclamav loads the bytecode, it will compile to native code (if using the JIT), so it should offer quite good performance.

The compiler currently uses re2c to compile regular expressions to C code, and then compile that to bytecode. The internal workings are all transparent

¹In case of a duplicate virusname the prefix is appended a unique number by the SI

11

Program 5 Multiple subsignatures

```
1 /* You are only allowed to set these virusnames as found */
  VIRUSNAME_PREFIX("Test")
3 VIRUSNAMES ("A", "B")
  TARGET (1)
  SIGNATURES_DECL_BEGIN
7 DECLARE_SIGNATURE(magic)
  DECLARE_SIGNATURE(zero)
9 DECLARE_SIGNATURE (check)
  DECLARE_SIGNATURE(fivetoten)
11 DECLARE_SIGNATURE (check2)
  SIGNATURES_DECL_END
  SIGNATURES_DEF_BEGIN
15 DEFINE_SIGNATURE(magic, "EP+0:aabb")
  DEFINE_SIGNATURE(zero, "ffff")
17 DEFINE_SIGNATURE(fivetoten, "aaccee")
  DEFINE_SIGNATURE(check, "f00d")
19 DEFINE_SIGNATURE(check2, "dead")
  SIGNATURES_END
  bool logical_trigger(void)
23 {
      unsigned sum_matches = count_match(Signatures.magic)+
          count_match(Signatures.zero) +
25
              count_match(Signatures.fivetoten);
      unsigned unique_matches = matches(Signatures.magic)+
              matches(Signatures.zero)+
27
                  matches(Signatures.fivetoten);
      if (sum_matches == 42 && unique_matches == 2) {
          // The above 3 signatures have matched a total of 42
              times, and at least
          // 2 of them have matched
31
          return true;
      // If the check signature matches 10 times we still have
33
         a match
      if (count_match(Signatures.check) == 10)
          return true;
35
      // No match
      return false;
37
  }
  int entrypoint(void)
41 {
      unsigned count = count_match(Signatures.check2);
      if (count >= 2)
          foundVirus(count == 2 ? "A" : "B");
        if (count == 2)
45
          foundVirus("A");
                                 11
47
          foundVirus("B");
      return 0;
49
  }
```

to the user: the compiler automatically uses re2c when needed, and re2c is embedded in the compiler, so you don't need to install it.

The syntax of regular expressions are similar to the one used by POSIX regular expressions, except you have to quote literals, since unquoted they are interpreted as regular expression names.

2.3.1. A very simple regular expression

Lets start with a simple example, to match this POSIX regular expression: $eval([a-zA-Z_] [a-zA-Z0-9_]*\.unescape.$

See Program 6¹.

Program 6 Simple regular expression example

```
int entrypoint(void)
2 {
    REGEX_SCANNER;
    seek(0, SEEK_SET);
    for (;;) {
      REGEX_LOOP_BEGIN
      /*!re2c
8
        ANY = [^];
         "eval ("[a-zA-Z_][a-zA-Z_0-9]*".unescape" {
                          long pos = REGEX_POS;
12
                          if (pos < 0)
                                  continue;
14
                          debug("unescape found at");
                          debug (pos);
16
        ANY { continue; }
18
20
    return 0;
22 }
```

There are several new features introduced here, here is a step by step breakdown:

REGEX_SCANNER this declares the data structures needed by the regular expression matcher

¹This omits the virusname, and logical signature declarations

seek(0, SEEK_SET) this sets the current file offset to position 0, matching will start at this position. For offset 0 it is not strictly necessary to do this, but it serves as a reminder that you might want to start matching somewhere, that is not necessarily 0.

- for(;;) { REGEX_LOOP_BEGIN this creates the regular expression matcher main loop. It takes the current file byte-by-byte ¹ and tries to match one of the regular expressions.
- /*!re2c This mark the beginning of the regular expression description. The entire regular expression block is a C comment, starting with !re2c
- ANY = [^]; This declares a regular expression named ANY that matches any byte.
- "eval("[a-zA-Z_][a-zA-Z_0-9]*".unescape" { This is the actual regular expression.
 - "eval(" This matches the literal string eval(. Literals have to be placed in double quotes " here, unlike in POSIX regular expressions or PCRE. If you want case-insensitive matching, you can use '.
 - [a-zA-Z_] This is a character class, it matches any lowercase, uppercase or _ characters.
 - [a-zA-Z_0-9]*" Same as before, but with repetition. * means match zero or more times, + means match one or more times, just like in POSIX regular expressions.
 - ".unescape" A literal string again
 - { start of the *action* block for this regular expression. Whenever the regular expression matches, the attached C code is executed.
- long pos = REGEX_POS; this determines the absolute file offset where the
 regular expression has matched. Note that because the regular expression matcher uses a buffer, using just seek(0, SEEK_CUR) would
 give the current position of the end of that buffer, and not the current position during regular expression matching. You have to use the
 REGEX_POS macro to get the correct position.
- debug(...) Shows a debug message about what was found and where. This is extremely helpful when you start writing regular expressions, and nothing works: you can determine whether your regular expression

¹it is not really reading byte-by-byte, it is using a buffer to speed things up

matched at all, and if it matched where you thought it would. There is also a DEBUG_PRINT_MATCH that prints the entire matched string to the debug output. Of course before publishing the bytecode you might want to turn off these debug messages.

- } closes the action block for this regular expression
- ANY { continue; } If none of the regular expressions matched so far, just keep running the matcher, at the next byte
- */ closes the regular expression description block
- } closes the for() loop

You may have multiple regular expressions, or declare multiple regular expressions with a name, and use those names to build more complex regular expressions.

2.3.2. Named regular expressions

2.4. Writing unpackers

2.4.1. Structure of a bytecode for unpacking (and other hooks)

When writing an unpacker, the bytecode should consist of:

- Define which hook you use (for example PE_UNPACKER_DECLARE for a PE hook)
- An int entrypoint(void) function that reads the current file and unpacks it to a new file
- Return 0 from entrypoint if you want the unpacked file to be scanned
- (Optional) Other functions and global constants used by entrypoint

2.4.2. Detecting clam.exe via bytecode

Example provided by aCaB:

Chapter 2. Tutorial	15
2.4.3. Detecting clam.exe via bytecode (disasm)	
Example provided by aCaB:	
2.4.4. A simple unpacker	
2.4.5. Matching PDF javascript	
2.4.6. YC unpacker rewritten as bytecode	

CHAPTER 3 Usage

3.1. Invoking the compiler

Compiling is similar to gcc^{-1} :

\$ /usr/local/clamav/bin/clambc-compiler foo.c -o foo.cbc -02

This will compile the file foo.c into a file called foo.cbc, that can be loaded by ClamAV, and packed inside a .cvd file.

The compiler by default has all warnings turned on.

Supported optimization levels: -00, -01, -02, -03. ² It is recommended that you always compile with at least -01.

Warning options: -Werror (transforms all warnings into errors).

Preprocessor flags:

- -I <directory> Searches in the given directory when it encounters a #include "headerfile" directive in the source code, in addition to the system defined header search directories.
- -D <MACRONAME>=<VALUE> Predefine given <MACRONAME> to be equal to <VALUE>.
- -U <MACRONAME> Undefine a predefined macro

The compiler also supports some other commandline options (see clambc-compiler --help for a full list), however some of them have no effect when using the ClamAV bytecode backend (such as the X86 backend options). You shouldn't need to use any flags not documented above.

 $^{^1\}mathrm{Note}$ that the ClamAV by tecode compiler will refuse to compile code it considers in secure

²Currently -O0 doesn't work

3.1.1. Compiling C++ files

Filenames with a .cpp extension are compiled as C++ files, however clang++ is not yet ready for production use, so this is EXPERIMENTAL currently. For now write bytecodes in C.

3.2. Running compiled bytecode

After compiling a C source file to bytecode, you can load it in ClamAV:

3.2.1. ClamBC

ClamBC is a tool you can use to test whether the bytecode loads, compiles, and can execute its entrypoint successfully. Usage:

```
clambc <file> [function] [param1 ...]
```

For example loading a simple bytecode with 2 functions is done like this:

```
$ clambc foo.cbc
```

```
LibClamAV debug: searching for unrar, user-searchpath: /usr/local/lib
```

LibClamAV debug: unrar support loaded from libclamunrar_iface.so.6.0.4 libclamatelement libclamatelement loaded from libclamatelement libclamatelement loaded from libclamatelement libclamatelem

LibClamAV debug: bytecode: Parsed O APIcalls, maxapi O

LibClamAV debug: Parsed 1 BBs, 2 instructions LibClamAV debug: Parsed 1 BBs, 2 instructions

LibClamAV debug: Parsed 2 functions

Bytecode loaded

Running bytecode function :0

Bytecode run finished Bytecode returned: 0x8

Exiting

3.2.2. clamscan, clamd

You can tell clamscan to load the bytecode as a database directly:

\$ clamscan -dfoo.cbc

Or you can instruct it to load all databases from a directory, then clamscan will load all supported formats, including files with bytecode, which have the .cbc extension.

\$ clamscan -ddirectory

You can also put the bytecode files into the default database directory of ClamAV (usually /usr/local/share/clamav) to have it loaded automatically from there. Of course, the bytecode can be stored inside CVD files, too.

3.3. Debugging bytecode

3.3.1. "printf" style debugging

You can use debug_print_str and debug_print_int API calls to print debug messages during the execution of the bytecode.

3.3.2. Single-stepping

If you have GDB 7.0 (or newer) you can single-step $^{1\ 2}$ during the execution of the bytecode.

• Run clambe or clamscan under gdb:

```
$ ./libtool --mode=execute gdb clamscan/clamscan
...
(gdb) b cli_vm_execute_jit
Are you sure ....? y
(gdb) run -dfoo.cbc
...
Breakpoint ....
(gdb) step
(gdb) next
```

You can single-step through the execution of the bytecode, however you can't (yet) print values of individual variables, you'll need to add debug statements in the bytecode to print interesting values.

¹not yet implemented in libclamav

²assuming you have JIT support

CHAPTER 4 ClamAV bytecode language

The bytecode that ClamAV loads is a simplified form of the LLVM Intermediate Representation, and as such it is language-independent.

However currently the only supported language from which such by tecode can be generated is a simplified form of C $^{\rm 1}$

The language supported by the ClamAV bytecode compiler is a restricted set of C99 with some GNU extensions.

4.1. Differences from C99 and GNU C

These restrictions are enforced at compile time:

- No standard include files. ²
- The ClamAV API header files are preincluded.
- No external function calls, except to the ClamAV API ³
- No inline assembly ⁴
- Globals can only be readonly constants ⁵
- inline is C99 inline (equivalent to GNU C89 extern inline), thus it cannot be used outside of the definition of the ClamAV API, you should use static inline

 $^{^{1}\}mathrm{In}$ the future more languages could be supported, see the Internals Manual on language frontends

²For portability reasons: preprocessed C code is not portable

³For safety reasons we can't allow the bytecode to call arbitrary system functions

⁴This is both for safety and portability reasons

⁵For thread safety reasons

- sizeof(int) == 4 always
- sizeof(long) == sizeof(long long) == 8 always
- ptr_diff_t = int, intptr_t = int, intmax_t = long, uintmax t = unsigned long 1
- No pointer to integer casts and integer to pointer casts (pointer arithmetic is allowed though)
- No __thread support
- Size of memory region associated with each pointer must be known in each function, thus if you pass a pointer to a function, you must also pass its allocated size as a parameter.
- Endianness must be handled via the __is_bigendian() API function call, or via the cli_{read,write}int{16,32} wrappers, and not by casting pointers
- Predefines __CLAMBC__
- All integer types have fixed width
- main or entrypoint must have the following prototype: int main(void), the prototype int main(int argc, char *argv[]) is not accepted

They are meant to ensure the following:

- Thread safe execution of multiple different bytecodes, and multiple instances of the same bytecode
- Portability to multiple CPU architectures and OSes: the bytecode must execute on both the libclamav/LLVM JIT where that is supported (x86, x86_64, ppc, arm?), and on the libclamav interpreter where that is not supported.
- No external runtime dependency: libclamav should have everything needed to run the bytecode, thus no external calls are allowed, not even to libc!

¹Note that a pointer's size of is runtime-platform dependent, although at compile time size of (void*) == 4, at runtime it can be something else. Thus you should avoid using size of (pointer)

• Same behaviour on all platforms: fixed size integers.

These restrictions are checked at runtime (checks are inserted at compile time):

- Accessing an out-of-bounds pointer will result in a call to abort()
- Calling abort() interrupts the execution of the bytecode in a thread safe manner, and doesn't halt ClamAV ¹.

The ClamAV API header has further restriction, see the Internals manual. Although the bytecode undergoes a series of automated tests (see Publishing chapter in Internals manual), the above restrictions don't guarantee that the resulting bytecode will execute correctly! You must still test the code yourself, these restrictions only avoid the most common errors. Although the compiler and verifier aims to accept only code that won't crash ClamAV, no code is 100% perfect, and a bug in the verifier could allow unsafe code be executed by ClamAV.

4.2. Limitations

The bytecode format has the following limitations:

- At most 64k bytecode kinds (hooks)
- At most 64k types (including pointers, and all nested types)
- At most 16 parameters to functions, no vararg functions
- At most 64-bit integers
- No vector types or vector operations
- No opaque types
- No floating point
- Global variable initializer must be compile-time computable
- At most 32k global variables (and at most 32k API globals)
- Pointer indexing at most 15 levels deep (can be worked around if needed by using temporaries)

¹in fact it calls a ClamAV API function, and not the libc abort function.

- No struct return or byval parameters
- At most 32k instructions in a single function
- No Variable Length Arrays

4.3. Logical signatures

Logical signatures can be used as triggers for executing a bytecode. Instead of describing a logical signatures as a .ldb pattern, you use C code which is then translated to a .ldb-style logical signature.

Logical signatures in ClamAV support the following operations:

- Sum the count of logical subsignatures that matched inside a subexpression
- Sum the number of different subsignatures that matched inside a subexpression
- Compare the above counts using the >, =, < relation operators
- Perform logical &&, || operations on above boolean values
- Nest subexpressions
- Maximum 64 subexpressions

Out of the above operations the ClamAV Bytecode Compiler doesn't support computing sums of nested subexpressions, (it does support nesting though).

The C code that can be converted into a logical signature must obey these restrictions:

- a function named logical_trigger with the following prototype: bool logical_trigger(void)
- no function calls, except for count match and matches
- no global variable access (except as done by the above 2 functions internally)
- return true when signature should trigger, false otherwise

- use only integer compare instructions, branches, integer add, logical and, logical or, logical xor, zero extension, store/load from local variables
- the final boolean expression must be convertible to disjunctive normal form without negation
- the final logical expression must not have more than 64 subexpressions
- it can have early returns (all true returns are unified using ||)
- you can freely use comments, they are ignored
- the final boolean expression cannot be a true or false constant

The compiler does the following transformations (not necessarily in this order):

- convert shortcircuit boolean operations into non-shortcircuit ones (since all operands are boolean expressions or local variables, it is safe to execute these unconditionally)
- propagate constants
- simplify control flow graph
- (sparse) conditional constant propagation
- dead store elimination
- dead code elimination
- instruction combining (arithmetic simplifications)
- jump threading

If after this transformation the program meets the requirements outlined above, then it is converted to a logical signature. The resulting logical signature is simplified using basic properties of boolean operations, such as associativity, distributivity, De Morgan's law.

The final logical signature is not unique (there might be another logical signature with identical behavior), however the boolean part is in a canonical form: it is in disjunctive normal form, with operands sorted in ascending order.

For best results the C code should consist of:

• local variables declaring the sums you want to use

- a series of if branches that return true, where the if's condition is a single comparison or a logical and of comparisons
- a final return false

You can use || in the if condition too, but be careful that after expanding to disjunctive normal form, the number of subexpressions doesn't exceed 64.

Note that you do not have to use all the subsignatures you declared in logical_trigger, you can do more complicated checks (that wouldn't obey the above restrictions) in the bytecode itself at runtime. The logical_trigger function is fully compiled into a logical signature, it won't be a runtime executed function (hence the restrictions).

4.4. Headers and runtime environment

When compiling a bytecode program, bytecode.h is automatically included, so you don't need to explicitly include it. These headers (and the compiler itself) predefine certain macros, see Appendix A for a full list. In addition the following types are defined:

```
typedef unsigned char uint8_t;
typedef char int8_t;
typedef unsigned short uint16_t;
typedef short int16_t;
typedef unsigned int uint32_t;
typedef int int32_t;
typedef unsigned long uint64_t;
typedef long int64_t;
typedef unsigned int size_t;
typedef struct signature { unsigned id } __Signature;
```

As described in Section 4.1 the width of integer types are fixed, the above typedefs show that.

A bytecode's entrypoint is the function entrypoint and it's required by ClamAV to load the bytecode.

Bytecode that is triggered by a logical signature must have a list of virusnames and patterns defined. Bytecodes triggered via hooks can optionally have them, but for example a PE unpacker doesn't need virus names as it only processes the data.

CHAPTER 5 Bytecode security & portability

CHAPTER 6 Reporting bugs

CHAPTER 7 Bytecode API

7.1. Structure types

7.1.1. cli_exe_info Struct Reference

Public Member Functions

• struct cli_exe_section *section EBOUNDS (nsections)

Data Fields

- uint32_t offset
- uint32_t ep
- uint16_t nsections
- struct cli hashset * vinfo

7.1.1.1 Detailed Description

Executable file information

7.1.1.2. Member Function Documentation

7.1.1.2.1. struct cli_exe_section* section EBOUNDS (nsections) [read] Information about all the sections of this file. This array has nsection elements

7.1. Structure types

7.1.1.3. Field Documentation

7.1.1.3.1. uint32_t ep

Entrypoint of executable

7.1.1.3.2. uint16_t nsections

Number of sections

7.1.1.3.3. uint32_t offset Offset where this executable start in file (nonzero if embedded)

7.1.1.3.4. struct cli_hashset* vinfo Hashset for versioninfo matching

7.1.2. cli exe section Struct Reference

Data Fields

- uint32_t rva
- uint32_t vsz
- uint32_t raw
- uint32 t rsz
- uint32_t chr
- uint32_t urva
- uint32_t uvsz
- uint32_t uraw
- uint32_t ursz

7.1.2.1. Detailed Description

Section of executable file

7.1.2.2. Field Documentation

7.1.2.2.1. uint32_t chr

Section characteristics

7.1.2.2.2. uint32_t raw

Raw offset (in file)

าา

Chamton	7	Bytecode	A DI
Chapter	1.	Dytecode	API

7.1.2.2.3. uint32_t rsz

Raw size (in file)

7.1.2.2.4. uint32_t rva

Relative VirtualAddress

7.1.2.2.5. uint32_t uraw

PE - unaligned PointerToRawData

7.1.2.2.6. uint32_t ursz

PE - unaligned SizeOfRawData

7.1.2.2.7. uint32_t urva

PE - unaligned VirtualAddress

7.1.2.2.8. uint32_t uvsz

PE - unaligned VirtualSize

7.1.2.2.9. uint32_t vsz

VirtualSize

7.1.3. cli_pe_hook_data Struct Reference

Data Fields

- uint32_t ep
- uint16_t nsections
- struct pe_image_file_hdr file_hdr
- struct pe_image_optional_hdr32 opt32
- struct pe_image_optional_hdr64 opt64
- struct pe_image_data_dir dirs [16]
- uint32_t e_lfanew
- uint32_t overlays
- int32_t overlays_sz
- uint32_t hdr_size

7.1.3.1. Detailed Description

Data for the bytecode PE hook

7.1. Structure types

7.1.3.2. Field Documentation

7.1.3.2.1. struct pe_image_data_dir dirs[16] PE data directory header

7.1.3.2.2. uint32_t e_lfanew address of new exe header

7.1.3.2.3. uint32_t ep EntryPoint as file offset

7.1.3.2.4. struct pe_image_file_hdr file_hdr Header for this PE file

7.1.3.2.5. uint32_t hdr_size internally needed by rawaddr

7.1.3.2.6. uint16_t nsections Number of sections

7.1.3.2.7. struct pe_image_optional_hdr32 opt32 32-bit PE optional header

7.1.3.2.8. struct pe_image_optional_hdr64 opt64 64-bit PE optional header

7.1.3.2.9. uint32_t overlays number of overlays

7.1.3.2.10. int32 t overlays sz size of overlays

7.1.4. DIS arg Struct Reference

Data Fields

- enum DIS_ACCESS access_type
- enum DIS SIZE access size
- struct DIS_mem_arg mem
- enum X86REGS reg
- uint64_t other

7.1.4.1. Detailed Description

disassembled operand

7.1.4.2. Field Documentation

7.1.4.2.1. enum DIS_SIZE access_size size size of access

7.1.4.2.2. enum DIS_ACCESS access_type type of access

7.1.4.2.3. struct DIS_mem_arg mem memory operand

7.1.4.2.4. uint64_t other other other

7.1.4.2.5. enum X86REGS reg register operand

7.1.5. DIS fixed Struct Reference

Data Fields

- enum X86OPS x86_opcode
- enum DIS_SIZE operation_size
- enum DIS SIZE address size
- uint8_t segment

7.1.5.1. Detailed Description

disassembled instruction

7.1.5.2. Field Documentation

7.1.5.2.1. enum DIS_SIZE address_size size size of address

7.1.5.2.2. enum DIS SIZE operation size size of operation

7.1. Structure types

7.1.5.2.3. uint8_t segment

segment

7.1.5.2.4. enum X86OPS x86_opcode opcode of X86 instruction

7.1.6. DIS mem arg Struct Reference

Data Fields

- enum DIS_SIZE access_size
- enum X86REGS scale_reg
- enum X86REGS add_reg
- uint8 t scale
- int32_t displacement

7.1.6.1. Detailed Description

disassembled memory operand: scale_reg*scale + add_reg + displacement

7.1.6.2. Field Documentation

7.1.6.2.1. enum DIS_SIZE access_size

size of access

7.1.6.2.2. enum X86REGS add_reg register used as displacemenet

7.1.6.2.3. int32 t displacement displacement as immediate number

7.1.6.2.4. uint 8_t scale

scale as immediate number

7.1.6.2.5. enum X86REGS scale_reg

register used as scale

7.1.7. DISASM RESULT Struct Reference

7.1.7.1. Detailed Description

disassembly result, 64-byte, matched by type-8 signatures

7.1.8. pe_image_data_dir Struct Reference

7.1.8.1. Detailed Description

PE data directory header

7.1.9. pe_image_file_hdr Struct Reference

Data Fields

- uint32 t Magic
- uint16_t Machine
- uint16 t NumberOfSections
- uint32_t TimeDateStamp
- uint32_t PointerToSymbolTable
- uint32_t NumberOfSymbols
- uint16_t SizeOfOptionalHeader

7.1.9.1. Detailed Description

Header for this PE file

7.1.9.2. Field Documentation

7.1.9.2.1. uint16_t Machine libclamav/pe.c for possible values

CPU this executable runs on, see

7.1.9.2.2. uint32_t Magic

7.1.9.2.3. uint16_t NumberOfSections executable

Number of sections in this

PE magic header: $PE \setminus 0 \setminus 0$

7.1.9.2.4. uint32_t NumberOfSymbols

debug

7.1.9.2.5. uint32 t PointerToSymbolTable

debug

38

7.1. Structure types

7.1.9.2.6. uint16_t SizeOfOptionalHeader

== 224

7.1.9.2.7. uint32_t TimeDateStamp

Unreliable

7.1.10. pe image optional hdr32 Struct Reference

Data Fields

- uint8_t MajorLinkerVersion
- uint8 t MinorLinkerVersion
- uint32_t SizeOfCode
- uint32 t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- uint32_t ImageBase
- uint32_t SectionAlignment
- uint32 t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32_t NumberOfRvaAndSizes

7.1.10.1. Detailed Description

32-bit PE optional header

7.1.10.2. Field Documentation

7.1.10.2.1. uint32_t CheckSum

NT drivers only

7.1.10.2.2. uint32_t FileAlignment

usually 32 or 512

7.1.10.2.3. uint32_t ImageBase

multiple of 64 KB

Chapter 1. By toodae III I	93
$7.1.10.2.4.~\mathrm{uint}16_\mathrm{t}~\mathrm{MajorImageVersion}$	unreliable
7.1.10.2.5. uint8_t MajorLinkerVersion	unreliable
$7.1.10.2.6.~uint 16_t~Major Operating System Version$	not used
$7.1.10.2.7.~uint 16_t~Minor Image Version$	unreliable
7.1.10.2.8. uint8_t MinorLinkerVersion	unreliable
$7.1.10.2.9.~uint 16_t~Minor Operating System Version$	not used
$7.1.10.2.10.\ uint 32_t\ Number Of Rva And Sizes$	unreliable
7.1.10.2.11. uint32_t SectionAlignment usuall	y 32 or 4096
$7.1.10.2.12.$ uint 32 _t SizeOfCode	unreliable
$7.1.10.2.13.~uint 32_t~Size Of Initialized Data$	unreliable
$7.1.10.2.14.~uint 32_t~Size Of Uninitialized Data$	unreliable
7.1.11. pe_image_optional_hdr64 Struct Ref	erence

Data Fields

- uint8_t MajorLinkerVersion
- uint8_t MinorLinkerVersion
- uint32_t SizeOfCode
- uint32_t SizeOfInitializedData
- uint64_t ImageBase
- uint32_t SectionAlignment
- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32_t NumberOfRvaAndSizes

7.1. Structure types

7.1.11.1. Detailed Description

PE 64-bit optional header

7.1.11.2. Field Documentation	entatio	ocumer	\mathbf{D}	eld	Fie	.2.	11	.1	7
-------------------------------	---------	--------	--------------	-----	-----	-----	----	----	---

7.1.11.2.1. uint32_t CheckSum	NT drivers only
7.1.11.2.2. uint32_t FileAlignment	usually 32 or 512

$$7.1.11.2.4.\ uint 16_t\ Major Image Version \\$$

7.1.11.2.14. uint 32_t Size Of Uninitialized Data

unreliable

7.1.12. pe image section hdr Struct Reference

Data Fields

- uint8_t Name [8]
- uint32 t SizeOfRawData
- uint32 t PointerToRawData
- uint32 t PointerToRelocations
- uint32 t PointerToLinenumbers
- uint16 t NumberOfRelocations
- uint16_t NumberOfLinenumbers

7.1.12.1. Detailed Description

PE section header

7.1.12.2. Field Documentation

7.1.12.2.1. uint8_t Name[8] may not end with NULL

7.1.12.2.2. uint16_t NumberOfLinenumbers object files only

7.1.12.2.3. uint16_t NumberOfRelocations object files only

7.1.12.2.4. uint32_t PointerToLinenumbers object files only

7.1.12.2.5. uint32_t PointerToRawData offset to the section's data

7.1.12.2.6. uint32_t PointerToRelocations object files only

7.1.12.2.7. uint32_t SizeOfRawData multiple of FileAlignment

7.2. Low level API

7.2.1. bytecode_api.h File Reference

Enumerations

- enum Bytecode Kind { BC_GENERIC = 0 , BC_LOGICAL = 256, BC_PE_UNPACKER }
- enum FunctionalityLevels
- enum { SEEK_SET = 0, SEEK_CUR, SEEK_END }

Functions

- uint32 t test1 (uint32 t a, uint32 t b)
- int32_t read (uint8_t *data, int32_t size)

Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

- int32_t write (uint8_t *data, int32_t size)

 Writes the specified amount of bytes from a buffer to the current temporary file.
- int32_t seek (int32_t pos, uint32_t whence)

 Changes the current file position to the specified one.
- uint32_t setvirusname (const uint8_t *name, uint32_t len)
- uint32_t debug_print_str (const uint8_t *str, uint32_t len)
- uint32_t debug_print_uint (uint32_t a)
- uint32 t disasm x86 (struct DISASM RESULT *result, uint32 t len)
- uint32_t pe_rawaddr (uint32_t rva)
- int32 t file find (const uint8 t *data, uint32 t len)
- int32_t file_byteat (uint32_t offset)
- void * malloc (uint32 t size)
- uint32_t test2 (uint32_t a)
- int32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
- int32_t fill_buffer (uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)

- int32 t extract new (int32 t id)
- int32_t read_number (uint32_t radix)
- int32_t hashset_new (void)
- int32_t hashset_add (int32_t hs, uint32_t key)
- int32_t hashset_remove (int32_t hs, uint32_t key)
- int32_t hashset_contains (int32_t hs, uint32_t key)
- int32_t hashset_done (int32_t id)
- int32_t hashset_empty (int32_t id)
- int32_t buffer_pipe_new (uint32_t size)
- int32_t buffer_pipe_new_fromfile (uint32_t pos)
- uint32_t buffer_pipe_read_avail (int32_t id)
- uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)
- int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)
- uint32_t buffer_pipe_write_avail (int32_t id)
- uint8_t * buffer_pipe_write_get (int32_t id, uint32_t size)
- int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)
- int32_t buffer_pipe_done (int32_t id)
- int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
- int32_t inflate_process (int32_t id)
- int32_t inflate_done (int32_t id)
- int32 t bytecode rt error (int32 t locationid)
- int32_t jsnorm_init (int32_t from_buffer)
- int32_t jsnorm_process (int32_t id)
- int32_t jsnorm_done (int32_t id)
- int32 t ilog2 (uint32 t a, uint32 t b)
- int32_t ipow (int32_t a, int32_t b, int32_t c)
- int32 t iexp (int32 t a, int32 t b, int32 t c)
- int32_t isin (int32_t a, int32_t b, int32_t c)
- int32_t icos (int32_t a, int32_t b, int32_t c)
- int32_t memstr (const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needlesize)
- int32_t hex2ui (uint32_t hex1, uint32_t hex2)
- int32_t atoi (const uint8_t *str, int32_t size)
- uint32_t debug_print_str_start (const uint8_t *str, uint32_t len)
- uint32_t debug_print_str_nonl (const uint8_t *str, uint32_t len)

- uint32_t entropy_buffer (uint8_t *buffer, int32_t size)
- int32_t map_new (int32_t keysize, int32_t valuesize)
- int32_t map_addkey (const uint8_t *key, int32_t ksize, int32_t id)
- int32_t map_setvalue (const uint8_t *value, int32_t vsize, int32_t id)
- int32_t map_remove (const uint8_t *key, int32_t ksize, int32_t id)
- int32_t map_find (const uint8_t *key, int32_t ksize, int32_t id)
- int32_t map_getvaluesize (int32_t id)
- uint8_t * map_getvalue (int32_t id, int32_t size)
- int32_t map_done (int32_t id)
- int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)
- uint32_t engine_functionality_level (void)
- uint32_t engine_dconf_level (void)
- uint32_t engine_scan_options (void)
- uint32_t engine_db_options (void)
- int32_t extract_set_container (uint32_t container)
- int32 t input switch (int32 t extracted file)

Variables

- const uint32_t __clambc_match_counts [64] Logical signature match counts.
- const uint32_t ___clambc_match_offsets [64]

 Logical signature match offsets This is a low-level variable, use the Macros in bytecode_local.h instead to access it.
- struct cli pe hook data clambo pedata
- const uint32_t __clambc_filesize [1]
- const uint16 t clambc kind

7.2.1.1. Detailed Description

7.2.1.2. Enumeration Type Documentation

7.2.1.2.1. anonymous enum

Enumerator:

SEEK_SET set file position to specified absolute position

SEEK_CUR set file position relative to current position SEEK_END set file position relative to file end

7.2.1.2.2. enum BytecodeKind

Bytecode trigger kind

Enumerator:

 $BC_GENERIC$ generic bytecode, not tied a specific hook $BC_LOGICAL$ triggered by a logical signature $BC_PE_UNPACKER$ a PE unpacker

7.2.1.2.3. enum FunctionalityLevels LibClamAV functionality level constants

7.2.1.3. Function Documentation

7.2.1.3.1. $int32_t$ atoi (const uint8 $_t * str$, $int32_t$ size) Converts string to positive number.

Parameters:

str buffer size size of str

Returns:

>0 string converted to number if possible, -1 on error

7.2.1.3.2. int32_t buffer_pipe_done (int32_t *id*) Deallocate memory used by buffer. After this all attempts to use this buffer will result in error. All buffer_pipes are automatically deallocated when bytecode finishes execution.

Parameters:

id ID of buffer_pipe

Returns:

0 on success

7.2.1.3.3. int32_t buffer_pipe_new (uint32_t size) Creates a new pipe with the specified buffer size

Parameters:

size size of buffer

Returns:

ID of newly created buffer_pipe

7.2.1.3.4. int32_t buffer_pipe_new_fromfile (uint32_t pos) Same as buffer_pipe_new, except the pipe's input is tied to the current file, at the specified position.

Parameters:

pos starting position of pipe input in current file

Returns:

ID of newly created buffer_pipe

7.2.1.3.5. uint32_t buffer_pipe_read_avail (int32_t *id*) Returns the amount of bytes available to read.

Parameters:

id ID of buffer_pipe

Returns:

amount of bytes available to read

7.2.1.3.6. uint8_t* buffer_pipe_read_get (int32_t id, uint32_t amount) Returns a pointer to the buffer for reading. The 'amount' parameter should be obtained by a call to buffer_pipe_read_avail().

Parameters:

id ID of buffer_pipeamount to read

Returns:

pointer to buffer, or NULL if buffer has less than specified amount

7.2.1.3.7. int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount) Updates read cursor in buffer_pipe.

Parameters:

id ID of buffer_pipe

amount amount of bytes to move read cursor

Returns:

0 on success

7.2.1.3.8. uint32_t buffer_pipe_write_avail (int32_t *id*) Returns the amount of bytes available for writing.

Parameters:

id ID of buffer_pipe

Returns:

amount of bytes available for writing

7.2.1.3.9. uint8_t* buffer_pipe_write_get (int32_t id, uint32_t size) Returns pointer to writable buffer. The 'amount' parameter should be obtained by a call to buffer_pipe_write_avail().

Parameters:

 \boldsymbol{id} ID of buffer_pipe

size amount of bytes to write

Returns:

pointer to write buffer, or NULL if requested amount is more than what is available in the buffer

7.2.1.3.10. int32_t buffer_pipe_write_stopped (int32_t *id*, uint32_t *amount*) Updates the write cursor in buffer_pipe.

Parameters:

id ID of buffer_pipe

amount amount of bytes to move write cursor

Returns:

0 on success

7.2.1.3.11. int32_t bytecode_rt_error (int32_t locationid) Report a runtime error at the specified locationID.

Parameters:

locationid (line << 8) | (column&0xff)

Returns:

0

7.2.1.3.12. $uint32_t$ $debug_print_str$ (const $uint8_t$ * str, $uint32_t$ len)

Prints a debug message.

Parameters:

- $\leftarrow str$ Message to print
- \leftarrow *len* length of message to print

Returns:

0

7.2.1.3.13. uint32_t debug_print_str_nonl (const uint8_t * str, uint32_t len) Prints a debug message with a trailing newline, and not preceded by 'LibClamAV debug'.

Parameters:

str the string len length of str

Returns:

0

7.2.1.3.14. uint32_t debug_print_str_start (const uint8_t * str, uint32_t len) Prints a debug message with a trailing newline, but preceded by 'LibClamAV debug'.

Parameters:

str the string len length of str

Returns:

0

7.2.1.3.15. uint32_t debug_print_uint (uint32_t a) Prints a number as a debug message.

Parameters:

 $\leftarrow a$ number to print

Returns:

0

7.2.1.3.16. uint32_t disasm_x86 (struct DISASM_RESULT * result, uint32_t len) Disassembles starting from current file position, the specified amount of bytes.

Parameters:

- \rightarrow **result** pointer to struct holding result
- \leftarrow *len* how many bytes to disassemble

Returns:

0 for success

You can use lseek to disassemble starting from a different location. This is a low-level API, the result is in ClamAV type-8 signature format (64 bytes/instruction).

See also:

DisassembleAt

7.2.1.3.17. uint32_t engine_db_options (void) Returns the current engine's db options.

7.2.1.3.18. uint32_t engine_dconf_level (void) Returns the current engine (dconf) functionality level.

7.2.1.3.19. uint32_t engine_functionality_level (void) ------- engine query ---------- Returns the current engine (feature) functionality level.

7.2.1.3.20. uint32_t engine_scan_options (void) Returns the current engine's scan options.

7.2.1.3.21. uint32_t entropy_buffer (uint8_t * buffer, int32_t size) Returns an approximation for the entropy of buffer.

Parameters:

buffer input buffersize size of buffer

Returns:

entropy estimation $*2^{26}$

7.2.1.3.22. int32_t extract_new (int32_t *id*) Prepares for extracting a new file, if we've already extracted one it scans it.

Parameters:

 $\leftarrow id$ an id for the new file (for example position in container)

Returns:

1 if previous extracted file was infected

7.2.1.3.23. int32_t extract_set_container (uint32_t container)
Sets the container type for the currently extracted file.

Parameters:

container container type (CL TYPE *)

Returns:

current setting for container (CL_TYPE_ANY default)

7.2.1.3.24. int32_t file_byteat (uint32_t offset) Read a single byte from current file

Parameters:

offset file offset

Returns:

byte at offset off in the current file, or -1 if offset is invalid

7.2.1.3.25. int32_t file_find (const uint8_t * data, uint32_t len) Looks for the specified sequence of bytes in the current file.

Parameters:

 \leftarrow data the sequence of bytes to look for len length of data, cannot be more than 1024

Returns:

offset in the current file if match is found, -1 otherwise

7.2.1.3.26. int32_t file_find_limit (const uint8_t * data, uint32_-t len, int32_t maxpos) ------ file operations ------ Looks for the specified sequence of bytes in the current file, up to the specified position.

Parameters:

 \leftarrow data the sequence of bytes to look for len length of data, cannot be more than 1024

Returns:

offset in the current file if match is found, -1 otherwise

7.2.1.3.27. int32_t fill_buffer (uint8_t * buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill) Fills the specified buffer with at least fill bytes.

Parameters:

- \rightarrow **buffer** the buffer to fill
- $\leftarrow len$ length of buffer
- \leftarrow *filled* how much of the buffer is currently filled
- $\leftarrow cursor$ position of cursor in buffer
- \leftarrow *fill* amount of bytes to fill in (0 is valid)

Returns:

<0 on error, 0 on EOF, number bytes available in buffer (starting from 0) The character at the cursor will be at position 0 after this call.

7.2.1.3.28. int32_t get_pe_section (struct cli_exe_section * section, uint32_t num) Gets information about the specified PE section.

Parameters:

- \rightarrow section PE section information will be stored here
- $\leftarrow num$ PE section number

7.2.1.3.29. int32_t hashset_add (int32_t hs, uint32_t key) Add a new 32-bit key to the hashset.

Parameters:

hs ID of hashset (from hashset_new)key the key to add

Returns:

0 on success

7.2.1.3.30. int32_t hashset_contains (int32_t hs, uint32_t key) Returns whether the hashset contains the specified key.

Parameters:

hs ID of hashset (from hashset_new)key the key to lookup

Returns:

1 if found, 0 if not found, <0 on invalid hashset ID

7.2.1.3.31. int32_t hashset_done (int32_t *id*) Deallocates the memory used by the specified hashset. Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution.

Parameters:

id ID of hashset (from hashset_new)

Returns:

0 on success

7.2.1.3.32. int32_t hashset_empty (int32_t id) Returns whether the hashset is empty.

Parameters:

id of hashset (from hashset_new)

Returns:

0 on success

7.2.1.3.33. int32_t hashset_new (void) Creates a new hashset and returns its id.

Returns:

ID for new hashset

7.2.1.3.34. int32_t hashset_remove (int32_t hs, uint32_t key) Remove a 32-bit key from the hashset.

Parameters:

hs ID of hashset (from hashset_new)

key the key to add

Returns:

0 on success

7.2.1.3.35. int32_t hex2ui (uint32_t hex1, uint32_t hex2) Returns hexadecimal characters hex1 and hex2 converted to 8-bit number.

Parameters:

hex1 hexadecimal character

hex2 hexadecimal character

Returns:

hex1 hex2 converted to 8-bit integer, -1 on error

7.2.1.3.36. int32_t icos (int32_t a, int32_t b, int32_t c) Returns c*cos(a/b).

Parameters:

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns:

c*sin(a/b)

7.2.1.3.37. int32_t iexp (int32_t a, int32_t b, int32_t c) Returns $\exp(a/b)*c$

Parameters:

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns:

c*exp(a/b)

Parameters:

- a input
- \boldsymbol{b} input

Returns:

 2^{2} 4 klog2(a/b)

7.2.1.3.39. int32_t inflate_done (int32_t id) Deallocates inflate data structure. Using the inflate data structure after this will result in an error. All inflate data structures are automatically deallocated when bytecode finishes execution.

Parameters:

id ID of inflate data structure

Returns:

0 on success.

7.2.1.3.40. int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits) Initializes inflate data structures for decompressing data 'from_buffer' and writing uncompressed uncompressed data 'to buffer'.

Parameters:

from_buffer ID of buffer_pipe to read compressed data from
to_buffer ID of buffer_pipe to write decompressed data to
windowBits (see zlib documentation)

Returns:

ID of newly created inflate data structure, <0 on failure

7.2.1.3.41. int32_t inflate_process (int32_t id) Inflate all available data in the input buffer, and write to output buffer. Stops when the input buffer becomes empty, or write buffer becomes full. Also attempts to recover from corrupted inflate stream (via inflateSync). This function can be called repeatedly on success after filling the input buffer, and flushing the output buffer. The inflate stream is done processing when 0 bytes are available from output buffer, and input buffer is not empty.

Parameters:

id ID of inflate data structure

Returns:

0 on success, zlib error code otherwise

7.2.1.3.42. int32_t input_switch (int32_t extracted_file) Toggles the read/seek API to read from the currently extracted file, and back.

Parameters:

 $extracted_file\ 1$ - switch to reading from extracted file, 0 - switch back to original input

Returns:

-1 on error (if no extracted file exists) 0 on success

7.2.1.3.43. int32_t ipow (int32_t a, int32_t b, int32_t c) Returns c*a^b.

Parameters:

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns:

c*pow(a,b)

7.2.1.3.44. int32_t isin (int32_t a, int32_t b, int32_t c) Returns c*sin(a/b).

Parameters:

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns:

c*sin(a/b)

7.2.1.3.45. int32_t jsnorm_done (int32_t id) Flushes JS normalizer.

Parameters:

id ID of js normalizer to flush

7.2.1.3.46. int32_t jsnorm_init (int32_t from_buffer) Initializes JS normalizer for reading 'from_buffer'. Normalized JS will be written to a single tempfile, one normalized JS per line, and automatically scanned when the bytecode finishes execution.

Parameters:

from_buffer ID of buffer_pipe to read javascript from

Returns:

ID of JS normalizer, <0 on failure

7.2.1.3.47. int32_t jsnorm_process (int32_t id) Normalize all javascript from the input buffer, and write to tempfile. You can call this function repeatedly on success, if you (re)fill the input buffer.

Parameters:

id ID of JS normalizer

Returns:

0 on success, <0 on failure

7.2.1.3.48. void* malloc (uint32_t *size)* Allocates memory. Currently this memory is freed automatically on exit from the bytecode, and there is no way to free it sooner.

Parameters:

size amount of memory to allocate in bytes

Returns:

pointer to allocated memory

7.2.1.3.49. $int32_t$ map_addkey (const uint8_t * key, $int32_t$ ksize, $int32_t$ id) Inserts the specified key/value pair into the map.

Parameters:

id id of table

key key

ksize size of key

Returns:

0 - if key didn't exist before 1 - if key existed -1 - if ksize doesn't match keysize specified at table creation

7.2.1.3.50. int32_t map_done (int32_t *id*) Deallocates the memory used by the specified map. Trying to use the map after this will result in an error. All maps are automatically deallocated when the bytecode finishes execution.

7.2.1.3.51. int32_t map_find (const uint8_t * key, int32_t ksize, int32_t id) Looks up key in map. The map remember the last looked up key (so you can retrieve the value).

Parameters:

id id of map

key key

ksize size of key

Returns:

0 - if not found 1 - if found -1 - if ksize doesn't match the size specified at table creation

7.2.1.3.52. uint8_t* map_getvalue (int32_t id, int32_t size) Returns the value obtained during last map_find.

Parameters:

id id of map.

size size of value (obtained from map_getvaluesize)

Returns:

value

7.2.1.3.53. int32_t map_getvaluesize (int32_t id) Returns the size of value obtained during last map_find.

Parameters:

id id of map.

Returns:

size of value

7.2.1.3.54. int32_t map_new (int32_t keysize, int32_t valuesize) Creates a new map and returns its id.

Parameters:

keysize size of key

valuesize size of value, if 0 then value is allocated separately

Returns:

ID of new map

7.2.1.3.55. $int32_t$ map_remove (const uint8_t * key, $int32_t$ ksize, $int32_t$ id)

Remove an element from the map.

Parameters:

id id of mapkey keyksize size of key

Returns:

0 on success, key was present 1 if key was not present -1 if ksize doesn't match keysize specified at table creation

7.2.1.3.56. int32_t map_setvalue (const uint8_t * value, int32_t vsize, int32_t id) Sets the value for the last inserted key with map_addkey.

Parameters:

id id of table value value vsize size of value

Returns:

0 - if update was successful -1 - if there is no last key

Parameters:

haystack buffer to searchhaysize size of haystackneedle substring to searchneedlesize size of needle

Returns:

location of match, -1 otherwise

7.2.1.3.58. uint32_t pe_rawaddr (uint32_t rva) Converts a RVA (Relative Virtual Address) to an absolute PE file offset.

Parameters:

rva a rva address from the PE file

Returns:

absolute file offset mapped to the rva, or PE_INVALID_RVA if the rva is invalid.

7.2.1.3.59. $int32_t$ read $(uint8_t * data, int32_t$ size)

Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

Parameters:

- \leftarrow **size** amount of bytes to read
- \rightarrow data pointer to buffer where data is read into

Returns:

amount read.

7.2.1.3.60. int32_t read_number (uint32_t radix) Reads a number in the specified radix starting from the current position. Non-numeric characters are ignored.

Parameters:

 $\leftarrow radix 10 \text{ or } 16$

Returns:

the number read

7.2.1.3.61. int32_t seek (int32_t pos, uint32_t whence)

Changes the current file position to the specified one.

See also:

SEEK_SET, SEEK_CUR, SEEK_END

Parameters:

- $\leftarrow pos$ offset (absolute or relative depending on whence param)
- \leftarrow whence one of SEEK_SET, SEEK_CUR, SEEK_END

Returns:

absolute position in file

Test api2.

7.2.1.3.62. uint32_t setvirusname (const uint8_t * name, uint32_t len)

Sets the name of the virus found.

Parameters:

- \leftarrow *name* the name of the virus
- \leftarrow *len* length of the virusname

Returns:

0

7.2.1.3.63. $uint32_t test1 (uint32_t a, uint32_t b)$ Test api.

Parameters:

- a 0xf00dbeef
- b 0xbeeff00d

Returns:

0x12345678 if parameters match, 0x55 otherwise

7.2.1.3.64. uint32_t test2 (uint32_t a)

Parameters:

 \boldsymbol{a} 0xf00d

Returns:

0xd00f if parameter matches, 0x5555 otherwise

7.2.1.3.65. int32_t write (uint8_t * data, int32_t size)

Writes the specified amount of bytes from a buffer to the current temporary file.

Parameters:

- $\leftarrow data$ pointer to buffer of data to write
- \leftarrow size amount of bytes to write size bytes to temporary file, from the buffer pointed to byte

Returns:

amount of bytes successfully written

7.2.1.4. Variable Documentation

7.2.1.4.1. const uint32_t ___clambc_filesize[1] File size (max 4G)

7.2.1.4.2. const uint16_t ___clambc_kind Kind of the bytecode

$7.2.1.4.3.\ const\ uint 32_t\ __clambc_match_counts [64]$

Logical signature match counts.

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

7.2.1.4.4. struct cli_pe_hook_data ___clambc_pedata PE data, if this is a PE hook

7.2.2. bytecode disasm.h File Reference

Data Structures

• struct DISASM RESULT

Enumerations

```
enum X86OPS { ,
OP_AAA, OP_AAD, OP_AAM, OP_AAS,
OP_ADD, OP_ADC, OP_AND, OP_ARPL,
OP_BOUND, OP_BSF, OP_BSR, OP_BSWAP,
OP_BT, OP_BTC, OP_BTR, OP_BTS,
OP_CALL, OP_CDQ , OP_CWDE, OP_CBW,
OP_CLC, OP_CLD, OP_CLI, OP_CLTS,
OP_CMC, OP_CMOVO, OP_CMOVNO, OP_CMOVC,
OP_CMOVNC, OP_CMOVZ, OP_CMOVNZ, OP_CMOVBE,
OP_CMOVA, OP_CMOVS, OP_CMOVNS, OP_CMOVP,
OP_CMOVNP, OP_CMOVL, OP_CMOVGE, OP_CMOVLE,
OP_CMOVG, OP_CMP, OP_CMPSD, OP_CMPSW,
OP_CMPSB, OP_CMPXCHG, OP_CMPXCHG8B, OP_CPUID,
OP_DAA, OP_DAS, OP_DEC, OP_DIV,
OP_ENTER, OP_FWAIT, OP_HLT, OP_IDIV,
```

- OP IMUL, OP INC, OP IN, OP INSD,
- OP INSW, OP INSB, OP INT, OP INT3,
- OP INTO, OP INVD, OP INVLPG, OP IRET,
- OP_JO, OP_JNO, OP_JC, OP_JNC,
- OP_JZ, OP_JNZ, OP_JBE, OP_JA,
- OP_JS, OP_JNS, OP_JP, OP_JNP,
- OP_JL, OP_JGE, OP_JLE, OP_JG,
- OP_JMP, OP_LAHF, OP_LAR, OP_LDS,
- OP_LES, OP_LFS, OP_LGS, OP_LEA,
- OP LEAVE, OP LGDT, OP LIDT, OP LLDT,
- OP PREFIX LOCK, OP LODSD, OP LODSW, OP LODSB,
- OP_LOOP, OP_LOOPE, OP_LOOPNE, OP_JECXZ,
- OP_LSL, OP_LSS, OP_LTR, OP_MOV,
- OP MOVSD, OP MOVSW, OP MOVSB, OP MOVSX,
- OP MOVZX, OP MUL, OP NEG, OP NOP,
- OP NOT, OP OR, OP OUT, OP OUTSD,
- OP_OUTSW, OP_OUTSB, OP_PUSH, OP_PUSHAD,
- OP_PUSHFD, OP_POP, OP_POPAD, OP_POPFD,
- OP RCL, OP_RCR, OP_RDMSR, OP_RDPMC,
- OP_RDTSC, OP_PREFIX_REPE, OP_PREFIX_REPNE, OP_RETF,
- OP_RETN, OP_ROL, OP_ROR, OP_RSM,
- OP SAHF, OP SAR, OP SBB, OP SCASD,
- OP_SCASW, OP_SCASB, OP_SETO, OP_SETNO,
- OP_SETC, OP_SETNC, OP_SETZ, OP_SETNZ,
- OP_SETBE, OP_SETA, OP_SETS, OP_SETNS,
- OP SETP, OP SETNP, OP SETL, OP SETGE,
- OP_SETLE, OP_SETG, OP_SGDT, OP_SIDT,
- OP_SHL, OP_SHLD, OP_SHR, OP_SHRD,
- OP SLDT, OP STOSD, OP STOSW, OP STOSB,
- OP_STR, OP_STC, OP_STD, OP_STI,

```
OP SUB, OP SYSCALL, OP SYSENTER, OP SYSEXIT,
 OP SYSRET, OP TEST, OP UD2, OP VERR,
 OP VERRW, OP WBINVD, OP WRMSR, OP XADD,
 OP_XCHG, OP_XLAT, OP_XOR, OP_FPU,
 OP_F2XM1, OP_FABS, OP_FADD, OP_FADDP,
 OP FBLD, OP FBSTP, OP FCHS, OP FCLEX,
 OP FCMOVB, OP FCMOVBE, OP FCMOVE, OP FCMOVNB,
 OP FCMOVNBE, OP FCMOVNE, OP FCMOVNU,
                                               OP -
 FCMOVU,
 OP_FCOM, OP_FCOMI, OP_FCOMIP, OP_FCOMP,
 OP FCOMPP, OP FCOS, OP FDECSTP, OP FDIV,
 OP FDIVP, OP FDIVR, OP FDIVRP, OP FFREE,
 OP FIADD, OP FICOM, OP FICOMP, OP FIDIV.
 OP_FIDIVR, OP_FILD, OP_FIMUL, OP_FINCSTP,
 OP_FINIT, OP_FIST, OP_FISTP, OP_FISTTP,
 OP_FISUB, OP_FISUBR, OP_FLD, OP_FLD1,
 OP FLDCW, OP FLDENV, OP FLDL2E, OP FLDL2T,
 OP FLDLG2, OP FLDLN2, OP FLDPI, OP FLDZ,
 OP_FMUL, OP_FMULP, OP_FNOP, OP_FPATAN,
 OP FPREM, OP FPREM1, OP FPTAN, OP FRNDINT,
 OP_FRSTOR, OP_FSCALE, OP_FSINCOS, OP_FSQRT,
 OP_FSAVE, OP_FST, OP_FSTCW, OP_FSTENV,
 OP FSTP, OP FSTSW, OP FSUB, OP FSUBP,
 OP FSUBR, OP FSUBRP, OP FTST, OP FUCOM,
 OP FUCOMI, OP FUCOMIP, OP FUCOMP, OP FUCOMPP,
 OP FXAM, OP FXCH, OP FXTRACT, OP FYL2X,
 OP FYL2XP1 }
• enum DIS ACCESS {
 ACCESS NOARG, ACCESS IMM, ACCESS REL, ACCESS REG,
 ACCESS MEM }
```

```
enum DIS_SIZE {SIZEB, SIZEW, SIZED, SIZEF,SIZEQ, SIZET, SIZEPTR }
```

• enum X86REGS

7.2.2.1. Detailed Description

7.2.2.2. Enumeration Type Documentation

7.2.2.2.1. enum DIS ACCESS

Access type

Enumerator:

ACCESS_NOARG arg not present
ACCESS_IMM immediate
ACCESS_REL +/- immediate
ACCESS_REG register
ACCESS_MEM [memory]

7.2.2.2.2. enum DIS_SIZE for mem access, immediate and relative

Enumerator:

SIZEB Byte size access

SIZEW Word size access

SIZED Doubleword size access

SIZEF 6-byte access (seg+reg pair)

SIZEQ Quadword access

SIZET 10-byte access

SIZEPTR ptr

7.2.2.2.3. enum X86OPS

X86 opcode

Enumerator:

 OP_AAA Ascii Adjust after Addition

OP_AAD Ascii Adjust AX before Division

OP_AAM Ascii Adjust AX after Multiply

OP_AAS Ascii Adjust AL after Subtraction

- OP_ADD Add
- **OP ADC** Add with Carry
- OP_AND Logical And
- OP_ARPL Adjust Requested Privilege Level
- OP BOUND Check Array Index Against Bounds
- OP BSF Bit Scan Forward
- OP_BSR Bit Scan Reverse
- OP_BSWAP Byte Swap
- OP_BT Bit Test
- OP_BTC Bit Test and Complement
- OP BTR Bit Test and Reset
- **OP BTS** Bit Test and Set
- OP CALL Call
- **OP_CDQ** Convert DoubleWord to QuadWord
- OP CWDE Convert Word to DoubleWord
- **OP_CBW** Convert Byte to Word
- OP_CLC Clear Carry Flag
- **OP CLD** Clear Direction Flag
- OP_CLI Clear Interrupt Flag
- *OP_CLTS* Clear Task-Switched Flag in CR0
- OP_CMC Complement Carry Flag
- **OP CMOVO** Conditional Move if Overflow
- OP CMOVNO Conditional Move if Not Overflow
- **OP_CMOVC** Conditional Move if Carry
- *OP_CMOVNC* Conditional Move if Not Carry
- **OP CMOVZ** Conditional Move if Zero
- OP CMOVNZ Conditional Move if Non-Zero
- **OP CMOVBE** Conditional Move if Below or Equal
- **OP_CMOVA** Conditional Move if Above
- **OP CMOVS** Conditional Move if Sign
- OP CMOVNS Conditional Move if Not Sign

- **OP_CMOVP** Conditional Move if Parity
- *OP_CMOVNP* Conditional Move if Not Parity
- *OP_CMOVL* Conditional Move if Less
- OP_CMOVGE Conditional Move if Greater or Equal
- **OP_CMOVLE** Conditional Move if Less than or Equal
- **OP CMOVG** Conditional Move if Greater
- **OP_CMP** Compare
- *OP_CMPSD* Compare String DoubleWord
- **OP_CMPSW** Compare String Word
- OP_CMPSB Compare String Byte
- *OP_CMPXCHG* Compare and Exchange
- *OP_CMPXCHG8B* Compare and Exchange Bytes
- OP_CPUID CPU Identification
- OP_DAA Decimal Adjust AL after Addition
- OP_DAS Decimal Adjust AL after Subtraction
- OP_DEC Decrement by 1
- **OP_DIV** Unsigned Divide
- OP ENTER Make Stack Frame for Procedure Parameters
- **OP FWAIT** Wait
- **OP_HLT** Halt
- **OP IDIV** Signed Divide
- **OP_IMUL** Signed Multiply
- OP_INC Increment by 1
- **OP_IN** INput from port
- **OP_INSD** INput from port to String Doubleword
- **OP_INSW** INput from port to String Word
- **OP_INSB** INput from port to String Byte
- **OP INT** INTerrupt
- **OP_INT3** INTerrupt 3 (breakpoint)
- **OP INTO** INTerrupt 4 if Overflow
- **OP_INVD** Invalidate Internal Caches

68 7.2. Low level API

- OP_INVLPG Invalidate TLB Entry
- OP IRET Interrupt Return
- OP_JO Jump if Overflow
- **OP_JNO** Jump if Not Overflow
- **OP_JC** Jump if Carry
- **OP_JNC** Jump if Not Carry
- OP_JZ Jump if Zero
- **OP_JNZ** Jump if Not Zero
- OP_JBE Jump if Below or Equal
- OP_JA Jump if Above
- OP_JS Jump if Sign
- **OP_JNS** Jump if Not Sign
- **OP_JP** Jump if Parity
- **OP_JNP** Jump if Not Parity
- **OP JL** Jump if Less
- **OP_JGE** Jump if Greater or Equal
- OP_JLE Jump if Less or Equal
- $OP \ JG$ Jump if Greater
- **OP_JMP** Jump (unconditional)
- *OP_LAHF* Load Status Flags into AH Register
- **OP** LAR load Access Rights Byte
- **OP** LDS Load Far Pointer into DS
- OP LES Load Far Pointer into ES
- OP LFS Load Far Pointer into FS
- **OP_LGS** Load Far Pointer into GS
- **OP LEA** Load Effective Address
- **OP LEAVE** High Level Procedure Exit
- **OP LGDT** Load Global Descript Table Register
- **OP_LIDT** Load Interrupt Descriptor Table Register
- OP_LLDT Load Local Descriptor Table Register
- OP_PREFIX_LOCK Assert LOCK# Signal Prefix

- OP_LODSD Load String Dword
- OP LODSW Load String Word
- **OP LODSB** Load String Byte
- **OP_LOOP** Loop According to ECX Counter
- *OP LOOPE* Loop According to ECX Counter and ZF=1
- **OP_LOOPNE** Looop According to ECX Counter and ZF=0
- OP_JECXZ Jump if ECX is Zero
- *OP_LSL* Load Segment Limit
- **OP** LSS Load Far Pointer into SS
- **OP_LTR** Load Task Register
- **OP MOV** Move
- *OP_MOVSD* Move Data from String to String Doubleword
- **OP_MOVSW** Move Data from String to String Word
- **OP MOVSB** Move Data from String to String Byte
- OP MOVSX Move with Sign-Extension
- **OP MOVZX** Move with Zero-Extension
- **OP_MUL** Unsigned Multiply
- *OP_NEG* Two's Complement Negation
- **OP_NOP** No Operation
- **OP NOT** One's Complement Negation
- *OP_OR* Logical Inclusive OR
- **OP_OUT** Output to Port
- *OP_OUTSD* Output String to Port Doubleword
- **OP OUTSW** Output String to Port Word
- *OP_OUTSB* Output String to Port Bytes
- OP_PUSH Push Onto the Stack
- OP_PUSHAD Push All Double General Purpose Registers
- **OP PUSHFD** Push EFLAGS Register onto the Stack
- **OP POP** Pop a Value from the Stack
- OP_POPAD Pop All Double General Purpose Registers from the Stack

7.2. Low level API

- OP_POPFD Pop Stack into EFLAGS Register
- OP RCL Rotate Carry Left
- OP RCR Rotate Carry Right
- OP_RDMSR Read from Model Specific Register
- *OP RDPMC* Read Performance Monitoring Counters
- *OP_RDTSC* Read Time-Stamp Coutner
- OP_PREFIX_REPE Repeat String Operation Prefix while Equal
- OP__PREFIX__REPNE Repeat String Operation Prefix while Not Equal
- **OP_RETF** Return from Far Procedure
- **OP RETN** Return from Near Procedure
- OP ROL Rotate Left
- OP_ROR Rotate Right
- **OP_RSM** Resumse from System Management Mode
- OP_SAHF Store AH into Flags
- *OP_SAR* Shift Arithmetic Right
- **OP SBB** Subtract with Borrow
- OP SCASD Scan String Doubleword
- OP_SCASW Scan String Word
- *OP_SCASB* Scan String Byte
- **OP_SETO** Set Byte on Overflow
- **OP_SETNO** Set Byte on Not Overflow
- **OP_SETC** Set Byte on Carry
- **OP** _**SETNC** Set Byte on Not Carry
- **OP_SETZ** Set Byte on Zero
- **OP_SETNZ** Set Byte on Not Zero
- **OP SETBE** Set Byte on Below or Equal
- **OP_SETA** Set Byte on Above
- OP_SETS Set Byte on Sign
- OP_SETNS Set Byte on Not Sign
- **OP_SETP** Set Byte on Parity

- **OP_SETNP** Set Byte on Not Parity
- OP SETL Set Byte on Less
- **OP_SETGE** Set Byte on Greater or Equal
- **OP_SETLE** Set Byte on Less or Equal
- OP_SETG Set Byte on Greater
- OP_SGDT Store Global Descriptor Table Register
- $\boldsymbol{OP}_\boldsymbol{SIDT}$ Store Interrupt Descriptor Table Register
- OP SHL Shift Left
- **OP_SHLD** Double Precision Shift Left
- OP_SHR Shift Right
- *OP_SHRD* Double Precision Shift Right
- *OP_SLDT* Store Local Descriptor Table Register
- **OP_STOSD** Store String Doubleword
- **OP_STOSW** Store String Word
- *OP_STOSB* Store String Byte
- *OP_STR* Store Task Register
- OP_STC Set Carry Flag
- **OP_STD** Set Direction Flag
- *OP_STI* Set Interrupt Flag
- OP_SUB Subtract
- OP SYSCALL Fast System Call
- *OP_SYSENTER* Fast System Call
- OP_SYSEXIT Fast Return from Fast System Call
- OP_SYSRET Return from Fast System Call
- **OP_TEST** Logical Compare
- *OP_UD2* Undefined Instruction
- **OP_VERR** Verify a Segment for Reading
- **OP VERRW** Verify a Segment for Writing
- **OP_WBINVD** Write Back and Invalidate Cache
- *OP_WRMSR* Write to Model Specific Register
- **OP_XADD** Exchange and Add

72 7.2. Low level API

OP_XCHG Exchange Register/Memory with Register

- **OP_XLAT** Table Look-up Translation
- **OP_XOR** Logical Exclusive OR
- OP_FPU FPU operation
- OP F2XM1 Compute 2x-1
- **OP FABS** Absolute Value
- *OP_FADD* Floating Point Add
- *OP_FADDP* Floating Point Add, Pop
- *OP_FBLD* Load Binary Coded Decimal
- **OP FBSTP** Store BCD Integer and Pop
- *OP_FCHS* Change Sign
- OP_FCLEX Clear Exceptions
- *OP_FCMOVB* Floating Point Move on Below
- *OP_FCMOVBE* Floating Point Move on Below or Equal
- **OP_FCMOVE** Floating Point Move on Equal
- **OP_FCMOVNB** Floating Point Move on Not Below
- **OP_FCMOVNBE** Floating Point Move on Not Below or Equal
- OP FCMOVNE Floating Point Move on Not Equal
- *OP_FCMOVNU* Floating Point Move on Not Unordered
- **OP FCMOVU** Floating Point Move on Unordered
- *OP_FCOM* Compare Floating Pointer Values and Set FPU Flags
- **OP FCOMI** Compare Floating Pointer Values and Set EFLAGS
- **OP_FCOMIP** Compare Floating Pointer Values and Set EFLAGS, Pop
- OP_FCOMP Compare Floating Pointer Values and Set FPU Flags, Pop
- OP_FCOMPP Compare Floating Pointer Values and Set FPU Flags, Pop Twice
- **OP FCOS** Cosine
- *OP_FDECSTP* Decrement Stack Top Pointer
- **OP_FDIV** Floating Point Divide
- **OP_FDIVP** Floating Point Divide, Pop

- **OP_FDIVR** Floating Point Reverse Divide
- *OP_FDIVRP* Floating Point Reverse Divide, Pop
- **OP_FFREE** Free Floating Point Register
- OP FIADD Floating Point Add
- OP_FICOM Compare Integer
- OP_FICOMP Compare Integer, Pop
- **OP_FIDIV** Floating Point Divide by Integer
- *OP_FIDIVR* Floating Point Reverse Divide by Integer
- OP_FILD Load Integer
- OP_FIMUL Floating Point Multiply with Integer
- *OP_FINCSTP* Increment Stack-Top Pointer
- OP FINIT Initialize Floating-Point Unit
- OP_FIST Store Integer
- **OP_FISTP** Store Integer, Pop
- OP FISTTP Store Integer with Truncation
- OP_FISUB Floating Point Integer Subtract
- OP_FISUBR Floating Point Reverse Integer Subtract
- OP FLD Load Floating Point Value
- OP FLD1 Load Constant 1
- OP FLDCW Load x87 FPU Control Word
- OP FLDENV Load x87 FPU Environment
- **OP_FLDL2E** Load Constant log_2(e)
- OP_FLDL2T Load Constant log_2(10)
- **OP_FLDLG2** Load Constant log_10(2)
- OP_FLDLN2 Load Constant $log_e(2)$
- OP_FLDPI Load Constant PI
- OP FLDZ Load Constant Zero
- **OP FMUL** Floating Point Multiply
- **OP_FMULP** Floating Point Multiply, Pop
- **OP_FNOP** No Operation
- **OP_FPATAN** Partial Arctangent

74 7.2. Low level API

- OP FPREM Partial Remainder
- OP FPREM1 Partial Remainder
- OP_FPTAN Partial Tangent
- **OP_FRNDINT** Round to Integer
- OP FRSTOR Restore x86 FPU State
- OP FSCALE Scale
- **OP FSINCOS** Sine and Cosine
- **OP_FSQRT** Square Root
- OP FSAVE Store x87 FPU State
- **OP_FST** Store Floating Point Value
- OP_FSTCW Store x87 FPU Control Word
- OP_FSTENV Store x87 FPU Environment
- OP_FSTP Store Floating Point Value, Pop
- OP FSTSW Store x87 FPU Status Word
- OP_FSUB Floating Point Subtract
- OP FSUBP Floating Point Subtract, Pop
- *OP_FSUBR* Floating Point Reverse Subtract
- *OP_FSUBRP* Floating Point Reverse Subtract, Pop
- OP_FTST Floating Point Test
- **OP_FUCOM** Floating Point Unordered Compare
- *OP_FUCOMI* Floating Point Unordered Compare with Integer
- **OP_FUCOMIP** Floating Point Unorder Compare with Integer, Pop
- OP_FUCOMP Floating Point Unorder Compare, Pop
- **OP_FUCOMPP** Floating Point Unorder Compare, Pop Twice
- **OP_FXAM** Examine ModR/M
- **OP_FXCH** Exchange Register Contents
- OP_FXTRACT Extract Exponent and Significand
- OP FYL2X Compute y*log2x
- $OP_FYL2XP1$ Compute y*log2(x+1)

7.2.2.2.4. enum X86REGS

X86 registers

7.2.3. bytecode execs.h File Reference

Data Structures

- struct cli_exe_section
- struct cli_exe_info

7.2.3.1. Detailed Description

7.2.4. bytecode_pe.h File Reference

Data Structures

- struct pe_image_file_hdr
- struct pe_image_data_dir
- struct pe_image_optional_hdr32
- struct pe_image_optional_hdr64
- struct pe_image_section_hdr
- struct cli pe hook data

7.2.4.1. Detailed Description

7.3. High level API

7.3.1. bytecode_local.h File Reference

Data Structures

- struct DIS_mem_arg
- struct DIS arg
- struct DIS_fixed

Defines

- #define VIRUSNAME_PREFIX(name) const char __clambc_-virusname_prefix[] = name;
- #define VIRUSNAMES(...) const char *const ___clambc_virusnames[] = {___VA_ARGS___};
- #define SIGNATURES_DECL_BEGIN struct ___Signatures {

76 7.3. High level API

- #define DECLARE_SIGNATURE(name)
- #define SIGNATURES_DECL_END };
- #define TARGET(tgt) const unsigned short ___Target = (tgt);
- #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short
 __FuncMin = (m);
- #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short
 __FuncMax = (m);
- #define SIGNATURES_DEF_BEGIN
- #define DEFINE_SIGNATURE(name, hex)
- #define SIGNATURES_END \};\

Functions

- static force_inline uint32_t count_match (___Signature sig)
- static force_inline uint32_t matches (___Signature sig)
- static force_inline void __attribute__ ((overloadable)) found-Virus(const char *virusname)
- static force_inline uint32_t getFilesize (void)
- bool <u>is_bigendian</u> (void) <u>attribute</u> ((const)) <u>attribute</u> ((nothrow))
- static uint32 t force inline le32 to host (uint32 t v)
- static uint32 t force inline le64 to host (uint32 t v)
- static uint16 t force inline le16 to host (uint16 t v)
- static uint32 t force inline cli readint32 (const void *buff)
- static uint16 t force inline cli readint16 (const void *buff)
- static void force_inline cli_writeint32 (void *offset, uint32_t v)
- static force inline bool has ExeInfo (void)
- static force inline bool is PE64 (void)
- static static force_inline force_inline uint8_t getPEMajorLinkerVersion (void)
- static force inline uint8 t getPEMinorLinkerVersion (void)
- static force_inline uint32_t getPESizeOfCode (void)
- static force_inline uint32_t getPESizeOfInitializedData (void)
- static force_inline uint32_t getPESizeOfUninitializedData (void)
- static force_inline uint32_t getPEBaseOfCode (void)
- static force_inline uint32_t getPEBaseOfData (void)
- static force_inline uint64_t getPEImageBase (void)

- static force_inline uint32_t getPESectionAlignment (void)
- static force inline uint32 t getPEFileAlignment (void)
- static force_inline uint16_t getPEMajorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMajorImageVersion (void)
- static force_inline uint16_t getPEMinorImageVersion (void)
- static force_inline uint16_t getPEMajorSubsystemVersion (void)
- static force_inline uint16_t getPEMinorSubsystemVersion (void)
- static force_inline uint32_t getPEWin32VersionValue (void)
- static force_inline uint32_t getPESizeOfImage (void)
- static force_inline uint32_t getPESizeOfHeaders (void)
- static force_inline uint32_t getPECheckSum (void)
- static force_inline uint16_t getPESubsystem (void)
- static force_inline uint16_t getPEDllCharacteristics (void)
- static force inline uint32 t getPESizeOfStackReserve (void)
- static force_inline uint32_t getPESizeOfStackCommit (void)
- static force_inline uint32_t getPESizeOfHeapReserve (void)
- static force_inline uint32_t getPESizeOfHeapCommit (void)
- static force_inline uint32_t getPELoaderFlags (void)
- static force inline uint16 t getPEMachine ()
- static force_inline uint32_t getPETimeDateStamp ()
- static force_inline uint32_t getPEPointerToSymbolTable ()
- static force_inline uint32_t getPENumberOfSymbols ()
- static force inline uint16 t getPESizeOfOptionalHeader ()
- static force_inline uint16_t getPECharacteristics ()
- static force inline bool getPEisDLL ()
- static force inline uint32 t getPEDataDirRVA (unsigned n)
- static force inline uint32 t getPEDataDirSize (unsigned n)
- static force inline uint16 t getNumberOfSections (void)
- static uint32_t getPELFANew (void)
- static force_inline int readPESectionName (unsigned char name[8], unsigned n)
- static force_inline uint32_t getEntryPoint (void)
- static force_inline uint32_t getExeOffset (void)
- static force_inline uint32_t getImageBase (void)

- static force_inline bool readRVA (uint32_t rva, void *buf, size_t buf-size)
- static void * memchr (const void *s, int c, size_t n)
- void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__((__nonnull__((1))))
- void * memmove (void *dst, const void *src, uintptr_t n) __attribute_-_((__nothrow__)) __attribute__((__nonnull__(1
- void *void * memcpy (void *restrict dst, const void *restrict src, uintptr_t n) __attribute__((__nothrow___)) __attribute__((_-nonnull__(1
- void *void *int memcmp (const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow__)) __attribute__((__pure__)) __attribute__((__nonnull__(1
- static force_inline uint32_t DisassembleAt (struct DIS_fixed *result, uint32_t offset, uint32_t len)

7.3.1.1. Detailed Description

7.3.1.2. Define Documentation

7.3.1.2.1. #define DECLARE SIGNATURE(name) Value:

```
const char *name##_sig;\
   __Signature name;
```

Declares a name for a subsignature

7.3.1.2.2. #define DEFINE SIGNATURE(name, hex) Value:

```
.name##_sig = (hex),\
    .name = {__COUNTER__ - __signature_bias},
```

Defines the pattern for a previously declared subsignature.

See also:

DECLARE SIGNATURE

Parameters:

name the name of a previously declared subsignaturehex the pattern for this subsignature

7.3.1.2.3. #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m); Define the maximum engine functionality level required for this bytecode/logical signature. Engines newer than this will skip loading the bytecode. You can use the 'enum FunctionalityLevels' constants here.

7.3.1.2.4. #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m); Define the minimum engine functionality level required for this bytecode/logical signature. Engines older than this will skip loading the bytecode. You can use the 'enum FunctionalityLevels' constants here.

7.3.1.2.5. #define SIGNATURES_DECL_BEGIN struct ___-Signatures { Marks the beginning of the subsignature name declaration section

7.3.1.2.6. #define SIGNATURES_DECL_END }; Marks the end of the subsignature name declaration section

7.3.1.2.7. #define SIGNATURES DEF BEGIN Value:

```
static const unsigned __signature_bias = __COUNTER__+1;\
const struct __Signatures Signatures = {\
```

Marks the beginning of subsignature pattern definitions.

See also:

SIGNATURES_DECL_BEGIN

7.3.1.2.8. #define SIGNATURES_END $\}$;\ Marks the end of the subsignature pattern definitions.

7.3.1.2.9. #define TARGET(tgt) const unsigned short ___Target = (tgt); Defines the ClamAV file target.

Parameters:

tgt ClamAV signature type (0 - raw, 1 - PE, etc.)

7.3.1.2.10. #define VIRUSNAME_PREFIX(name) const char __clambc_virusname_prefix[] = name; Declares the virusname prefix.

Parameters:

name the prefix common to all viruses reported by this bytecode

7.3.1.2.11. #define VIRUSNAMES(...) const char *const ___-clambc_virusnames[] = {___VA_ARGS___}; Declares all the virusnames that this bytecode can report.

Parameters:

... a comma-separated list of strings interpreted as virusnames

7.3.1.3. Function Documentation

7.3.1.3.1. static force_inline void ___attribute___ ((overloadable)) const [static] Sets the specified virusname as the virus detected by this bytecode.

Parameters:

virusname the name of the virus, excluding the prefix, must be one of the virusnames declared in VIRUSNAMES.

See also:

VIRUSNAMES

7.3.1.3.2. bool ___is_bigendian (void) const Returns true if the bytecode is executing on a big-endian CPU.

Returns:

true if executing on bigendian CPU, false otherwise

This will be optimized away in libclamav, but it must be used when dealing with endianess for portability reasons. For example whenever you read a 32-bit integer from a file, it can be written in little-endian convention (x86 CPU for example), or big-endian convention (PowerPC CPU for example). If the file always contains little-endian integers, then conversion might be needed. ClamAV bytecodes by their nature must only handle known-endian integers, if endianness can change, then both situations must be taken into account (based on a 1-byte field for example).

7.3.1.3.3. static uint16_t force_inline cli_readint16 (const void * buff) [static] Reads from the specified buffer a 16-bit of little-endian integer.

Parameters:

 $\leftarrow buff$ pointer to buffer

Returns:

16-bit little-endian integer converted to host endianness

7.3.1.3.4. static uint32_t force_inline cli_readint32 (const void * buff) [static] Reads from the specified buffer a 32-bit of little-endian integer.

Parameters:

 $\leftarrow buff$ pointer to buffer

Returns:

32-bit little-endian integer converted to host endianness

7.3.1.3.5. static void force_inline cli_writeint32 (void * offset, uint32_t v) [static] Writes the specified value into the specified buffer in little-endian order

Parameters:

- \rightarrow offset pointer to buffer to write to
- $\leftarrow v$ value to write

7.3.1.3.6. static force_inline uint32_t count_match (__Signature sig) [static] Returns how many times the specified signature matched.

Parameters:

sig name of subsignature queried

Returns:

number of times this subsignature matched in the entire file

This is a constant-time operation, the counts for all subsignatures are already computed.

82 7.3. High level API

7.3.1.3.7. static force_inline uint32_t DisassembleAt (struct DIS_fixed * result, uint32_t offset, uint32_t len) [static] Disassembles one X86 instruction starting at the specified offset.

Parameters:

- $\rightarrow result$ disassembly result
- \leftarrow offset start disassembling from this offset, in the current file
- \leftarrow len max amount of bytes to disassemble

Returns:

offset where disassembly ended

7.3.1.3.8. static force_inline uint32_t getEntryPoint (void) [static] Returns the offset of the EntryPoint in the executable file.

Returns:

offset of EP as 32-bit unsigned integer

7.3.1.3.9. static force_inline uint32_t getExeOffset (void) [static] Returns the offset of the executable in the file.

Returns:

offset of embedded executable inside file.

7.3.1.3.10. static force_inline uint32_t getFilesize (void) [static] Returns the currently scanned file's size.

Returns:

file size as 32-bit unsigned integer

7.3.1.3.11. static force_inline uint32_t getImageBase (void) [static] Returns the ImageBase with the correct endian conversion

7.3.1.3.12. static force_inline uint16_t getNumberOfSections (void) [static] Returns the number of sections in this executable file.

Returns:

number of sections as 16-bit unsigned integer

- 7.3.1.3.13. static force_inline uint32_t getPEBaseOfCode (void) [static] Return the PE BaseOfCode.
- 7.3.1.3.14. static force_inline uint32_t getPEBaseOfData (void) [static] Return the PE BaseOfData.
- 7.3.1.3.15. static force_inline uint16_t getPECharacteristics () [static] Returns PE characteristics.
- 7.3.1.3.16. static force_inline uint32_t getPECheckSum (void) [static] Return the PE CheckSum.
- 7.3.1.3.17. static force_inline uint32_t getPEDataDirRVA (unsigned n) [static] Gets the virtual address of specified image data directory.

Parameters:

n image directory requested

Returns:

Virtual Address of requested image directory

7.3.1.3.18. static force_inline uint32_t getPEDataDirSize (unsigned n) [static] Gets the size of the specified image data directory.

Parameters:

n image directory requested

Returns:

Size of requested image directory

7.3.1.3.19. static force_inline uint16_t getPEDllCharacteristics (void) [static] Return the PE DllCharacteristics.

7.3. High level API

7.3.1.3.20. static force_inline uint32_t getPEFileAlignment (void) [static] Return the PE FileAlignment.

- 7.3.1.3.21. static force_inline uint64_t getPEImageBase (void) [static] Return the PE ImageBase as 64-bit integer.
- 7.3.1.3.22. static force_inline bool getPEisDLL () [static] Returns whether this is a DLL
- 7.3.1.3.23. static uint32_t getPELFANew (void) [static] Gets the offset to the PE header.
- 7.3.1.3.24. static force_inline uint32_t getPELoaderFlags (void) [static] Return the PE LoaderFlags.
- 7.3.1.3.25. static force_inline uint16_t getPEMachine () [static] Returns the CPU this executable runs on, see libclamav/pe.c for possible values
- 7.3.1.3.26. static force_inline uint16_t getPEMajorImageVersion (void) [static] Return the PE MajorImageVersion
- 7.3.1.3.27. static static force_inline force_inline uint8_t getPEMa-jorLinkerVersion (void) [static] Returns MajorLinkerVersion for this PE file.
- 7.3.1.3.28. static force_inline uint16_t getPEMajorOperatingSystemVersion (void) [static] Return the PE MajorOperatingSystemVersion.
- 7.3.1.3.29. static force_inline uint16_t getPEMajorSubsystemVersion (void) [static] Return the PE MajorSubsystemVersion

- 7.3.1.3.30. static force_inline uint16_t getPEMinorImageVersion (void) [static] Return the PE MinorImageVersion
- 7.3.1.3.31. static force_inline uint8_t getPEMinorLinkerVersion (void) [static] Returns MinorLinkerVersion for this PE file.
- 7.3.1.3.32. static force_inline uint16_t getPEMinorOperatingSystemVersion (void) [static] Return the PE MinorOperatingSystemVersion.
- 7.3.1.3.33. static force_inline uint16_t getPEMinorSubsystemVersion (void) [static] Return the PE MinorSubsystemVersion
- 7.3.1.3.34. static force_inline uint32_t getPENumberOfSymbols ()
 [static] Returns the PE number of debug symbols
- 7.3.1.3.35. static force_inline uint32_t getPEPointerToSymbol-Table () [static] Returns pointer to the PE debug symbol table
- 7.3.1.3.36. static force_inline uint32_t getPESectionAlignment (void) [static] Return the PE SectionAlignment.
- 7.3.1.3.37. static force_inline uint32_t getPESizeOfCode (void) [static] Return the PE SizeOfCode.
- 7.3.1.3.38. static force_inline uint32_t getPESizeOfHeaders (void)
 [static] Return the PE SizeOfHeaders.
- 7.3.1.3.40. static force_inline uint32_t getPESizeOfHeapReserve (void) [static] Return the PE SizeOfHeapReserve.

7.3. High level API

7.3.1.3.41. static force_inline uint32_t getPESizeOfImage (void) [static] Return the PE SizeOfImage.

- 7.3.1.3.42. static force_inline uint32_t getPESizeOfInitialized-Data (void) [static] Return the PE SizeofInitializedData.
- 7.3.1.3.43. static force_inline uint16_t getPESizeOfOptional-Header () [static] Returns the size of PE optional header.
- 7.3.1.3.44. static force_inline uint32_t getPESizeOfStackCommit (void) [static] Return the PE SizeOfStackCommit.
- 7.3.1.3.45. static force_inline uint32_t getPESizeOfStackReserve (void) [static] Return the PE SizeOfStackReserve.
- 7.3.1.3.46. static force_inline uint32_t getPESizeOfUninitialized-Data (void) [static] Return the PE SizeofUninitializedData.
- 7.3.1.3.47. static force_inline uint16_t getPESubsystem (void) [static] Return the PE Subsystem.
- 7.3.1.3.48. static force_inline uint32_t getPETimeDateStamp () [static] Returns the PE TimeDateStamp from headers
- 7.3.1.3.49. static force_inline uint32_t getPEWin32VersionValue (void) [static] Return the PE Win32VersionValue.
- 7.3.1.3.50. static force_inline bool hasExeInfo (void) [static] Returns whether the current file has executable information.

Returns:

true if the file has exe info, false otherwise

7.3.1.3.51. static force_inline bool isPE64 (void) [static] Returns whether this is a PE32+ executable.

Returns:

true if this is a PE32+ executable

7.3.1.3.52. static uint16_t force_inline le16_to_host (uint16_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Parameters:

 $\leftarrow v$ 16-bit integer as read from a file

Returns:

integer converted to host's endianess

7.3.1.3.53. static uint32_t force_inline le32_to_host (uint32_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Parameters:

 $\leftarrow v$ 32-bit integer as read from a file

Returns:

integer converted to host's endianess

7.3.1.3.54. static uint32_t force_inline le64_to_host (uint32_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Parameters:

 $\leftarrow v$ 64-bit integer as read from a file

Returns:

integer converted to host's endianess

7.3.1.3.55. static force_inline uint32_t matches (___Signature sig) [static] Returns whether the specified subsignature has matched at least once.

Parameters:

sig name of subsignature queried

Returns:

1 if subsignature one or more times, 0 otherwise

7.3.1.3.56. static void* memchr (const void * s, int c, size_t n) [static] Scan the first n bytes of the buffer s, for the character c.

Parameters:

- $\leftarrow s$ buffer to scan
- \boldsymbol{c} character to look for
- n size of buffer

Returns:

a pointer to the first byte to match, or NULL if not found.

7.3.1.3.57. void* void* int memcmp (const void * s1, const void * s2, uint32_t n) Compares two memory buffers.

Parameters:

- $\leftarrow s1$ buffer one
- \leftarrow **s2** buffer two
- $\leftarrow n$ amount of bytes to copy

Returns:

an integer less than, equal to, or greater than zero if the first n bytes of $\mathfrak{s1}$ are found, respectively, to be less than, to match, or be greater than the first n bytes of $\mathfrak{s2}$.

7.3.1.3.58. void* void* memcpy (void *restrict dst, const void *restrict src, uintptr_t n) Copies data between two non-overlapping buffers.

Parameters:

 $\rightarrow dst$ destination buffer

- $\leftarrow src$ source buffer
- $\leftarrow n$ amount of bytes to copy

Returns:

dst

7.3.1.3.59. void* memmove (void * dst, const void * src, uintptr_t n) Copies data between two possibly overlapping buffers.

Parameters:

- $\rightarrow dst$ destination buffer
- $\leftarrow src$ source buffer
- $\leftarrow n$ amount of bytes to copy

Returns:

dst

7.3.1.3.60. void* memset (void * src, int c, uintptr_t n) Fills the specified buffer to the specified value.

Parameters:

- $\rightarrow src$ pointer to buffer
- $\leftarrow c$ character to fill buffer with
- $\leftarrow n$ length of buffer

Returns:

src

7.3.1.3.61. static force_inline int readPESectionName (unsigned char name[8], unsigned n) [static] Read name of requested PE section.

Parameters:

- \rightarrow *name* name of PE section
- $\leftarrow n$ PE section requested

Returns:

0 if successful, <0 otherwise

90 7.3. High level API

7.3.1.3.62. static force_inline bool readRVA (uint32_t rva, void * buf, size_t bufsize) [static] read the specified amount of bytes from the PE file, starting at the address specified by RVA. Returns true on success (full read), false on any failure

CHAPTER 8 Copyright and License

8.1. The ClamAV Bytecode Compiler

The ClamAV Bytecode Compiler is released under the GNU General Public License version 2.

The following directories are under the GNU General Public License version 2: ClamBC, docs, driver, editor, examples, ifacegen.

Copyright (C) 2009 Sourcefire, Inc.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License version 2 as published by the Free Software Foundation.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

It uses the LLVM compiler framework, contained in the following directories: llvm, clang. They have this copyright:

LLVM Release License

University of Illinois/NCSA Open Source License

Copyright (c) 2003-2009 University of Illinois at Urbana-Champaign. All rights reserved.

Developed by:

LLVM Team

University of Illinois at Urbana-Champaign

http://llvm.org

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal with the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimers.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimers in the documentation and/or other materials provided with the distribution.
- * Neither the names of the LLVM Team, University of Illinois at Urbana-Champaign, nor the names of its contributors may be used to endorse or promote products derived from this Software without specific prior written permission.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

Copyrights and Licenses for Third Party Software Distributed with LLVM:

The LLVM software contains code written by third parties. Such software will have its own individual LICENSE.TXT file in the directory in which it appears. This file will describe the copyrights, license, and restrictions which apply to that code.

The disclaimer of warranty in the University of Illinois Open Source License applies to all code in the LLVM Distribution, and nothing in any of the other licenses gives permission to use the names of the LLVM Team or the University of Illinois to endorse or promote products derived from this Software.

The following pieces of software have additional or alternate copyrights, licenses, and/or restrictions:

Program Directory
-----Autoconf Directory
-----1lvm/autoconf

llvm/projects/ModuleMaker/autoconf

llvm/projects/sample/autoconf

CellSPU backend llvm/lib/Target/CellSPU/README.txt
Google Test llvm/utils/unittest/googletest

It also uses re2c, contained in driver/clamdriver/re2c. This code is public domain:

Originally written by Peter Bumbulis (peter@csg.uwaterloo.ca)

Currently maintained by:

- * Dan Nuffer <nuffer@users.sourceforge.net>
- * Marcus Boerger <helly@users.sourceforge.net>
- * Hartmut Kaiser <hkaiser@users.sourceforge.net>

The re2c distribution can be found at:

http://sourceforge.net/projects/re2c/

re2c is distributed with no warranty whatever. The code is certain to contain errors. Neither the author nor any contributor takes responsibility for any consequences of its use.

re2c is in the public domain. The data structures and algorithms used in re2c are all either taken from documents available to the general public or are inventions of the author. Programs generated by re2c may be distributed freely. re2c itself may be distributed freely, in source or binary, unchanged or modified. Distributors may charge whatever fees they can obtain for re2c.

If you do make use of re2c, or incorporate it into a larger project an acknowledgement somewhere (documentation, research report, etc.) would be appreciated.

8.2. Bytecode

The headers used when compiling bytecode have these license (clang/lib/Headers/{bcfeatures,bytecode*}.h):

8.2. Bytecode

Copyright (C) 2009 Sourcefire, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The other header files in clang/lib/Headers/ are from clang with this license (see individual files for copyright owner):

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

When using the ClamAV bytecode compiler to compile your own bytecode programs, you can release it under the license of your choice, provided that you comply with the license of the above header files.

APPENDIX A Predefined macros

```
1 \ \# define \ \_\_llvm \_\_ 1
                                                                                                                                                     clang 1
GNUC MINOR 2
GNUC PATCHLEVEL
                                        #define
                   3 #define
                                          #define
#define GNUC_4
#define GXX_ABL_VERSION 1002
7 #define VERSION_ "4.2.1 Compatible Clang Compiler
#define STIDC_I
9 #define STIDC_I
9 #define STIDC_HOSTED_0
11 #define STIDC_HOSTED_0
12 #define STIDC_HOSTED_0
13 #define SCHAR_MAX_ 127
#define SHRT_MAX_ 32767
15 #define INT_MAX_ 2147483647
#define INT_MAX_ 2147483647
#define LONG_MAX_ 9223372036854775807L
#define LONG_MAX_ 9223372036854775807L
#define INT_MAX_MAX_ 9223372036854775807L
#define INT_MAX_TYPE_long_int
#define INT_MAX_WDTH_ 64
23 #define PIRDIFF_TYPE_ int
#define PIRDIFF_TYPE_ int
#define NIT_MAX_WDTH_ 64
27 #define SIZE_TYPE_ unsigned int
#define SIZE_TYPE_ unsigned int
#define WCHAR_WIDH_ 32
4 #define WCHAR_WIDH_ 32
4 #define WCHAR_WIDH_ 32
4 #define WCHAR_WIDH_ 32
4 #define FIT_DENORM_MIN_ 1.40129846e-45F
4 #define FIT_DENORM_MIN_ 1.40129846e-45F
4 #define FIT_HAS_DENORM_ 1
#define FIT_HAS_DENORM_ 1
#define FIT_HAS_DENORM_ 1
#define FIT_MAX_ 10_EXP_ 38
#define FIT_MAX_ 10_EXP_ 38
#define FIT_MAX_ 10_EXP_ 38
#define FIT_MAX_ 10_EXP_ 138
#define DBL_HAS_DENORM_ 1
#define DBL_HAS_DEN
                   5 #define _
                                                                                                                                                     GNUC 4
GXX_ABI_VERSION 1002
                                          #define
                                                                                                                                                        VERSION___ "4.2.1 Compatible Clang Compiler"
```

```
LDBL_DIG___15

LDBL_EPSILON____2.2204460492503131e-
LDBL_HAS_INFINITY___1

LDBL_HAS_QUIET_NAN___1

LDBL_MANT_DIG___53

LDBL_MAX_I0_EXP___308

LDBL_MAX_EXP___1024

LDBL_MAX_EXP___1024

LDBL_MIN__1.7976931348623157e+308

LDBL_MIN_EXP___(-307)

LDBL_MIN_EXP___(-1021)

LDBL_MIN__2.2250738585072014e-308

POINTER_WIDTH___64

INT8_TYPE___char

INT16_TYPE___ short

INT32_TYPE__ int

INT64_TYPE__ long int

INT64_C_SUFFIX__L
                                                                            2.2204460492503131e-16
    63 #define
            #define
    65
          #define
           #define
    69 #define
          #define
    73
          #define
            "
#define
          #define
          #define
#define
                              #define
#define
            ..
#define
    81
          #define
            #define
           #define
                              FLT_RADIX 2
DECIMAL_DIG 17
          #define
#define
          #define
#define
                               __CLAMBC _ 1
BYTECODE_API_H
           #define _EXECS_H
#define BC_FEATURES_H
#define EBOUNDS(x)
          #define
#define
                              __PE_H
DISASM_BC_H
           #define
           #define
                               __STDBOOL_H
bool __Bool
true 1
    93 #define
           #define
           #define
                               false 0
           #define
                                    _bool_true_false_are_defined 1
          #define __bool_true_raise_are_defined i
#define force_inline inline __attribute_ (((always_inline))
#define VIRUSNAME_PREFIX(name) const char __clambc_virusname_prefix[] = name;
#define VIRUSNAMES(...) const char *const __clambc_virusnames[] = {_VA_ARGS_}
#define PE_UNPACKER_DECLARE const unit16_t __clambc_kind = BC_PE_UNPACKER;
#define SIGNATURES_DECL_BEGIN struct __Signatures {
#define DECLARE_SIGNATURE(name) const char *name##_sig; __Signature name;
#define SIGNATURES_DECL_END_};
103 #define DECLARE_SIGNATURE(name) const char *name##_sig; __Signature name;
    #define SIGNATURES_DECL_END };
105 #define TARGET(tgt) const unsigned short __Target = (tgt);
    #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short __FuncMin = (m);
107 #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short __FuncMax = (m);
    #define SIGNATURES_DEF_BEGIN static const unsigned __signature_bias =
    __COUNTER__+1;const struct __Signatures Signatures = {
109 #define DEFINE_SIGNATURE(name, hex) .name##_sig = (hex), .name = {_COUNTER__ -
```