

ClamAV Bytecode Compiler

User Manual

## Contents

1	Inst	allation
	1.1	Requirements
	1.2	Obtaining the ClamAV Bytecode Compiler
	1.3	Building
	1.0	1.3.1 Disk space
		1.3.2 Create build directory
	1.4	Testing
	$1.4 \\ 1.5$	Installing
	1.0	
		1.5.1 Structure of installed files
2	Tut	orial
_	2.1	Short introduction to the bytecode language
		2.1.1 Types, variables and constants
		2.1.2 Arrays and pointers
		2.1.3 Arithmetics
		2.1.4 Functions
		2.1.5 Control flow
		2.1.6 Common functions
	0.0	
	2.2	Writing logical signatures
		2.2.1 Structure of a bytecode for algorithmic detection
		2.2.2 Virusnames
		2.2.3 Patterns
		2.2.4 Single subsignature
		2.2.5 Multiple subsignatures
		2.2.6 W32.Polipos.A detector rewritten as bytecode
		2.2.7 Virut detector in bytecode
	2.3	Writing regular expressions in bytecode
		2.3.1 A very simple regular expression
		2.3.2 Named regular expressions
	2.4	Writing unpackers
		2.4.1 Structure of a bytecode for unpacking (and other hooks)
		2.4.2 Detecting clam.exe via bytecode
		2.4.3 Detecting clam.exe via bytecode (disasm)
		2.4.4 A simple unpacker
		2.4.5 Matching PDF javascript
		2.4.6 YC unpacker rewritten as bytecode
3	Usa	<del>-</del>
	3.1	Invoking the compiler
		3.1.1 Compiling C++ files
	3.2	Running compiled bytecode
		3.2.1 ClamBC
		3.2.2 clamscan, clamd
	3.3	Debugging bytecode
		3.3.1 "printf" style debugging
		3.3.2 Single-stepping

ii	Cont	ents
4	ClamAV bytecode language	17
4	4.1 Differences from C99 and GNU C	
	4.2 Limitations	
	4.3 Logical signatures	19
	4.4 Headers and runtime environment	20
5	Bytecode security & portability	21
6	Reporting bugs	23
7	Bytecode API	25
•	7.1 API groups	25
	7.1.1 Bytecode Configuration	$\frac{25}{25}$
	7.1.1 Bytecode Configuration	
	* <del>-</del>	
		37
	7.1.4 Disassembly	
	7.1.5 Engine Queries	38
	7.1.6 Environment	40
	7.1.7 File Operations	44
	7.1.8 JavaScript Normalization	47
	7.1.9 Icon Matcher	48
	7.1.10 Math Operation	49
	7.1.11 PDF Handling	51
	7.1.12 PE Operations	
	7.1.13 Scan Control	
	7.1.14 String Operations	64
8	Copyright and License	67
G	8.1 The ClamAV Bytecode Compiler	
	8.2 Bytecode	
	J.Z. By occode	00
$\mathbf{A}$	Low-Level API Globals	71
	A.0.1 Global Variables	71
В	Low-Level API Structures	<b>73</b>
	B.0.2 cli_exe_info Struct Reference	73
	B.0.3 DIS_fixed Struct Reference	73
	B.0.4 pe_image_data_dir Struct Reference	74
	B.0.5 DIS_arg Struct Reference	74
	B.0.6 pe_image_optional_hdr64 Struct Reference	74
	B.0.7 cli_exe_info Struct Reference	75
	B.0.8 pe_image_section_hdr Struct Reference	76
	B.0.9 cli_pe_hook_data Struct Reference	77
	B.0.10 cli exe section Struct Reference	77
	B.0.11 pe_image_file_hdr Struct Reference	78
	B.0.12 pe_image_optional_hdr32 Struct Reference	79
	B.0.13 DIS_mem_arg Struct Reference	80
	B.0.14 DISASM RESULT Struct Reference	80
	D.O.14 DIDADIVI_ICEDOLI DICUCC RETERICE	80
$\mathbf{C}$	API Headers	81
_	C.0.15 File List	81
	C.0.16 bytecode_api.h File Reference	81
	C.0.17 bytecode_disasm.h File Reference	84
	C.0.17 bytecode_disasin.n File Reference	92
	· ·	
	C.0.19 bytecode_local.h File Reference	93
	C.0.20 bytecode_pe.h File Reference	90

Contents

97

#### D Predefined API Macros

ClamAV Bytecode Compiler - Internals Manual,

 $\ \, \odot$  2014 Cisco Systems, Inc.

© 2009-2013 Sourcefire, Inc.

Authors: Török Edvin, Kevin Lin

This document is distributed under the terms of the GNU General Public License v2.

Clam AntiVirus is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

ClamAV and Clam AntiVirus are trademarks of Cisco Systems, Inc.

iv Contents

## CHAPTER 1 Installation

## 1.1. Requirements

The ClamAV Bytecode Compiler uses the LLVM compiler framework, thus requires an Operating System where building LLVM is supported:

- FreeBSD/x86
- $Linux/\{x86,x86\_64,ppc\}$
- Mac OS  $X/\{x86,ppc\}$
- Solaris/sparcv9
- Windows/x86 using mingw32 or Visual Studio

The following packages are required to compile the ClamAV Bytecode Compiler:

- GCC C and C++ compilers (minimum 4.1.3, recommended: 4.3.4 or newer) <sup>1</sup>.
- Perl (version 5.6.0+)
- GNU make (version 3.79+, recommended 3.81)

The following packages are optional, but highly recommended:

• Python (version 2.5.4+?) - for running the tests

## 1.2. Obtaining the ClamAV Bytecode Compiler

You can obtain the source code in one of the following ways <sup>2</sup>

- Check out the source code using git native protocol: git clone git://git.clamav.net/git/clamav-bytecode-compiler
- Check out the source code using HTTP:

```
git clone http://git.clamav.net/git/clamav-bytecode-compiler.git
```

You can keep the source code updated using: git pull

<sup>&</sup>lt;sup>1</sup>Note that several versions of GCC have bugs when compiling LLVM, see http://llvm.org/docs/GettingStarted.html#brokengcc for a full list. Also LLVM requires support for atomic builtins for multithreaded mode, which gcc 3.4.x doesn't have

<sup>&</sup>lt;sup>2</sup>For now the use the internal clamtools repository: git clone username@git.clam.sourcefire.com:/var/lib/git/clamtools.git

2 1.3. Building

#### 1.3. Building

#### 1.3.1. Disk space

A minimalistic release build requires 100M of disk space.

Testing the compiler requires a full build, 320M of disk space. A debug build requires significantly more disk space (1.4G for a minimalistic debug build).

Note that this only needed during the build process, once installed only 12M is needed.

#### **1.3.2.** Create build directory

Building requires a separate object directory, building in the source directory is not supported. Create a build directory:

```
$ cd clamav-bytecode-compiler && mkdir obj
Run configure (you can use any prefix you want, this example uses /usr/local/clamav):
$ cd obj && ../llvm/configure --enable-optimized \
    --enable-targets=host-only --disable-bindings \
    --prefix=/usr/local/clamav
Run the build under ulimit 1:
```

## 1.4. Testing

```
$ (ulimit -t 3600 v 512000 && make -j4)
$ make check-all
```

\$ (ulimit -t 3600 -v 512000 && make clambc-only -j4)

If make check reports errors, check that your compiler is NOT on this list: http://llvm.org/docs/GettingStarted.html#brokengcc.

If it is, then your compiler is buggy, and you need to do one of the following: upgrade your compiler to a non-buggy version, upgrade the OS to one that has a non-buggy compiler, compile with export OPTMIZE\_OPTION=-02, or export OPTIMIZE\_OPTION=-01, or export OPTIMIZE\_OPTION=\-01.

If not you probably found a bug, report it at http://bugs.clamav.net

## 1.5. Installing

Install it:

```
$ make install-clambc -j8
```

#### 1.5.1. Structure of installed files

- 1. The ClamAV Bytecode compiler driver: \$PREFIX/bin/clambc-compiler
- 2. ClamAV bytecode header files:

```
$PREFIX/lib/clang/1.1/include:
bcfeatures.h
bytecode_{api_decl.c,api,disasm,execs,features}.h
bytecode.h
bytecode_{local,pe,types}.h
```

3. clang compiler (with ClamAV bytecode backend) compiler include files:

<sup>&</sup>lt;sup>1</sup>compiling some files can be very memory intensive, especially with older compilers

Chapter 1. Installation

```
$PREFIX/lib/clang/1.1/include:
emmintrin.h
float.h
iso646.h
limits.h
{,p,t,x}mmintrin.h
mm_malloc.h
std{arg,bool,def,int}.h
tgmath.h
```

4. User manual

\$PREFIX/docs/clamav/clambc-user.pdf

4 1.5. Installing

## CHAPTER 2 Tutorial

## 2.1. Short introduction to the bytecode language

- 2.1.1. Types, variables and constants
- 2.1.2. Arrays and pointers
- 2.1.3. Arithmetics
- 2.1.4. Functions
- 2.1.5. Control flow
- **2.1.6.** Common functions

## 2.2. Writing logical signature bytecodes

A bytecode triggered by a logical signature is much more powerful than a logical signature itself: you can write complex algorithmic detections, and use the logical signature as a *filter* (to speed up matching). Thus another name for "logical signature bytecodes" is "algorithmic detection bytecodes". The detection you write in bytecode has read-only access to the file being scanned and its metadata (PE sections, EP, etc.).

#### **2.2.1.** Structure of a bytecode for algorithmic detection

Algorithmic detection bytecodes are triggered when a logical signature matches. They can execute an algorithm that determines whether the file is infected and with which virus.

A bytecode can be either algorithmic or an unpacker (or other hook), but not both. It consists of:

- Definition of virusnames used in the bytecode
- Pattern definitions (for logical subexpressions)
- The logical signature as C function: bool logical\_trigger(void)
- The int entrypoint(void) function which gets executed when the logical signature matches
- (Optional) Other functions and global constants used in entrypoint

The syntax for defining logical signatures, and an example is described in Section 2.2.4.

The function entrypoint must report the detected virus by calling foundVirus and returning 0. It is recommended that you always return 0, otherwise a warning is shown and the file is considered clean. If foundVirus is not called, then ClamAV also assumes the file is clean.

<sup>&</sup>lt;sup>1</sup> Logical signatures can be used as triggers for executing bytecode. However, instead of describing a logical signature as a .ldb pattern, you use (simple) C code which is later translated to a .ldb-style logical signature by the ClamAV Bytecode Compiler.

<sup>&</sup>lt;sup>1</sup>See Section 4.3 for more details about logical signatures in bytecode.

#### 2.2.2. Virusnames

Each logical signature bytecode must have a virusname prefix, and one or more virusnames. The virusname prefix is used by the SI to ensure unique virusnames (a unique number is appended for duplicate prefixes).

#### Program 1 Declaring virusnames

```
1 /* Prefix, used for duplicate detection and fixing */
VIRUSNAME_PREFIX("Trojan.Foo")
3 /* You are only allowed to set these virusnames as found */
VIRUSNAMES("A", "B")
5 /* File type */
TARGET(2)
```

In Program 1 3 predefied macros are used:

- VIRUSNAME\_PREFIX which must have exactly one string argument
- VIRUSNAMES which must have one or more string arguments
- TARGET which must have exactly one integer argument

In this example, the bytecode could generate one of these virusnames: Trojan.Foo.A, or Trojan.Foo.B, by calling foundVirus("A") or foundVirus("B") respectively (notice that the prefix is not part of these calls).

#### 2.2.3. Patterns

Logical signatures use .ndb style patterns, an example on how to define these is shown in Program 2.

#### Program 2 Declaring patterns

```
SIGNATURES_DECL_BEGIN

DECLARE_SIGNATURE(magic)
DECLARE_SIGNATURE(check)

DECLARE_SIGNATURE(zero)
SIGNATURES_DECL_END

SIGNATURES_DEF_BEGIN
DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(check, "f00d")

DEFINE_SIGNATURE(zero, "fffff")
SIGNATURES_END
```

Each pattern has a name (like a variable), and a string that is the hex pattern itself. The declarations are delimited by the macros SIGNATURES\_DECL\_BEGIN, and SIGNATURES\_DECL\_END. The definitions are delimited by the macros SIGNATURES\_DEF\_BEGIN, and SIGNATURES\_END. Declarations must always come before definitions, and you can have only one declaration and declaration section! (think of declaration like variable declarations, and definitions as variable assignments, since that what they are under the hood). The order in which you declare the signatures is the order in which they appear in the generated logical signature.

You can use any name for the patterns that is a valid record field name in C, and doesn't conflict with anything else declared.

After using the above macros, the global variable Signatures will have two new fields: magic, and zero. These can be used as arguments to the functions count\_match(), and matches() anywhere in the program as shown in Program 3:

- matches (Signatures.match) will return true when the match signature matches (at least once)
- count\_match(Signatures.zero) will return the number of times the zero signature matched
- count\_match(Signatures.check) will return the number of times the check signature matched

The condition in the if can be interpreted as: if the match signature has matched at least once, and the number of times the zero signature matched is higher than the number of times the check signature matched, then we have found a virus A, otherwise the file is clean.

Chapter 2. Tutorial

#### Program 3 Using patterns

```
int entrypoint(void)
{
   if (matches(Signatures.match) && count_match(Signatures.zero) >
        count_match(Signatures.check))
      foundVirus("A");
   return 0;
}
```

#### 2.2.4. Single subsignature

The simplest logical signature is like a .ndb signature: a virus name, signature target, 0 as logical expression <sup>1</sup>, and a ndb-style pattern.

The code for this is shown in Program 4

#### Program 4 Single subsignature example

```
/* Declare the prefix of the virusname */
vIRUSNAME_PREFIX("Trojan.Foo")
  /* Declare the suffix of the virusname */
4 VIRUSNAMES ("A")
  /* Declare the signature target type (1 = PE) */
6 TARGET (1)
  /* Declare the name of all subsignatures used */
  SIGNATURES_DECL_BEGIN
10 DECLARE_SIGNATURE(magic)
  SIGNATURES_DECL_END
/* Define the pattern for each subsignature */ ^{\rm 14} SIGNATURES_DEF_BEGIN
  DEFINE_SIGNATURE(magic, "aabb")
16 SIGNATURES_END
18 /* All bytecode triggered by logical signatures must have this
     function */
  bool logical_trigger(void)
    /* return true if the magic subsignature matched,
22
     * its pattern is defined above to "aabb" */
    return count_match(Signatures.magic) != 2;
24
  }
26
  /* This is the bytecode function that is actually executed when the logical
   * signature matched */
  int entrypoint(void)
30 {
    /* call this function to set the suffix of the virus found */
    foundVirus("A");
32
    /* success, return 0 */
    return 0;
34
```

The logical signature (created by the compiler) looks like this: Trojan.Foo.{A}; Target:2;0; aabb Of course you should use a .ldb signature in this case when all the processing in entrypoint is only setting a virusname and returning. However, you can do more complex checks in entrypoint, once the bytecode was triggered by the logical\_trigger

In the example in Program 4 the pattern was used without an anchor; such a pattern matches at any offset. You can use offsets though, the same way as in .ndb signatures, see Program 5 for an example.

<sup>&</sup>lt;sup>1</sup>meaning that subexpression 0 must match

#### 2.2.5. Multiple subsignatures

An example for this is shown in Program 5. Here you see the following new features used: 1

- Multiple virusnames returned from a single bytecode (with common prefix)
- Multiple subsignatures, each with a name of your choice
- A pattern with an anchor (EP+0:aabb)
- More subsignatures defined than used in the logical expression

The logical signature looks like this:

 $Trojan.Foo.\{A,B\}; Target:2; (((0|1|2)=42,2)|(3=10)); EP+0:aabb; ffff; aaccee; f00d; dead$ 

Notice how the subsignature that is not used in the logical expression (number 4, dead) is used in entrypoint to decide the virus name. This works because ClamAV does collect the match counts for all subsignatures (regardless if they are used or not in a signature). The count\_match(Signatures.check2) call is thus a simple memory read of the count already determined by ClamAV.

Also notice that comments can be used freely: they are ignored by the compiler. You can use either C-style multiline comments (start comment with /\*, end with \*/), or C++-style single-line comments (start comment with //, automatically ended by newline).

#### 2.2.6. W32.Polipos.A detector rewritten as bytecode

#### 2.2.7. Virut detector in bytecode

## 2.3. Writing regular expressions in bytecode

ClamAV only supports a limited set of regular expressions in .ndb format : wildcards. The bytecode compiler allows you to compile fully generic regular expressions to bytecode directly. When libclamav loads the bytecode, it will compile to native code (if using the JIT), so it should offer quite good performance.

The compiler currently uses re2c to compile regular expressions to C code, and then compile that to bytecode. The internal workings are all transparent to the user: the compiler automatically uses re2c when needed, and re2c is embedded in the compiler, so you don't need to install it.

The syntax of regular expressions are similar to the one used by POSIX regular expressions, except you have to quote literals, since unquoted they are interpreted as regular expression names.

#### 2.3.1. A very simple regular expression

Lets start with a simple example, to match this POSIX regular expression: eval( $[a-zA-Z_]$ [ $a-zA-Z0-9_]*\.$ unescape. See Program 6 <sup>2</sup>.

There are several new features introduced here, here is a step by step breakdown:

REGEX\_SCANNER this declares the data structures needed by the regular expression matcher

- seek(0, SEEK\_SET) this sets the current file offset to position 0, matching will start at this position. For offset 0 it is not strictly necessary to do this, but it serves as a reminder that you might want to start matching somewhere, that is not necessarily 0.
- for(;;) { REGEX\_LOOP\_BEGIN this creates the regular expression matcher main loop. It takes the current file byte-by-byte <sup>3</sup> and tries to match one of the regular expressions.
- /\*!re2c This mark the beginning of the regular expression description. The entire regular expression block is a C comment, starting with !re2c
- ANY = [^]; This declares a regular expression named ANY that matches any byte.
- "eval("[a-zA-Z\_] [a-zA-Z\_0-9]\*".unescape" { This is the actual regular expression.

<sup>&</sup>lt;sup>1</sup>In case of a duplicate virusname the prefix is appended a unique number by the SI

<sup>&</sup>lt;sup>2</sup>This omits the virusname, and logical signature declarations

<sup>&</sup>lt;sup>3</sup>it is not really reading byte-by-byte, it is using a buffer to speed things up

g

#### Program 5 Multiple subsignatures

```
/* You are only allowed to set these virusnames as found */
  VIRUSNAME_PREFIX("Test")
3 VIRUSNAMES("A", "B")
  TARGET (1)
  SIGNATURES_DECL_BEGIN
7 DECLARE_SIGNATURE(magic)
  DECLARE_SIGNATURE(zero)
9 DECLARE_SIGNATURE(check)
  DECLARE_SIGNATURE(fivetoten)
11 DECLARE_SIGNATURE (check2)
  SIGNATURES_DECL_END
13
  SIGNATURES_DEF_BEGIN
15 DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(zero, "fffff")
17 DEFINE_SIGNATURE(fivetoten, "aaccee")
DEFINE_SIGNATURE(check, "f00d")
19 DEFINE_SIGNATURE(check2, "dead")
  SIGNATURES_END
21
  bool logical_trigger(void)
23 {
       unsigned sum_matches = count_match(Signatures.magic)+
           count_match(Signatures.zero) + count_match(Signatures.fivetoten);
25
       unsigned unique_matches = matches(Signatures.magic)+
                matches(Signatures.zero)+ matches(Signatures.fivetoten);
       if (sum_matches == 42 && unique_matches == 2) {
           // The above 3 signatures have matched a total of 42 times, and at least // 2 of them have matched
29
           return true;
31
       // If the check signature matches 10 times we still have a match
33
       if (count_match(Signatures.check) == 10)
35
           return true;
       // No match
       return false;
37
  }
39
  int entrypoint(void)
41 {
       unsigned count = count_match(Signatures.check2);
       if (count >= 2)
43
           foundVirus(count = 2 ? "A" : "B");
         if (count == 2)
45
           foundVirus("A");
         else
47
           foundVirus("B");
       return 0;
49
```

10 2.4. Writing unpackers

#### Program 6 Simple regular expression example

```
int entrypoint(void)
  {
2
       REGEX_SCANNER;
       seek(0, SEEK_SET);
       for (;;) {
           REGEX_LOOP_BEGIN
6
             /* !re2c
                ANY = [^];
                 "eval("[a-zA-Z_][a-zA-Z_0-9]*".unescape" {
                    long pos = REGEX_POS;
12
                    if (pos < 0)
                      continue;
14
                    debug("unescape found at:");
                    debug (pos);
16
                ANY { continue; }
20
       return 0;
22 }
```

"eval(" This matches the literal string eval(. Literals have to be placed in double quotes " here, unlike in POSIX regular expressions or PCRE. If you want case-insensitive matching, you can use '.

[a-zA-Z\_] This is a character class, it matches any lowercase, uppercase or \_ characters.

[a-zA-Z\_0-9]\*" Same as before, but with repetition. \* means match zero or more times, + means match one or more times, just like in POSIX regular expressions.

".unescape" A literal string again

{ start of the action block for this regular expression. Whenever the regular expression matches, the attached C code is executed.

long pos = REGEX\_POS; this determines the absolute file offset where the regular expression has matched.
Note that because the regular expression matcher uses a buffer, using just seek(0, SEEK\_CUR)
would give the current position of the end of that buffer, and not the current position during regular
expression matching. You have to use the REGEX\_POS macro to get the correct position.

debug(...) Shows a debug message about what was found and where. This is extremely helpful when you start writing regular expressions, and nothing works: you can determine whether your regular expression matched at all, and if it matched where you thought it would. There is also a DEBUG\_PRINT\_MATCH that prints the entire matched string to the debug output. Of course before publishing the bytecode you might want to turn off these debug messages.

} closes the action block for this regular expression

ANY { continue; } If none of the regular expressions matched so far, just keep running the matcher, at the next byte

\*/ closes the regular expression description block

} closes the for() loop

You may have multiple regular expressions, or declare multiple regular expressions with a name, and use those names to build more complex regular expressions.

#### 2.3.2. Named regular expressions

## 2.4. Writing unpackers

#### **2.4.1.** Structure of a bytecode for unpacking (and other hooks)

When writing an unpacker, the bytecode should consist of:

Chapter 2. Tutorial 11

- Define which hook you use (for example PE\_UNPACKER\_DECLARE for a PE hook)
- An int entrypoint(void) function that reads the current file and unpacks it to a new file
- Return 0 from entrypoint if you want the unpacked file to be scanned
- (Optional) Other functions and global constants used by entrypoint

#### 2.4.2. Detecting clam.exe via bytecode

Example provided by aCaB:

#### 2.4.3. Detecting clam.exe via bytecode (disasm)

Example provided by aCaB:

#### 2.4.4. A simple unpacker

#### 2.4.5. Matching PDF javascript

#### 2.4.6. YC unpacker rewritten as bytecode

12 2.4. Writing unpackers

# CHAPTER 3 Usage

## 3.1. Invoking the compiler

Compiling is similar to gcc <sup>1</sup>:

\$ /usr/local/clamav/bin/clambc-compiler foo.c -o foo.cbc -02

This will compile the file foo.c into a file called foo.cbc, that can be loaded by ClamAV, and packed inside a .cvd file.

The compiler by default has all warnings turned on.

Supported optimization levels: -00, -01, -02, -03. It is recommended that you always compile with at least -01.

Warning options: -Werror (transforms all warnings into errors).

Preprocessor flags:

- -I <directory> Searches in the given directory when it encounters a #include "headerfile" directive in the source code, in addition to the system defined header search directories.
- -D <MACRONAME>=<VALUE> Predefine given <MACRONAME> to be equal to <VALUE>.
- -U <MACRONAME> Undefine a predefined macro

The compiler also supports some other commandline options (see clambc-compiler --help for a full list), however some of them have no effect when using the ClamAV bytecode backend (such as the X86 backend options). You shouldn't need to use any flags not documented above.

#### **3.1.1.** Compiling C++ files

Filenames with a .cpp extension are compiled as C++ files, however clang++ is not yet ready for production use, so this is EXPERIMENTAL currently. For now write bytecodes in C.

## 3.2. Running compiled bytecode

After compiling a C source file to bytecode, you can load it in ClamAV:

#### **3.2.1.** ClamBC

ClamBC is a tool you can use to test whether the bytecode loads, compiles, and can execute its entrypoint successfully. Usage:

```
clambc <file> [function] [param1 ...]
```

For example loading a simple bytecode with 2 functions is done like this:

<sup>&</sup>lt;sup>1</sup>Note that the ClamAV bytecode compiler will refuse to compile code it considers insecure

 $<sup>^2</sup>$ Currently -O0 doesn't work

3.3. Debugging bytecode

```
$ clambc foo.cbc
LibClamAV debug: searching for unrar, user-searchpath: /usr/local/lib
LibClamAV debug: unrar support loaded from libclamunrar_iface.so.6.0.4 libclamunrar_iface_so_6_0
LibClamAV debug: bytecode: Parsed 0 APIcalls, maxapi 0
LibClamAV debug: Parsed 1 BBs, 2 instructions
LibClamAV debug: Parsed 1 BBs, 2 instructions
LibClamAV debug: Parsed 2 functions
Bytecode loaded
Running bytecode function :0
Bytecode run finished
Bytecode returned: 0x8
Exiting
```

#### 3.2.2. clamscan, clamd

You can tell clamscan to load the bytecode as a database directly:

```
$ clamscan -dfoo.cbc
```

Or you can instruct it to load all databases from a directory, then clamscan will load all supported formats, including files with bytecode, which have the .cbc extension.

```
$ clamscan -ddirectory
```

You can also put the bytecode files into the default database directory of ClamAV (usually /usr/local/share/clamav) to have it loaded automatically from there. Of course, the bytecode can be stored inside CVD files, too.

## 3.3. Debugging bytecode

#### **3.3.1.** "printf" style debugging

Printf, and printf-like format specifiers are not supported in the bytecode. You can use these functions instead of printf to print strings and integer to clamscan's —debug output:

```
debug_print_str, debug_print_uint, debug_print_str_start, debug_print_str_nonl.
```

You can also use the debug convenience wrapper that automatically prints as string or integer depending on parameter type: debug, debug, debug.

See Program 7 for an example.

#### 3.3.2. Single-stepping

If you have GDB 7.0 (or newer) you can single-step <sup>1 2</sup> during the execution of the bytecode.

• Run clambc or clamscan under gdb:

```
$ ./libtool --mode=execute gdb clamscan/clamscan
...
(gdb) b cli_vm_execute_jit
Are you sure ....? y
(gdb) run -dfoo.cbc
...
Breakpoint ....
(gdb) step
(gdb) next
```

You can single-step through the execution of the bytecode, however you can't (yet) print values of individual variables, you'll need to add debug statements in the bytecode to print interesting values.

<sup>&</sup>lt;sup>1</sup>not yet implemented in libclamav

<sup>&</sup>lt;sup>2</sup>assuming you have JIT support

Chapter 3. Usage

#### **Program 7** Example of using debug APIs

```
/* test debug APIs */
2 int entrypoint(void)
    /* print a debug message, followed by newline */
    debug_print_str("bytecode started", 16);
    /* start a new debug message, don't end with newline yet */
    debug_print_str_start("Engine functionality level: ", 28);
    /* print an integer, no newline */
    debug_print_uint(engine_functionality_level());
10
    /\ast print a string without starting a new debug message, and without
     * terminating with newline */
    debug_print_str_nonl(", dconf functionality level: ", 28);
    debug_print_uint(engine_dconf_level());
    debug_print_str_nonl("\n", 1);
    debug_print_str_start("Engine scan options: ", 21);
    debug_print_uint(engine_scan_options());
    debug_print_str_nonl(", db options: ", 13);
18
    debug_print_uint(engine_db_options());
    debug_print_str_nonl("\n", 1);
    /* convenience wrapper to just print a string */
    debug("just print a string");
    /* convenience wrapper to just print an integer */
24
    debug(4);
    return OxfOOd;
26
```

16 3.3. Debugging bytecode

## CHAPTER 4

## ClamAV bytecode language

The bytecode that ClamAV loads is a simplified form of the LLVM Intermediate Representation, and as such it is language-independent.

However currently the only supported language from which such by tecode can be generated is a simplified form of C  $^{\rm 1}$ 

The language supported by the ClamAV bytecode compiler is a restricted set of C99 with some GNU extensions.

#### 4.1. Differences from C99 and GNU C

These restrictions are enforced at compile time:

- No standard include files. <sup>2</sup>
- The ClamAV API header files are preincluded.
- No external function calls, except to the ClamAV API <sup>3</sup>
- No inline assembly <sup>4</sup>
- Globals can only be readonly constants <sup>5</sup>
- inline is C99 inline (equivalent to GNU C89 extern inline), thus it cannot be used outside of the definition of the ClamAV API, you should use static inline
- sizeof(int) == 4 always
- sizeof(long) == sizeof(long long) == 8 always
- ptr\_diff\_t = int, intptr\_t = int, intmax\_t = long, uintmax\_t = unsigned long 6
- No pointer to integer casts and integer to pointer casts (pointer arithmetic is allowed though)
- No \_\_thread support
- Size of memory region associated with each pointer must be known in each function, thus if you pass a pointer to a function, you must also pass its allocated size as a parameter.
- Endianness must be handled via the \_\_is\_bigendian() API function call, or via the cli\_{read,write}int{16,32} wrappers, and not by casting pointers
- Predefines \_\_CLAMBC\_\_
- All integer types have fixed width

<sup>&</sup>lt;sup>1</sup>In the future more languages could be supported, see the Internals Manual on language frontends

<sup>&</sup>lt;sup>2</sup>For portability reasons: preprocessed C code is not portable

 $<sup>^3</sup>$ For safety reasons we can't allow the bytecode to call arbitrary system functions

<sup>&</sup>lt;sup>4</sup>This is both for safety and portability reasons

<sup>&</sup>lt;sup>5</sup>For thread safety reasons

 $<sup>^6</sup>$ Note that a pointer's size of is runtime-platform dependent, although at compile time size of(void\*) == 4, at runtime it can be something else. Thus you should avoid using size of(pointer)

4.2. Limitations

• main or entrypoint must have the following prototype: int main(void), the prototype int main(int argc, char is not accepted

They are meant to ensure the following:

- Thread safe execution of multiple different bytecodes, and multiple instances of the same bytecode
- Portability to multiple CPU architectures and OSes: the bytecode must execute on both the libclamav/LLVM JIT where that is supported (x86, x86\_64, ppc, arm?), and on the libclamav interpreter where that is not supported.
- No external runtime dependency: libclamav should have everything needed to run the bytecode, thus no external calls are allowed, not even to libc!
- Same behaviour on all platforms: fixed size integers.

These restrictions are checked at runtime (checks are inserted at compile time):

- Accessing an out-of-bounds pointer will result in a call to abort()
- Calling abort() interrupts the execution of the bytecode in a thread safe manner, and doesn't halt ClamAV <sup>1</sup>.

The ClamAV API header has further restriction, see the Internals manual.

Although the bytecode undergoes a series of automated tests (see Publishing chapter in Internals manual), the above restrictions don't guarantee that the resulting bytecode will execute correctly! You must still test the code yourself, these restrictions only avoid the most common errors. Although the compiler and verifier aims to accept only code that won't crash ClamAV, no code is 100% perfect, and a bug in the verifier could allow unsafe code be executed by ClamAV.

#### 4.2. Limitations

The bytecode format has the following limitations:

- At most 64k bytecode kinds (hooks)
- At most 64k types (including pointers, and all nested types)
- At most 16 parameters to functions, no vararg functions
- At most 64-bit integers
- No vector types or vector operations
- No opaque types
- No floating point
- Global variable initializer must be compile-time computable
- At most 32k global variables (and at most 32k API globals)
- Pointer indexing at most 15 levels deep (can be worked around if needed by using temporaries)
- No struct return or byval parameters
- At most 32k instructions in a single function
- No Variable Length Arrays

<sup>&</sup>lt;sup>1</sup>in fact it calls a ClamAV API function, and not the libc abort function.

## 4.3. Logical signatures

Logical signatures can be used as triggers for executing a bytecode. Instead of describing a logical signatures as a .ldb pattern, you use C code which is then translated to a .ldb-style logical signature. Logical signatures in ClamAV support the following operations:

- Sum the count of logical subsignatures that matched inside a subexpression
- Sum the number of different subsignatures that matched inside a subexpression
- Compare the above counts using the >, =, < relation operators
- Perform logical &&, || operations on above boolean values
- Nest subexpressions
- Maximum 64 subexpressions

Out of the above operations the ClamAV Bytecode Compiler doesn't support computing sums of nested subexpressions, (it does support nesting though).

The C code that can be converted into a logical signature must obey these restrictions:

- a function named logical\_trigger with the following prototype: bool logical\_trigger(void)
- no function calls, except for count\_match and matches
- no global variable access (except as done by the above 2 functions internally)
- return true when signature should trigger, false otherwise
- use only integer compare instructions, branches, integer add, logical and, logical or, logical xor, zero extension, store/load from local variables
- the final boolean expression must be convertible to disjunctive normal form without negation
- the final logical expression must not have more than 64 subexpressions
- it can have early returns (all true returns are unified using  $\mid\mid$ )
- you can freely use comments, they are ignored
- the final boolean expression cannot be a true or false constant

The compiler does the following transformations (not necessarily in this order):

- convert shortcircuit boolean operations into non-shortcircuit ones (since all operands are boolean expressions or local variables, it is safe to execute these unconditionally)
- propagate constants
- simplify control flow graph
- (sparse) conditional constant propagation
- dead store elimination
- dead code elimination
- instruction combining (arithmetic simplifications)
- jump threading

If after this transformation the program meets the requirements outlined above, then it is converted to a logical signature. The resulting logical signature is simplified using basic properties of boolean operations, such as associativity, distributivity, De Morgan's law.

The final logical signature is not unique (there might be another logical signature with identical behavior), however the boolean part is in a canonical form: it is in disjunctive normal form, with operands sorted in ascending order.

For best results the C code should consist of:

- local variables declaring the sums you want to use
- a series of if branches that return true, where the if's condition is a single comparison or a logical and of comparisons
- a final return false

You can use || in the if condition too, but be careful that after expanding to disjunctive normal form, the number of subexpressions doesn't exceed 64.

Note that you do not have to use all the subsignatures you declared in logical\_trigger, you can do more complicated checks (that wouldn't obey the above restrictions) in the bytecode itself at runtime. The logical\_trigger function is fully compiled into a logical signature, it won't be a runtime executed function (hence the restrictions).

#### 4.4. Headers and runtime environment

When compiling a bytecode program, bytecode.h is automatically included, so you don't need to explicitly include it. These headers (and the compiler itself) predefine certain macros, see Appendix D for a full list. In addition the following types are defined:

```
typedef unsigned char uint8_t;
typedef char int8_t;
typedef unsigned short uint16_t;

4 typedef short int16_t;
typedef unsigned int uint32_t;
6 typedef int int32_t;
typedef unsigned long uint64_t;
8 typedef long int64_t;
typedef unsigned int size_t;
10 typedef int off_t;
typedef struct signature { unsigned id } __Signature;
```

As described in Section 4.1 the width of integer types are fixed, the above typedefs show that.

A bytecode's entrypoint is the function entrypoint and it's required by ClamAV to load the bytecode. Bytecode that is triggered by a logical signature must have a list of virusnames and patterns defined. Bytecodes triggered via hooks can optionally have them, but for example a PE unpacker doesn't need virus names as it only processes the data.

# CHAPTER 5 Bytecode security & portability

# CHAPTER 6 Reporting bugs

# CHAPTER 7 Bytecode API

## 7.1. API groups

#### 7.1.1. Bytecode Configuration

#### Macros

```
• #define VIRUSNAME_PREFIX(name) const char ___clambc_virusname_prefix[] = name;
```

- #define VIRUSNAMES(...) const char \*const \_\_\_clambc\_virusnames[] = {\_\_\_VA\_ARGS\_\_\_};
- #define PE\_UNPACKER\_DECLARE const uint16\_t \_\_clambc\_kind = BC\_PE\_UNPACKER;
- #define PDF\_HOOK\_DECLARE const uint16\_t \_\_clambc\_kind = BC\_PDF;
- #define PE\_HOOK\_DECLARE const uint16\_t \_\_clambc\_kind = BC\_PE\_ALL;
- #define SIGNATURES\_DECL\_BEGIN struct \_\_\_Signatures {
- #define DECLARE\_SIGNATURE(name)
- #define SIGNATURES\_DECL\_END };
- #define TARGET(tgt) const unsigned short \_\_\_Target = (tgt);
- #define COPYRIGHT(c) const char \*const \_\_\_Copyright = (c);
- #define ICONGROUP1(group) const char \*const \_\_\_IconGroup1 = (group);
- $\bullet \ \ \# define \ ICONGROUP2 (group) \ const \ char \ *const \ \_\_IconGroup2 = (group);$
- #define FUNCTIONALITY\_LEVEL\_MIN(m) const unsigned short \_\_\_FuncMin = (m);
- #define FUNCTIONALITY\_LEVEL\_MAX(m) const unsigned short \_\_\_FuncMax = (m);
- #define SIGNATURES DEF BEGIN
- #define SIGNATURES DEF END };

#### **Enumerations**

```
enum BytecodeKind {
    BC_GENERIC =0, BC_STARTUP =1, BC_LOGICAL =256, BC_PE_UNPACKER,
    BC_PDF, BC_PE_ALL }
enum FunctionalityLevels {
    FUNC_LEVEL_096 = 51, FUNC_LEVEL_096_1 = 53, FUNC_LEVEL_096_2 = 54, FUNC_LEVEL_096_3 = 55,
    FUNC_LEVEL_096_4 = 56, FUNC_LEVEL_096_5 = 58, FUNC_LEVEL_097 = 60, FUNC_LEVEL_097_1 = 61,
    FUNC_LEVEL_097_2 = 62, FUNC_LEVEL_097_3 = 63, FUNC_LEVEL_097_4 = 64, FUNC_LEVEL_097_5 = 65,
    FUNC_LEVEL_097_6 = 67, FUNC_LEVEL_097_7 = 68, FUNC_LEVEL_097_8 = 69, FUNC_LEVEL_098 = 74,
```

```
__LEVEL__036 = 74,
FUNC_LEVEL__098__1 = 76, FUNC__LEVEL__098__2 = 78 }
```

7.1. API groups

#### **Detailed Description**

Macro Definition Documentation

#define COPYRIGHT(c) const char \*const \_\_\_Copyright = (c); Defines an alternative copyright for this bytecode.

This will also prevent the sourcecode from being embedded into the bytecode.

#define DECLARE\_SIGNATURE( name ) Value:

```
const char *name##_sig;\
    __Signature name;
```

Declares a name for a subsignature.

#define FUNCTIONALITY\_LEVEL\_MAX(m) const unsigned short \_\_\_FuncMax = (m); Define the maximum engine functionality level required for this bytecode/logical signature. Engines newer than this will skip loading the bytecode. You can use the FunctionalityLevels enumeration here.

#define FUNCTIONALITY\_LEVEL\_MIN(m) const unsigned short \_\_\_FuncMin = (m); Define the minimum engine functionality level required for this bytecode/logical signature. Engines older than this will skip loading the bytecode. You can use the FunctionalityLevels enumeration here.

See logical signature documentation for what it is.

#define ICONGROUP2( group ) const char \*const \_\_\_IconGroup2 = (group); Define IconGroup2 for logical signature.

See logical signature documentation for what it is.

#define PDF\_HOOK\_DECLARE const uint16\_t \_\_\_clambc\_kind = BC\_PDF; Make the current bytecode a PDF hook.

Having a logical signature doesn't make sense here, since the logical signature is evaluated AFTER these hooks run.

This hook is called several times, use pdf get phase() to find out in which phase you got called.

#define PE\_HOOK\_DECLARE const uint16\_t \_\_\_clambc\_kind = BC\_PE\_ALL; Make the current bytecode a PE hook.

Bytecode will be called once the logical signature trigger matches (or always if there is none), and if you have access to all the PE information. By default you only have access to execs.h information, and not to PE field information (even for PE files).

#define PE\_UNPACKER\_DECLARE const uint16\_t \_\_clambc\_kind = BC\_PE\_UN-PACKER; Like PE\_HOOK\_DECLARE, but it is not run for packed files that pe.c can unpack (only on the unpacked file).

#define SIGNATURES\_DECL\_BEGIN struct \_\_\_Signatures { Marks the beginning of the subsignature name declaration section.

Chapter 7. Bytecode API

# define SIGNATURES\_DECL\_END  $\}$ ; Marks the end of the subsignature name declaration section.

#### #define SIGNATURES\_DEF\_BEGIN Value:

```
static const unsigned __signature_bias = __COUNTER__+1;\ const struct __Signatures Signatures = {\
```

Marks the beginning of subsignature pattern definitions.

See Also

SIGNATURES DECL BEGIN

#define SIGNATURES\_DEF\_END }; Marks the end of the subsignature pattern definitions. Alternative: SIGNATURES\_END

#define TARGET( tgt ) const unsigned short \_\_\_Target = (tgt); Defines the ClamAV file target.

Parameters

in $tgt \mid \text{ClamAV signature type } (0 - \text{raw}, 1 - \text{PE}, \text{etc.})$
--

#define VIRUSNAME\_PREFIX( name ) const char \_\_\_clambc\_virusname\_prefix[] = name; Declares the virusname prefix.

Parameters

in	name	the prefix common to all viruses reported by this bytecode
----	------	--

 $\# define \ VIRUSNAMES( \ \dots \ ) \ const \ char * const \_\_clambc\_virusnames[] = \{ \_\_VA\_-ARGS\_\_ \}; \ \ Declares \ all \ the \ virusnames \ that \ this \ bytecode \ can \ report.$ 

Parameters

in	 a comma-separated list of strings interpreted as virusnames

#### **Enumeration Type Documentation**

enum BytecodeKind Specifies the bytecode type and how ClamAV executes it

#### Enumerator

 $BC\_GENERIC$  generic bytecode, not tied a specific hook

BC\_STARTUP triggered at startup, only one is allowed per ClamAV startup

 $BC\_LOGICAL$  executed on a logical trigger

BC\_PE\_UNPACKER specifies a PE unpacker, executed on PE files on a logical trigger

BC\_PDF specifies a PDF hook, executes at a predetermined point of PDF parsing for PDF files

 $BC\_PE\_ALL$  specifies a PE hook, executes at a predetermined point in PE parsing for PE files, both packed and unpacked files

#### enum FunctionalityLevels LibClamAV functionality level constants

#### Enumerator

 $FUNC\_LEVEL\_096$  LibClamAV release 0.96.0: bytecode engine released

FUNC\_LEVEL\_096\_1 LibClamAV release 0.96.1: logical signature use of VI/macros requires this minimum functionality level

FUNC\_LEVEL\_096\_2 LibClamAV release 0.96.2: PDF Hooks require this minimum level

FUNC\_LEVEL\_096\_3 LibClamAV release 0.96.3: BC\_PE\_ALL bytecodes require this minimum level

7.1. API groups

 $FUNC\_LEVEL\_096\_4$  LibClamAV release 0.96.4: minimum recommended engine version, older versions have quadratic load time

 $FUNC\_LEVEL\_096\_5$  LibClamAV release 0.96.5

FUNC\_LEVEL\_097 LibClamAV release 0.97.0: older bytecodes may incorrectly use 57

 $FUNC\_LEVEL\_097\_1$  LibClamAV release 0.97.1

FUNC\_LEVEL\_097\_2 LibClamAV release 0.97.2

 $FUNC\_LEVEL\_097\_3$  LibClamAV release 0.97.3

FUNC\_LEVEL\_097\_4 LibClamAV release 0.97.4

FUNC\_LEVEL\_097\_5 LibClamAV release 0.97.5

FUNC\_LEVEL\_097\_6 LibClamAV release 0.97.6

FUNC\_LEVEL\_097\_7 LibClamAV release 0.97.7

 $FUNC\_LEVEL\_097\_8$  LibClamAV release 0.97.8

 $FUNC\_LEVEL\_098$  LibClamAV release 0.98.0

 $FUNC\_LEVEL\_098\_1$  LibClamAV release 0.98.1

 $FUNC\_LEVEL\_098\_2$  LibClamAV release 0.98.2

Chapter 7. Bytecode API 29

#### 7.1.2. Abstract Data Types

#### **Functions**

- void \* malloc (uint32\_t size)
- int32\_t hashset\_new (void)
- int32\_t hashset\_add (int32\_t hs, uint32\_t key)
- int32 t hashset remove (int32 t hs, uint32 t key)
- int32\_t hashset\_contains (int32\_t hs, uint32\_t key)
- int32\_t hashset\_done (int32\_t id)
- int32 t hashset empty (int32 t id)
- int32\_t buffer\_pipe\_new (uint32\_t size)
- int32\_t buffer\_pipe\_new\_fromfile (uint32\_t pos)
- uint32 t buffer pipe read avail (int32 t id)
- const uint8\_t \* buffer\_pipe\_read\_get (int32\_t id, uint32\_t amount)
- int32\_t buffer\_pipe\_read\_stopped (int32\_t id, uint32\_t amount)
- uint32\_t buffer\_pipe\_write\_avail (int32\_t id)
- uint8\_t \* buffer\_pipe\_write\_get (int32\_t id, uint32\_t size)
- int32\_t buffer\_pipe\_write\_stopped (int32\_t id, uint32\_t amount)
- int32\_t buffer\_pipe\_done (int32\_t id)
- int32\_t inflate\_init (int32\_t from\_buffer, int32\_t to\_buffer, int32\_t windowBits)
- int32 t inflate process (int32 t id)
- int32\_t inflate\_done (int32\_t id)
- int32\_t map\_new (int32\_t keysize, int32\_t valuesize)
- int32\_t map\_addkey (const uint8\_t \*key, int32\_t ksize, int32\_t id)
- int32\_t map\_setvalue (const uint8\_t \*value, int32\_t vsize, int32\_t id)
- int32 t map remove (const uint8 t \*key, int32 t ksize, int32 t id)
- int32 t map find (const uint8 t \*key, int32 t ksize, int32 t id)
- int32 t map getvaluesize (int32 t id)
- uint8\_t \* map\_getvalue (int32\_t id, int32\_t size)
- int32\_t map\_done (int32\_t id)

#### **Detailed Description**

#### **Function Documentation**

 $int32\_t$  buffer\_pipe\_done (  $int32\_t$  id ) Deallocate memory used by buffer. After this all attempts to use this buffer will result in error. All buffer\_pipes are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of buffer_pipe
----	----	-------------------

#### Returns

0 on success

 $int32\_t \ buffer\_pipe\_new$  (  $uint32\_t \ size$  ) Creates a new pipe with the specified buffer size Parameters

in	size	size of buffer

#### Returns

ID of newly created buffer\_pipe

7.1. API groups

int32\_t buffer\_pipe\_new\_fromfile ( uint32\_t pos ) Creates a new pipe with the specified buffer size w/ tied input to the current file, at the specified position. Parameters

in	pos	starting position of pipe input in current file

#### Returns

ID of newly created buffer pipe

in	id	ID of buffer_pipe

#### Returns

amount of bytes available to read

const uint8\_t\* buffer\_pipe\_read\_get ( int32\_t id, uint32\_t amount ) Returns a pointer to the buffer for reading. The 'amount' parameter should be obtained by a call to buffer\_pipe\_read\_avail().

Parameters

in	id	ID of buffer_pipe
in	amount	to read

#### Returns

pointer to buffer, or NULL if buffer has less than specified amount

int32\_t buffer\_pipe\_read\_stopped ( int32\_t id, uint32\_t amount ) Updates read cursor in buffer\_pipe.

Parameters

in	id	ID of buffer_pipe
in	amount	amount of bytes to move read cursor

#### Returns

0 on success

 ${\tt uint32\_t\ buffer\_pipe\_write\_avail}$  (  ${\tt int32\_t\ id}$  ) Returns the amount of bytes available for writing.

Parameters

in	id	ID of buffer_pipe

#### Returns

amount of bytes available for writing

uint8\_t\* buffer\_pipe\_write\_get ( int32\_t id, uint32\_t size ) Returns pointer to writable buffer. The 'size' parameter should be obtained by a call to buffer\_pipe\_write\_avail(). Parameters

in	id	ID of buffer_pipe

in	size	amount of bytes to write

#### Returns

pointer to write buffer, or NULL if requested amount is more than what is available in the buffer

 $int32\_t\ buffer\_pipe\_write\_stopped\ (\ int32\_t\ id,\ uint32\_t\ amount\ )$  Updates the write cursor in buffer\\_pipe.

Parameters

in	id	ID of buffer_pipe
in	amount	amount of bytes to move write cursor

#### Returns

0 on success

 $int32\_t\ hashset\_add\ (\ int32\_t\ hs,\ uint32\_t\ key\ )$  Add a new 32-bit key to the hashset. Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to add

#### Returns

0 on success

 $int32\_t\ hashset\_contains$  (  $int32\_t\ hs$ ,  $uint32\_t\ key$  ) Returns whether the hashset contains the specified key.

Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to lookup

#### Returns

1 if found

0 if not found

<0 on invalid hashset ID

 $int32\_t$  hashset\_done (  $int32\_t$  id ) Deallocates the memory used by the specified hashset. Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution.

Parameters

in	$id$	ID of hashset (from hashset_new)
----	------	----------------------------------

#### Returns

0 on success

int32\_t hashset\_empty ( int32\_t id ) Returns whether the hashset is empty.

Parameters

in	id	of hashset (from hashset_new)

#### Returns

0 on success

int32\_t hashset\_new ( void ) Creates a new hashset and returns its id.

#### Returns

ID for new hashset

 $int32\_t\ hashset\_remove\ (int32\_t\ hs,\ uint32\_t\ key\ )$  Remove a 32-bit key from the hashset. Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to add

#### Returns

0 on success

int32\_t inflate\_done ( int32\_t id ) Deallocates inflate data structure. Using the inflate data structure after this will result in an error. All inflate data structures are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of inflate data structure

#### Returns

0 on success.

int32\_t inflate\_init ( int32\_t from\_buffer, int32\_t to\_buffer, int32\_t windowBits ) Initializes inflate data structures for decompressing data 'from\_buffer' and writing uncompressed uncompressed data 'to\_buffer'.

Parameters

in	from_buffer	ID of buffer_pipe to read compressed data from
in	to_buffer	ID of buffer_pipe to write decompressed data to
in	window Bits	(see zlib documentation)

### Returns

ID of newly created inflate data structure, <0 on failure

int32\_t inflate\_process ( int32\_t id ) Inflate all available data in the input buffer, and write to output buffer. Stops when the input buffer becomes empty, or write buffer becomes full. Also attempts to recover from corrupted inflate stream (via inflateSync). This function can be called repeatedly on success after filling the input buffer, and flushing the output buffer. The inflate stream is done processing when 0 bytes are available from output buffer, and input buffer is not empty.

Parameters

in	id	ID of inflate data structure
----	----	------------------------------

### Returns

0 on success, zlib error code otherwise

void\* malloc ( uint32\_t size ) Allocates memory. Currently this memory is freed automatically on exit from the bytecode, and there is no way to free it sooner.
Parameters

in	size	amount of memory to allocate in bytes

### Returns

pointer to allocated memory

int32\_t map\_addkey ( const uint8\_t \* key, int32\_t ksize, int32\_t id ) Inserts the specified key/value pair into the map.

Parameters

in	id	id of table
in	key	key
in	ksize	size of key

#### Returns

- 0 if key existed before
- 1 if key didn't exist before
- < 0 if ksize doesn't match keysize specified at table creation

 $int32\_t$  map\_done (  $int32\_t$  id ) Deallocates the memory used by the specified map. Trying to use the map after this will result in an error. All maps are automatically deallocated when the bytecode finishes execution.

Parameters

in	id	id of map
----	----	-----------

#### Returns

- 0 success
- -1 invalid map

 $int32\_t map\_find$  (  $const uint8\_t * key$ ,  $int32\_t ksize$ ,  $int32\_t id$  ) Looks up key in map. The map remember the last looked up key (so you can retrieve the value).

Parameters

in	id	id of map
in	key	key
in	ksize	size of key

### Returns

- 0 if not found
- 1 if found
- $<\!0$  if k size doesn't match the size specified at table creation

 $wint8_t* map\_getvalue ( int32_t id, int32_t size )$  Returns the value obtained during last map\_find.

Parameters

in	id	id of map.
in	size	size of value (obtained from map_getvaluesize)

### Returns

value

 $int32\_t\ map\_getvaluesize\ (\ int32\_t\ id\ )$  Returns the size of value obtained during last map\_find. Parameters

in	id	id of map.
		1

### Returns

size of value

 $int32\_t\ map\_new\ (\ int32\_t\ keysize,\ int32\_t\ valuesize\ )$  Creates a new map and returns its id.

Parameters

in	keysize	size of key
in	valuesize	size of value, if 0 then value is allocated separately

### Returns

ID of new map

 $int 32\_t \ map\_remove \ ( \ const \ uint 8\_t * \textit{key}, \ int 32\_t \ \textit{ksize}, \ int 32\_t \ \textit{id} \ ) \ \ \text{Remove an element from the map}.$ 

Parameters

in	id	id of map
in	key	key
in	ksize	size of key

### Returns

0 on success, key was present

1 if key was not present

<0 if ksize doesn't match key size specified at table creation

 $int 32\_t \ map\_set value \ ( \ const \ uint 8\_t * value, \ int 32\_t \ vsize, \ int 32\_t \ id \ ) \ \ Sets \ the \ value \ for \ the \ last \ inserted \ key \ with \ map\_add key.$ 

Parameters

in	id	id of table
in	value	value
in	vsize	size of value

### Returns

0 - if update was successful

<0 - if there is no last key

Chapter 7. Bytecode API 35

### 7.1.3. Debugging

#### **Functions**

```
• uint32_t debug_print_str (const uint8_t *str, uint32_t len)
```

- uint32\_t debug\_print\_uint (uint32\_t a)
- uint32\_t debug\_print\_str\_start (const uint8\_t \*str, uint32\_t len)
- uint32\_t debug\_print\_str\_nonl (const uint8\_t \*str, uint32\_t len)
- void debug (...) \_\_attribute\_\_((overloadable
- static force\_inline void overloadable\_func debug (const char \*str)
- static force\_inline void overloadable\_func debug (const uint8\_t \*str)
- static force\_inline void overloadable\_func debug (uint32\_t a)

### **Detailed Description**

### **Function Documentation**

**debug** ( const char \* <math>str ) [static] Prints str to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in	str	null terminated string
----	-----	------------------------

**debug ( const uint8\_t \*** str **) [static]** Prints str to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in	str	null terminated string

**debug (uint32\_t** a) [static] Prints a integer to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

```
in a integer
```

 ${f void\ debug\ (}$  ... ) debug is an overloaded function (yes clang supports that in C!), but it only works on strings, and integers. Give an error on any other type.

See Also

```
debug(const char * str),
debug(const uint8_t* str),
debug(uint32_t a)
```

 ${\tt uint32\_t\ debug\_print\_str}$  (  ${\tt const\ uint8\_t*str},\ {\tt uint32\_t\ len}$  ) Prints a debug message string.

Parameters

in	str	Message to print
in	len	length of message to print

### Returns

0

in	str	the string
in	len	length of str

### Returns

0

in	str	the string
in	len	length of str

### Returns

0

 ${\tt uint32\_t\ debug\_print\_uint}$  (  ${\tt uint32\_t\ a}$  ) Prints a number as a debug message. This is similar to debug\_print\_str\_nonl.

Parameters

		1 ,
ın	a	number to print

### Returns

0

### 7.1.4. Disassembly

### **Data Structures**

- struct DIS\_mem\_arg
- struct DIS arg
- struct DIS\_fixed

#### **Functions**

- uint32\_t disasm\_x86 (struct DISASM\_RESULT \*result, uint32\_t len)
- static force\_inline uint32\_t DisassembleAt (struct DIS\_fixed \*result, uint32\_t offset, uint32\_t len)

### **Detailed Description**

### **Function Documentation**

out	result	pointer to struct holding result
in	len	how many bytes to disassemble

### Returns

0 for success

You can use lseek to disassemble starting from a different location. This is a low-level API, the result is in ClamAV type-8 signature format (64 bytes/instruction).

See Also

DisassembleAt

static force\_inline uint32\_t DisassembleAt ( struct DIS\_fixed \* result, uint32\_t offset, uint32\_t len ) [static] Disassembles one X86 instruction starting at the specified offset.

Parameters

out	result	disassembly result
in	offset	start disassembling from this offset, in the current file
in	len	max amount of bytes to disassemble

### Returns

offset where disassembly ended

### 7.1.5. Engine Queries

#### **Functions**

- uint32\_t engine\_functionality\_level (void)
- uint32\_t engine\_dconf\_level (void)
- uint32\_t engine\_scan\_options (void)
- uint32\_t engine\_db\_options (void)
- int32\_t running\_on\_jit (void)
- static force\_inline uint32\_t count\_match (\_\_\_Signature sig)
- static force inline uint32 t matches ( Signature sig)
- static force\_inline uint32\_t match\_location (\_\_\_Signature sig, uint32\_t goback)
- static force\_inline int32\_t match\_location\_check (\_\_Signature sig, uint32\_t goback, const char \*static\_start, uint32\_t static\_len)

### **Detailed Description**

#### **Function Documentation**

static force\_inline uint32\_t count\_match ( \_\_\_Signature sig ) [static] Returns how many times the specified signature matched.

Parameters

in sig name of subsignature queried	
-------------------------------------	--

#### Returns

number of times this subsignature matched in the entire file

This is a constant-time operation, the counts for all subsignatures are already computed.

uint32\_t engine\_db\_options (void) Returns the current engine's db options.

Returns

CL DB \* flags

 $\label{lem:cond_level} \begin{tabular}{ll} \bf uint 32\_t \ engine\_dconf\_level \ (\ void\ ) \ \ Returns the current engine (dconf) functionality level. \\ Usually identical to engine\_functionality\_level(), unless distro backported patches. Compare with FunctionalityLevels. \\ \end{tabular}$ 

### Returns

an integer representing the DCONF (security fixes) level.

 $\label{lem:condity_level} \begin{tabular}{ll} \bf uint 32\_t \ engine\_functionality\_level \ (\ void\ ) \ \ Returns the current engine (feature) functionality level. To map these to ClamAV releases, compare it with FunctionalityLevels. \\ \end{tabular}$ 

### Returns

an integer representing current engine functionality level.

uint32\_t engine\_scan\_options (void) Returns the current engine's scan options.

Returns

 $CL\_SCAN*$  flags

static force\_inline uint32\_t match\_location ( \_\_\_Signature sig, uint32\_t goback ) [static] Returns the offset of the match.

Parameters

in	sig	- Signature
in	goback	- max length of signature

#### Returns

offset of match

static force\_inline int32\_t match\_location\_check ( \_\_\_Signature sig, uint32\_t goback, const char \*  $static\_start$ , uint32\_t  $static\_len$  ) [static] Like match\_location(), but also checks that the match starts with the specified hex string.

It is recommended to use this for safety and compatibility with 0.96.1

Parameters

in	sig	- signature
in	goback	- maximum length of signature (till start of last subsig)
in	$static\_start$	- static string that sig must begin with
in	$static\_len$	- static string that sig must begin with - length

### Returns

>=0 - offset of match

-1 - no match

static force\_inline uint32\_t matches ( \_\_\_Signature sig ) [static] Returns whether the specified subsignature has matched at least once. Parameters

in
----

### Returns

1 if subsignature one or more times, 0 otherwise

int32\_t running\_on\_jit ( void ) Returns whether running on JIT. As side-effect it disables interp / JIT comparisons in test mode (errors are still checked)

### Returns

- 1 running on JIT
- 0 running on ClamAV interpreter

### 7.1.6. Environment

#### **Functions**

- uint32\_t get\_environment (struct cli\_environment \*env, uint32\_t len)
- uint32\_t disable\_bytecode\_if (const int8\_t \*reason, uint32\_t len, uint32\_t cond)
- uint32\_t disable\_jit\_if (const int8\_t \*reason, uint32\_t len, uint32\_t cond)
- int32\_t version\_compare (const uint8\_t \*lhs, uint32\_t lhs\_len, const uint8\_t \*rhs, uint32\_t rhs\_len)
- uint32\_t check\_platform (uint32\_t a, uint32\_t b, uint32\_t c)
- bool \_\_is\_bigendian (void) \_\_attribute\_\_((const )) \_\_attribute\_\_((nothrow))
- static uint32 t force inline le32 to host (uint32 t v)
- static uint32\_t force\_inline be32\_to\_host (uint32\_t v)
- static uint64\_t force\_inline le64\_to\_host (uint64\_t v)
- static uint64\_t force\_inline be64\_to\_host (uint64\_t v)
- static uint16 t force inline le16 to host (uint16 t v)
- static uint16 t force inline be16 to host (uint16 t v)
- static uint32 t force inline cli readint32 (const void \*buff)
- static uint16 t force inline cli readint16 (const void \*buff)
- static void force\_inline cli\_writeint32 (void \*offset, uint32\_t v)

### **Detailed Description**

### **Function Documentation**

**bool** \_\_\_is\_bigendian ( void ) const Returns true if the bytecode is executing on a big-endian CPU.

### Returns

true if executing on bigendian CPU, false otherwise

This will be optimized away in libclamav, but it must be used when dealing with endianess for portability reasons

For example whenever you read a 32-bit integer from a file, it can be written in little-endian convention (x86 CPU for example), or big-endian convention (PowerPC CPU for example).

If the file always contains little-endian integers, then conversion might be needed.

ClamAV bytecodes by their nature must only handle known-endian integers, if endianness can change, then both situations must be taken into account (based on a 1-byte field for example).

static uint16\_t force\_inline be16\_to\_host ( uint16\_t v ) [static] Converts the specified value if needed, knowing it is in big endian order. Parameters

in $v \mid 16$ -bit integer as read from a file
---

### Returns

integer converted to host's endianess

static uint32\_t force\_inline be32\_to\_host ( uint32\_t v ) [static] Converts the specified value if needed, knowing it is in big endian order. Parameters

in $v \mid 32$ -bit integer as read from a file
---

### Returns

integer converted to host's endianess

Parameters

in	v	64-bit integer as read from a file

#### Returns

integer converted to host's endianess

Parameters

in	a	- os_category $<<$ 24   arch $<<$ 20   compiler $<<$ 16   flevel $<<$ 8
		dconf
in	b	- big_endian $<<$ 28   sizeof_ptr $<<$ 24   cpp_version
in	c	- os_features << 24   c_version

### Returns

0 - no match

1 - match

Parameters

in	$\mathit{buff}$	pointer to buffer
----	-----------------	-------------------

### Returns

16-bit little-endian integer converted to host endianness

static uint 32\_t force\_inline cli\_readint 32 ( const void \* buff ) [static] Reads from the specified buffer a 32-bit of little-endian integer.

Parameters

in oug pointer to burier	in	buff	pointer to buffer
--------------------------	----	------	-------------------

### Returns

32-bit little-endian integer converted to host endianness

static void force\_inline cli\_writeint32 ( void \* offset, uint32\_t v ) [static] Writes the specified value into the specified buffer in little-endian order Parameters

out	offset	pointer to buffer to write to
in	v	value to write

 $\label{lem:cond} \begin{tabular}{ll} uint 32\_t & disable\_bytecode\_if (const int 8\_t * reason, uint 32\_t len, uint 32\_t cond) \\ Disables & the bytecode completely if condition is true. Can only be called from the BC_STARTUP bytecode. \\ \end{tabular}$ 

Parameters

in	reason	- why the bytecode had to be disabled
in	len	- length of reason
in	cond	- condition

### Returns

- 0 auto mode
- 1 JIT disabled
- 2 fully disabled

in	reason	- why the JIT had to be disabled
in	len	- length of reason
in	cond	- condition

#### Returns

- 0 auto mode
- 1 JIT disabled
- 2 fully disabled

uint32\_t get\_environment ( struct cli\_environment \* env, uint32\_t len ) Queries the environment this bytecode runs in. Used by BC\_STARTUP to disable bytecode when bugs are known for the current platform.

Parameters

out	env	- the full environment
in	len	- size of env

### Returns

0

static uint16\_t force\_inline le16\_to\_host ( uint16\_t v ) [static] Converts the specified value if needed, knowing it is in little endian order. Parameters

in	v	16-bit integer as read from a file

#### Returns

integer converted to host's endianess

static uint32\_t force\_inline le32\_to\_host ( uint32\_t v ) [static] Converts the specified value if needed, knowing it is in little endian order. Parameters

in	v	32-bit integer as read from a file

### Returns

integer converted to host's endianess

static uint64\_t force\_inline le64\_to\_host ( uint64\_t v ) [static] Converts the specified value if needed, knowing it is in little endian order.

### Chapter 7. Bytecode API

//3

### Parameters

in	v	64-bit integer as read from a file

### Returns

integer converted to host's endianess

Parameters

in	lhs	- left hand side of comparison
in	lhs_len	- length of lhs
in	rhs	- right hand side of comparison
in	rhs_len	- length of rhs

### Returns

-1 - lhs < rhs

0 - lhs == rhs

1 - lhs > rhs

### 7.1.7. File Operations

#### **Enumerations**

• enum { SEEK\_SET =0, SEEK\_CUR, SEEK\_END }

### **Functions**

- int32 t read (uint8 t \*data, int32 t size)
- int32 t write (uint8 t \*data, int32 t size)
- int32\_t seek (int32\_t pos, uint32\_t whence)
- int32\_t file\_find (const uint8\_t \*data, uint32\_t len)
- int32\_t file\_byteat (uint32\_t offset)
- $\bullet \ \ int 32\_t \ fill\_buffer \ (uint 8\_t \ *buffer, \ uint 32\_t \ len, \ uint 32\_t \ filled, \ uint 32\_t \ cursor, \ uint 32\_t \ fill)$
- int32 t read number (uint32 t radix)
- int32\_t file\_find\_limit (const uint8\_t \*data, uint32\_t len, int32\_t maxpos)
- int32\_t get\_file\_reliability (void)
- static force\_inline uint32\_t getFilesize (void)

### **Detailed Description**

### **Enumeration Type Documentation**

#### anonymous enum

#### Enumerator

 $SEEK\_SET$  set file position to specified absolute position

SEEK\_CUR set file position relative to current position

**SEEK** END set file position relative to file end

### **Function Documentation**

 $int32\_t$  file\_byteat (  $uint32\_t$  offset ) Read a single byte from current file

Parameters

in	offset	file offset

### Returns

byte at offset off in the current file, or -1 if offset is invalid

int32\_t file\_find ( const uint8\_t \* data, uint32\_t len ) Looks for the specified sequence of bytes in the current file.

Parameters

in	data	the sequence of bytes to look for
in	len	length of data, cannot be more than 1024

### Returns

offset in the current file if match is found, -1 otherwise

int32\_t file\_find\_limit ( const uint8\_t \* data, uint32\_t len, int32\_t maxpos ) Looks for the specified sequence of bytes in the current file, up to the specified position. Parameters

in	data	the sequence of bytes to look for
in	len	length of data, cannot be more than 1024
in	maxpos	maximum position to look for a match, note that this is 1 byte after
		the end of last possible match: $match\_pos + len < maxpos$

### Returns

offset in the current file if match is found, -1 otherwise

int32\_t fill\_buffer ( uint8\_t \* buffer, uint32\_t len, uint32\_t filled, uint32\_t cursor, uint32\_t fill ) Fills the specified buffer with at least fill bytes.

Parameters

out	buffer	the buffer to fill
in	len	length of buffer
in	filled	how much of the buffer is currently filled
in	cursor	position of cursor in buffer
in	fill	amount of bytes to fill in (0 is valid)

### Returns

<0 on error

0 on EOF

number bytes available in buffer (starting from 0)

The character at the cursor will be at position 0 after this call.

 $int32\_t$  get\_file\_reliability ( void ) Get file reliability flag, higher value means less reliable. When >0 import tables and such are not reliable

### Returns

0 - normal

1 - embedded PE

2 - unpacker created file (not impl. yet)

static force\_inline uint32\_t getFilesize ( void ) [static] Returns the currently scanned file's size.

### Returns

file size as 32-bit unsigned integer

 $int32\_t\ read\ (\ uint8\_t*data,\ int32\_t\ size\ )$  Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

Parameters

in	size	amount of bytes to read
out	data	pointer to buffer where data is read into

### Returns

amount read.

 $int32\_t\ read\_number\ (\ uint32\_t\ radix\ )$  Reads a number in the specified radix starting from the current position. Non-numeric characters are ignored.

Parameters

in	radix	10 or 16

### Returns

the number read

 $int32\_t$  seek (  $int32\_t$  pos,  $uint32\_t$  whence ) Changes the current file position to the specified one.

See Also

SEEK\_SET, SEEK\_CUR, SEEK\_END

### Parameters

in	pos	offset (absolute or relative depending on whence param)
in	whence	one of SEEK_SET, SEEK_CUR, SEEK_END

### Returns

absolute position in file

 $\label{lem:continuity} \textbf{int32\_t write ( uint8\_t*data, int32\_t\ size )} \quad \text{Writes the specified amount of bytes from a buffer to the current temporary file.}$ 

### Parameters

in	data	pointer to buffer of data to write
in	size	amount of bytes to write size bytes to temporary file, from the buffer
		pointed to byte

### Returns

amount of bytes successfully written

### 7.1.8. JavaScript Normalization

### **Functions**

- int32\_t jsnorm\_init (int32\_t from\_buffer)
- int32\_t jsnorm\_process (int32\_t id)
- int32\_t jsnorm\_done (int32\_t id)

### **Detailed Description**

### **Function Documentation**

int32\_t jsnorm\_done ( int32\_t id ) Flushes JS normalizer.

Parameters

in	id	ID of js normalizer to flush

#### Returns

0 on success, <0 on failure

int32\_t jsnorm\_init ( int32\_t from\_buffer ) Initializes JS normalizer for reading 'from\_buffer'. Normalized JS will be written to a single tempfile, one normalized JS per line, and automatically scanned when the bytecode finishes execution.

Parameters

in	from_buffer	ID of buffer_pipe to read javascript from
----	-------------	---

### Returns

ID of JS normalizer, <0 on failure

int32\_t jsnorm\_process ( int32\_t id ) Normalize all javascript from the input buffer, and write to tempfile. You can call this function repeatedly on success, if you (re)fill the input buffer. Parameters

in	id	ID of JS normalizer

### Returns

0 on success, <0 on failure

### 7.1.9. Icon Matcher

### **Functions**

- int 32\_t matchicon (const uint 8\_t \*group1, int 32\_t group1\_len, const uint 8\_t \*group2, int 32\_t group2\_len)

### **Detailed Description**

### **Function Documentation**

in	group1	- same as GROUP1 in LDB signatures
in	$group1\_len$	- length of group1
in	group2	- same as GROUP2 in LDB signatures
in	$group2\_len$	- length of group2

### ${\rm Returns}$

- -1 invalid call, or sizes (only valid for PE hooks)
- 0 not a match
- 1 match

### 7.1.10. Math Operation

### **Functions**

- int32\_t ilog2 (uint32\_t a, uint32\_t b)
- int32\_t ipow (int32\_t a, int32\_t b, int32\_t c)
- uint32\_t iexp (int32\_t a, int32\_t b, int32\_t c)
- int32\_t isin (int32\_t a, int32\_t b, int32\_t c)
- int32\_t icos (int32\_t a, int32\_t b, int32\_t c)

### **Detailed Description**

### **Function Documentation**

 $\mathbf{int32\_t\ icos}\ (\ \mathbf{int32\_t}\ a,\ \mathbf{int32\_t}\ b,\ \mathbf{int32\_t}\ c\ )\ \mathrm{Returns}\ \mathbf{c}*\mathbf{cos}(\mathbf{a/b}).$ 

Parameters

in	a	integer
in	b	integer
in	c	integer

### Returns

c\*sin(a/b)

### uint32\_t iexp ( int32\_t a, int32\_t b, int32\_t c ) Returns exp(a/b)\*c

Parameters

in	a	integer
in	b	integer
in	c	integer

### Returns

c\*exp(a/b)

### int32\_t ilog2 ( uint32\_t a, uint32\_t b ) Returns $2^26*\log 2(a/b)$

Parameters

in	a	input
in	b	input

### Returns

 $2^{2}$ 4 \* log2(a/b)

### int32\_t ipow ( int32\_t a, int32\_t b, int32\_t c ) Returns c\*a^b.

Parameters

in	a	integer
in	b	integer
in	c	integer

### Returns

c\*pow(a,b)

 $\mathbf{int32\_t} \ \mathbf{isin} \ ( \ \mathbf{int32\_t} \ a, \ \mathbf{int32\_t} \ b, \ \mathbf{int32\_t} \ c \ ) \ \ \mathbf{Returns} \ \mathbf{c*sin}(\mathbf{a/b}).$ 

Parameters

in	a	integer
in	b	integer
in	c	integer

### ${\rm Returns}$

c\*sin(a/b)

Chapter 7. Bytecode API 51

### 7.1.11. PDF Handling

#### **Enumerations**

- enum pdf\_phase { , PDF\_PHASE\_PARSED, PDF\_PHASE\_POSTDUMP, PDF\_PHASE\_END, PDF\_PHASE\_PRE }
- enum pdf\_flag
- enum pdf\_objflags

### **Functions**

- int32\_t pdf\_get\_obj\_num (void)
- int32\_t pdf\_get\_flags (void)
- int32\_t pdf\_set\_flags (int32\_t flags)
- int32 t pdf lookupobj (uint32 t id)
- uint32 t pdf getobjsize (int32 t objidx)
- const uint8\_t \* pdf\_getobj (int32\_t objidx, uint32\_t amount)
- int32\_t pdf\_getobjid (int32\_t objidx)
- int32 t pdf getobjflags (int32 t objidx)
- int32 t pdf setobjflags (int32 t objidx, int32 t flags)
- int32\_t pdf\_get\_offset (int32\_t objidx)
- int32\_t pdf\_get\_phase (void)
- int32\_t pdf\_get\_dumpedobjid (void)

### **Detailed Description**

```
Enumeration Type Documentation
```

```
enum pdf_flag PDF flags
```

enum pdf\_objflags PDF obj flags

enum pdf\_phase Phase of PDF parsing used for PDF Hooks

#### Enumerator

```
PDF_PHASE_PARSED after parsing a PDF, object flags can be set etc.
```

PDF\_PHASE\_POSTDUMP after an obj was dumped and scanned

 $PDF\_PHASE\_END$  after the pdf scan finished

PDF\_PHASE\_PRE before pdf is parsed at all

### **Function Documentation**

 $int32\_t\ pdf\_get\_dumpedobjid$  ( void ) Return the currently dumped obj index. Valid only in PDF\_PHASE\_POSTDUMP.

### Returns

- >=0 object index
- -1 invalid phase

int32\_t pdf\_get\_flags (void) Return the flags for the entire PDF (as set so far).

### Returns

- -1 if not called from PDF hook
- >=0 pdf flags

int32\_t pdf\_get\_obj\_num ( void ) Return number of pdf objects

#### Returns

-1 - if not called from PDF hook

>=0 - number of PDF objects

int32\_t pdf\_get\_offset ( int32\_t objidx ) Return the object's offset in the PDF.

Parameters

in	objidx	- object index (from 0)
----	--------	-------------------------

### Returns

-1 - object index invalid

>=0 - offset

int32\_t pdf\_get\_phase ( void ) Return an 'enum pdf\_phase'. Identifies at which phase this bytecode was called.

#### Returns

the current pdf\_phase

in	objidx	- object index (from 0), not object id!
in	amount	- size returned by pdf_getobjsize (or smaller)

### Returns

NULL - invalid objidx/amount

pointer - pointer to original object

 $int32\_t\ pdf\_getobjflags$  (  $int32\_t\ objidx$  ) Return the object flags for the specified object index. Parameters

in	objidx	- object index (from 0)

### Returns

-1 - object index invalid

>=0 - object flags

 $int32\_t\ pdf\_getobjid$  (  $int32\_t\ objidx$  ) Return the object id for the specified object index. Parameters

in |objidx| - object index (from 0)

### Returns

-1 - object index invalid

>=0 - object id (obj id << 8 | generation id)

uint32\_t pdf\_getobjsize ( int32\_t objidx ) Return the size of the specified PDF obj.

53

### Parameters

in	objidx	- object index (from 0), not object id!	

### Returns

0 - if not called from PDF hook, or invalid objnum

>=0 - size of object

### int32\_t pdf\_lookupobj ( uint32\_t id ) Lookup pdf object with specified id.

Parameters

in	id	- pdf id (objnumber << 8   generationid)

#### Returns

-1 - if object id doesn't exist

>=0 - object index

 $int32\_t\ pdf\_set\_flags$  (  $int32\_t\ flags$  ) Sets the flags for the entire PDF. It is recommended that you retrieve old flags, and just add new ones.

Parameters

in	flags	- flags to set.
----	-------	-----------------

#### Returns

0 - success -1 - invalid phase

 $int32\_t\ pdf\_setobjflags$  (  $int32\_t\ objidx$ ,  $int32\_t\ flags$  ) Sets the object flags for the specified object index. This can be used to force dumping of a certain obj, by setting the OBJ\_FORCEDUMP flag for example.

Parameters

in	objidx	- object index (from 0)
in	flags	- value to set flags

### Returns

-1 - object index invalid

>=0 - flags set

### 7.1.12. PE Operations

#### **Data Structures**

- struct cli\_exe\_section
- struct cli\_exe\_info
- struct pe\_image\_file\_hdr
- struct pe image data dir
- struct pe\_image\_optional\_hdr32
- struct pe image optional hdr64
- struct pe\_image\_section\_hdr
- struct cli\_pe\_hook\_data

#### **Functions**

- uint32\_t pe\_rawaddr (uint32\_t rva)
- int32\_t get\_pe\_section (struct cli\_exe\_section \*section, uint32\_t num)
- static force inline bool hasExeInfo (void)
- static force\_inline bool hasPEInfo (void)
- static force\_inline bool isPE64 (void)
- static force inline uint8 t getPEMajorLinkerVersion (void)
- static force inline uint8 t getPEMinorLinkerVersion (void)
- static force inline uint32 t getPESizeOfCode (void)
- static force\_inline uint32\_t getPESizeOfInitializedData (void)
- static force\_inline uint32\_t getPESizeOfUninitializedData (void)
- static force\_inline uint32\_t getPEBaseOfCode (void)
- static force inline uint32 t getPEBaseOfData (void)
- static force\_inline uint64\_t getPEImageBase (void)
- static force\_inline uint32\_t getPESectionAlignment (void)
- static force\_inline uint32\_t getPEFileAlignment (void)
- static force\_inline uint16\_t getPEMajorOperatingSystemVersion (void)
- static force\_inline uint16\_t getPEMinorOperatingSystemVersion (void)
- static force\_inline uint16\_t getPEMajorImageVersion (void)
- static force inline uint16 t getPEMinorImageVersion (void)
- static force\_inline uint16\_t getPEMajorSubsystemVersion (void)
- static force\_inline uint16\_t getPEMinorSubsystemVersion (void)
- static force\_inline uint32\_t getPEWin32VersionValue (void)
- static force inline uint32 t getPESizeOfImage (void)
- static force\_inline uint32\_t getPESizeOfHeaders (void)
- static force\_inline uint32\_t getPECheckSum (void)
- static force\_inline uint16\_t getPESubsystem (void)
- static force\_inline uint16\_t getPEDllCharacteristics (void)
  static force\_inline uint32\_t getPESizeOfStackReserve (void)
- static force inline uint32 t getPESizeOfStackCommit (void)
- static force inline uint32 t getPESizeOfHeapReserve (void)
- static force inline uint32 t getPESizeOfHeapCommit (void)
- static force\_inline uint32\_t getPELoaderFlags (void)
- static force\_inline uint16\_t getPEMachine ()
- static force\_inline uint32\_t getPETimeDateStamp ()
- static force\_inline uint32\_t getPEPointerToSymbolTable ()
- static force\_inline uint32\_t getPENumberOfSymbols ()
- static force\_inline uint16\_t getPESizeOfOptionalHeader ()
- static force\_inline uint16\_t getPECharacteristics ()
- static force\_inline bool getPEisDLL ()
- static force inline uint32 t getPEDataDirRVA (unsigned n)
- static force inline uint32 t getPEDataDirSize (unsigned n)

Chapter 7. Bytecode API 55

- static force\_inline uint16\_t getNumberOfSections (void)
- static uint32 t getPELFANew (void)
- static force inline int readPESectionName (unsigned char name[8], unsigned n)
- static force\_inline uint32\_t getEntryPoint (void)
- static force\_inline uint32\_t getExeOffset (void)
- static force inline uint32 t getImageBase (void)
- static uint32 t getVirtualEntryPoint (void)
- static uint32\_t getSectionRVA (unsigned i)
- static uint32\_t getSectionVirtualSize (unsigned i)
- static force\_inline bool readRVA (uint32\_t rva, void \*buf, size\_t bufsize)

### **Detailed Description**

### **Function Documentation**

int32\_t get\_pe\_section ( struct cli\_exe\_section \* section, uint32\_t num ) Gets information about the specified PE section.

Parameters

out	section	PE section information will be stored here
in	num	PE section number

#### Returns

0 - success

-1 - failure

static force\_inline uint32\_t getEntryPoint ( void ) [static] Returns the offset of the EntryPoint in the executable file.

### Returns

offset of EP as 32-bit unsigned integer

 $static\ force\_inline\ uint32\_t\ getExeOffset\ (void)\ [static]$  Returns the offset of the executable in the file.

### Returns

offset of embedded executable inside file

static force\_inline uint32\_t getImageBase ( void ) [static] Returns the ImageBase with the correct endian conversion.

Only works if the bytecode is a PE hook (i.e. you invoked PE\_UNPACKER\_DECLARE).

### Returns

ImageBase of PE file, 0 - for non-PE hook

static force\_inline uint16\_t getNumberOfSections (void) [static] Returns the number of sections in this executable file.

### Returns

number of sections as 16-bit unsigned integer

static force\_inline uint32\_t getPEBaseOfCode ( void ) [static] Return the PE BaseOfCode.

#### Returns

PE BaseOfCode, or 0 if not in PE hook

static force\_inline uint32\_t getPEBaseOfData (void ) [static] Return the PE BaseOfData.

Returns

PE BaseOfData, or 0 if not in PE hook

static force\_inline uint16\_t getPECharacteristics ( ) [static] Returns PE characteristics. For example you can use this to check whether it is a DLL (0x2000).

Returns

characteristic of PE file, or 0 if not in PE hook

static force\_inline uint32\_t getPECheckSum ( void ) [static] Return the PE CheckSum.

Returns

PE CheckSum, or 0 if not in PE hook

static force\_inline uint32\_t getPEDataDirRVA (unsigned n) [static] Gets the virtual address of specified image data directory.

Parameters

in $n \mid \text{im}$	nage directory requested
-----------------------	--------------------------

### Returns

Virtual Address of requested image directory

static force\_inline uint32\_t getPEDataDirSize ( unsigned n ) [static] Gets the size of the specified image data directory.

Parameters

in	n	image directory requested

### Returns

Size of requested image directory

static force\_inline uint16\_t getPEDllCharacteristics ( void ) [static] Return the PE DllCharacteristics.

Returns

PE DllCharacteristics, or 0 if not in PE hook

static force\_inline uint32\_t getPEFileAlignment ( void ) [static] Return the PE File-Alignment.

Returns

PE File Alignment, or 0 if not in PE hook

static force\_inline uint64\_t getPEImageBase ( void ) [static] Return the PE ImageBase as 64-bit integer.

Returns

PE ImageBase as 64-bit int, or 0 if not in PE hook

static force\_inline bool getPEisDLL ( ) [static] Returns whether this is a DLL. Use this only in a PE hook!

Returns

true - the file is a DLL false - file is not a DLL

static uint32\_t getPELFANew ( void ) [static] Gets the offset to the PE header.

Returns

offset to the PE header, or 0 if not in PE hook

 ${\bf static\ force\_inline\ uint 32\_t\ get PELoader Flags\ (\ void\ \ )} \quad {\bf [static]} \quad {\bf Return\ the\ PE\ Loader Flags.}$ 

Returns

PE LoaderFlags or 0 if not in PE hook

static force\_inline uint16\_t getPEMachine ( ) [static] Returns the CPU this executable runs on, see libclamav/pe.c for possible values.

Returns

PE Machine or 0 if not in PE hook

static force\_inline uint16\_t getPEMajorImageVersion ( void ) [static] Return the PE MajorImageVersion.

Returns

PE MajorImageVersion, or 0 if not in PE hook

static force\_inline uint8\_t getPEMajorLinkerVersion ( void ) [static] Returns MajorLinkerVersion for this PE file.

Returns

PE MajorLinkerVersion or 0 if not in PE hook

 $static\ force\_inline\ uint 16\_t\ get PEMajor Operating System Version\ (\ void\ )\ [static]\ Return\ the\ PE\ Major Operating System Version.$ 

Returns

PE MajorOperatingSystemVersion, or 0 if not in PE hook

static force\_inline uint16\_t getPEMajorSubsystemVersion (void ) [static] Return the PE MajorSubsystemVersion.

Returns

PE Major Subsystem<br/>Version or 0 if not in PE hook

static force\_inline uint16\_t getPEMinorImageVersion ( void ) [static] Return the PE MinorImageVersion.

Returns

PE MinorrImageVersion, or 0 if not in PE hook

static force\_inline uint8\_t getPEMinorLinkerVersion ( void ) [static] Returns MinorLinkerVersion for this PE file.

Returns

PE MinorLinkerVersion or 0 if not in PE hook

 $static\ force\_inline\ uint 16\_t\ get PEM in or Operating System Version\ (\ void\ )\ [static] \ Return\ the\ PE\ Min or Operating System Version.$ 

Returns

PE MinorOperatingSystemVersion, or 0 if not in PE hook

static force\_inline uint16\_t getPEMinorSubsystemVersion (void) [static] Return the PE MinorSubsystemVersion.

Returns

PE MinorSubsystemVersion, or 0 if not in PE hook

static force\_inline uint32\_t getPENumberOfSymbols ( ) [static] Returns the PE number of debug symbols

Returns

PE NumberOfSymbols or 0 if not in PE hook

static force\_inline uint32\_t getPEPointerToSymbolTable ( ) [static] Returns pointer to the PE debug symbol table

Returns

PE PointerToSymbolTable or 0 if not in PE hook

static force\_inline uint32\_t getPESectionAlignment ( void ) [static] Return the PE SectionAlignment.

Returns

PE SectionAlignment, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfCode (void ) [static] Return the PE SizeOfCode.

Returns

PE SizeOfCode or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfHeaders ( void ) [static] Return the PE Size-OfHeaders.

Returns

PE SizeOfHeaders, or 0 if not in PE hook

Returns

PE SizeOfHeapCommit, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfHeapReserve ( void ) [static] Return the PE SizeOfHeapReserve.

Returns

PE SizeOfHeapReserve, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfImage (void ) [static] Return the PE SizeOfImage.

Returns

PE SizeOfImage, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfInitializedData ( void ) [static] Return the PE SizeofInitializedData.

Returns

PE SizeOfInitializeData or 0 if not in PE hook

static force\_inline uint16\_t getPESizeOfOptionalHeader ( ) [static] Returns the size of PE optional header.

Returns

size of PE optional header, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfStackCommit ( void ) [static] Return the PE SizeOfStackCommit.

Returns

PE SizeOfStackCommit, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfStackReserve ( void ) [static] Return the PE SizeOfStackReserve.

Returns

PE SizeOfStackReserver, or 0 if not in PE hook

static force\_inline uint32\_t getPESizeOfUninitializedData ( void ) [static] Return the PE SizeofUninitializedData.

Returns

PE SizeofUninitializedData or 0 if not in PE hook

 $\mathbf{static} \ \mathbf{force\_inline} \ \mathbf{uint16\_t} \ \mathbf{getPESubsystem} \ ( \ \mathbf{void} \ \ ) \ \ [\mathbf{static}] \ \ \mathbf{Return} \ \mathbf{the} \ \mathbf{PE} \ \mathbf{Subsystem}.$ 

Returns

PE subsystem, or 0 if not in PE hook

static force\_inline uint32\_t getPETimeDateStamp ( ) [static] Returns the PE Time-DateStamp from headers

Returns

PE TimeDateStamp or 0 if not in PE hook

static force\_inline uint32\_t getPEWin32VersionValue (void ) [static] Return the PE Win32VersionValue.

Returns

PE Win32VersionValue, or 0 if not in PE hook

static uint32\_t getSectionRVA ( unsigned i ) [static] Return the RVA of the specified section.

Parameters

 $i \mid \text{section index (from 0)}$ 

Returns

RVA of section, or -1 if invalid

static uint32\_t getSectionVirtualSize ( unsigned i ) [static] Return the virtual size of the specified section.

Parameters

 $i \mid \text{section index (from 0)}$ 

Returns

VSZ of section, or -1 if invalid

static uint32\_t getVirtualEntryPoint (void ) [static] The address of the EntryPoint. Use this for matching EP against sections.

Returns

virtual address of EntryPoint, or 0 if not in PE hook

static force\_inline bool has ExeInfo ( void ) [static] Returns whether the current file has executable information.

Returns

true if the file has exe info, false otherwise

static force\_inline bool hasPEInfo ( void ) [static] Returns whether PE information is available

Returns

true if PE information is available (in PE hooks)

static force\_inline bool isPE64 (void ) [static] Returns whether this is a PE32+ executable.

Returns

true if this is a PE32+ executable

uint32\_t pe\_rawaddr ( uint32\_t rva ) Converts a RVA (Relative Virtual Address) to an absolute PE file offset.

Parameters

in rva a rva address from the PE file

Returns

absolute file offset mapped to the rva, or PE\_INVALID\_RVA if the rva is invalid.

static force\_inline int read PESectionName ( unsigned char name[8], unsigned n ) [static] Read name of requested PE section.

Parameters

out	name	name of PE section
in	n	PE section requested

### Returns

0 if successful,

<0 otherwise

static force\_inline bool readRVA ( uint32\_t rva, void \* buf, size\_t bufsize ) [static] read the specified amount of bytes from the PE file, starting at the address specified by RVA. Parameters

in	rva	the Relative Virtual Address you want to read from (will be converted
		to file offset)
out	buf	destination buffer
in	bufsize	size of buffer

### Returns

true on success (full read) false on any failure

### 7.1.13. Scan Control

#### **Functions**

- uint32\_t setvirusname (const uint8\_t \*name, uint32\_t len)
- int32 t extract new (int32 t id)
- int32\_t bytecode\_rt\_error (int32\_t locationid)
- int32\_t extract\_set\_container (uint32\_t container)
- int32\_t input\_switch (int32\_t extracted\_file)
- static force\_inline overloadable\_func void foundVirus (const char \*virusname)

### **Detailed Description**

#### **Function Documentation**

int32\_t bytecode\_rt\_error ( int32\_t locationid ) Report a runtime error at the specified locationID.

Parameters

in	$locationid \mid (line << 8) \mid (column \& 0xff)$	
----	---	--

#### Returns

0

 ${\bf int32\_t~extract\_new}$  (  ${\bf int32\_t~id}$  ) Prepares for extracting a new file, if we've already extracted one it scans it.

Parameters

in	id an id for the new file (for example position in container)	
----	---	--

### Returns

1 if previous extracted file was infected

 $int32\_t\ extract\_set\_container\ (\ uint32\_t\ container\ )$  Sets the container type for the currently extracted file.

Parameters

in   container   container type (CL_TYPE_*)
---

### Returns

current setting for container (CL\_TYPE\_ANY default)

static force\_inline overloadable\_func void found Virus ( const char \* virus name ) [static] Sets the specified virus name as the virus detected by this bytecode. Parameters

in	virusname	the name of the virus, excluding the prefix, must be one of the virus-
		names declared in VIRUSNAMES.

### See Also

### VIRUSNAMES

<code>int32\_t input\_switch</code> ( <code>int32\_t extracted\_file</code> ) Toggles the read/seek API to read from the currently extracted file, and back. You must call seek after switching inputs to position the cursor to a valid position.

Chapter 7. Bytecode API	6
Chapter 7. Bytecode AF1	

### Parameters

in	$extracted\_file$	1 - switch to reading from extracted file
		0 - switch back to original input

### Returns

-1 on error (if no extracted file exists)

0 on success

## $uint32\_t \ setvirusname \ ( \ const \ uint8\_t * name, \ uint32\_t \ len \ )$ Sets the name of the virus found. Parameters

in	name	the name of the virus
in	len	length of the virusname

### Returns

0

### 7.1.14. String Operations

#### **Functions**

- int32\_t memstr (const uint8\_t \*haystack, int32\_t haysize, const uint8\_t \*needle, int32\_t needle-size)
- int32 t hex2ui (uint32 t hex1, uint32 t hex2)
- int32 t atoi (const uint8 t \*str, int32 t size)
- uint32\_t entropy\_buffer (uint8\_t \*buffer, int32\_t size)
- static force\_inline void \* memchr (const void \*s, int c, size\_t n)
- void \* memset (void \*src, int c, uintptr\_t n) \_\_attribute\_\_((nothrow)) \_\_attribute\_\_((\_\_-nonnull\_\_((1))))
- void \* memmove (void \*dst, const void \*src, uintptr\_t n) \_\_attribute\_\_((\_\_nothrow\_\_)) \_\_attribute\_\_((\_\_nonnull\_\_(1
- void void \* memcpy (void \*restrict dst, const void \*restrict src, uintptr\_t n) \_\_attribute\_\_((\_\_-nothrow\_\_)) \_\_attribute\_\_((\_\_nonnull\_\_(1
- void void int memcmp (const void \*s1, const void \*s2, uint32\_t n) \_\_attribute\_\_((\_\_nothrow\_\_)) \_\_attribute\_\_((\_nonnull\_\_(1

### **Detailed Description**

### **Function Documentation**

 $int32\_t$  atoi ( const uint8 $\_t*str$ ,  $int32\_t$  size ) Converts string to positive number. Parameters

in	str	buffer
in	size	size of str

### Returns

>0 string converted to number if possible, -1 on error

 ${\tt uint32\_t\ entropy\_buffer}$  (  ${\tt uint8\_t\ *\ buffer}, {\tt int32\_t\ size}$  ) Returns an approximation for the entropy of buffer.

Parameters

in	buffer	input buffer
in	size	size of buffer

#### Returns

entropy estimation \*  $2^26$ 

 $int32\_t\ hex2ui\ (\ uint32\_t\ hex1,\ uint32\_t\ hex2\ )$  Returns hexadecimal characters hex1 and hex2 converted to 8-bit number.

Parameters

in	hex1	hexadecimal character
in	hex2	hexadecimal character

### Returns

hex1 hex2 converted to 8-bit integer, -1 on error

static force\_inline void\* memchr ( const void \* s, int c, size\_t n ) [static] Scan the first n bytes of the buffer s, for the character c.

#### Parameters

in	s	buffer to scan
in	c	character to look for
in	n	size of buffer

### Returns

a pointer to the first byte to match, or NULL if not found.

void void int memcmp ( const void \* s1, const void \* s2, uint32\_t n ) [LLVM Intrinsic] Compares two memory buffers, s1 and s2 to length n.

Parameters

in	s1	buffer one
in	s2	buffer two
in	n	amount of bytes to copy

### Returns

an integer less than, equal to, or greater than zero if the first n bytes of s1 are found, respectively, to be less than, to match, or be greater than the first n bytes of s2.

void void\* memcpy ( void \*restrict dst, const void \*restrict src, uintptr\_t n ) [LLVM Intrinsic] Copies data between two non-overlapping buffers, from src to dst to length n. Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

### Returns

dst

Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

### Returns

dst

Parameters

out	src	pointer to buffer
in	c	character to fill buffer with
in	n	length of buffer

### Returns

src

Parameters

in	haystack	buffer to search
in	hay size	size of haystack
in	needle	substring to search
in	needle size	size of needle

### Returns

location of match, -1 otherwise

# CHAPTER 8

# Copyright and License

### 8.1. The ClamAV Bytecode Compiler

The ClamAV Bytecode Compiler is released under the GNU General Public License version 2.

The following directories are under the GNU General Public License version 2: ClamBC, docs, driver, editor, examples, ifacegen.

Copyright (C) 2009 Sourcefire, Inc.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License version 2 as published by the Free Software Foundation.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

It uses the LLVM compiler framework, contained in the following directories: llvm, clang. They have this copyright:

\_\_\_\_\_

LLVM Release License

\_\_\_\_\_

University of Illinois/NCSA Open Source License

Copyright (c) 2003-2009 University of Illinois at Urbana-Champaign. All rights reserved.

Developed by:

LLVM Team

University of Illinois at Urbana-Champaign

http://llvm.org

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal with the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

- \* Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimers.
- \* Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimers in the documentation and/or other materials provided with the distribution.

\* Neither the names of the LLVM Team, University of Illinois at Urbana-Champaign, nor the names of its contributors may be used to endorse or promote products derived from this Software without specific prior written permission.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

\_\_\_\_\_\_

Copyrights and Licenses for Third Party Software Distributed with LLVM:

The LLVM software contains code written by third parties. Such software will have its own individual LICENSE.TXT file in the directory in which it appears.

This file will describe the copyrights, license, and restrictions which apply to that code.

The disclaimer of warranty in the University of Illinois Open Source License applies to all code in the LLVM Distribution, and nothing in any of the other licenses gives permission to use the names of the LLVM Team or the University of Illinois to endorse or promote products derived from this Software.

The following pieces of software have additional or alternate copyrights, licenses, and/or restrictions:

 Program
 Directory

 ---- ----- 

 Autoconf
 11vm/autoconf

llvm/projects/ModuleMaker/autoconf
llvm/projects/sample/autoconf
llvm/lib/Target/CellSPU/README.txt

CellSPU backend llvm/lib/Target/CellSPU/README.tr
Google Test llvm/utils/unittest/googletest

OpenBSD regex llvm/lib/Support/{reg\*, COPYRIGHT.regex}

It also uses re2c, contained in driver/clamdriver/re2c. This code is public domain:

Originally written by Peter Bumbulis (peter@csg.uwaterloo.ca)

Currently maintained by:

- \* Dan Nuffer <nuffer@users.sourceforge.net>
- \* Marcus Boerger <helly@users.sourceforge.net>
- \* Hartmut Kaiser <hkaiser@users.sourceforge.net>

The re2c distribution can be found at:

http://sourceforge.net/projects/re2c/

re2c is distributed with no warranty whatever. The code is certain to contain errors. Neither the author nor any contributor takes responsibility for any consequences of its use.

re2c is in the public domain. The data structures and algorithms used in re2c are all either taken from documents available to the general public or are inventions of the author. Programs generated by re2c may be distributed freely. re2c itself may be distributed freely, in source or binary, unchanged or modified. Distributors may charge whatever fees they can obtain for re2c.

If you do make use of re2c, or incorporate it into a larger project an acknowledgement somewhere (documentation, research report, etc.) would be appreciated.

## 8.2. Bytecode

The headers used when compiling bytecode have these license (clang/lib/Headers/{bcfeatures,bytecode\*}.h):

Copyright (C) 2009 Sourcefire, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The other header files in clang/lib/Headers/ are from clang with this license (see individual files for copyright owner):

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

When using the ClamAV bytecode compiler to compile your own bytecode programs, you can release it under the license of your choice, provided that you comply with the license of the above header files.

70 8.2. Bytecode

# APPENDIX A

# Low-Level API Globals

#### A.0.1. Global Variables

#### Variables

```
• const uint32_t __clambc_match_counts [64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.
```

• const uint32\_t \_\_clambc\_match\_offsets [64]

This is a low-level variable, use the Macros in bytecode\_local.h instead to access it.

- const struct cli\_pe\_hook\_data \_\_\_clambc\_pedata
- $\bullet$  const uint32\_t \_\_clambc\_filesize [1]
- $\bullet$  const uint16\_t \_\_clambc\_kind

#### **Detailed Description**

#### Variable Documentation

```
\mathbf{const}\ \mathbf{uint32\_t}\ \underline{\hspace{1.5cm}}\mathbf{clambc\_filesize[1]}\quad \mathrm{File}\ \mathrm{size}\ (\mathrm{max}\ 4\mathrm{G}).
```

const uint16\_t \_\_\_clambc\_kind Kind of the bytecode, affects LibClamAV usage

 ${\color{blue} const\ uint 32\_t\ \_\_clambc\_match\_counts} [64] \quad {\color{blue} This\ is\ a\ low-level\ variable,\ use\ the\ Macros\ in\ bytecode\_local.h\ instead\ to\ access\ it.}$ 

Logical signature match counts

 $const\ uint32\_t\ \_\_clambc\_match\_offsets[64]$  This is a low-level variable, use the Macros in bytecode\_local.h instead to access it.

Logical signature match offsets

const struct cli\_pe\_hook\_data \_\_\_clambc\_pedata PE data, if this is a PE hook.

# APPENDIX B

# Low-Level API Structures

#### B.0.2. cli\_exe\_info Struct Reference

#### **Data Fields**

- struct cli $\_$ exe $\_$ section \* section
- uint32 t offset
- $uint32\_t ep$
- uint16\_t nsections
- uint32\_t res\_addr
- uint32\_t hdr\_size

#### **Detailed Description**

Executable file information.

#### Field Documentation

```
uint32_t ep Entrypoint of executable
```

```
uint32_t hdr_size Address size - PE ONLY
```

uint16\_t nsections Number of sections

uint32\_t offset Offset where this executable start in file (nonzero if embedded)

uint32\_t res\_addr Resrources RVA - PE ONLY

struct cli\_exe\_section\* section Information about all the sections of this file. This array has nsection elements

#### B.0.3. DIS fixed Struct Reference

- enum X86OPS x86\_opcode
- enum DIS\_SIZE operation\_size
- enum DIS\_SIZE address\_size
- uint8\_t segment
- struct DIS\_arg arg [3]

Disassembled instruction.

#### Field Documentation

enum DIS\_SIZE address\_size size of address

struct DIS\_arg arg[3] arguments

enum DIS\_SIZE operation\_size size of operation

uint8\_t segment segment

enum X86OPS x86\_opcode opcode of X86 instruction

#### B.0.4. pe\_image\_data\_dir Struct Reference

#### **Detailed Description**

PE data directory header

#### B.0.5. DIS\_arg Struct Reference

#### **Data Fields**

- enum DIS\_ACCESS access\_type
- $\bullet \;\; {\rm enum} \; {\rm DIS\_SIZE} \; {\rm access\_size}$
- struct DIS\_mem\_arg mem
- enum X86REGS reg
- uint64\_t other

#### **Detailed Description**

Disassembled operand.

#### Field Documentation

 $\mathbf{enum\ DIS\_SIZE\ access\_size}\quad \mathrm{size\ of\ access}$ 

enum DIS\_ACCESS access\_type type of access

 $\mathbf{struct}\ \mathbf{DIS\_mem\_arg}\ \mathbf{mem}\quad \mathbf{memory}\ \mathbf{operand}$ 

uint64\_t other operand

enum X86REGS reg register operand

#### B.0.6. pe\_image\_optional\_hdr64 Struct Reference

- $\bullet \quad uint8\_t \ {\rm MajorLinkerVersion}$
- uint8 t MinorLinkerVersion
- uint32 t SizeOfCode
- uint32\_t SizeOfInitializedData
- uint32\_t SizeOfUninitializedData
- uint64 t ImageBase
- $\bullet \ \ uint 32\_t \ Section Alignment$

- uint32\_t FileAlignment
- uint16\_t MajorOperatingSystemVersion
- uint16\_t MinorOperatingSystemVersion
- uint16\_t MajorImageVersion
- uint16\_t MinorImageVersion
- uint32 t CheckSum
- uint32 t NumberOfRvaAndSizes

PE 64-bit optional header

#### Field Documentation

uint32\_t CheckSum NT drivers only

uint32\_t FileAlignment usually 32 or 512

uint64\_t ImageBase multiple of 64 KB

uint16\_t MajorImageVersion unreliable

 ${\bf uint 8\_t\ Major Linker Version}\quad {\bf unreliable}$ 

uint16\_t MajorOperatingSystemVersion not used

uint16\_t MinorImageVersion unreliable

uint8\_t MinorLinkerVersion unreliable

uint16\_t MinorOperatingSystemVersion not used

 $uint 32\_t\ Number Of Rva And Sizes \quad unreliable$ 

uint32\_t SectionAlignment usually 32 or 4096

uint32\_t SizeOfCode unreliable

 ${\bf uint 32\_t~Size Of Initialized Data} \quad {\bf unreliable}$ 

 $uint32\_t$  SizeOfUninitializedData unreliable

#### B.0.7. cli\_exe\_info Struct Reference

- $\bullet \ \ struct \ cli\_exe\_section * section$
- $\bullet \ \ uint 32\_t \ offset$
- uint32\_t ep
- uint16\_t nsections
- $uint32\_t res\_addr$
- uint32 t hdr size

Executable file information.

#### Field Documentation

uint32\_t ep Entrypoint of executable

uint32\_t hdr\_size Address size - PE ONLY

uint16\_t nsections Number of sections

uint32\_t offset Offset where this executable start in file (nonzero if embedded)

uint32\_t res\_addr Resrources RVA - PE ONLY

struct cli\_exe\_section\* section Information about all the sections of this file. This array has nsection elements

#### B.0.8. pe\_image\_section\_hdr Struct Reference

#### **Data Fields**

- uint8\_t Name [8]
- uint32 t SizeOfRawData
- uint32\_t PointerToRawData
- uint32 t PointerToRelocations
- uint32\_t PointerToLinenumbers
- uint16 t NumberOfRelocations
- uint16 t NumberOfLinenumbers

#### **Detailed Description**

PE section header

#### Field Documentation

uint8\_t Name[8] may not end with NULL

uint16\_t NumberOfLinenumbers object files only

uint16\_t NumberOfRelocations object files only

uint32\_t PointerToLinenumbers object files only

uint32\_t PointerToRawData offset to the section's data

 ${\bf uint 32\_t\ Pointer To Relocations}\quad {\bf object\ files\ only}$ 

#### ${\bf uint 32\_t~Size Of Raw Data} \quad {\bf multiple~of~File Alignment}$

#### B.0.9. cli\_pe\_hook\_data Struct Reference

#### **Data Fields**

- uint32\_t ep
- uint16\_t nsections
- struct pe\_image\_file\_hdr file\_hdr
- struct pe\_image\_optional\_hdr32 opt32
- $\bullet \ \ \mathbf{struct} \ \ \mathbf{pe\_image\_optional\_hdr} \mathbf{64} \ \ \mathbf{opt} \mathbf{64}$
- struct pe\_image\_data\_dir dirs [16]
- uint32\_t e\_lfanew
- uint32 t overlays
- int32\_t overlays\_sz
- uint32 t hdr size

#### **Detailed Description**

Data for the bytecode PE hook

#### Field Documentation

```
struct pe_image_data_dir dirs[16] PE data directory header
uint32_t e_lfanew address of new exe header
uint32_t ep EntryPoint as file offset
```

struct pe\_image\_file\_hdr file\_hdr Header for this PE file

uint32\_t hdr\_size internally needed by rawaddr

uint16\_t nsections Number of sections

struct pe\_image\_optional\_hdr32 opt32 32-bit PE optional header

struct pe\_image\_optional\_hdr64 opt64 64-bit PE optional header

uint32\_t overlays number of overlays

int32\_t overlays\_sz size of overlays

#### B.0.10. cli\_exe\_section Struct Reference

- uint32 t rva
- $uint32\_t vsz$
- uint32 t raw
- uint32\_t rsz
- $uint32\_t chr$
- uint32\_t urva
- $\bullet$  uint32\_t uvsz
- uint32 t uraw
- uint32\_t ursz

Section of executable file.

#### Field Documentation

```
uint32_t chr Section characteristics
```

uint32\_t raw Raw offset (in file)

uint32\_t rsz Raw size (in file)

uint32\_t rva Relative VirtualAddress

uint32\_t uraw PE - unaligned PointerToRawData

uint32\_t ursz PE - unaligned SizeOfRawData

uint32\_t urva PE - unaligned VirtualAddress

uint32\_t uvsz PE - unaligned VirtualSize

 $uint32\_t vsz$  VirtualSize

#### B.0.11. pe\_image\_file\_hdr Struct Reference

#### **Data Fields**

- uint32 t Magic
- $uint16\_t$  Machine
- uint16 t NumberOfSections
- uint32\_t TimeDateStamp
- uint32\_t PointerToSymbolTable
- uint32 t NumberOfSymbols
- uint16\_t SizeOfOptionalHeader

#### **Detailed Description**

Header for this PE file

#### Field Documentation

uint16\_t Machine CPU this executable runs on, see libclamav/pe.c for possible values

uint32\_t Magic PE magic header:  $PE \setminus 0 \setminus 0$ 

uint16\_t NumberOfSections Number of sections in this executable

uint32\_t NumberOfSymbols debug

 $uint32\_t$  PointerToSymbolTable debug

uint16\_t SizeOfOptionalHeader == 224

uint32\_t TimeDateStamp Unreliable

#### B.0.12. pe\_image\_optional\_hdr32 Struct Reference

#### **Data Fields**

- uint8 t MajorLinkerVersion
- uint8\_t MinorLinkerVersion
- uint32\_t SizeOfCode
- uint32 t SizeOfInitializedData
- $\bullet$  uint32\_t SizeOfUninitializedData
- uint32 t ImageBase
- uint32\_t SectionAlignment
- uint32\_t FileAlignment
- uint16\_t MajorOperatingSystemVersion
- $\bullet \ \ uint16\_t \ Minor Operating System Version$
- uint16 t MajorImageVersion
- uint16 t MinorImageVersion
- uint32\_t CheckSum
- uint32 t NumberOfRvaAndSizes

#### **Detailed Description**

32-bit PE optional header

#### Field Documentation

uint32\_t CheckSum NT drivers only

uint32\_t FileAlignment usually 32 or 512

uint32\_t ImageBase multiple of 64 KB

uint16\_t MajorImageVersion unreliable

uint8\_t MajorLinkerVersion unreliable

uint16\_t MajorOperatingSystemVersion not used

 $uint16\_t\ MinorImageVersion$  unreliable

uint8\_t MinorLinkerVersion unreliable

 ${\bf uint 16\_t\ Minor Operating System Version}\quad {\bf not\ used}$ 

 $uint32\_t NumberOfRvaAndSizes$  unreliable

uint32\_t SectionAlignment usually 32 or 4096

 $uint32\_t$  SizeOfCode unreliable

uint32\_t SizeOfInitializedData unreliable

 $uint32\_t$  SizeOfUninitializedData unreliable

#### B.0.13. DIS\_mem\_arg Struct Reference

#### **Data Fields**

- enum DIS\_SIZE access\_size
- enum X86REGS scale reg
- enum X86REGS add\_reg
- $uint8\_t$  scale
- int32\_t displacement

#### **Detailed Description**

Disassembled memory operand: scale\_reg\*scale + add\_reg + displacement.

#### Field Documentation

enum DIS\_SIZE access\_size size of access

enum X86REGS add\_reg register used as displacemenet

int32\_t displacement displacement as immediate number

 $uint8\_t$  scale as immediate number

enum X86REGS scale\_reg register used as scale

#### B.0.14. DISASM\_RESULT Struct Reference

#### **Detailed Description**

disassembly result, 64-byte, matched by type-8 signatures

# API Headers

C.0.15. File List	
bytecode_execs.h	81 84 92 93 95
C.0.16. bytecode_api.h File Reference	
Enumerations	
<ul> <li>enum BytecodeKind {     BC_GENERIC =0, BC_STARTUP =1 , BC_LOGICAL =256, BC_PE_UNPACKER,     BC_PDF, BC_PE_ALL }</li> <li>enum { PE_INVALID_RVA = 0xFFFFFFFF }</li> <li>enum FunctionalityLevels {     FUNC_LEVEL_096 = 51 , FUNC_LEVEL_096_1 = 53 , FUNC_LEVEL_096_2 = 54 , FUNC_LEVEL_096_3 = 55,     FUNC_LEVEL_096_4 = 56, FUNC_LEVEL_096_5 = 58, FUNC_LEVEL_097 = 60, FUNC_LEVEL_097_1 = 61,     FUNC_LEVEL_097_2 = 62, FUNC_LEVEL_097_3 = 63, FUNC_LEVEL_097_4 = 64, FUNC_LEVEL_097_5 = 65,     FUNC_LEVEL_097_6 = 67, FUNC_LEVEL_097_7 = 68, FUNC_LEVEL_097_8 = 69, FUNC_LEVEL_098 = 74,     FUNC_LEVEL_098_1 = 76, FUNC_LEVEL_098_2 = 78 }</li> <li>enum pdf_phase { , PDF_PHASE_PARSED, PDF_PHASE_POSTDUMP, PDF_PHASE_EN_PDF_PHASE_PRE }</li> <li>enum pdf_flag</li> <li>enum pdf_objflags</li> <li>enum { SEEK_SET =0, SEEK_CUR, SEEK_END }</li> </ul>	C_ NC
Functions	
<ul> <li>uint32_t test1 (uint32_t a, uint32_t b)</li> <li>int32_t read (uint8_t *data, int32_t size)</li> <li>int32_t write (uint8_t *data, int32_t size)</li> <li>int32_t seek (int32_t pos, uint32_t whence)</li> <li>uint32_t setvirusname (const uint8_t *name, uint32_t len)</li> <li>uint32_t debug_print_str (const uint8_t *str, uint32_t len)</li> <li>uint32_t debug_print_uint (uint32_t a)</li> <li>uint32_t disasm_x86 (struct DISASM_RESULT *result, uint32_t len)</li> <li>uint32_t pe_rawaddr (uint32_t rva)</li> <li>int32_t file_find (const uint8_t *data, uint32_t len)</li> </ul>	

```
• int32_t file_byteat (uint32_t offset)
• void * malloc (uint32 t size)
• uint32 t test2 (uint32 t a)
• int32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
• int32 t fill buffer (uint8 t *buffer, uint32 t len, uint32 t filled, uint32 t cursor, uint32 t fill)
• int32 t extract new (int32 t id)
• int32 t read number (uint32 t radix)
• int32 t hashset new (void)
• int32\_t hashset_add (int32\_t hs, uint32\_t key)
• int32_t hashset_remove (int32_t hs, uint32_t key)
• int32 t hashset contains (int32 t hs, uint32 t key)
• int32_t hashset_done (int32_t id)
• int32 t hashset empty (int32 t id)
• int32_t buffer_pipe_new (uint32_t size)
• int32_t buffer_pipe_new_fromfile (uint32_t pos)
• uint32 t buffer pipe read avail (int32 t id)
• const uint8 t * buffer pipe read get (int32 t id, uint32 t amount)
• int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)
• uint32_t buffer_pipe_write_avail (int32_t id)
• uint8_t * buffer_pipe_write_get (int32_t id, uint32_t size)
• int32 t buffer pipe write stopped (int32 t id, uint32 t amount)
• int32_t buffer_pipe_done (int32_t id)
• int32 t inflate init (int32 t from buffer, int32 t to buffer, int32 t windowBits)
• int32 t inflate process (int32 t id)
• int32_t inflate_done (int32_t id)
• int32_t bytecode_rt_error (int32_t locationid)
• int32 t jsnorm init (int32 t from buffer)
• int32_t jsnorm_process (int32_t id)
• int32 t jsnorm done (int32 t id)
• int32_t ilog2 (uint32_t a, uint32_t b)
• int32_t ipow (int32_t a, int32_t b, int32_t c)
• uint32 t iexp (int32 t a, int32 t b, int32 t c)
• int32_t isin (int32_t a, int32_t b, int32_t c)
• int32_t icos (int32_t a, int32_t b, int32_t c)
• int32 t memstr (const uint8 t *haystack, int32 t haysize, const uint8 t *needle, int32 t needle-
  size)
• int32_t hex2ui (uint32_t hex1, uint32_t hex2)
• int32_t atoi (const uint8_t *str, int32_t size)
• uint32 t debug print str start (const uint8 t *str, uint32 t len)
• uint32_t debug_print_str_nonl (const uint8_t *str, uint32_t len)
• uint32_t entropy_buffer (uint8_t *buffer, int32_t size)
• int32 t map new (int32 t keysize, int32 t valuesize)
• int32 t map addkey (const uint8 t *key, int32 t ksize, int32 t id)
• int32 t map setvalue (const uint8 t *value, int32 t vsize, int32 t id)
• int32 t map remove (const uint8 t *key, int32 t ksize, int32 t id)
• int32_t map_find (const uint8_t *key, int32_t ksize, int32_t id)
• int32 t map getvaluesize (int32 t id)
• uint8 t * map getvalue (int32 t id, int32 t size)
• int32_t map_done (int32_t id)
• int32 t file find limit (const uint8 t *data, uint32 t len, int32 t maxpos)
• uint32_t engine_functionality_level (void)
• uint32_t engine_dconf_level (void)
• uint32 t engine scan options (void)
```

• uint32\_t engine\_db\_options (void)

Appendix C. API Headers 83

- int32\_t extract\_set\_container (uint32\_t container)
- int32 t input switch (int32 t extracted file)
- uint32\_t get\_environment (struct cli\_environment \*env, uint32\_t len)
- uint32\_t disable\_bytecode\_if (const int8\_t \*reason, uint32\_t len, uint32\_t cond)
- uint32\_t disable\_jit\_if (const int8\_t \*reason, uint32\_t len, uint32\_t cond)
- int32\_t version\_compare (const uint8\_t \*lhs, uint32\_t lhs\_len, const uint8\_t \*rhs, uint32\_t rhs\_len)
- uint32\_t check\_platform (uint32\_t a, uint32\_t b, uint32\_t c)
- int32\_t pdf\_get\_obj\_num (void)
- int32\_t pdf\_get\_flags (void)
- int32 t pdf set flags (int32 t flags)
- int32\_t pdf\_lookupobj (uint32\_t id)
- uint32\_t pdf\_getobjsize (int32\_t objidx)
- const uint8\_t \* pdf\_getobj (int32\_t objidx, uint32\_t amount)
- int32\_t pdf\_getobjid (int32\_t objidx)
- int32\_t pdf\_getobjflags (int32\_t objidx)
- int32 t pdf setobjflags (int32 t objidx, int32 t flags)
- int32 t pdf get offset (int32 t objidx)
- int32 t pdf get phase (void)
- int32\_t pdf\_get\_dumpedobjid (void)
- int32\_t matchicon (const uint8\_t \*group1, int32\_t group1\_len, const uint8\_t \*group2, int32\_t group2\_len)
- int32 trunning on jit (void)
- int32\_t get\_file\_reliability (void)

#### Variables

- const uint32\_t \_\_\_clambc\_match\_counts [64]
  - This is a low-level variable, use the Macros in bytecode\_local.h instead to access it.
- const uint32\_t \_\_clambc\_match\_offsets [64]

This is a low-level variable, use the Macros in bytecode local.h instead to access it.

- const struct cli\_pe\_hook\_data \_\_\_clambc\_pedata
- const uint32\_t \_\_clambc\_filesize [1]
- const uint16\_t \_\_clambc\_kind

#### **Enumeration Type Documentation**

#### anonymous enum

Enumerator

 $PE\_INVALID\_RVA$  Invalid RVA specified

#### **Function Documentation**

#### $uint32\_t test1 ( uint32\_t a, uint32\_t b )$ Test api.

Parameters

in	a	0xf00dbeef
in	b	0xbeeff00d

#### Returns

0x12345678 if parameters match, 0x55 otherwise

#### 84

 $\mathbf{uint32\_t\ test2}\ (\ \mathbf{uint32\_t}\ a\ )\ \mathrm{Test\ api2}.$ 

#### Parameters

in	a	0xf00d

#### Returns

0xd00f if parameter matches, 0x5555 otherwise

## $\textbf{C.0.17.} \ \ \textbf{bytecode\_disasm.h} \ \ \textbf{File} \ \ \textbf{Reference}$

#### **Data Structures**

#### **Enumerations**

```
• enum X86OPS {,
 OP_AAA, OP_AAD, OP_AAM, OP_AAS,
 OP ADD, OP ADC, OP AND, OP ARPL.
 OP BOUND, OP BSF, OP BSR, OP BSWAP,
 OP_BT, OP_BTC, OP_BTR, OP_BTS,
 OP_CALL, OP_CDQ, OP_CWDE, OP_CBW,
 OP_CLC, OP_CLD, OP_CLI, OP_CLTS,
 OP_CMC, OP_CMOVO, OP_CMOVNO, OP_CMOVC,
 OP CMOVNC, OP CMOVZ, OP CMOVNZ, OP CMOVBE,
 OP_CMOVA, OP_CMOVS, OP_CMOVNS, OP_CMOVP,
 OP_CMOVNP, OP_CMOVL, OP_CMOVGE, OP_CMOVLE,
 OP_CMOVG, OP_CMP, OP_CMPSD, OP_CMPSW,
 OP_CMPSB, OP_CMPXCHG, OP_CMPXCHG8B, OP_CPUID,
 OP_DAA, OP_DAS, OP_DEC, OP_DIV,
 OP ENTER, OP_FWAIT, OP_HLT, OP_IDIV,
 OP IMUL, OP INC, OP IN, OP INSD,
 OP INSW, OP INSB, OP INT, OP INT3,
 OP_INTO, OP_INVD, OP_INVLPG, OP_IRET,
 OP_JO, OP_JNO, OP_JC, OP_JNC,
 OP_JZ, OP_JNZ, OP_JBE, OP_JA,
 OP_JS, OP_JNS, OP_JP, OP_JNP,
 OP_JL, OP_JGE, OP_JLE, OP_JG,
 OP JMP, OP LAHF, OP LAR, OP LDS,
 OP LES, OP LFS, OP LGS, OP LEA,
 OP LEAVE, OP LGDT, OP LIDT, OP LLDT,
 OP_PREFIX_LOCK, OP_LODSD, OP_LODSW, OP_LODSB,
 OP_LOOP, OP_LOOPE, OP_LOOPNE, OP_JECXZ,
 OP LSL, OP_LSS, OP_LTR, OP_MOV,
 OP_MOVSD, OP_MOVSW, OP_MOVSB, OP_MOVSX,
 OP_MOVZX, OP_MUL, OP_NEG, OP_NOP,
 OP_NOT, OP_OR, OP_OUT, OP_OUTSD,
 OP_OUTSW, OP_OUTSB, OP_PUSH, OP_PUSHAD,
 OP_PUSHFD, OP_POP, OP_POPAD, OP_POPFD,
 OP_RCL, OP_RCR, OP_RDMSR, OP_RDPMC,
 OP_RDTSC, OP_PREFIX_REPE, OP_PREFIX_REPNE, OP_RETF,
 OP_RETN, OP_ROL, OP_ROR, OP_RSM,
 OP_SAHF, OP_SAR, OP_SBB, OP_SCASD,
 OP SCASW, OP SCASB, OP SETO, OP SETNO,
 OP SETC, OP SETNC, OP SETZ, OP SETNZ,
 OP SETBE, OP SETA, OP SETS, OP SETNS,
 OP_SETP, OP_SETNP, OP_SETL, OP_SETGE,
 OP_SETLE, OP_SETG, OP_SGDT, OP_SIDT,
 OP_SHL, OP_SHLD, OP_SHR, OP_SHRD,
 OP_SLDT, OP_STOSD, OP_STOSW, OP_STOSB,
 OP_STR, OP_STC, OP_STD, OP_STI,
 OP_SUB, OP_SYSCALL, OP_SYSENTER, OP_SYSEXIT,
 OP SYSRET, OP TEST, OP UD2, OP VERR,
 OP VERRW, OP_WBINVD, OP_WRMSR, OP_XADD,
 OP_XCHG, OP_XLAT, OP_XOR, OP_FPU,
 OP_F2XM1, OP_FABS, OP_FADD, OP_FADDP,
 OP_FBLD, OP_FBSTP, OP_FCHS, OP_FCLEX,
 OP_FCMOVB, OP_FCMOVBE, OP_FCMOVE, OP_FCMOVNB,
 OP_FCMOVNBE, OP_FCMOVNE, OP_FCMOVNU, OP_FCMOVU,
 OP_FCOM, OP_FCOMI, OP_FCOMIP, OP_FCOMP,
 OP FCOMPP, OP FCOS, OP FDECSTP, OP FDIV,
 OP FDIVP, OP FDIVR, OP FDIVRP, OP FFREE,
 OP FIADD, OP FICOM, OP FICOMP, OP FIDIV,
    FIDIVR, OP FILD, OP FIMUL, OP FINCSTP,
 OP_FINIT, OP_FIST, OP_FISTP, OP_FISTTP,
 OP_FISUB, OP_FISUBR, OP_FLD, OP_FLD1,
```

OP\_FLDCW, OP\_FLDENV, OP\_FLDL2E, OP\_FLDL2T, OP\_FLDLG2, OP\_FLDLN2, OP\_FLDPI, OP\_FLDZ,

```
OP_FYL2XP1 }
   • enum DIS ACCESS {
     ACCESS_NOARG, ACCESS_IMM, ACCESS_REL, ACCESS_REG,
     ACCESS_MEM }
   • enum DIS_SIZE {
     SIZEB, SIZEW, SIZED, SIZEF,
     SIZEQ, SIZET, SIZEPTR }
   • enum X86REGS
Enumeration Type Documentation
enum DIS_ACCESS Access type
Enumerator
    ACCESS_NOARG arg not present
    ACCESS_IMM immediate
    ACCESS\_REL +/-immediate
    ACCESS_REG register
    ACCESS_MEM [memory]
enum DIS_SIZE for mem access, immediate and relative
Enumerator
    SIZEB Byte size access
    SIZEW Word size access
    SIZED Doubleword size access
    SIZEF 6-byte access (seg+reg pair)
    SIZEQ Quadword access
    SIZET 10-byte access
    SIZEPTR ptr
enum X86OPS X86 opcode
Enumerator
    OP\_AAA Ascii Adjust after Addition
    OP_AAD Ascii Adjust AX before Division
    OP_AAM Ascii Adjust AX after Multiply
    OP\_AAS Ascii Adjust AL after Subtraction
    OP ADD Add
    OP_ADC Add with Carry
    OP\_AND Logical And
    OP_ARPL Adjust Requested Privilege Level
    OP_BOUND Check Array Index Against Bounds
    OP\_BSF Bit Scan Forward
    OP\_BSR Bit Scan Reverse
    OP\_BSWAP Byte Swap
    OP\_BT Bit Test
    OP\_BTC Bit Test and Complement
    OP_BTR Bit Test and Reset
```

 $OP\_BTS$  Bit Test and Set

- OP CALL Call
- OP CDQ Convert DoubleWord to QuadWord
- OP CWDE Convert Word to DoubleWord
- OP\_CBW Convert Byte to Word
- OP\_CLC Clear Carry Flag
- OP\_CLD Clear Direction Flag
- OP\_CLI Clear Interrupt Flag
- OP\_CLTS Clear Task-Switched Flag in CR0
- OP\_CMC Complement Carry Flag
- OP\_CMOVO Conditional Move if Overflow
- *OP\_CMOVNO* Conditional Move if Not Overflow
- OP\_CMOVC Conditional Move if Carry
- OP\_CMOVNC Conditional Move if Not Carry
- OP\_CMOVZ Conditional Move if Zero
- OP CMOVNZ Conditional Move if Non-Zero
- OP CMOVBE Conditional Move if Below or Equal
- OP\_CMOVA Conditional Move if Above
- OP\_CMOVS Conditional Move if Sign
- $OP\_CMOVNS$  Conditional Move if Not Sign
- OP\_CMOVP Conditional Move if Parity
- OP\_CMOVNP Conditional Move if Not Parity
- OP CMOVL Conditional Move if Less
- *OP\_CMOVGE* Conditional Move if Greater or Equal
- OP\_CMOVLE Conditional Move if Less than or Equal
- *OP\_CMOVG* Conditional Move if Greater
- **OP\_CMP** Compare
- *OP\_CMPSD* Compare String DoubleWord
- OP\_CMPSW Compare String Word
- OP\_CMPSB Compare String Byte
- *OP\_CMPXCHG* Compare and Exchange
- $OP\_CMPXCHG8B$  Compare and Exchange Bytes
- OP\_CPUID CPU Identification
- OP\_DAA Decimal Adjust AL after Addition
- $OP\_DAS$  Decimal Adjust AL after Subtraction
- $OP\_DEC$  Decrement by 1
- $OP\_DIV$  Unsigned Divide
- *OP ENTER* Make Stack Frame for Procedure Parameters
- $OP\_FWAIT$  Wait
- $OP\_HLT$  Halt
- $OP\_IDIV$  Signed Divide
- **OP\_IMUL** Signed Multiply
- **OP\_INC** Increment by 1
- **OP\_IN** INput from port
- OP\_INSD INput from port to String Doubleword
- OP\_INSW INput from port to String Word

- *OP\_INSB* INput from port to String Byte
- $OP\_INT$  INTerrupt
- OP\_INT3 INTerrupt 3 (breakpoint)
- **OP\_INTO** INTerrupt 4 if Overflow
- OP\_INVD Invalidate Internal Caches
- OP\_INVLPG Invalidate TLB Entry
- $OP\_IRET$  Interrupt Return
- **OP\_JO** Jump if Overflow
- **OP JNO** Jump if Not Overflow
- **OP\_JC** Jump if Carry
- **OP\_JNC** Jump if Not Carry
- $OP\_JZ$  Jump if Zero
- $OP\_JNZ$  Jump if Not Zero
- $OP\_JBE$  Jump if Below or Equal
- $OP\_JA$  Jump if Above
- $OP\_JS$  Jump if Sign
- $OP\_JNS$  Jump if Not Sign
- **OP\_JP** Jump if Parity
- **OP\_JNP** Jump if Not Parity
- $OP\_JL$  Jump if Less
- **OP\_JGE** Jump if Greater or Equal
- OP\_JLE Jump if Less or Equal
- **OP JG** Jump if Greater
- **OP\_JMP** Jump (unconditional)
- OP\_LAHF Load Status Flags into AH Register
- $OP\_LAR$  load Access Rights Byte
- OP\_LDS Load Far Pointer into DS
- $OP\_LES$  Load Far Pointer into ES
- OP\_LFS Load Far Pointer into FS
- *OP\_LGS* Load Far Pointer into GS
- OP\_LEA Load Effective Address
- **OP\_LEAVE** High Level Procedure Exit
- $OP\_LGDT$  Load Global Descript Table Register
- $OP\_LIDT$  Load Interrupt Descriptor Table Register
- $OP\_LLDT$  Load Local Descriptor Table Register
- OP\_PREFIX\_LOCK Assert LOCK# Signal Prefix
- OP\_LODSD Load String Dword
- $OP\_LODSW$  Load String Word
- $OP\_LODSB$  Load String Byte
- $OP\_LOOP$  Loop According to ECX Counter
- *OP\_LOOPE* Loop According to ECX Counter and ZF=1
- *OP\_LOOPNE* Looop According to ECX Counter and ZF=0
- $OP\_JECXZ$  Jump if ECX is Zero
- *OP\_LSL* Load Segment Limit
- $OP\_LSS$  Load Far Pointer into SS

- $OP\_LTR$  Load Task Register
- **OP MOV** Move
- OP\_MOVSD Move Data from String to String Doubleword
- OP\_MOVSW Move Data from String to String Word
- OP\_MOVSB Move Data from String to String Byte
- *OP\_MOVSX* Move with Sign-Extension
- $OP\_MOVZX$  Move with Zero-Extension
- **OP\_MUL** Unsigned Multiply
- **OP NEG** Two's Complement Negation
- $OP\_NOP$  No Operation
- **OP\_NOT** One's Complement Negation
- $OP\_OR$  Logical Inclusive OR
- OP\_OUT Output to Port
- OP\_OUTSD Output String to Port Doubleword
- OP\_OUTSW Output String to Port Word
- OP\_OUTSB Output String to Port Bytes
- $OP\_PUSH$  Push Onto the Stack
- OP\_PUSHAD Push All Double General Purpose Registers
- $OP\_PUSHFD$  Push EFLAGS Register onto the Stack
- **OP\_POP** Pop a Value from the Stack
- *OP\_POPAD* Pop All Double General Purpose Registers from the Stack
- OP\_POPFD Pop Stack into EFLAGS Register
- OP RCL Rotate Carry Left
- OP\_RCR Rotate Carry Right
- *OP\_RDMSR* Read from Model Specific Register
- $OP\_RDPMC$  Read Performance Monitoring Counters
- $OP\_RDTSC$  Read Time-Stamp Coutner
- OP\_PREFIX\_REPE Repeat String Operation Prefix while Equal
- OP\_PREFIX\_REPNE Repeat String Operation Prefix while Not Equal
- **OP\_RETF** Return from Far Procedure
- OP RETN Return from Near Procedure
- OP\_ROL Rotate Left
- OP\_ROR Rotate Right
- $OP\_RSM$  Resumse from System Management Mode
- OP\_SAHF Store AH into Flags
- OP SAR Shift Arithmetic Right
- OP SBB Subtract with Borrow
- $OP\_SCASD$  Scan String Doubleword
- OP\_SCASW Scan String Word
- $OP\_SCASB$  Scan String Byte
- **OP\_SETO** Set Byte on Overflow
- **OP\_SETNO** Set Byte on Not Overflow
- OP\_SETC Set Byte on Carry
- $OP\_SETNC$  Set Byte on Not Carry
- $OP\_SETZ$  Set Byte on Zero

- $OP\_SETNZ$  Set Byte on Not Zero
- **OP\_SETBE** Set Byte on Below or Equal
- **OP\_SETA** Set Byte on Above
- **OP\_SETS** Set Byte on Sign
- $OP\_SETNS$  Set Byte on Not Sign
- **OP\_SETP** Set Byte on Parity
- OP\_SETNP Set Byte on Not Parity
- $OP\_SETL$  Set Byte on Less
- OP SETGE Set Byte on Greater or Equal
- **OP\_SETLE** Set Byte on Less or Equal
- **OP\_SETG** Set Byte on Greater
- $OP\_SGDT$  Store Global Descriptor Table Register
- $OP\_SIDT$  Store Interrupt Descriptor Table Register
- OP\_SHL Shift Left
- OP SHLD Double Precision Shift Left
- OP SHR Shift Right
- $OP\_SHRD$  Double Precision Shift Right
- $OP\_SLDT$  Store Local Descriptor Table Register
- OP\_STOSD Store String Doubleword
- $OP\_STOSW$  Store String Word
- OP\_STOSB Store String Byte
- $OP\_STR$  Store Task Register
- OP STC Set Carry Flag
- OP\_STD Set Direction Flag
- *OP\_STI* Set Interrupt Flag
- OP\_SUB Subtract
- OP\_SYSCALL Fast System Call
- OP\_SYSENTER Fast System Call
- OP\_SYSEXIT Fast Return from Fast System Call
- OP\_SYSRET Return from Fast System Call
- $OP\_TEST$  Logical Compare
- OP\_UD2 Undefined Instruction
- *OP\_VERR* Verify a Segment for Reading
- $OP\_VERRW$  Verify a Segment for Writing
- OP\_WRMSR Write to Model Specific Register
- **OP\_XADD** Exchange and Add
- *OP\_XCHG* Exchange Register/Memory with Register
- $OP\_XLAT$  Table Look-up Translation
- OP\_XOR Logical Exclusive OR
- $OP\_FPU$  FPU operation
- $OP\_F2XM1$  Compute 2x-1
- $OP\_FABS$  Absolute Value
- $OP\_FADD$  Floating Point Add
- OP\_FADDP Floating Point Add, Pop

- OP\_FBLD Load Binary Coded Decimal
- *OP\_FBSTP* Store BCD Integer and Pop
- **OP\_FCHS** Change Sign
- OP\_FCLEX Clear Exceptions
- *OP\_FCMOVB* Floating Point Move on Below
- OP\_FCMOVBE Floating Point Move on Below or Equal
- OP\_FCMOVE Floating Point Move on Equal
- OP\_FCMOVNB Floating Point Move on Not Below
- OP\_FCMOVNBE Floating Point Move on Not Below or Equal
- OP\_FCMOVNE Floating Point Move on Not Equal
- $OP\_FCMOVNU$  Floating Point Move on Not Unordered
- $OP\_FCMOVU$  Floating Point Move on Unordered
- **OP\_FCOM** Compare Floating Pointer Values and Set FPU Flags
- *OP\_FCOMI* Compare Floating Pointer Values and Set EFLAGS
- OP\_FCOMIP Compare Floating Pointer Values and Set EFLAGS, Pop
- OP FCOMP Compare Floating Pointer Values and Set FPU Flags, Pop
- OP\_FCOMPP Compare Floating Pointer Values and Set FPU Flags, Pop Twice
- OP\_FCOS Cosine
- OP\_FDECSTP Decrement Stack Top Pointer
- **OP\_FDIV** Floating Point Divide
- $OP\_FDIVP$  Floating Point Divide, Pop
- OP\_FDIVR Floating Point Reverse Divide
- *OP\_FDIVRP* Floating Point Reverse Divide, Pop
- OP\_FFREE Free Floating Point Register
- **OP\_FIADD** Floating Point Add
- OP\_FICOM Compare Integer
- *OP\_FICOMP* Compare Integer, Pop
- OP\_FIDIV Floating Point Divide by Integer
- OP\_FIDIVR Floating Point Reverse Divide by Integer
- *OP\_FILD* Load Integer
- OP\_FIMUL Floating Point Multiply with Integer
- OP\_FINCSTP Increment Stack-Top Pointer
- **OP\_FINIT** Initialize Floating-Point Unit
- $OP\_FIST$  Store Integer
- $OP\_FISTP$  Store Integer, Pop
- OP\_FISTTP Store Integer with Truncation
- *OP\_FISUB* Floating Point Integer Subtract
- OP\_FISUBR Floating Point Reverse Integer Subtract
- $OP\_FLD$  Load Floating Point Value
- OP\_FLD1 Load Constant 1
- OP\_FLDCW Load x87 FPU Control Word
- OP\_FLDENV Load x87 FPU Environment
- OP\_FLDL2E Load Constant log\_2(e)
- OP\_FLDL2T Load Constant log\_2(10)
- OP\_FLDLG2 Load Constant log 10(2)

```
OP_FLDLN2 Load Constant log_e(2)OP_FLDPI Load Constant PI
```

OP\_FLDZ Load Constant Zero

OI\_IBBZ Load Constant Zero

OP\_FMUL Floating Point MultiplyOP FMULP Floating Point Multiply, Pop

OP\_FNOP No Operation

OP\_FPATAN Partial Arctangent

 $OP\_FPREM$  Partial Remainder

 $OP\_FPREM1$  Partial Remainder

 $OP\_FPTAN$  Partial Tangent

**OP\_FRNDINT** Round to Integer

OP\_FRSTOR Restore x86 FPU State

OP\_FSCALE Scale

 $OP\_FSINCOS$  Sine and Cosine

 $OP\_FSQRT$  Square Root

 $OP\_FSAVE$  Store x87 FPU State

 $OP\_FST$  Store Floating Point Value

OP\_FSTCW Store x87 FPU Control Word

OP FSTENV Store x87 FPU Environment

**OP\_FSTP** Store Floating Point Value, Pop

 $OP\_FSTSW$  Store x87 FPU Status Word

OP\_FSUB Floating Point Subtract

 $OP\_FSUBP$  Floating Point Subtract, Pop

OP\_FSUBR Floating Point Reverse Subtract

OP\_FSUBRP Floating Point Reverse Subtract, Pop

 $OP\_FTST$  Floating Point Test

OP\_FUCOM Floating Point Unordered Compare

 $OP\_FUCOMI$  Floating Point Unordered Compare with Integer

 $OP\_FUCOMIP$  Floating Point Unorder Compare with Integer, Pop

 $OP\_FUCOMP$  Floating Point Unorder Compare, Pop

OP\_FUCOMPP Floating Point Unorder Compare, Pop Twice

 $OP\_FXAM$  Examine ModR/M

OP\_FXCH Exchange Register Contents

OP\_FXTRACT Extract Exponent and Significand

 $OP\_FYL2X$  Compute y\*log2x

 $OP\_FYL2XP1$  Compute y\*log2(x+1)

enum X86REGS X86 registers

#### C.0.18. bytecode execs.h File Reference

#### **Data Structures**

- struct cli\_exe\_section
- struct cli\_exe\_info

#### C.0.19. bytecode\_local.h File Reference

#### **Data Structures**

```
• struct DIS mem arg
```

- struct DIS arg
- struct DIS fixed

#### Macros

```
• #define VIRUSNAME_PREFIX(name) const char ___clambc_virusname_prefix[] = name;
```

- #define VIRUSNAMES(...) const char \*const \_\_\_clambc\_virusnames[] = {\_\_\_VA\_ARGS\_\_\_};
- #define PE\_UNPACKER\_DECLARE const uint16\_t \_\_\_clambc\_kind = BC\_PE\_UNPACKER;
- #define PDF\_HOOK\_DECLARE const uint16\_t \_\_\_clambc\_kind = BC\_PDF;
- #define BYTECODE ABORT HOOK 0xcea5e
- #define PE HOOK DECLARE const uint16 t clambc kind = BC PE ALL;
- #define SIGNATURES\_DECL\_BEGIN struct \_\_\_Signatures {
- #define DECLARE\_SIGNATURE(name)
- #define SIGNATURES\_DECL\_END };
- #define TARGET(tgt) const unsigned short \_\_\_Target = (tgt);
- #define COPYRIGHT(c) const char \*const Copyright = (c);
- #define ICONGROUP1(group) const char \*const \_\_\_IconGroup1 = (group);
- #define ICONGROUP2(group) const char \*const \_\_\_IconGroup2 = (group);
- #define FUNCTIONALITY\_LEVEL\_MIN(m) const unsigned short \_\_\_FuncMin = (m);
- #define FUNCTIONALITY\_LEVEL\_MAX(m) const unsigned short \_\_\_FuncMax = (m);
- #define SIGNATURES\_DEF\_BEGIN
- #define SIGNATURES END };
- #define SIGNATURES\_DEF\_END };

#### **Functions**

- static force\_inline void overloadable func debug (const char \*str)
- static force\_inline void
  - overloadable\_func debug (const uint8\_t \*str)
- static force\_inline void overloadable\_func debug (uint32\_t a)
- void debug (...) attribute ((overloadable
- static force\_inline uint32\_t count\_match (\_\_\_Signature sig)
- static force inline uint32 t matches ( Signature sig)
- static force\_inline uint32\_t match\_location (\_\_\_Signature sig, uint32\_t goback)
- static\_force\_inline int32\_t match\_location\_check (\_\_Signature sig, uint32\_t goback, const char \*static\_start, uint32\_t static\_len)
- static force inline
  - overloadable\_func void foundVirus (const char \*virusname)
- static force\_inline void
- overloadable func foundVirus (void)
- static force\_inline uint32\_t getFilesize (void)
- bool <u>is bigendian (void)</u> <u>attribute</u> ((const )) <u>attribute</u> ((nothrow))
- static uint32\_t force\_inline le32\_to\_host (uint32\_t v)
- static uint32\_t force\_inline be32\_to\_host (uint32\_t v)
- static uint64\_t force\_inline le64\_to\_host (uint64\_t v)
- static uint64\_t force\_inline be64\_to\_host (uint64\_t v)
- static uint16\_t force\_inline le16\_to\_host (uint16\_t v)
  static uint16\_t force\_inline be16\_to\_host (uint16\_t v)
- static uint32 t force inline cli readint32 (const void \*buff)
- static uint16 t force inline cli readint16 (const void \*buff)

```
• static void force inline cli writeint32 (void *offset, uint32 t v)
 static force inline bool has ExeInfo (void)
  static force inline bool hasPEInfo (void)
  static force_inline bool isPE64 (void)
  static force inline uint8 t getPEMajorLinkerVersion (void)
 static force inline uint8 t getPEMinorLinkerVersion (void)
  static force_inline uint32_t getPESizeOfCode (void)
  static force_inline uint32_t getPESizeOfInitializedData (void)
  static force inline uint32 t getPESizeOfUninitializedData (void)
 static force inline uint32 t getPEBaseOfCode (void)
  static force_inline uint32_t getPEBaseOfData (void)
  static force_inline uint64_t getPEImageBase (void)
• static force_inline uint32_t getPESectionAlignment (void)
  static force_inline uint32_t getPEFileAlignment (void)
  static force inline uint16 t getPEMajorOperatingSystemVersion (void)
  static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
  static force inline uint16 t getPEMajorImageVersion (void)
  static force_inline uint16_t getPEMinorImageVersion (void)
  static force inline uint16 t getPEMajorSubsystemVersion (void)
  static force inline uint16 t getPEMinorSubsystemVersion (void)
 static force inline uint32 t getPEWin32VersionValue (void)
  static force inline uint32 t getPESizeOfImage (void)
  static force_inline uint32_t getPESizeOfHeaders (void)
• static force inline uint32 t getPECheckSum (void)
  static force inline uint16 t getPESubsystem (void)
  static force_inline uint16_t getPEDllCharacteristics (void)
  static force_inline uint32_t getPESizeOfStackReserve (void)
  static force inline uint32 t getPESizeOfStackCommit (void)
  static force inline uint32 t getPESizeOfHeapReserve (void)
  static force_inline uint32_t getPESizeOfHeapCommit (void)
  static force inline uint32 t getPELoaderFlags (void)
  static force_inline uint16_t getPEMachine ()
  static force inline uint32 t getPETimeDateStamp ()
  static force inline uint32 t getPEPointerToSymbolTable ()
• static force inline uint32 t getPENumberOfSymbols ()
  static force_inline uint16_t getPESizeOfOptionalHeader ()
  static force_inline uint16_t getPECharacteristics ()
 static force inline bool getPEisDLL ()
  static force inline uint32 t getPEDataDirRVA (unsigned n)
  static force inline uint32 t getPEDataDirSize (unsigned n)
  static force_inline uint16_t getNumberOfSections (void)
  static uint32 t getPELFANew (void)
  static force inline int readPESectionName (unsigned char name[8], unsigned n)
  static force inline uint32 t getEntryPoint (void)
 static force_inline uint32_t getExeOffset (void)
• static force inline uint32 t getImageBase (void)
  static uint32_t getVirtualEntryPoint (void)
  static uint32_t getSectionRVA (unsigned i)
• static uint32 t getSectionVirtualSize (unsigned i)
  static force inline bool readRVA (uint32 t rva, void *buf, size t bufsize)
  static force_inline void * memchr (const void *s, int c, size_t n)
```

 $\operatorname{nonnull}_{--}((1)))$ 

void \* memset (void \*src, int c, uintptr\_t n) \_\_attribute\_\_((nothrow)) \_\_attribute\_\_((\_\_-

- void \* memmove (void \*dst, const void \*src, uintptr\_t n) \_\_attribute\_\_((\_\_nothrow\_\_)) \_\_attribute\_\_((\_\_nonnull\_\_(1
- void void int memcmp (const void \*s1, const void \*s2, uint32\_t n) \_\_attribute\_\_((\_\_nothrow\_\_)) \_\_attribute\_\_((\_\_nonnull\_\_(1
- static force\_inline uint32\_t DisassembleAt (struct DIS\_fixed \*result, uint32\_t offset, uint32\_t len)
- static int32 t ilog2 compat (uint32 t a, uint32 t b)

#### Macro Definition Documentation

#define BYTECODE\_ABORT\_HOOK 0xcea5e entrypoint() return code that tells hook invoker that it should skip executing, probably because it'd trigger a bug in it

#define SIGNATURES\_END }; Old macro used to mark the end of the subsignature pattern definitions.

#### **Function Documentation**

 $\begin{tabular}{ll} static force\_inline\ void\ overloadable\_func\ foundVirus\ (\ void\ )\ [static] \ Like\ foundVirus\ ()\ but\ just\ use\ the\ prefix\ as\ virusname \end{tabular}$ 

static int32\_t ilog2\_compat ( uint32\_t a, uint32\_t b ) [inline], [static] ilog2\_compat for 0.96 compatibility, you should use ilog2() 0.96.1 API instead of this one!

Parameters

a	input
b	input

#### Returns

 $2^{2}$   $4 \cdot \log 2(a/b)$ 

#### C.0.20. bytecode\_pe.h File Reference

#### **Data Structures**

- struct pe\_image\_file\_hdr
- struct pe\_image\_data\_dir
- struct pe\_image\_optional\_hdr32
- $struct pe_image_optional_hdr64$
- struct pe\_image\_section\_hdr
- struct cli\_pe\_hook\_data

# APPENDIX D

# Predefined API Macros

```
### DECAL DE
```