

Clam
AV Bytecode Compiler $User\ Manual$

Contents

1	Inst	stallation					
	1.1	Requirements	1				
	1.2	Obtaining the ClamAV Bytecode Compiler	2				
	1.3	Building	2				
		1.3.1 Disk space	2				
		1.3.2 Create build directory	2				
	1.4	Testing	3				
	1.5	Installing	3				
		1.5.1 Structure of installed files	3				
2	Tut	orial	5				
	2.1	Short introduction to the bytecode language	5				
			5				
			5				
		2.1.3 Arithmetics	5				
		2.1.4 Functions	5				
		2.1.5 Control flow	5				
		2.1.6 Common functions	5				
	2.2	Writing logical signatures	5				
			6				
		2.2.2 Virusnames	6				
		2.2.3 Patterns	7				
			8				
			0				
		1 0	0				
			0				
	2.3		0				
			2				
		v 1 c 1	4				
	2.4		4				
		9 1	4				
		v 1 0 \					

ii				Conte	ente
"				Conte	21103
		2.4.2 2.4.3 2.4.4 2.4.5 2.4.6	Detecting clam.exe via bytecode		14 15 15 15 15
3	Usa	ന്മ			17
J	3.1	_	ng the compiler		17
	0.1	3.1.1	Compiling C++ files		18
	3.2		ng compiled bytecode		18
	5.2	3.2.1	ClamBC		18
		3.2.1 $3.2.2$	clamscan, clamd		18
	3.3		ging bytecode		19
	5.5	3.3.1	"printf" style debugging		19
		3.3.1	Single-stepping		19
		ე.ე.∠	Single-stepping		19
4	Clai	mAV b	oytecode language		21
	4.1		ences from C99 and GNU C		21
	4.2	Limita	tions		23
	4.3		l signatures		24
	4.4	_	rs and runtime environment		26
5	\mathbf{Byt}	ecode :	security & portability		27
6	Rep	orting	bugs		29
7	Byt	ecode .	Л DI		31
•	7.1	. API gr			31
	1.1	7.1.1	Bytecode configuration		31
		7.1.1 $7.1.2$	Data structure handling functions		32
		7.1.2	Disassemble APIs		$\frac{32}{34}$
		7.1.3	Engine queries		35
		7.1.4	Environment detection functions		35
		7.1.6	File operations		36
		7.1.0	Global variables		
					36
		7.1.8	Icon matcher APIs		37
		7.1.9	JS normalize API		37
		7.1.10	Math functions		37
		7.1.11	PDF handling functions		37
			PE functions		38 41
		7 1 13	Scan control linctions		4.1

Contents	;		iii	
7.1.14 Ct.:				
7.0		String operations	42	
7.2		ure types	43	
	7.2.1	cli_exe_info Struct Reference	43	
		7.2.1.1 Detailed Description	43	
	700	7.2.1.2 Field Documentation	43	
	7.2.2	cli_exe_section Struct Reference	44	
		7.2.2.1 Detailed Description	44	
	7 0 0	7.2.2.2 Field Documentation	44	
	7.2.3	cli_pe_hook_data Struct Reference	45	
		7.2.3.1 Detailed Description	45	
		7.2.3.2 Field Documentation	45	
	7.2.4	DIS_arg Struct Reference	46	
		7.2.4.1 Detailed Description	46	
		7.2.4.2 Field Documentation	47	
	7.2.5	DIS_fixed Struct Reference	47	
		7.2.5.1 Detailed Description	47	
		7.2.5.2 Field Documentation	47	
	7.2.6	DIS_mem_arg Struct Reference	48	
		7.2.6.1 Detailed Description	48	
		7.2.6.2 Field Documentation	48	
	7.2.7	DISASM_RESULT Struct Reference	48	
		7.2.7.1 Detailed Description	48	
	7.2.8	pe_image_data_dir Struct Reference	49	
		7.2.8.1 Detailed Description	49	
	7.2.9	pe_image_file_hdr Struct Reference	49	
		7.2.9.1 Detailed Description	49	
		7.2.9.2 Field Documentation	49	
	7.2.10	pe_image_optional_hdr32 Struct Reference	50	
		7.2.10.1 Detailed Description	50	
		7.2.10.2 Field Documentation	51	
	7.2.11	pe_image_optional_hdr64 Struct Reference	51	
		7.2.11.1 Detailed Description	52	
		7.2.11.2 Field Documentation	52	
	7.2.12	pe_image_section_hdr Struct Reference	53	
		7.2.12.1 Detailed Description	53	
		7.2.12.2 Field Documentation	53	
7.3	Low le	vel API	54	
	7.3.1	bytecode_api.h File Reference	54	
		7.3.1.1 Detailed Description	57	
		7.3.1.2 Enumeration Type Documentation	57	
		7.3.1.3 Function Documentation		

			7.3.1.4	Variable Documentation		
		7.3.2	bytecode	e_disasm.h File Reference		
			7.3.2.1	Detailed Description		
			7.3.2.2	Enumeration Type Documentation 88		
		7.3.3		e_execs.h File Reference		
			7.3.3.1	Detailed Description		
		7.3.4	bytecode	e_pe.h File Reference		
			7.3.4.1	Detailed Description		
	7.4	High l	evel API			
		7.4.1	bytecode	e_local.h File Reference 99		
			7.4.1.1	Detailed Description		
			7.4.1.2	Define Documentation		
			7.4.1.3	Function Documentation		
			7.4.1.4	Variable Documentation		
8	Cop	yright	and Lic	eense 125		
	8.1 The ClamAV Bytecode Compiler					
	8.2					
Δ	Pre	define	d macros	129		

Contents

ClamAV Bytecode Compiler - Internals Manual,

© 2009 Sourcefire, Inc.

iv

Authors: Török Edvin

This document is distributed under the terms of the GNU General Public License v2.

Clam AntiVirus is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation; version 2 of the License.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

Contents

ClamAV and Clam AntiVirus are trademarks of Sourcefire, Inc.

vi

CHAPTER 1 Installation

1.1. Requirements

The ClamAV Bytecode Compiler uses the LLVM compiler framework, thus requires an Operating System where building LLVM is supported:

- FreeBSD/x86
- $Linux/\{x86,x86_64,ppc\}$
- Mac OS $X/\{x86,ppc\}$
- Solaris/sparcv9
- Windows/x86 using mingw32 or Visual Studio

The following packages are required to compile the ClamAV Bytecode Compiler:

- GCC C and C++ compilers (minimum 4.1.3, recommended: 4.3.4 or newer) ¹.
- Perl (version 5.6.0+)
- GNU make (version 3.79+, recommended 3.81)

The following packages are optional, but highly recommended:

• Python (version 2.5.4+?) - for running the tests

¹Note that several versions of GCC have bugs when compiling LLVM, see http://llvm.org/docs/GettingStarted.html#brokengcc for a full list. Also LLVM requires support for atomic builtins for multithreaded mode, which gcc 3.4.x doesn't have

1.2. Obtaining the ClamAV Bytecode Compiler

You can obtain the source code in one of the following ways ¹

- Check out the source code using git native protocol:
 git clone git://git.clamav.net/git/clamav-bytecode-compiler
- Check out the source code using HTTP:
 git clone http://git.clamav.net/git/clamav-bytecode-compiler.git
 You can keep the source code updated using:
 git pull

1.3. Building

1.3.1. Disk space

A minimalistic release build requires 100M of disk space.

Testing the compiler requires a full build, 320M of disk space. A debug build requires significantly more disk space (1.4G for a minimalistic debug build).

Note that this only needed during the build process, once installed only 12M is needed.

1.3.2. Create build directory

Building requires a separate object directory, building in the source directory is not supported. Create a build directory:

```
$ cd clamav-bytecode-compiler && mkdir obj
```

Run configure (you can use any prefix you want, this example uses /usr/local/clamav):

```
$ cd obj && ../llvm/configure --enable-optimized \
   --enable-targets=host-only --disable-bindings \
   --prefix=/usr/local/clamav
```

Run the build under ulimit ²:

\$ (ulimit -t 3600 -v 512000 && make clambc-only -j4)

¹For now the use the internal clamtools repository:

git clone username@git.clam.sourcefire.com:/var/lib/git/clamtools.git

²compiling some files can be very memory intensive, especially with older compilers

1.4. Testing

```
$ (ulimit -t 3600 v 512000 && make -j4)
$ make check-all
```

If make check reports errors, check that your compiler is NOT on this list: http://llvm.org/docs/GettingStarted.html#brokengcc.

If it is, then your compiler is buggy, and you need to do one of the following: upgrade your compiler to a non-buggy version, upgrade the OS to one that has a non-buggy compiler, compile with export OPTMIZE_OPTION=-02, or export OPTIMIZE OPTION=-01, or export OPTIMIZE OPTION=\-01.

If not you probably found a bug, report it at http://bugs.clamav.net

1.5. Installing

Install it:

\$ make install-clambc -j8

1.5.1. Structure of installed files

- 1. The ClamAV Bytecode compiler driver: \$PREFIX/bin/clambc-compiler
- 2. ClamAV bytecode header files:

```
$PREFIX/lib/clang/1.1/include:
bcfeatures.h
bytecode_{api_decl.c,api,disasm,execs,features}.h
bytecode.h
bytecode_{local,pe,types}.h
```

3. clang compiler (with ClamAV bytecode backend) compiler include files:

```
$PREFIX/lib/clang/1.1/include:
emmintrin.h
float.h
iso646.h
limits.h
{,p,t,x}mmintrin.h
mm_malloc.h
std{arg,bool,def,int}.h
```

tgmath.h

4 1.5. Installing

4. User manual

\$PREFIX/docs/clamav/clambc-user.pdf

CHAPTER 2 Tutorial

2.1. Short introduction to the bytecode language

2.	.1.	1.	Types.	variables	and	constants
			- ,, P = >,	TOTAL TOTAL		COLLOCALIO

- 2.1.2. Arrays and pointers
- 2.1.3. Arithmetics
- 2.1.4. Functions
- 2.1.5. Control flow
- **2.1.6.** Common functions

2.2. Writing logical signature bytecodes

A bytecode triggered by a logical signature is much more powerful than a logical signature itself: you can write complex algorithmic detections, and use the logical signature as a *filter* (to speed up matching). Thus another name for "logical signature bytecodes" is "algorithmic detection bytecodes". The detection you write in bytecode has read-only access to the file being scanned and its metadata (PE sections, EP, etc.).

¹ Logical signatures can be used as triggers for executing bytecode. However, instead of describing a logical signature as a .ldb pattern, you use (simple) C code which is later translated to a .ldb-style logical signature by the ClamAV Bytecode Compiler.

¹See Section 4.3 for more details about logical signatures in bytecode.

2.2.1. Structure of a bytecode for algorithmic detection

Algorithmic detection bytecodes are triggered when a logical signature matches. They can execute an algorithm that determines whether the file is infected and with which virus.

A bytecode can be either algorithmic or an unpacker (or other hook), but not both.

It consists of:

- Definition of virusnames used in the bytecode
- Pattern definitions (for logical subexpressions)
- The logical signature as C function: bool logical_trigger(void)
- The int entrypoint(void) function which gets executed when the logical signature matches
- (Optional) Other functions and global constants used in entrypoint

The syntax for defining logical signatures, and an example is described in Section 2.2.4.

The function entrypoint must report the detected virus by calling foundVirus and returning 0. It is recommended that you always return 0, otherwise a warning is shown and the file is considered clean. If foundVirus is not called, then ClamAV also assumes the file is clean.

2.2.2. Virusnames

Each logical signature bytecode must have a virusname prefix, and one or more virusnames. The virusname prefix is used by the SI to ensure unique virusnames (a unique number is appended for duplicate prefixes).

Program 1 Declaring virusnames

```
1 /* Prefix, used for duplicate detection and fixing */
VIRUSNAME_PREFIX("Trojan.Foo")
3 /* You are only allowed to set these virusnames as found */
VIRUSNAMES("A", "B")
5 /* File type */
TARGET(2)
```

In Program 1 3 predefied macros are used:

• VIRUSNAME PREFIX which must have exactly one string argument

- VIRUSNAMES which must have one or more string arguments
- TARGET which must have exactly one integer argument

In this example, the bytecode could generate one of these virus-names: Trojan.Foo.A, or Trojan.Foo.B, by calling foundVirus("A") or foundVirus("B") respectively (notice that the prefix is not part of these calls).

2.2.3. Patterns

Logical signatures use .ndb style patterns, an example on how to define these is shown in Program 2.

Program 2 Declaring patterns

```
SIGNATURES_DECL_BEGIN

DECLARE_SIGNATURE(magic)
DECLARE_SIGNATURE(check)

DECLARE_SIGNATURE(zero)
SIGNATURES_DECL_END

SIGNATURES_DEF_BEGIN
DEFINE_SIGNATURE(magic, "EP+0:aabb")
DEFINE_SIGNATURE(check, "f00d")
DEFINE_SIGNATURE(zero, "fffff")
SIGNATURES_END
```

Each pattern has a name (like a variable), and a string that is the hex pattern itself. The declarations are delimited by the macros SIGNATURES_DECL_BEGIN, and SIGNATURES_DECL_END. The definitions are delimited by the macros SIGNATURES_DEF_BEGIN, and SIGNATURES_END. Declarations must always come before definitions, and you can have only one declaration and declaration section! (think of declaration like variable declarations, and definitions as variable assignments, since that what they are under the hood). The order in which you declare the signatures is the order in which they appear in the generated logical signature.

You can use any name for the patterns that is a valid record field name in C, and doesn't conflict with anything else declared.

After using the above macros, the global variable Signatures will have two new fields: magic, and zero. These can be used as arguments to the functions count_match(), and matches() anywhere in the program as shown in Program 3:

- matches(Signatures.match) will return true when the match signature matches (at least once)
- count_match(Signatures.zero) will return the number of times the zero signature matched
- count_match(Signatures.check) will return the number of times the check signature matched

The condition in the if can be interpreted as: if the match signature has matched at least once, and the number of times the zero signature matched is higher than the number of times the check signature matched, then we have found a virus A, otherwise the file is clean.

Program 3 Using patterns

```
int entrypoint(void)
{
   if (matches(Signatures.match) &&
       count_match(Signatures.zero) >
       count_match(Signatures.check))
      foundVirus("A");
   return 0;
}
```

2.2.4. Single subsignature

The simplest logical signature is like a .ndb signature: a virus name, signature target, 0 as logical expression ¹, and a ndb-style pattern.

The code for this is shown in Program 4

The logical signature (created by the compiler) looks like this: Trojan.Foo.{A}; Target:2;0; aabb

Of course you should use a .1db signature in this case when all the processing in entrypoint is only setting a virusname and returning. However, you can do more complex checks in entrypoint, once the bytecode was triggered by the logical_trigger

In the example in Program 4 the pattern was used without an anchor; such a pattern matches at any offset. You can use offsets though, the same way as in .ndb signatures, see Program 5 for an example.

¹meaning that subexpression 0 must match

Program 4 Single subsignature example

```
/* Declare the prefix of the virusname */
2 VIRUSNAME_PREFIX("Trojan.Foo")
  /* Declare the suffix of the virusname */
4 VIRUSNAMES ("A")
  /* Declare the signature target type (1 = PE) */
6 TARGET (1)
8 /* Declare the name of all subsignatures used */
  SIGNATURES_DECL_BEGIN
10 DECLARE_SIGNATURE(magic)
  SIGNATURES_DECL_END
  /* Define the pattern for each subsignature */
14 SIGNATURES_DEF_BEGIN
  DEFINE_SIGNATURE(magic, "aabb")
16 SIGNATURES_END
18 /* All bytecode triggered by logical signatures must have
     this
     function */
20 bool logical_trigger(void)
    /* return true if the magic subsignature matched,
    * its pattern is defined above to "aabb" */
   return count_match(Signatures.magic) != 2;
  }
26
  /* This is the bytecode function that is actually executed
     when the logical
  * signature matched */
  int entrypoint(void)
30 {
    /* call this function to set the suffix of the virus found
       */
    foundVirus("A");
    /* success, return 0 */
    return 0;
  }
```

2.2.5. Multiple subsignatures

An example for this is shown in Program 5. Here you see the following new features used: ¹

- Multiple virusnames returned from a single bytecode (with common prefix)
- Multiple subsignatures, each with a name of your choice
- A pattern with an anchor (EP+0:aabb)
- More subsignatures defined than used in the logical expression

The logical signature looks like this:

Trojan.Foo. $\{A,B\}$; Target:2; (((0|1|2)=42,2)|(3=10)); EP+0:aabb; fffff; aaccee; f00d; dead

Notice how the subsignature that is not used in the logical expression (number 4, dead) is used in entrypoint to decide the virus name. This works because ClamAV does collect the match counts for all subsignatures (regardless if they are used or not in a signature). The count_match(Signatures.check2) call is thus a simple memory read of the count already determined by ClamAV.

Also notice that comments can be used freely: they are ignored by the compiler. You can use either C-style multiline comments (start comment with /*, end with */), or C++-style single-line comments (start comment with //, automatically ended by newline).

2.2.6. W32.Polipos.A detector rewritten as bytecode

2.2.7. Virut detector in bytecode

2.3. Writing regular expressions in bytecode

ClamAV only supports a limited set of regular expressions in .ndb format: wildcards. The bytecode compiler allows you to compile fully generic regular expressions to bytecode directly. When libclamav loads the bytecode, it will compile to native code (if using the JIT), so it should offer quite good performance.

The compiler currently uses re2c to compile regular expressions to C code, and then compile that to bytecode. The internal workings are all transparent

¹In case of a duplicate virusname the prefix is appended a unique number by the SI

11

Program 5 Multiple subsignatures

```
1 /* You are only allowed to set these virusnames as found */
  VIRUSNAME_PREFIX("Test")
3 VIRUSNAMES ("A", "B")
  TARGET (1)
  SIGNATURES_DECL_BEGIN
7 DECLARE_SIGNATURE(magic)
  DECLARE_SIGNATURE(zero)
9 DECLARE_SIGNATURE (check)
  DECLARE_SIGNATURE(fivetoten)
11 DECLARE_SIGNATURE(check2)
  SIGNATURES_DECL_END
  SIGNATURES_DEF_BEGIN
15 DEFINE_SIGNATURE(magic, "EP+0:aabb")
  DEFINE_SIGNATURE(zero, "ffff")
17 DEFINE_SIGNATURE(fivetoten, "aaccee")
  DEFINE_SIGNATURE(check, "f00d")
19 DEFINE_SIGNATURE(check2, "dead")
  SIGNATURES_END
  bool logical_trigger(void)
23 {
      unsigned sum_matches = count_match(Signatures.magic)+
          count_match(Signatures.zero) +
25
              count_match(Signatures.fivetoten);
      unsigned unique_matches = matches(Signatures.magic)+
              matches(Signatures.zero)+
27
                  matches(Signatures.fivetoten);
      if (sum_matches == 42 && unique_matches == 2) {
          // The above 3 signatures have matched a total of 42
              times, and at least
          // 2 of them have matched
31
          return true;
      // If the check signature matches 10 times we still have
33
         a match
      if (count_match(Signatures.check) == 10)
          return true;
35
      // No match
      return false;
37
  }
  int entrypoint(void)
41 {
      unsigned count = count_match(Signatures.check2);
      if (count >= 2)
          foundVirus(count == 2 ? "A" : "B");
        if (count == 2)
45
          foundVirus("A");
                                 11
47
          foundVirus("B");
      return 0;
49
  }
```

to the user: the compiler automatically uses re2c when needed, and re2c is embedded in the compiler, so you don't need to install it.

The syntax of regular expressions are similar to the one used by POSIX regular expressions, except you have to quote literals, since unquoted they are interpreted as regular expression names.

2.3.1. A very simple regular expression

Lets start with a simple example, to match this POSIX regular expression: eval([a-zA-Z_] [a-zA-Z0-9_]*\.unescape.

See Program 6¹.

Program 6 Simple regular expression example

```
int entrypoint(void)
2 {
    REGEX_SCANNER;
    seek(0, SEEK_SET);
    for (;;) {
      REGEX_LOOP_BEGIN
      /*!re2c
8
        ANY = [^];
         "eval ("[a-zA-Z_][a-zA-Z_0-9]*".unescape" {
                          long pos = REGEX_POS;
12
                          if (pos < 0)
                                  continue;
14
                          debug("unescape found at");
                          debug (pos);
16
        ANY { continue; }
18
20
    return 0;
22 }
```

There are several new features introduced here, here is a step by step breakdown:

REGEX_SCANNER this declares the data structures needed by the regular expression matcher

¹This omits the virusname, and logical signature declarations

seek(0, SEEK_SET) this sets the current file offset to position 0, matching will start at this position. For offset 0 it is not strictly necessary to do this, but it serves as a reminder that you might want to start matching somewhere, that is not necessarily 0.

- for(;;) { REGEX_LOOP_BEGIN this creates the regular expression matcher main loop. It takes the current file byte-by-byte ¹ and tries to match one of the regular expressions.
- /*!re2c This mark the beginning of the regular expression description. The entire regular expression block is a C comment, starting with !re2c
- ANY = [^]; This declares a regular expression named ANY that matches any byte.
- "eval("[a-zA-Z_][a-zA-Z_0-9]*".unescape" { This is the actual regular expression.
 - "eval(" This matches the literal string eval(. Literals have to be placed in double quotes " here, unlike in POSIX regular expressions or PCRE. If you want case-insensitive matching, you can use '.
 - [a-zA-Z_] This is a character class, it matches any lowercase, uppercase or _ characters.
 - [a-zA-Z_0-9]*" Same as before, but with repetition. * means match zero or more times, + means match one or more times, just like in POSIX regular expressions.
 - ".unescape" A literal string again
 - { start of the *action* block for this regular expression. Whenever the regular expression matches, the attached C code is executed.
- long pos = REGEX_POS; this determines the absolute file offset where the
 regular expression has matched. Note that because the regular expression matcher uses a buffer, using just seek(0, SEEK_CUR) would
 give the current position of the end of that buffer, and not the current position during regular expression matching. You have to use the
 REGEX_POS macro to get the correct position.
- debug(...) Shows a debug message about what was found and where. This is extremely helpful when you start writing regular expressions, and nothing works: you can determine whether your regular expression

¹it is not really reading byte-by-byte, it is using a buffer to speed things up

matched at all, and if it matched where you thought it would. There is also a DEBUG_PRINT_MATCH that prints the entire matched string to the debug output. Of course before publishing the bytecode you might want to turn off these debug messages.

- } closes the action block for this regular expression
- ANY { continue; } If none of the regular expressions matched so far, just keep running the matcher, at the next byte
- */ closes the regular expression description block
- } closes the for() loop

You may have multiple regular expressions, or declare multiple regular expressions with a name, and use those names to build more complex regular expressions.

2.3.2. Named regular expressions

2.4. Writing unpackers

2.4.1. Structure of a bytecode for unpacking (and other hooks)

When writing an unpacker, the bytecode should consist of:

- Define which hook you use (for example PE_UNPACKER_DECLARE for a PE hook)
- An int entrypoint(void) function that reads the current file and unpacks it to a new file
- Return 0 from entrypoint if you want the unpacked file to be scanned
- (Optional) Other functions and global constants used by entrypoint

2.4.2. Detecting clam.exe via bytecode

Example provided by aCaB:

Chapter 2. Tutorial	15
2.4.3. Detecting clam.exe via bytecode (disasm)	
Example provided by aCaB:	
2.4.4. A simple unpacker	
2.4.5. Matching PDF javascript	
2.4.6. YC unpacker rewritten as bytecode	

CHAPTER 3 Usage

3.1. Invoking the compiler

Compiling is similar to gcc^{-1} :

\$ /usr/local/clamav/bin/clambc-compiler foo.c -o foo.cbc -02

This will compile the file foo.c into a file called foo.cbc, that can be loaded by ClamAV, and packed inside a .cvd file.

The compiler by default has all warnings turned on.

Supported optimization levels: -00, -01, -02, -03. ² It is recommended that you always compile with at least -01.

Warning options: -Werror (transforms all warnings into errors).

Preprocessor flags:

- -I <directory> Searches in the given directory when it encounters a #include "headerfile" directive in the source code, in addition to the system defined header search directories.
- -D <MACRONAME>=<VALUE> Predefine given <MACRONAME> to be equal to <VALUE>.
- -U <MACRONAME> Undefine a predefined macro

The compiler also supports some other commandline options (see clambc-compiler --help for a full list), however some of them have no effect when using the ClamAV bytecode backend (such as the X86 backend options). You shouldn't need to use any flags not documented above.

 $^{^1\}mathrm{Note}$ that the ClamAV by tecode compiler will refuse to compile code it considers in secure

²Currently -O0 doesn't work

3.1.1. Compiling C++ files

Filenames with a .cpp extension are compiled as C++ files, however clang++ is not yet ready for production use, so this is EXPERIMENTAL currently. For now write bytecodes in C.

3.2. Running compiled bytecode

After compiling a C source file to bytecode, you can load it in ClamAV:

3.2.1. ClamBC

ClamBC is a tool you can use to test whether the bytecode loads, compiles, and can execute its entrypoint successfully. Usage:

```
clambc <file> [function] [param1 ...]
```

For example loading a simple bytecode with 2 functions is done like this:

```
$ clambc foo.cbc
```

```
LibClamAV debug: searching for unrar, user-searchpath: /usr/local/lib
```

LibClamAV debug: unrar support loaded from libclamunrar_iface.so.6.0.4 libclamatelement libclamatelement loaded from libclamatelement libclamatelement loaded from libclamatelement libclamatelem

LibClamAV debug: bytecode: Parsed O APIcalls, maxapi O

LibClamAV debug: Parsed 1 BBs, 2 instructions LibClamAV debug: Parsed 1 BBs, 2 instructions

LibClamAV debug: Parsed 2 functions

Bytecode loaded

Running bytecode function :0

Bytecode run finished Bytecode returned: 0x8

Exiting

3.2.2. clamscan, clamd

You can tell clamscan to load the bytecode as a database directly:

\$ clamscan -dfoo.cbc

Or you can instruct it to load all databases from a directory, then clamscan will load all supported formats, including files with bytecode, which have the .cbc extension.

\$ clamscan -ddirectory

You can also put the bytecode files into the default database directory of ClamAV (usually /usr/local/share/clamav) to have it loaded automatically from there. Of course, the bytecode can be stored inside CVD files, too.

3.3. Debugging bytecode

3.3.1. "printf" style debugging

You can use debug_print_str and debug_print_int API calls to print debug messages during the execution of the bytecode.

3.3.2. Single-stepping

If you have GDB 7.0 (or newer) you can single-step $^{1\ 2}$ during the execution of the bytecode.

• Run clambe or clamscan under gdb:

```
$ ./libtool --mode=execute gdb clamscan/clamscan
...
(gdb) b cli_vm_execute_jit
Are you sure ....? y
(gdb) run -dfoo.cbc
...
Breakpoint ....
(gdb) step
(gdb) next
```

You can single-step through the execution of the bytecode, however you can't (yet) print values of individual variables, you'll need to add debug statements in the bytecode to print interesting values.

¹not yet implemented in libclamav

²assuming you have JIT support

CHAPTER 4 ClamAV bytecode language

The bytecode that ClamAV loads is a simplified form of the LLVM Intermediate Representation, and as such it is language-independent.

However currently the only supported language from which such by tecode can be generated is a simplified form of C $^{\rm 1}$

The language supported by the ClamAV bytecode compiler is a restricted set of C99 with some GNU extensions.

4.1. Differences from C99 and GNU C

These restrictions are enforced at compile time:

- No standard include files. ²
- The ClamAV API header files are preincluded.
- No external function calls, except to the ClamAV API ³
- No inline assembly ⁴
- Globals can only be readonly constants ⁵
- inline is C99 inline (equivalent to GNU C89 extern inline), thus it cannot be used outside of the definition of the ClamAV API, you should use static inline

 $^{^{1}\}mathrm{In}$ the future more languages could be supported, see the Internals Manual on language frontends

²For portability reasons: preprocessed C code is not portable

³For safety reasons we can't allow the bytecode to call arbitrary system functions

⁴This is both for safety and portability reasons

⁵For thread safety reasons

- sizeof(int) == 4 always
- sizeof(long) == sizeof(long long) == 8 always
- ptr_diff_t = int, intptr_t = int, intmax_t = long, uintmax t = unsigned long 1
- No pointer to integer casts and integer to pointer casts (pointer arithmetic is allowed though)
- No __thread support
- Size of memory region associated with each pointer must be known in each function, thus if you pass a pointer to a function, you must also pass its allocated size as a parameter.
- Endianness must be handled via the __is_bigendian() API function call, or via the cli_{read,write}int{16,32} wrappers, and not by casting pointers
- Predefines __CLAMBC__
- All integer types have fixed width
- main or entrypoint must have the following prototype: int main(void), the prototype int main(int argc, char *argv[]) is not accepted

They are meant to ensure the following:

- Thread safe execution of multiple different bytecodes, and multiple instances of the same bytecode
- Portability to multiple CPU architectures and OSes: the bytecode must execute on both the libclamav/LLVM JIT where that is supported (x86, x86_64, ppc, arm?), and on the libclamav interpreter where that is not supported.
- No external runtime dependency: libclamav should have everything needed to run the bytecode, thus no external calls are allowed, not even to libc!

¹Note that a pointer's size of is runtime-platform dependent, although at compile time size of (void*) == 4, at runtime it can be something else. Thus you should avoid using size of (pointer)

• Same behaviour on all platforms: fixed size integers.

These restrictions are checked at runtime (checks are inserted at compile time):

- Accessing an out-of-bounds pointer will result in a call to abort()
- Calling abort() interrupts the execution of the bytecode in a thread safe manner, and doesn't halt ClamAV ¹.

The ClamAV API header has further restriction, see the Internals manual. Although the bytecode undergoes a series of automated tests (see Publishing chapter in Internals manual), the above restrictions don't guarantee that the resulting bytecode will execute correctly! You must still test the code yourself, these restrictions only avoid the most common errors. Although the compiler and verifier aims to accept only code that won't crash ClamAV, no code is 100% perfect, and a bug in the verifier could allow unsafe code be executed by ClamAV.

4.2. Limitations

The bytecode format has the following limitations:

- At most 64k bytecode kinds (hooks)
- At most 64k types (including pointers, and all nested types)
- At most 16 parameters to functions, no vararg functions
- At most 64-bit integers
- No vector types or vector operations
- No opaque types
- No floating point
- Global variable initializer must be compile-time computable
- At most 32k global variables (and at most 32k API globals)
- Pointer indexing at most 15 levels deep (can be worked around if needed by using temporaries)

¹in fact it calls a ClamAV API function, and not the libc abort function.

- No struct return or byval parameters
- At most 32k instructions in a single function
- No Variable Length Arrays

4.3. Logical signatures

Logical signatures can be used as triggers for executing a bytecode. Instead of describing a logical signatures as a .ldb pattern, you use C code which is then translated to a .ldb-style logical signature.

Logical signatures in ClamAV support the following operations:

- Sum the count of logical subsignatures that matched inside a subexpression
- Sum the number of different subsignatures that matched inside a subexpression
- Compare the above counts using the >, =, < relation operators
- Perform logical &&, || operations on above boolean values
- Nest subexpressions
- Maximum 64 subexpressions

Out of the above operations the ClamAV Bytecode Compiler doesn't support computing sums of nested subexpressions, (it does support nesting though).

The C code that can be converted into a logical signature must obey these restrictions:

- a function named logical_trigger with the following prototype: bool logical_trigger(void)
- no function calls, except for count match and matches
- no global variable access (except as done by the above 2 functions internally)
- return true when signature should trigger, false otherwise

- use only integer compare instructions, branches, integer add, logical and, logical or, logical xor, zero extension, store/load from local variables
- the final boolean expression must be convertible to disjunctive normal form without negation
- the final logical expression must not have more than 64 subexpressions
- it can have early returns (all true returns are unified using ||)
- you can freely use comments, they are ignored
- the final boolean expression cannot be a true or false constant

The compiler does the following transformations (not necessarily in this order):

- convert shortcircuit boolean operations into non-shortcircuit ones (since all operands are boolean expressions or local variables, it is safe to execute these unconditionally)
- propagate constants
- simplify control flow graph
- (sparse) conditional constant propagation
- dead store elimination
- dead code elimination
- instruction combining (arithmetic simplifications)
- jump threading

If after this transformation the program meets the requirements outlined above, then it is converted to a logical signature. The resulting logical signature is simplified using basic properties of boolean operations, such as associativity, distributivity, De Morgan's law.

The final logical signature is not unique (there might be another logical signature with identical behavior), however the boolean part is in a canonical form: it is in disjunctive normal form, with operands sorted in ascending order.

For best results the C code should consist of:

• local variables declaring the sums you want to use

- a series of if branches that return true, where the if's condition is a single comparison or a logical and of comparisons
- a final return false

You can use || in the if condition too, but be careful that after expanding to disjunctive normal form, the number of subexpressions doesn't exceed 64.

Note that you do not have to use all the subsignatures you declared in logical_trigger, you can do more complicated checks (that wouldn't obey the above restrictions) in the bytecode itself at runtime. The logical_trigger function is fully compiled into a logical signature, it won't be a runtime executed function (hence the restrictions).

4.4. Headers and runtime environment

When compiling a bytecode program, bytecode.h is automatically included, so you don't need to explicitly include it. These headers (and the compiler itself) predefine certain macros, see Appendix A for a full list. In addition the following types are defined:

```
typedef unsigned char uint8_t;
typedef char int8_t;
typedef unsigned short uint16_t;
typedef short int16_t;
typedef unsigned int uint32_t;
typedef int int32_t;
typedef unsigned long uint64_t;
typedef long int64_t;
typedef unsigned int size_t;
typedef struct signature { unsigned id } __Signature;
```

As described in Section 4.1 the width of integer types are fixed, the above typedefs show that.

A bytecode's entrypoint is the function entrypoint and it's required by ClamAV to load the bytecode.

Bytecode that is triggered by a logical signature must have a list of virusnames and patterns defined. Bytecodes triggered via hooks can optionally have them, but for example a PE unpacker doesn't need virus names as it only processes the data.

CHAPTER 5 Bytecode security & portability

CHAPTER 6 Reporting bugs

CHAPTER 7 Bytecode API

7.1. API groups

7.1.1. Bytecode configuration

Global COPYRIGHT(c) This will also prevent the sourcecode from being embedded into the bytecode

Global DECLARE_SIGNATURE(name)

Global DEFINE_SIGNATURE(name, hex)

Global FUNCTIONALITY_LEVEL_MAX(m)

Global FUNCTIONALITY_LEVEL_MIN(m)

Global ICONGROUP1(group)

Global ICONGROUP2(group)

Global PDF_HOOK_DECLARE This hook is called several times, use pdf_get_phase() to find out in which phase you got called.

Global PE_UNPACKER_DECLARE

7.1. API groups

Global SIGNATURES_DECL_BEGIN

Global SIGNATURES_DECL_END

Global SIGNATURES_DEF_BEGIN

Global SIGNATURES_END

Global TARGET(tgt)

Global VIRUSNAME_PREFIX(name)

Global VIRUSNAMES(...)

7.1.2. Data structure handling functions

Global buffer_pipe_done(int32_t id) After this all attempts to use this buffer will result in error. All buffer_pipes are automatically deallocated when bytecode finishes execution.

Global buffer pipe new(uint32 t size)

Global buffer_pipe_new_fromfile(uint32_t pos)

Global buffer_pipe_read_avail(int32_t id)

Global buffer_pipe_read_get(int32_t id, uint32_t amount) The 'amount' parameter should be obtained by a call to buffer_pipe_read_-avail().

Global buffer_pipe_read_stopped(int32_t id, uint32_t amount)
Updates read cursor in buffer_pipe.

Global buffer_pipe_write_avail(int32_t id)

```
Global buffer_pipe_write_get(int32_t id, uint32_t size)
     Returns pointer to writable buffer.
                                           The 'amount' parameter
     should be obtained by a call to buffer pipe write avail().
Global buffer_pipe_write_stopped(int32_t id, uint32_t amount)
Global cli_readint16(const void *buff)
Global cli_readint32(const void *buff)
Global cli_writeint32(void *offset, uint32_t v)
Global hashset_add(int32_t hs, uint32_t key)
Global hashset_contains(int32_t hs, uint32_t key)
Global hashset_done(int32_t id) Trying to use the hashset after this
     will result in an error. The hashset may not be used after this. All
     hashsets are automatically deallocated when bytecode finishes execution.
Global hashset_empty(int32_t id)
Global hashset new(void)
Global hashset_remove(int32_t hs, uint32_t key)
Global inflate done(int32 t id)
Global inflate_init(int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
    'from_buffer' and writing uncompressed uncompressed data 'to_buffer'.
Global inflate_process(int32_t id)
```

7.1. API groups

```
Global le16_to_host(uint16_t v)
Global le32_to_host(uint32_t v)
Global le64_to_host(uint64_t v)
Global malloc(uint32_t size)
Global map_addkey(const uint8_t *key, int32_t ksize, int32_t id)
Global map_done(int32_t id)
Global map_find(const uint8_t *key, int32_t ksize, int32_t id)
Global map getvalue(int32 t id, int32 t size)
Global map_getvaluesize(int32_t id)
Global map_new(int32_t keysize, int32_t valuesize)
Global map_remove(const uint8_t *key, int32_t ksize, int32_t id)
Global map_setvalue(const uint8_t *value, int32_t vsize, int32_t id)
7.1.3. Disassemble APIs
Global ___attribute_
Class DIS_arg
Class DIS fixed
Global disasm_x86(struct DISASM_RESULT *result, uint32_t len)
Global DisassembleAt(struct DIS_fixed *result, uint32_t offset, uint32_t len)
```

7.1.4. Engine queries

Global count_match(___Signature sig)

Global engine_db_options(void)

Global engine_dconf_level(void)

Global engine_functionality_level(void)

Global engine_scan_options(void)

Global match_location(___Signature sig, uint32_t goback)

Global match_location_check(___Signature sig, uint32_t goback, const char *static_s

It is recommended to use this for safety and compatibility with 0.96.1

Global matches (Signature sig)

7.1.5. Environment detection functions

 $Global \ \underline{\hspace{1cm}} is \underline{\hspace{1cm}} bigendian (void) \ \underline{\hspace{1cm}} attribute \underline{\hspace{1cm}} ((const\)) \ \underline{\hspace{1cm}} attribute \underline{\hspace{1cm}} ((nothrow))$

Global check_platform(uint32_t a, uint32_t b, uint32_t c)

Global disable_bytecode_if(const int8_t *reason, uint32_t len, uint32_t cond)

Global disable_jit_if(const int8_t *reason, uint32_t len, uint32_t cond)

Global get_environment(struct cli_environment *env, uint32_t len)

Global version_compare(const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint

7.1. API groups

7.1.6. File operations

```
Global buffer_pipe_new_fromfile(uint32_t pos) to the current file, at the specified position.
```

```
Global file byteat(uint32 t offset)
```

```
Global file_find(const uint8_t *data, uint32_t len)
```

```
Global file_find_limit(const uint8_t *data, uint32_t len, int32_t maxpos)
```

Global fill_buffer(uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t curso

Global getFilesize(void)

Global read(uint8_t *data, int32_t size)

Global read_number(uint32_t radix) Non-numeric characters are ignored.

Global seek(int32_t pos, uint32_t whence)

Global write(uint8_t *data, int32_t size)

7.1.7. Global variables

 $Global __clambc_filesize[1]$

Global ___clambc_kind

Global ___clambc_match_counts[64]

Global ___clambc_match_offsets[64]

Global clambc pedata

7.1.8. Icon matcher APIs

Global matchicon(const uint8_t *group1, int32_t group1_len, const uint8_t *group2,

7.1.9. JS normalize API

Global jsnorm_done(int32_t id)

Global jsnorm_init(int32_t from_buffer)

Global jsnorm_process(int32_t id)

7.1.10. Math functions

Global icos(int32_t a, int32_t b, int32_t c)

Global iexp(int32_t a, int32_t b, int32_t c)

Global ilog2(uint32 t a, uint32 t b)

Global ipow(int32_t a, int32_t b, int32_t c)

Global isin(int32 t a, int32 t b, int32 t c)

7.1.11. PDF handling functions

Global pdf_get_dumpedobjid(void) Valid only in PDF_PHASE_-POSTDUMP.

Global pdf_get_flags(void)

Global pdf_get_obj_num(void)

Global pdf_get_phase(void) Identifies at which phase this bytecode was called.

Global pdf_getobj(int32_t objidx, uint32_t amount) Meant only for reading, write modifies the fmap buffer, so avoid!

Global pdf_getobjsize(int32_t objidx)

Global pdf_lookupobj(uint32_t id)

Global pdf set flags(int32 t flags)

7.1. API groups

7.1.12. PE functions

```
Class cli_exe_info
Class cli_exe_section
Class cli_pe_hook_data
Global get_pe_section(struct cli_exe_section *section, uint32_t num)
Global getEntryPoint(void)
Global getExeOffset(void)
Global getImageBase(void)
Global getNumberOfSections(void)
Global getPEBaseOfCode(void)
Global getPEBaseOfData(void)
Global getPECharacteristics()
Global getPECheckSum(void)
Global getPEDataDirRVA(unsigned n)
Global getPEDataDirSize(unsigned n)
Global getPEDllCharacteristics(void)
```

Global getPEFileAlignment(void)

Global getPEImageBase(void)

Global getPEisDLL()

Global getPELFANew(void)

Global getPELoaderFlags(void)

Global getPEMachine()

Global getPEMajorImageVersion(void)

Global getPEMajorLinkerVersion(void)

Global getPEMajorOperatingSystemVersion(void)

Global getPEMajorSubsystemVersion(void)

Global getPEMinorImageVersion(void)

Global getPEMinorLinkerVersion(void)

Global getPEMinorOperatingSystemVersion(void)

Global getPEMinorSubsystemVersion(void)

Global getPENumberOfSymbols()

Global getPEPointerToSymbolTable()

7.1. API groups

Global getPESectionAlignment(void)

Global getPESizeOfCode(void)

Global getPESizeOfHeaders(void)

Global getPESizeOfHeapCommit(void)

Global getPESizeOfHeapReserve(void)

Global getPESizeOfImage(void)

Global getPESizeOfInitializedData(void)

Global getPESizeOfOptionalHeader()

Global getPESizeOfStackCommit(void)

Global getPESizeOfStackReserve(void)

Global getPESizeOfUninitializedData(void)

Global getPESubsystem(void)

Global getPETimeDateStamp()

Global getPEWin32VersionValue(void)

Global getSectionRVA(unsigned i) .

Global getSectionVirtualSize(unsigned i)

```
41
Chapter 7. Bytecode API
Global getVirtualEntryPoint(void)
Global hasExeInfo(void)
Global isPE64(void)
Class pe_image_data_dir
Class pe image file hdr
Class pe_image_optional_hdr32
Class pe_image_optional_hdr64
Class pe_image_section_hdr
Global pe_rawaddr(uint32_t rva)
Global readPESectionName(unsigned char name[8], unsigned n)
Global readRVA(uint32_t rva, void *buf, size_t bufsize)
7.1.13. Scan control functions
Global bytecode_rt_error(int32_t locationid)
Global extract_new(int32_t id)
Global extract_set_container(uint32_t container)
Global foundVirus(const char *virusname)
Global input_switch(int32_t extracted_file)
Global setvirusname(const uint8_t *name, uint32_t len)
```

42 7.1. API groups

7.1.14. String operations

```
Global atoi(const\ uint8\_t\ *str,\ int32\_t\ size)
Global debug print str(const uint8 t *str, uint32 t len)
Global debug_print_str_nonl(const uint8_t *str, uint32_t len)
Global debug_print_str_start(const uint8_t *str, uint32_t len)
Global debug_print_uint(uint32_t a)
Global entropy_buffer(uint8_t *buffer, int32_t size)
Global hex2ui(uint32_t hex1, uint32_t hex2)
Global memchr(const void *s, int c, size_t n)
Global memcmp(const void *s1, const void *s2, uint32_t n) __attribute___((__
Global memcpy(void *restrict dst, const void *restrict src, uintptr_t n) ___attri
Global memmove(void *dst, const void *src, uintptr_t n) __attribute__((__r
Global memset(void *src, int c, uintptr_t n) __attribute__((nothrow)) __att
```

Global memstr(const uint8_t *haystack, int32_t haysize, const uint8_t *needle

7.2. Structure types

7.2.1. cli_exe_info Struct Reference

Data Fields

- struct cli_exe_section * section
- uint32_t offset
- uint32_t ep
- uint16_t nsections
- struct cli_hashset * vinfo
- uint32_t res_addr
- uint32_t hdr_size

7.2.1.1. Detailed Description

Executable file information

 \mathbf{PE}

7.2.1.2. Field Documentation

7.2.1.2.1. uint 32_t ep

Entrypoint of executable

7.2.1.2.2. uint32_t hdr_size

Address size - PE ONLY

7.2.1.2.3. uint16_t nsections

Number of sections

7.2.1.2.4. uint32_t offset (nonzero if embedded)

Offset where this executable start in file

7.2.1.2.5. uint32_t res_addr

Resrources RVA - PE ONLY

7.2.1.2.6. struct cli_exe_section* section Information about all the sections of this file. This array has **nsection** elements

7.2.1.2.7. struct cli_hashset* vinfo Hashset for versioninfo matching

7.2.2. cli exe section Struct Reference

Data Fields

- uint32_t rva
- uint32_t vsz
- uint32_t raw
- uint32 t rsz
- uint32_t chr
- uint32_t urva
- uint32_t uvsz
- uint32_t uraw
- uint32_t ursz

7.2.2.1. Detailed Description

Section of executable file.

 \mathbf{PE}

7.2.2.2. Field Documentation

7.2.2.2.1. uint32_t chr Section characteristics

7.2.2.2. uint32_t raw Raw offset (in file)

7.2.2.2.3. uint32_t rsz Raw size (in file)

7.2.2.2.4. uint32_t rva Relative VirtualAddress

7.2.2.2.5. uint32_t uraw PE - unaligned PointerToRawData

7.2.2.6. uint32_t ursz PE - unaligned SizeOfRawData

7.2.2.2.7. uint32_t urva PE - unaligned VirtualAddress

7.2.2.2.8. uint32 t uvsz PE - unaligned VirtualSize

7.2.2.2.9. uint32_t vsz VirtualSize

7.2.3. cli pe hook data Struct Reference

Data Fields

- uint32_t ep
- uint16_t nsections
- struct pe_image_file_hdr file_hdr
- struct pe_image_optional_hdr32 opt32
- struct pe_image_optional_hdr64 opt64
- struct pe_image_data_dir dirs [16]
- uint32 t e lfanew
- uint32_t overlays
- int32_t overlays_sz
- uint32_t hdr_size

7.2.3.1. Detailed Description

Data for the bytecode PE hook

 \mathbf{PE}

7.2.3.2. Field Documentation

7.2.3.2.1. struct pe_image_data_dir dirs[16] PE data directory header

7.2. Structure types

7.2.3.2.2. uint32 t e lfanew address of new exe header

7.2.3.2.3. uint32_t ep EntryPoint as file offset

7.2.3.2.4. struct pe__image__file__hdr file__hdr Header for this PE file

7.2.3.2.5. uint32 t hdr size internally needed by rawaddr

7.2.3.2.6. uint16_t nsections Number of sections

7.2.3.2.7. struct pe_image_optional_hdr32 opt32 32-bit PE optional header

7.2.3.2.8. struct pe_image_optional_hdr64 opt64 64-bit PE optional header

7.2.3.2.9. uint32 t overlays number of overlays

7.2.3.2.10. int32_t overlays_sz size of overlays

7.2.4. DIS_arg Struct Reference

Data Fields

- enum DIS_ACCESS access_type
- enum DIS_SIZE access_size
- struct DIS_mem_arg mem
- enum X86REGS reg
- uint64_t other

7.2.4.1. Detailed Description

disassembled operand

Disassemble

7.2.4.2. Field Documentation

7.2.4.2.1. enum DIS_SIZE access_size

size of access

7.2.4.2.2. enum DIS_ACCESS access_type

type of access

7.2.4.2.3. struct DIS mem arg mem

memory operand

7.2.4.2.4. uint64_t other

other operand

7.2.4.2.5. enum X86REGS reg

register operand

7.2.5. DIS fixed Struct Reference

Data Fields

- enum X86OPS x86_opcode
- enum DIS_SIZE operation_size
- enum DIS SIZE address size
- uint8_t segment

7.2.5.1. Detailed Description

disassembled instruction.

Disassemble

7.2.5.2. Field Documentation

7.2.5.2.1. enum DIS_SIZE address_size

size of address

7.2.5.2.2. enum DIS_SIZE operation_size

size of operation

7.2.5.2.3. uint8_t segment

segment

7.2.5.2.4. enum X86OPS x86_opcode opcode of X86 instruction

7.2.6. DIS_mem_arg Struct Reference

Data Fields

- enum DIS SIZE access size
- enum X86REGS scale reg
- enum X86REGS add_reg
- uint8 t scale
- int32_t displacement

7.2.6.1. Detailed Description

disassembled memory operand: scale_reg*scale + add_reg + displacement

Disassemble

7.2.6.2. Field Documentation

7.2.6.2.1. enum DIS_SIZE access_size

size of access

7.2.6.2.2. enum X86REGS add_reg register used as displacement

7.2.6.2.3. int32_t displacement displacement as immediate number

7.2.6.2.4. uint8_t scale

scale as immediate number

7.2.6.2.5. enum X86REGS scale_reg

register used as scale

7.2.7. DISASM_RESULT Struct Reference

7.2.7.1. Detailed Description

disassembly result, 64-byte, matched by type-8 signatures

7.2.8. pe_image_data_dir Struct Reference

7.2.8.1. Detailed Description

PE data directory header

 \mathbf{PE}

7.2.9. pe_image_file_hdr Struct Reference

Data Fields

- uint32_t Magic
- uint16_t Machine
- uint16 t NumberOfSections
- uint32_t TimeDateStamp
- uint32_t PointerToSymbolTable
- uint32_t NumberOfSymbols
- uint16_t SizeOfOptionalHeader

7.2.9.1. Detailed Description

Header for this PE file

 \mathbf{PE}

7.2.9.2. Field Documentation

7.2.9.2.1. uint16_t Machine libclamav/pe.c for possible values

CPU this executable runs on, see

7.2.9.2.2. uint32_t Magic

PE magic header: $PE \setminus 0 \setminus 0$

7.2.9.2.3. uint 16_t NumberOfSections executable

Number of sections in this

50	7.2. Structure types
7.2.9.2.4. uint32_t NumberOfSymbols	debug
$7.2.9.2.5.\ uint 32_t\ Pointer To Symbol Table$	debug
$7.2.9.2.6.~uint 16_t~Size Of Optional Header$	== 224
7.2.9.2.7. uint32_t TimeDateStamp	Unreliable

7.2.10. pe_image_optional_hdr32 Struct Reference

Data Fields

- uint8_t MajorLinkerVersion
- uint8_t MinorLinkerVersion
- uint32 t SizeOfCode
- uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- uint32_t ImageBase
- uint32_t SectionAlignment
- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- \bullet uint32_t NumberOfRvaAndSizes

7.2.10.1. Detailed Description

32-bit PE optional header

 \mathbf{PE}

Chapter 7. Bytecode API	21
7.2.10.2. Field Documentation	
7.2.10.2.1. uint32_t CheckSum	NT drivers only
7.2.10.2.2. uint32_t FileAlignment	usually 32 or 512
$7.2.10.2.3.$ uint 32 _t ImageBase	multiple of 64 KB
$7.2.10.2.4.~uint16_t~MajorImageVersion$	unreliable
$7.2.10.2.5.\ uint8_t\ MajorLinkerVersion$	unreliable
$7.2.10.2.6.~uint16_t~MajorOperatingSystemVersi$	on not used
$7.2.10.2.7.~uint16_t~MinorImageVersion$	unreliable
$7.2.10.2.8.\ uint8_t\ MinorLinkerVersion$	unreliable
7.2.10.2.9. uint16_t MinorOperatingSystemVersi	on not used
$7.2.10.2.10.\ uint 32_t\ Number Of Rva And Sizes$	unreliable
$7.2.10.2.11.$ uint 32_t SectionAlignment	usually 32 or 4096
$7.2.10.2.12.$ uint 32 _t SizeOfCode	unreliable
$7.2.10.2.13.\ uint 32_t\ Size Of Initialized Data$	unreliable
$7.2.10.2.14.~uint 32_t~Size Of Uninitialized Data$	unreliable

${\bf 7.2.11.\ pe_image_optional_hdr64\ Struct\ Reference}$

Data Fields

- uint8_t MajorLinkerVersion
- uint8_t MinorLinkerVersion
- uint32_t SizeOfCode
- uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData

52 7.2. Structure types

- uint64_t ImageBase
- uint32_t SectionAlignment
- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16 t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32_t NumberOfRvaAndSizes

7.2.11.1. Detailed Description

PE 64-bit optional header

\mathbf{PE}

7.2.11.2.1. uint32_t CheckSum NT drivers only 7.2.11.2.2. uint32_t FileAlignment 1.2.11.2.3. uint64_t ImageBase 1.2.11.2.4. uint16_t MajorImageVersion 1.2.11.2.5. uint8_t MajorLinkerVersion 1.2.11.2.6. uint16_t MajorOperatingSystemVersion 1.2.11.2.7. uint16_t MinorImageVersion 1.2.11.2.7. uint16_t MinorImageVersion

	_
Ь	ĸ
	74)

7.2.11.2.8. uint8_t MinorLinkerVersion

unreliable

7.2.11.2.9. uint16_t MinorOperatingSystemVersion

not used

7.2.11.2.10. uint32 t NumberOfRvaAndSizes

unreliable

7.2.11.2.11. uint32_t SectionAlignment

usually 32 or 4096

 $7.2.11.2.12.~uint \\ 32_t~Size Of Code$

unreliable

7.2.11.2.13. uint32_t SizeOfInitializedData

unreliable

7.2.11.2.14. uint32_t SizeOfUninitializedData

unreliable

7.2.12. pe_image_section_hdr Struct Reference

Data Fields

- uint8_t Name [8]
- uint32_t SizeOfRawData
- uint32_t PointerToRawData
- uint32 t PointerToRelocations
- uint32_t PointerToLinenumbers
- uint16 t NumberOfRelocations
- uint16_t NumberOfLinenumbers

7.2.12.1. Detailed Description

PE section header

PE

7.2.12.2. Field Documentation

7.2.12.2.1. uint8_t Name[8]

may not end with NULL

7.2.12.2.2. uint16_t NumberOfLinenumbers object files only
7.2.12.2.3. uint16_t NumberOfRelocations object files only
7.2.12.2.4. uint32_t PointerToLinenumbers object files only
7.2.12.2.5. uint32_t PointerToRawData offset to the section's data
7.2.12.2.6. uint32_t PointerToRelocations object files only
7.2.12.2.7. uint32_t SizeOfRawData multiple of FileAlignment

7.3. Low level API

7.3.1. bytecode_api.h File Reference

Enumerations

- enum Bytecode Kind { BC_GENERIC = 0 , BC_LOGICAL = 256, BC_PE_UNPACKER }
- enum { PE_INVALID_RVA = 0xFFFFFFFF }
- enum FunctionalityLevels
- enum pdf_phase
- enum pdf flag
- enum pdf_objflags
- enum { SEEK_SET = 0, SEEK_CUR, SEEK_END }

Functions

- uint32_t test1 (uint32_t a, uint32_t b)
- int32_t read (uint8_t *data, int32_t size)

 Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.
- int32_t write (uint8_t *data, int32_t size)

 Writes the specified amount of bytes from a buffer to the current temporary file.

- int32_t seek (int32_t pos, uint32_t whence)

 Changes the current file position to the specified one.
- uint32_t setvirusname (const uint8_t *name, uint32_t len)
- uint32 t debug print str (const uint8 t *str, uint32 t len)
- uint32_t debug_print_uint (uint32_t a)
- uint32_t disasm_x86 (struct DISASM_RESULT *result, uint32_t len)
- uint32_t pe_rawaddr (uint32_t rva)
- int32_t file_find (const uint8_t *data, uint32_t len)
- int32_t file_byteat (uint32_t offset)
- void * malloc (uint32 t size)
- uint32 t test2 (uint32 t a)
- int32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
- int32_t fill_buffer (uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)
- int32_t extract_new (int32_t id)
- int32_t read_number (uint32_t radix)
- int32_t hashset_new (void)
- int32_t hashset_add (int32_t hs, uint32_t key)
- int32 t hashset remove (int32 t hs, uint32 t key)
- int32 t hashset contains (int32 t hs, uint32 t key)
- int32_t hashset_done (int32_t id)
- int32 t hashset empty (int32 t id)
- int32_t buffer_pipe_new (uint32_t size)
- int32_t buffer_pipe_new_fromfile (uint32_t pos)
- uint32_t buffer_pipe_read_avail (int32_t id)
- uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)
- int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)
- uint32 t buffer pipe write avail (int32 t id)
- uint8_t * buffer_pipe_write_get (int32_t id, uint32_t size)
- int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)
- int32_t buffer_pipe_done (int32_t id)
- int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
- int32_t inflate_process (int32_t id)

56 7.3. Low level API

- int32_t inflate_done (int32_t id)
- int32_t bytecode_rt_error (int32_t locationid)
- int32_t jsnorm_init (int32_t from_buffer)
- int32 t jsnorm process (int32 t id)
- int32_t jsnorm_done (int32_t id)
- int32_t ilog2 (uint32_t a, uint32_t b)
- int32_t ipow (int32_t a, int32_t b, int32_t c)
- uint32 t iexp (int32 t a, int32 t b, int32 t c)
- int32_t isin (int32_t a, int32_t b, int32_t c)
- int32_t icos (int32_t a, int32_t b, int32_t c)
- int32_t memstr (const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needlesize)
- int32_t hex2ui (uint32_t hex1, uint32_t hex2)
- int32 t atoi (const uint8 t *str, int32 t size)
- uint32 t debug print str start (const uint8 t *str, uint32 t len)
- uint32 t debug print str nonl (const uint8 t *str, uint32 t len)
- uint32_t entropy_buffer (uint8_t *buffer, int32_t size)
- int32 t map new (int32 t keysize, int32 t valuesize)
- int32_t map_addkey (const uint8_t *key, int32_t ksize, int32_t id)
- int32 t map setvalue (const uint8 t *value, int32 t vsize, int32 t id)
- int32_t map_remove (const uint8_t *key, int32_t ksize, int32_t id)
- int32 t map find (const uint8 t *key, int32 t ksize, int32 t id)
- int32_t map_getvaluesize (int32_t id)
- uint8_t * map_getvalue (int32_t id, int32_t size)
- int32_t map_done (int32_t id)
- int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)
- uint32_t engine_functionality_level (void)
- uint32 t engine dconf level (void)
- uint32 t engine scan options (void)
- uint32_t engine_db_options (void)
- int32 t extract set container (uint32 t container)
- int32_t input_switch (int32_t extracted_file)
- uint32_t get_environment (struct cli_environment *env, uint32_t len)
- uint32_t disable_bytecode_if (const int8_t *reason, uint32_t len, uint32_t cond)

- uint32_t disable_jit_if (const int8_t *reason, uint32_t len, uint32_t cond)
- int32_t version_compare (const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_t rhs_len)
- uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c)
- int32_t pdf_get_obj_num (void)
- int32_t pdf_get_flags (void)
- int32_t pdf_set_flags (int32_t flags)
- int32 t pdf lookupobj (uint32 t id)
- uint32 t pdf getobjsize (int32 t objidx)
- uint8 t * pdf getobj (int32 t objidx, uint32 t amount)
- int32_t pdf_get_phase (void)
- int32_t pdf_get_dumpedobjid (void)
- int32_t matchicon (const uint8_t *group1, int32_t group1_len, const uint8_t *group2, int32_t group2_len)

Variables

- const uint32_t __clambc_match_counts [64] Logical signature match counts.
- const uint32_t __clambc_match_offsets [64]

 Logical signature match offsets This is a low-level variable, use the Macros in bytecode_local.h instead to access it.
- struct cli_pe_hook_data ___clambc_pedata
- const uint32_t __clambc_filesize [1]
- const uint16_t __clambc_kind

7.3.1.1. Detailed Description

7.3.1.2. Enumeration Type Documentation

7.3.1.2.1. anonymous enum

Enumerator:

PE_INVALID_RVA Invalid RVA specified

58 7.3. Low level API

7.3.1.2.2. anonymous enum

Enumerator:

 $SEEK_SET$ set file position to specified absolute position

SEEK_CUR set file position relative to current position

SEEK_END set file position relative to file end

7.3.1.2.3. enum BytecodeKind

Bytecode trigger kind

Enumerator:

 $BC_GENERIC$ generic bytecode, not tied a specific hook

BC_LOGICAL triggered by a logical signature

 $BC_PE_UNPACKER$ a PE unpacker

7.3.1.2.4. enum FunctionalityLevels LibClamAV functionality level constants

7.3.1.2.5. enum pdf_flag

PDF flags

7.3.1.2.6. enum pdf_objflags

PDF obj flags

7.3.1.2.7. enum pdf_phase

Phase of PDF parsing

7.3.1.3. Function Documentation

7.3.1.3.1. int32_t atoi (const uint8_t * str, int32_t size) Converts string to positive number.

Parameters

str buffer

size size of str

Returns

>0 string converted to number if possible, -1 on error

String operation

7.3.1.3.2. int32_t buffer_pipe_done (int32_t id) Deallocate memory used by buffer.

Data structure

After this all attempts to use this buffer will result in error. All buffer_-pipes are automatically deallocated when bytecode finishes execution.

Parameters

id ID of buffer_pipe

Returns

0 on success

7.3.1.3.3. int32_t buffer_pipe_new (uint32_t size) Creates a new pipe with the specified buffer size

Data structure

Parameters

size size of buffer

Returns

ID of newly created buffer_pipe

7.3.1.3.4. int32_t buffer_pipe_new_fromfile (uint32_t pos) Same as buffer_pipe_new, except the pipe's input is tied

Data structure

File operation

to the current file, at the specified position.

Parameters

pos starting position of pipe input in current file

Returns

ID of newly created buffer_pipe

7.3. Low level API

7.3.1.3.5. uint32_t buffer_pipe_read_avail (int32_t id) Returns the amount of bytes available to read.

Data structure

Parameters

id ID of buffer_pipe

Returns

amount of bytes available to read

7.3.1.3.6. uint8_t* buffer_pipe_read_get (int32_t id, uint32_t amount) Returns a pointer to the buffer for reading.

Data structure

The 'amount' parameter should be obtained by a call to buffer_pipe_-read_avail().

Parameters

id ID of buffer_pipeamount to read

Returns

pointer to buffer, or NULL if buffer has less than specified amount

7.3.1.3.7. int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)

Data structure

Updates read cursor in buffer_pipe.

Parameters

id ID of buffer_pipeamount amount of bytes to move read cursor

Returns

0 on success

7.3.1.3.8. uint32_t buffer_pipe_write_avail (int32_t id) Returns the amount of bytes available for writing.

Data structure

Parameters

id ID of buffer_pipe

Returns

amount of bytes available for writing

7.3.1.3.9. uint8_t* buffer_pipe_write_get (int32_t id, uint32_t size)

Data structure

Returns pointer to writable buffer. The 'amount' parameter should be obtained by a call to buffer_pipe_write_avail().

Parameters

id ID of buffer_pipesize amount of bytes to write

Returns

pointer to write buffer, or NULL if requested amount is more than what is available in the buffer

7.3.1.3.10. int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount) Updates the write cursor in buffer_pipe.

Data structure

Parameters

id ID of buffer_pipeamount amount of bytes to move write cursor

Returns

0 on success

62 7.3. Low level API

7.3.1.3.11. int32_t bytecode_rt_error (int32_t locationid) Report a runtime error at the specified locationID.

Scan

Parameters

locationid (line << 8) | (column&0xff)

Returns

0

7.3.1.3.12. uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c) Disables the JIT if the platform id matches. 0xff can be used instead of a field to mark ANY.

Parameters

- \boldsymbol{a} os_category << 24 | arch << 20 | compiler << 16 | flevel << 8 | dconf
- b big_endian << 28 | sizeof_ptr << 24 | cpp_version
- c os_features << 24 | c_version

Returns

0 - no match 1 - match

Environment

7.3.1.3.13. uint32_t debug_print_str (const uint8_t * str, uint32_t len) Prints a debug message.

Parameters

- [in] *str* Message to print
- [in] *len* length of message to print

Returns

0

String operation

7.3.1.3.14. uint32_t debug_print_str_nonl (const uint8_t * str, uint32_t len) Prints a debug message with a trailing newline, and not preceded by 'LibClamAV debug'.

Parameters

str the string len length of str

Returns

0

String operation

7.3.1.3.15. uint32_t debug_print_str_start (const uint8_t * str, uint32_t len) Prints a debug message with a trailing newline, but preceded by 'LibClamAV debug'.

Parameters

str the string len length of str

Returns

0

String operation

7.3.1.3.16. uint32_t debug_print_uint (uint32_t a) Prints a number as a debug message. This is like debug_print_str_nonl!

Parameters

[in] a number to print

Returns

0

String operation

7.3. Low level API

7.3.1.3.17. uint32_t disable_bytecode_if (const int8_t * reason, uint32_t len, uint32_t cond) Disables the bytecode completely if condition is true. Can only be called from the BC_STARTUP bytecode.

Parameters

reason - why the bytecode had to be disabled len - length of reason cond - condition

Returns

0 - auto mode 1 - JIT disabled 2 - fully disabled

Environment

7.3.1.3.18. uint32_t disable_jit_if (const int8_t * reason, uint32_t len, uint32_t cond) Disables the JIT completely if condition is true. Can only be called from the BC_STARTUP bytecode.

Parameters

reason - why the JIT had to be disabled len - length of reason cond - condition

Returns

0 - auto mode 1 - JIT disabled 2 - fully disabled

Environment

7.3.1.3.19. uint32_t disasm_x86 (struct DISASM_RESULT * result, uint32_t len) Disassembles starting from current file position, the specified amount of bytes.

Parameters

[out] result pointer to struct holding result[in] len how many bytes to disassemble

Returns

0 for success

You can use lseek to disassemble starting from a different location. This is a low-level API, the result is in ClamAV type-8 signature format (64 bytes/instruction).

See also

DisassembleAt

Disassemble

7.3.1.3.20. uint32_t engine_db_options (void) Returns the current engine's db options.

Returns

CL_DB_* flags

Engine query

7.3.1.3.21. uint32_t engine_dconf_level (void) Returns the current engine (dconf) functionality level. Usually identical to engine_functionality_level(), unless distro backported patches. Compare with FunctionalityLevels.

Returns

an integer representing the DCONF (security fixes) level.

Engine query

7.3.1.3.22. uint32_t engine_functionality_level (void) Returns the current engine (feature) functionality level. To map these to ClamAV releases, compare it with FunctionalityLevels.

Returns

an integer representing current engine functionality level.

Engine query

7.3.1.3.23. uint32_t engine_scan_options (void) Returns the current engine's scan options.

Returns

CL SCAN* flags

Engine query

7.3.1.3.24. uint32_t entropy_buffer (uint8_t * buffer, int32_t size) Returns an approximation for the entropy of buffer.

Parameters

 $\it buffer$ input buffer

size size of buffer

Returns

entropy estimation $*2^{26}$

String operation

7.3.1.3.25. int32_t extract_new (int32_t id) Prepares for extracting a new file, if we've already extracted one it scans it.

Scan

Parameters

[in] *id* an id for the new file (for example position in container)

Returns

1 if previous extracted file was infected

7.3.1.3.26. int32_t extract_set_container (uint32_t container)

Sets the container type for the currently extracted file.

Parameters

container container type (CL TYPE *)

Returns

current setting for container (CL TYPE ANY default)

Scan

 $7.3.1.3.27.\ int 32_t\ file_byteat$ ($uint 32_t\ of\!fset$) Read a single byte from current file

File operation

Parameters

offset file offset

Returns

byte at offset off in the current file, or -1 if offset is invalid

7.3.1.3.28. int32_t file_find (const uint8_t * data, uint32_t len) Looks for the specified sequence of bytes in the current file.

File operation

Parameters

[in] data the sequence of bytes to look for len length of data, cannot be more than 1024

Returns

offset in the current file if match is found, -1 otherwise

7.3.1.3.29. int32_t file_find_limit (const uint8_t * data, uint32_t len, int32_t maxpos) Looks for the specified sequence of bytes in the current file, up to the specified position.

Parameters

[in] data the sequence of bytes to look for len length of data, cannot be more than 1024

maxpos maximum position to look for a match, note that this is 1 byte after the end of last possible match: match_pos + len < maxpos

Returns

offset in the current file if match is found, -1 otherwise

File operation

7.3.1.3.30. int32_t fill_buffer (uint8_t * buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill) Fills the specified buffer with at least fill bytes.

File operation

Parameters

[out] buffer the buffer to fill

[in] *len* length of buffer

[in] *filled* how much of the buffer is currently filled

[in] *cursor* position of cursor in buffer

[in] *fill* amount of bytes to fill in (0 is valid)

Returns

<0 on error, 0 on EOF, number bytes available in buffer (starting from 0) The character at the cursor will be at position 0 after this call.

7.3.1.3.31. uint32_t get_environment (struct cli_environment * env, uint32_t len) Queries the environment this bytecode runs in. Used by BC_STARTUP to disable bytecode when bugs are known for the current platform.

Parameters

[out] env - the full environment len - size of env

Returns

0

Environment

7.3.1.3.32. int32_t get_pe_section (struct cli_exe_section * section, uint32_t num) Gets information about the specified PE section.

PE

Parameters

[out] section PE section information will be stored here[in] num PE section number

Returns

0 - success -1 - failure

7.3.1.3.33. int32_t hashset_add (int32_t hs, uint32_t key) Add a new 32-bit key to the hashset.

Data structure

Parameters

hs ID of hashset (from hashset_new)key the key to add

Returns

0 on success

7.3.1.3.34. int32_t hashset_contains (int32_t hs, uint32_t key) Returns whether the hashset contains the specified key.

Data structure

Parameters

hs ID of hashset (from hashset_new)key the key to lookup

Returns

1 if found, 0 if not found, <0 on invalid hashset ID

7.3.1.3.35. int32_t hashset_done (int32_t id) Deallocates the memory used by the specified hashset.

Data structure

Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution.

Parameters

id ID of hashset (from hashset_new)

Returns

0 on success

7.3.1.3.36. int32_t hashset_empty (int32_t id) Returns whether the hashset is empty.

Data structure

Parameters

id of hashset (from hashset_new)

Returns

0 on success

7.3.1.3.37. int32_t hashset_new (void) Creates a new hashset and returns its id.

Data structure

Returns

ID for new hashset

7.3.1.3.38. int32_t hashset_remove (int32_t hs, uint32_t key) Remove a 32-bit key from the hashset.

Parameters

hs ID of hashset (from hashset_new)

key the key to add

Returns

0 on success

7.3.1.3.39. int32_t hex2ui (uint32_t hex1, uint32_t hex2) Returns hexadecimal characters hex1 and hex2 converted to 8-bit number.

Parameters

hex1 hexadecimal character

hex2 hexadecimal character

Returns

hex1 hex2 converted to 8-bit integer, -1 on error

String operation

7.3.1.3.40. int32_t icos (int32_t a, int32_t b, int32_t c) Returns c*cos(a/b).

Parameters

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns

c*sin(a/b)

Math function

7.3.1.3.41. uint32_t iexp (int32_t a, int32_t b, int32_t c) Returns exp(a/b)*c

Parameters

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns

c*exp(a/b)

Math function

7.3.1.3.42. int32_t ilog2 (uint32_t a, uint32_t b) Returns $2^26*\log 2(a/b)$

Parameters

- \boldsymbol{a} input
- \boldsymbol{b} input

Returns

 2^{2} 6*log2(a/b)

Math function

7.3.1.3.43. int32_t inflate_done (int32_t id) Deallocates inflate data structure. Using the inflate data structure after this will result in an error. All inflate data structures are automatically deallocated when bytecode finishes execution.

Data structure

Parameters

id ID of inflate data structure

Returns

0 on success.

7.3.1.3.44. int32_t inflate_init (int32_t $from_buffer$, int32_t to_buffer , int32_t windowBits) Initializes inflate data structures for decompressing data

Data structure

'from_buffer' and writing uncompressed uncompressed data 'to_buffer'.

Parameters

from_buffer ID of buffer_pipe to read compressed data from
to_buffer ID of buffer_pipe to write decompressed data to
windowBits (see zlib documentation)

Returns

ID of newly created inflate data structure, <0 on failure

7.3.1.3.45. int32_t inflate_process (int32_t id) Inflate all available data in the input buffer, and write to output buffer. Stops when the input buffer becomes empty, or write buffer becomes full. Also attempts to recover from corrupted inflate stream (via inflateSync). This function can be called repeatedly on success after filling the input buffer, and flushing the output buffer. The inflate stream is done processing when 0 bytes are available from output buffer, and input buffer is not empty.

Data structure

Parameters

id ID of inflate data structure

Returns

0 on success, zlib error code otherwise

7.3.1.3.46. int32_t input_switch (int32_t extracted_file) Toggles the read/seek API to read from the currently extracted file, and back. You must call seek after switching inputs to position the cursor to a valid position.

Parameters

extracted_file 1 - switch to reading from extracted file, 0 - switch back
to original input

Returns

-1 on error (if no extracted file exists) 0 on success

Scan

7.3.1.3.47. int32_t ipow (int32_t a, int32_t b, int32_t c) Returns c*a^b.

Parameters

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns

c*pow(a,b)

Math function

7.3.1.3.48. int32_t isin (int32_t a, int32_t b, int32_t c) Returns c*sin(a/b).

Parameters

- \boldsymbol{a} integer
- \boldsymbol{b} integer
- \boldsymbol{c} integer

Returns

c*sin(a/b)

Math function

7.3.1.3.49. int32_t jsnorm_done (int32_t id) Flushes JS normalizer.

JavaScript

Parameters

id ID of js normalizer to flush

Returns

0 - success -1 - failure

7.3.1.3.50. int32_t jsnorm_init (int32_t from_buffer) Initializes JS normalizer for reading 'from_buffer'. Normalized JS will be written to a single tempfile, one normalized JS per line, and automatically scanned when the bytecode finishes execution.

JavaScript

Parameters

from_buffer ID of buffer_pipe to read javascript from

Returns

ID of JS normalizer, <0 on failure

7.3.1.3.51. int32_t jsnorm_process (int32_t *id*) Normalize all javascript from the input buffer, and write to tempfile. You can call this function repeatedly on success, if you (re)fill the input buffer.

JavaScript

Parameters

id ID of JS normalizer

Returns

0 on success, <0 on failure

7.3.1.3.52. void* malloc ($uint32_t$ size) Allocates memory. Currently this memory is freed automatically on exit from the bytecode, and there is no way to free it sooner.

Data structure

Parameters

size amount of memory to allocate in bytes

Returns

pointer to allocated memory

7.3.1.3.53. int32_t map_addkey (const uint8_t * key, int32_t ksize, int32_t id) Inserts the specified key/value pair into the map.

Parameters

id id of table

key key

ksize size of key

Returns

0 - if key existed before 1 - if key didn't exist before <0 - if ksize doesn't match keysize specified at table creation

Data structure

7.3.1.3.54. int32_t map_done (int32_t id) Deallocates the memory used by the specified map. Trying to use the map after this will result in an error. All maps are automatically deallocated when the bytecode finishes execution.

Parameters

id id of map

Returns

0 - success -1 - invalid map

7.3.1.3.55. int32_t map_find (const uint8_t * key, int32_t ksize, int32_t id) Looks up key in map. The map remember the last looked up key (so you can retrieve the value).

Parameters

id id of mapkey keyksize size of key

Returns

0 - if not found 1 - if found $<\!0$ - if ksize doesn't match the size specified at table creation

Data structure

7.3.1.3.56. uint8_t* map_getvalue (int32_t id, int32_t size) Returns the value obtained during last map_find.

Parameters

id id of map.size size of value (obtained from map_getvaluesize)

Returns

value

Data structure

7.3.1.3.57. int32_t map_getvaluesize (int32_t id) Returns the size of value obtained during last map_find.

Parameters

id id of map.

Returns

size of value

```
7.3.1.3.58. int32_t map_new ( int32_t keysize, int32_t value-size ) Creates a new map and returns its id.
```

Parameters

keysize size of key

valuesize size of value, if 0 then value is allocated separately

Returns

ID of new map

Data structure

```
7.3.1.3.59. int32_t map_remove ( const uint8_t * key, int32_t ksize, int32_t id ) Remove an element from the map.
```

Parameters

id id of map

key key

ksize size of key

Returns

0 on success, key was present 1 if key was not present <0 if ksize doesn't match keysize specified at table creation

Data structure

7.3.1.3.60. int32_t map_setvalue (const uint8_t * value, int32_t vsize, int32_t id) Sets the value for the last inserted key with map_addkey.

Parameters

id id of table

value value

vsize size of value

Returns

0 - if update was successful <0 - if there is no last key

7.3.1.3.61. int32_t matchicon (const uint8_t * group1, int32_t group1_len, const uint8_t * group2, int32_t group2_len) Attempts to match current executable's icon against the specified icon groups.

Icon

Parameters

[in] group1 - same as GROUP1 in LDB signatures

group1_len - length of group1

[in] group2 - same as GROUP2 in LDB signatures

group2_len - length of group2

Returns

-1 - invalid call, or sizes (only valid for PE hooks) 0 - not a match 1 - match

7.3.1.3.62. int32_t memstr (const uint8_t * haystack, int32_t haysize, const uint8_t * needle, int32_t needlesize) Return position of match, -1 otherwise.

Parameters

haystack buffer to search

haysize size of haystack

needle substring to search

needlesize size of needle

Returns

location of match, -1 otherwise

String operation

 $7.3.1.3.63. \ int 32_t \ pdf_get_dumped objid \ (\ void \) \qquad {\rm Return \ the}$ currently dumped obj index.

PDF

Valid only in PDF_PHASE_POSTDUMP.

Returns

>=0 - object index -1 - invalid phase

7.3.1.3.64. int32_t pdf_get_flags (void) Return the flags for the entire PDF (as set so far).

Returns

-1 - if not called from PDF hook >=0 - pdf flags

PDF

 $7.3.1.3.65.\ int32_t\ pdf_get_obj_num\ (\ void\)$ Return number of pdf objects

Returns

-1 - if not called from PDF hook >=0 - number of PDF objects

PDF

7.3.1.3.66. int32_t pdf_get_phase (void) Return an 'enum pdf_phase'.

PDF

Identifies at which phase this bytecode was called.

Returns

the current pdf_phase

7.3.1.3.67. uint8_t* pdf_getobj (int32_t objidx, uint32_t amount) Return the undecoded object.

PDF

Meant only for reading, write modifies the fmap buffer, so avoid!

Parameters

```
objidx - object index (from 0), not object id!amount - size returned by pdf_getobjsize (or smaller)
```

Returns

NULL - invalid objidx/amount pointer - pointer to original object

7.3.1.3.68. uint32_t pdf_getobjsize (int32_t objidx) Return the size of the specified PDF obj.

PDF

Parameters

objidx - object index (from 0), not object id!

Returns

0 - if not called from PDF hook, or invalid objnum >=0 - size of object

7.3.1.3.69. int32_t pdf_lookupobj (uint32_t id) Lookup pdf object with specified id.

PDF

Parameters

id - pdf id (objnumber << 8 | generationid)

Returns

-1 - if object id doesn't exist ≥ 0 - object index

7.3.1.3.70. int32_t pdf_set_flags (int32_t *flags*) Sets the flags for the entire PDF. It is recommended that you retrieve old flags, and just add new ones.

PDF

Parameters

flags - flags to set.

Returns

0 - success -1 - invalid phase

7.3.1.3.71. uint32_t pe_rawaddr (uint32_t rva) Converts a RVA (Relative Virtual Address) to an absolute PE file offset.

Parameters

rva a rva address from the PE file

Returns

absolute file offset mapped to the rva, or PE_INVALID_RVA if the rva is invalid.

PE

7.3.1.3.72. int32_t read (uint8_t * data, int32_t size) Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

Parameters

[in] size amount of bytes to read

[out] data pointer to buffer where data is read into

Returns

amount read.

File operation

7.3.1.3.73. int32_t read_number (uint32_t radix) Reads a number in the specified radix starting from the current position.

File operation

Non-numeric characters are ignored.

Parameters

[in] *radix* 10 or 16

Returns

the number read

7.3.1.3.74. int32_t seek (int32_t pos, uint32_t whence) Changes the current file position to the specified one.

See also

```
SEEK_SET, SEEK_CUR, SEEK_END
```

Parameters

[in] **pos** offset (absolute or relative depending on whence param)

[in] whence one of SEEK SET, SEEK CUR, SEEK END

Returns

absolute position in file

File operation

7.3.1.3.75. uint32_t setvirusname (const uint8_t *
$$name$$
, uint32_t len) Sets the name of the virus found.

Parameters

[in] *name* the name of the virus

[in] *len* length of the virusname

Returns

0

Scan

7.3.1.3.76. $uint32_t test1 (uint32_t a, uint32_t b)$ Test api.

Parameters

a 0xf00dbeef

 \boldsymbol{b} 0xbeeff00d

Returns

0x12345678 if parameters match, 0x55 otherwise

7.3.1.3.77.
$$uint32_t test2 (uint32_t a)$$

Test api2.

Parameters

 \boldsymbol{a} 0xf00d

Returns

0xd00f if parameter matches, 0x5555 otherwise

7.3.1.3.78. int32_t version_compare (const uint8_t *
$$lhs$$
, uint32_t lhs _ len , const uint8_t * rhs , uint32_t rhs _ len) Compares two version numbers.

Parameters

[in] *lhs* - left hand side of comparison

lhs_len - length of lhs

[in] *rhs* - right hand side of comparison

rhs_len - length of rhs

Returns

$$-1 - lhs < rhs 0 - lhs == rhs 1 - lhs > rhs$$

Environment

7.3.1.3.79. int32_t write (uint8_t * data, int32_t size)

Writes the specified amount of bytes from a buffer to the current temporary file.

Parameters

- [in] data pointer to buffer of data to write
- [in] *size* amount of bytes to write size bytes to temporary file, from the buffer pointed to byte

Returns

amount of bytes successfully written

File operation

7.3.1.4. Variable Documentation

7.3.1.4.1. const uint32_t ___clambc_filesize[1] File size (max 4G).

Global variable

7.3.1.4.2. const uint16_t ___clambc_kind Kind of the bytecode

Global variable

7.3.1.4.3. const uint32_t ___clambc_match_counts[64]

Logical signature match counts.

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Global variable

7.3.1.4.4. const uint32_t ___clambc_match_offsets[64]

Logical signature match offsets This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Global variable

7.3.1.4.5. struct cli_pe_hook_data ___clambc_pedata PE data, if this is a PE hook.

Global variable

7.3.2. bytecode disasm.h File Reference

Data Structures

• struct DISASM RESULT

Enumerations

```
• enum X86OPS { ,
 OP AAA, OP_AAD, OP_AAM, OP_AAS,
 OP ADD, OP ADC, OP AND, OP ARPL,
 OP_BOUND, OP_BSF, OP_BSR, OP_BSWAP,
 OP BT, OP BTC, OP BTR, OP BTS,
 OP_CALL, OP_CDQ, OP_CWDE, OP_CBW,
 OP CLC, OP CLD, OP CLI, OP CLTS,
 OP CMC, OP CMOVO, OP CMOVNO, OP CMOVC,
 OP_CMOVNC, OP_CMOVZ, OP_CMOVNZ, OP CMOVBE,
 OP_CMOVA, OP_CMOVS, OP_CMOVNS, OP_CMOVP,
 OP_CMOVNP, OP_CMOVL, OP_CMOVGE, OP_CMOVLE,
 OP_CMOVG, OP_CMP, OP_CMPSD, OP_CMPSW,
 OP CMPSB, OP_CMPXCHG, OP_CMPXCHG8B, OP_CPUID,
 OP DAA, OP DAS, OP DEC, OP DIV,
 OP_ENTER, OP_FWAIT, OP_HLT, OP_IDIV,
 OP_IMUL, OP_INC, OP_IN, OP_INSD,
 OP_INSW, OP_INSB, OP_INT, OP_INT3,
 OP INTO, OP INVD, OP INVLPG, OP IRET,
 OP_JO, OP_JNO, OP_JC, OP_JNC,
 OP_JZ, OP_JNZ, OP_JBE, OP_JA,
 OP_JS, OP_JNS, OP_JP, OP_JNP,
 OP_JL, OP_JGE, OP_JLE, OP_JG,
 OP_JMP, OP_LAHF, OP_LAR, OP_LDS,
 OP LES, OP LFS, OP LGS, OP LEA,
 OP LEAVE, OP LGDT, OP LIDT, OP LLDT,
 OP_PREFIX_LOCK, OP_LODSD, OP_LODSW, OP_LODSB,
 OP_LOOP, OP_LOOPE, OP_LOOPNE, OP_JECXZ,
 OP_LSL, OP_LSS, OP_LTR, OP_MOV,
 OP_MOVSD, OP_MOVSW, OP_MOVSB, OP_MOVSX,
```

- OP MOVZX, OP MUL, OP NEG, OP NOP,
- OP NOT, OP OR, OP OUT, OP OUTSD,
- OP OUTSW, OP OUTSB, OP PUSH, OP PUSHAD,
- OP_PUSHFD, OP_POP, OP_POPAD, OP_POPFD,
- OP_RCL, OP_RCR, OP_RDMSR, OP_RDPMC,
- OP_RDTSC, OP_PREFIX_REPE, OP_PREFIX_REPNE, OP_RETF,
- OP_RETN, OP_ROL, OP_ROR, OP_RSM,
- OP_SAHF, OP_SAR, OP_SBB, OP_SCASD,
- OP_SCASW, OP_SCASB, OP_SETO, OP_SETNO,
- OP_SETC, OP_SETNC, OP_SETZ, OP_SETNZ,
- OP_SETBE, OP_SETA, OP_SETS, OP_SETNS,
- OP_SETP, OP_SETNP, OP_SETL, OP_SETGE,
- OP SETLE, OP SETG, OP SGDT, OP SIDT,
- OP SHL, OP SHLD, OP SHR, OP SHRD,
- OP_SLDT, OP_STOSD, OP_STOSW, OP_STOSB,
- OP_STR, OP_STC, OP_STD, OP_STI,
- OP SUB, OP SYSCALL, OP SYSENTER, OP SYSEXIT,
- OP SYSRET, OP TEST, OP UD2, OP VERR,
- OP VERRW, OP WBINVD, OP WRMSR, OP XADD,
- OP_XCHG, OP_XLAT, OP_XOR, OP_FPU,
- OP_F2XM1, OP_FABS, OP_FADD, OP_FADDP,
- OP_FBLD, OP_FBSTP, OP_FCHS, OP_FCLEX,
- OP_FCMOVB, OP_FCMOVBE, OP_FCMOVE, OP_FCMOVNB,
- OP_FCMOVNBE, OP_FCMOVNE, OP_FCMOVNU, OP_FCMOVU,
- OP FCOM, OP FCOMI, OP FCOMIP, OP FCOMP,
- OP_FCOMPP, OP_FCOS, OP_FDECSTP, OP_FDIV,
- OP_FDIVP, OP_FDIVR, OP_FDIVRP, OP_FFREE,
- OP_FIADD, OP_FICOM, OP_FICOMP, OP_FIDIV,
- OP FIDIVR, OP FILD, OP FIMUL, OP FINCSTP,

```
OP_FINIT, OP_FIST, OP_FISTP, OP_FISTTP,
    OP FISUB, OP FISUBR, OP FLD, OP FLD1,
    OP FLDCW, OP FLDENV, OP FLDL2E, OP FLDL2T,
    OP_FLDLG2, OP_FLDLN2, OP_FLDPI, OP_FLDZ,
    OP_FMUL, OP_FMULP, OP_FNOP, OP_FPATAN,
    OP_FPREM, OP_FPREM1, OP_FPTAN, OP_FRNDINT,
    OP_FRSTOR, OP_FSCALE, OP_FSINCOS, OP_FSQRT,
    OP_FSAVE, OP_FST, OP_FSTCW, OP_FSTENV,
    OP_FSTP, OP_FSTSW, OP_FSUB, OP_FSUBP,
    OP FSUBR, OP FSUBRP, OP FTST, OP FUCOM,
    OP FUCOMI, OP FUCOMIP, OP FUCOMP, OP FUCOMPP,
    OP_FXAM, OP_FXCH, OP_FXTRACT, OP_FYL2X,
    OP FYL2XP1 }
  • enum DIS_ACCESS {
    ACCESS NOARG, ACCESS IMM, ACCESS REL, ACCESS REG,
    ACCESS MEM }
  • enum DIS_SIZE {
    SIZEB, SIZEW, SIZED, SIZEF,
    SIZEQ, SIZET, SIZEPTR }
  • enum X86REGS
7.3.2.1. Detailed Description
7.3.2.2. Enumeration Type Documentation
```

7.3.2.2.1. enum DIS ACCESS

Access type

Enumerator:

```
ACCESS_NOARG arg not present
ACCESS IMM immediate
ACCESS\_REL +/- immediate
ACCESS REG register
ACCESS MEM [memory]
```

7.3.2.2.2. enum DIS SIZE for mem access, immediate and relative

Enumerator:

SIZEB Byte size access

SIZEW Word size access

SIZED Doubleword size access

SIZEF 6-byte access (seg+reg pair)

SIZEQ Quadword access

SIZET 10-byte access

SIZEPTR ptr

7.3.2.2.3. enum X86OPS

X86 opcode

Enumerator:

OP_AAA Ascii Adjust after Addition

OP_AAD Ascii Adjust AX before Division

OP_AAM Ascii Adjust AX after Multiply

 OP_AAS Ascii Adjust AL after Subtraction

OP ADD Add

OP_ADC Add with Carry

OP AND Logical And

OP_ARPL Adjust Requested Privilege Level

OP_BOUND Check Array Index Against Bounds

OP BSF Bit Scan Forward

OP BSR Bit Scan Reverse

OP BSWAP Byte Swap

 OP_BT Bit Test

 OP_BTC Bit Test and Complement

OP BTR Bit Test and Reset

OP BTS Bit Test and Set

OP CALL Call

OP_CDQ Convert DoubleWord to QuadWord

OP_CWDE Convert Word to DoubleWord

- **OP_CBW** Convert Byte to Word
- OP CLC Clear Carry Flag
- OP_CLD Clear Direction Flag
- *OP_CLI* Clear Interrupt Flag
- OP CLTS Clear Task-Switched Flag in CR0
- OP_CMC Complement Carry Flag
- **OP_CMOVO** Conditional Move if Overflow
- OP CMOVNO Conditional Move if Not Overflow
- **OP_CMOVC** Conditional Move if Carry
- **OP CMOVNC** Conditional Move if Not Carry
- **OP CMOVZ** Conditional Move if Zero
- OP CMOVNZ Conditional Move if Non-Zero
- **OP CMOVBE** Conditional Move if Below or Equal
- OP CMOVA Conditional Move if Above
- OP CMOVS Conditional Move if Sign
- OP_CMOVNS Conditional Move if Not Sign
- **OP_CMOVP** Conditional Move if Parity
- **OP CMOVNP** Conditional Move if Not Parity
- OP CMOVL Conditional Move if Less
- **OP_CMOVGE** Conditional Move if Greater or Equal
- **OP CMOVLE** Conditional Move if Less than or Equal
- **OP CMOVG** Conditional Move if Greater
- **OP_CMP** Compare
- OP_CMPSD Compare String DoubleWord
- **OP_CMPSW** Compare String Word
- *OP_CMPSB* Compare String Byte
- **OP CMPXCHG** Compare and Exchange
- *OP CMPXCHG8B* Compare and Exchange Bytes
- *OP_CPUID* CPU Identification
- **OP DAA** Decimal Adjust AL after Addition
- **OP_DAS** Decimal Adjust AL after Subtraction

- OP_DEC Decrement by 1
- **OP DIV** Unsigned Divide
- **OP_ENTER** Make Stack Frame for Procedure Parameters
- **OP FWAIT** Wait
- **OP_HLT** Halt
- OP_IDIV Signed Divide
- **OP_IMUL** Signed Multiply
- OP_INC Increment by 1
- **OP_IN** INput from port
- OP_INSD INput from port to String Doubleword
- OP_INSW INput from port to String Word
- OP_INSB INput from port to String Byte
- **OP_INT** INTerrupt
- *OP_INT3* INTerrupt 3 (breakpoint)
- **OP INTO** INTerrupt 4 if Overflow
- **OP_INVD** Invalidate Internal Caches
- OP_INVLPG Invalidate TLB Entry
- **OP IRET** Interrupt Return
- OP_JO Jump if Overflow
- **OP_JNO** Jump if Not Overflow
- **OP_JC** Jump if Carry
- *OP_JNC* Jump if Not Carry
- OP_JZ Jump if Zero
- OP_JNZ Jump if Not Zero
- **OP_JBE** Jump if Below or Equal
- OP_JA Jump if Above
- **OP JS** Jump if Sign
- OP_JNS Jump if Not Sign
- **OP_JP** Jump if Parity
- **OP_JNP** Jump if Not Parity
- OP_JL Jump if Less

- **OP_JGE** Jump if Greater or Equal
- OP JLE Jump if Less or Equal
- OP_JG Jump if Greater
- **OP_JMP** Jump (unconditional)
- OP_LAHF Load Status Flags into AH Register
- **OP_LAR** load Access Rights Byte
- *OP_LDS* Load Far Pointer into DS
- OP LES Load Far Pointer into ES
- **OP_LFS** Load Far Pointer into FS
- **OP** LGS Load Far Pointer into GS
- OP LEA Load Effective Address
- OP $_LEAVE$ High Level Procedure Exit
- OP_LGDT Load Global Descript Table Register
- **OP_LIDT** Load Interrupt Descriptor Table Register
- **OP_LLDT** Load Local Descriptor Table Register
- OP_PREFIX_LOCK Assert LOCK# Signal Prefix
- OP_LODSD Load String Dword
- OP LODSW Load String Word
- **OP_LODSB** Load String Byte
- **OP_LOOP** Loop According to ECX Counter
- *OP_LOOPE* Loop According to ECX Counter and ZF=1
- **OP_LOOPNE** Looop According to ECX Counter and ZF=0
- OP_JECXZ Jump if ECX is Zero
- OP_LSL Load Segment Limit
- **OP_LSS** Load Far Pointer into SS
- *OP_LTR* Load Task Register
- $OP \quad MOV \quad Move$
- **OP MOVSD** Move Data from String to String Doubleword
- **OP_MOVSW** Move Data from String to String Word
- **OP_MOVSB** Move Data from String to String Byte
- **OP_MOVSX** Move with Sign-Extension

- **OP_MOVZX** Move with Zero-Extension
- **OP_MUL** Unsigned Multiply
- **OP NEG** Two's Complement Negation
- **OP_NOP** No Operation
- **OP_NOT** One's Complement Negation
- OP_OR Logical Inclusive OR
- **OP OUT** Output to Port
- *OP_OUTSD* Output String to Port Doubleword
- OP_OUTSW Output String to Port Word
- *OP_OUTSB* Output String to Port Bytes
- **OP_PUSH** Push Onto the Stack
- OP_PUSHAD Push All Double General Purpose Registers
- OP_PUSHFD Push EFLAGS Register onto the Stack
- **OP_POP** Pop a Value from the Stack
- OP_POPAD Pop All Double General Purpose Registers from the Stack
- *OP_POPFD* Pop Stack into EFLAGS Register
- OP RCL Rotate Carry Left
- OP_RCR Rotate Carry Right
- *OP_RDMSR* Read from Model Specific Register
- *OP_RDPMC* Read Performance Monitoring Counters
- *OP_RDTSC* Read Time-Stamp Coutner
- OP_PREFIX_REPE Repeat String Operation Prefix while Equal
- OP_PREFIX_REPNE Repeat String Operation Prefix while Not Equal
- **OP RETF** Return from Far Procedure
- **OP RETN** Return from Near Procedure
- **OP_ROL** Rotate Left
- **OP_ROR** Rotate Right
- **OP_RSM** Resumse from System Management Mode
- **OP_SAHF** Store AH into Flags

- OP_SAR Shift Arithmetic Right
- OP SBB Subtract with Borrow
- OP_SCASD Scan String Doubleword
- OP_SCASW Scan String Word
- OP_SCASB Scan String Byte
- **OP_SETO** Set Byte on Overflow
- **OP_SETNO** Set Byte on Not Overflow
- **OP_SETC** Set Byte on Carry
- *OP_SETNC* Set Byte on Not Carry
- OP_SETZ Set Byte on Zero
- **OP_SETNZ** Set Byte on Not Zero
- OP_SETBE Set Byte on Below or Equal
- **OP_SETA** Set Byte on Above
- **OP_SETS** Set Byte on Sign
- OP SETNS Set Byte on Not Sign
- **OP_SETP** Set Byte on Parity
- **OP_SETNP** Set Byte on Not Parity
- **OP_SETL** Set Byte on Less
- **OP_SETGE** Set Byte on Greater or Equal
- **OP_SETLE** Set Byte on Less or Equal
- **OP_SETG** Set Byte on Greater
- *OP_SGDT* Store Global Descriptor Table Register
- *OP_SIDT* Store Interrupt Descriptor Table Register
- OP SHL Shift Left
- **OP_SHLD** Double Precision Shift Left
- *OP_SHR* Shift Right
- *OP_SHRD* Double Precision Shift Right
- OP SLDT Store Local Descriptor Table Register
- **OP_STOSD** Store String Doubleword
- OP STOSW Store String Word
- *OP_STOSB* Store String Byte

- *OP_STR* Store Task Register
- OP STC Set Carry Flag
- **OP_STD** Set Direction Flag
- *OP_STI* Set Interrupt Flag
- OP SUB Subtract
- OP SYSCALL Fast System Call
- OP_SYSENTER Fast System Call
- OP_SYSEXIT Fast Return from Fast System Call
- OP_SYSRET Return from Fast System Call
- **OP_TEST** Logical Compare
- OP UD2 Undefined Instruction
- **OP_VERR** Verify a Segment for Reading
- **OP_VERRW** Verify a Segment for Writing
- OP WBINVD Write Back and Invalidate Cache
- *OP_WRMSR* Write to Model Specific Register
- **OP_XADD** Exchange and Add
- OP_XCHG Exchange Register/Memory with Register
- **OP XLAT** Table Look-up Translation
- **OP_XOR** Logical Exclusive OR
- OP FPU FPU operation
- **OP F2XM1** Compute 2x-1
- **OP FABS** Absolute Value
- OP_FADD Floating Point Add
- **OP_FADDP** Floating Point Add, Pop
- OP_FBLD Load Binary Coded Decimal
- **OP_FBSTP** Store BCD Integer and Pop
- *OP FCHS* Change Sign
- **OP FCLEX** Clear Exceptions
- *OP_FCMOVB* Floating Point Move on Below
- **OP FCMOVBE** Floating Point Move on Below or Equal
- **OP_FCMOVE** Floating Point Move on Equal

- *OP_FCMOVNB* Floating Point Move on Not Below
- OP FCMOVNBE Floating Point Move on Not Below or Equal
- OP_FCMOVNE Floating Point Move on Not Equal
- *OP_FCMOVNU* Floating Point Move on Not Unordered
- OP FCMOVU Floating Point Move on Unordered
- **OP_FCOM** Compare Floating Pointer Values and Set FPU Flags
- OP_FCOMI Compare Floating Pointer Values and Set EFLAGS
- OP_FCOMIP Compare Floating Pointer Values and Set EFLAGS, Pop
- OP_FCOMP Compare Floating Pointer Values and Set FPU Flags, Pop
- **OP_FCOMPP** Compare Floating Pointer Values and Set FPU Flags, Pop Twice
- OP_FCOS Cosine
- *OP_FDECSTP* Decrement Stack Top Pointer
- **OP_FDIV** Floating Point Divide
- **OP FDIVP** Floating Point Divide, Pop
- **OP_FDIVR** Floating Point Reverse Divide
- **OP_FDIVRP** Floating Point Reverse Divide, Pop
- OP FFREE Free Floating Point Register
- **OP FIADD** Floating Point Add
- **OP_FICOM** Compare Integer
- *OP_FICOMP* Compare Integer, Pop
- **OP FIDIV** Floating Point Divide by Integer
- *OP_FIDIVR* Floating Point Reverse Divide by Integer
- **OP_FILD** Load Integer
- **OP_FIMUL** Floating Point Multiply with Integer
- **OP FINCSTP** Increment Stack-Top Pointer
- OP FINIT Initialize Floating-Point Unit
- **OP_FIST** Store Integer
- **OP_FISTP** Store Integer, Pop
- OP_FISTTP Store Integer with Truncation

- *OP_FISUB* Floating Point Integer Subtract
- OP_FISUBR Floating Point Reverse Integer Subtract
- **OP_FLD** Load Floating Point Value
- *OP_FLD1* Load Constant 1
- OP FLDCW Load x87 FPU Control Word
- OP FLDENV Load x87 FPU Environment
- **OP_FLDL2E** Load Constant log_2(e)
- OP_FLDL2T Load Constant log_2(10)
- OP_FLDLG2 Load Constant log_10(2)
- *OP FLDLN2* Load Constant log e(2)
- OP FLDPI Load Constant PI
- OP_FLDZ Load Constant Zero
- *OP_FMUL* Floating Point Multiply
- **OP_FMULP** Floating Point Multiply, Pop
- OP_FNOP No Operation
- **OP_FPATAN** Partial Arctangent
- *OP_FPREM* Partial Remainder
- OP FPREM1 Partial Remainder
- **OP_FPTAN** Partial Tangent
- **OP_FRNDINT** Round to Integer
- *OP FRSTOR* Restore x86 FPU State
- OP FSCALE Scale
- **OP FSINCOS** Sine and Cosine
- **OP_FSQRT** Square Root
- *OP_FSAVE* Store x87 FPU State
- **OP_FST** Store Floating Point Value
- OP FSTCW Store x87 FPU Control Word
- OP FSTENV Store x87 FPU Environment
- *OP_FSTP* Store Floating Point Value, Pop
- OP FSTSW Store x87 FPU Status Word
- OP_FSUB Floating Point Subtract

OP FSUBP Floating Point Subtract, Pop

OP FSUBR Floating Point Reverse Subtract

OP FSUBRP Floating Point Reverse Subtract, Pop

OP_FTST Floating Point Test

OP_FUCOM Floating Point Unordered Compare

OP_FUCOMI Floating Point Unordered Compare with Integer

OP_FUCOMIP Floating Point Unorder Compare with Integer, Pop

OP_FUCOMP Floating Point Unorder Compare, Pop

OP_FUCOMPP Floating Point Unorder Compare, Pop Twice

 OP_FXAM Examine ModR/M

OP_FXCH Exchange Register Contents

OP_FXTRACT Extract Exponent and Significand

 OP_FYL2X Compute y*log2x

 $OP_FYL2XP1$ Compute y*log2(x+1)

7.3.2.2.4. enum X86REGS

X86 registers

7.3.3. bytecode_execs.h File Reference

Data Structures

- struct cli exe section
- struct cli_exe_info

7.3.3.1. Detailed Description

7.3.4. bytecode pe.h File Reference

Data Structures

- struct pe_image_file_hdr
- struct pe_image_data_dir
- struct pe_image_optional_hdr32
- struct pe_image_optional_hdr64
- struct pe_image_section_hdr
- struct cli_pe_hook_data

7.3.4.1. Detailed Description

7.4. High level API

7.4.1. bytecode local.h File Reference

Data Structures

- struct DIS_mem_arg
- struct DIS_arg
- struct DIS fixed

Defines

- #define VIRUSNAME_PREFIX(name) const char ___clambc_virusname_prefix[] = name;
- #define VIRUSNAMES(...) const char *const ___clambc_virusnames[] = {___VA_ARGS___};
- #define PE_UNPACKER_DECLARE const uint16_t __clambc_kind = BC_PE_UNPACKER;
- #define PDF_HOOK_DECLARE const uint16_t __clambc_kind = BC_PDF;
- #define SIGNATURES_DECL_BEGIN struct ___Signatures {
- #define DECLARE_SIGNATURE(name)
- #define SIGNATURES_DECL_END };
- #define TARGET(tgt) const unsigned short ___Target = (tgt);
- #define COPYRIGHT(c) const char *const ___Copyright = (c);
- #define ICONGROUP1(group) const char *const ___IconGroup1 = (group);
- #define ICONGROUP2(group) const char *const ___IconGroup2 = (group);
- #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short
 __FuncMin = (m);
- #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short
 __FuncMax = (m);
- #define SIGNATURES DEF BEGIN
- #define DEFINE_SIGNATURE(name, hex)
- #define SIGNATURES_END \};\

7.4. High level API

Functions

- static force_inline uint32_t count_match (___Signature sig)
- static force_inline uint32_t matches (___Signature sig)
- static force_inline uint32_t match_location (___Signature sig, uint32_t goback)
- static force_inline int32_t match_location_check (___Signature sig, uint32_t goback, const char *static_start, uint32_t static_len)
- static force inline overloadable void foundVirus (const char *virusname)
- static force_inline uint32_t getFilesize (void)
- bool <u>__is_bigendian</u> (void) <u>__attribute__</u>((const)) <u>__attribute__</u>- ((nothrow))
- static uint32_t force_inline le32_to_host (uint32_t v)
- static uint64_t force_inline le64_to_host (uint64_t v)
- static uint16_t force_inline le16_to_host (uint16_t v)
- static uint32_t force_inline cli_readint32 (const void *buff)
- static uint16_t force_inline cli_readint16 (const void *buff)
- static void force_inline cli_writeint32 (void *offset, uint32_t v)
- static force_inline bool hasExeInfo (void)
- static force_inline bool isPE64 (void)
- static static force_inline force_inline uint8_t getPEMajorLinkerVersion (void)
- static force inline uint8 t getPEMinorLinkerVersion (void)
- static force inline uint32 t getPESizeOfCode (void)
- static force inline uint32 t getPESizeOfInitializedData (void)
- static force_inline uint32_t getPESizeOfUninitializedData (void)
- static force_inline uint32_t getPEBaseOfCode (void)
- static force_inline uint32_t getPEBaseOfData (void)
- static force inline uint64 t getPEImageBase (void)
- static force inline uint32 t getPESectionAlignment (void)
- static force inline uint32 t getPEFileAlignment (void)
- static force_inline uint16_t getPEMajorOperatingSystemVersion (void)
- static force inline uint16 t getPEMinorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMajorImageVersion (void)
- static force_inline uint16_t getPEMinorImageVersion (void)
- static force_inline uint16_t getPEMajorSubsystemVersion (void)
- static force_inline uint16_t getPEMinorSubsystemVersion (void)

- static force_inline uint32_t getPEWin32VersionValue (void)
- static force_inline uint32_t getPESizeOfImage (void)
- static force_inline uint32_t getPESizeOfHeaders (void)
- static force_inline uint32_t getPECheckSum (void)
- static force_inline uint16_t getPESubsystem (void)
- static force_inline uint16_t getPEDllCharacteristics (void)

Return the PE DllCharacteristics.

- static force inline uint32 t getPESizeOfStackReserve (void)
- static force_inline uint32_t getPESizeOfStackCommit (void)
- static force_inline uint32_t getPESizeOfHeapReserve (void)
- static force_inline uint32_t getPESizeOfHeapCommit (void)
- static force_inline uint32_t getPELoaderFlags (void)
- static force_inline uint16_t getPEMachine ()
- static force_inline uint32_t getPETimeDateStamp ()
- static force inline uint32 t getPEPointerToSymbolTable ()
- static force inline uint32 t getPENumberOfSymbols ()
- static force_inline uint16_t getPESizeOfOptionalHeader ()
- static force_inline uint16_t getPECharacteristics ()
- static force_inline bool getPEisDLL ()
- static force inline uint32 t getPEDataDirRVA (unsigned n)
- static force_inline uint32_t getPEDataDirSize (unsigned n)
- static force inline uint16 t getNumberOfSections (void)
- static uint32 t getPELFANew (void)
- static force_inline int readPESectionName (unsigned char name[8], unsigned n)
- static force_inline uint32_t getEntryPoint (void)
- static force inline uint32 t getExeOffset (void)
- static force_inline uint32_t getImageBase (void)
- static uint32 t getVirtualEntryPoint (void)
- static uint32 t getSectionRVA (unsigned i)
- static uint32 t getSectionVirtualSize (unsigned i)
- static force_inline bool readRVA (uint32_t rva, void *buf, size_t buf-size)
- static void * memchr (const void *s, int c, size_t n)
- void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow))
 _attribute__((__nonnull__((1))))

- void * memmove (void *dst, const void *src, uintptr_t n) __attribute_-_((__nothrow__)) __attribute__((__nonnull___(1
- void *void * memcpy (void *restrict dst, const void *restrict src, uintptr_t n) __attribute__((__nothrow___)) __attribute__((_-nonnull___(1
- void *void *int memcmp (const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow__)) __attribute__((__pure__)) __attribute__((__nonnull__(1
- static force_inline uint32_t DisassembleAt (struct DIS_fixed *result, uint32_t offset, uint32_t len)
- static int32_t ilog2_compat (uint32_t a, uint32_t b)

Variables

void *void *int struct DIS_mem_arg __attribute__

7.4.1.1. Detailed Description

7.4.1.2. Define Documentation

7.4.1.2.1. #define COPYRIGHT(c) const char *const ____-Copyright = (c); Defines an alternative copyright for this bytecode.

config

This will also prevent the sourcecode from being embedded into the bytecode

7.4.1.2.2. #define DECLARE_SIGNATURE(name) Value:

```
const char *name##_sig;\
    __Signature name;
```

Declares a name for a subsignature.

config

7.4.1.2.3. #define DEFINE_SIGNATURE(name, hex) Value:

```
.name##_sig = (hex),\
    .name = {__COUNTER__ - __signature_bias},
```

Defines the pattern for a previously declared subsignature.

See also

DECLARE_SIGNATURE

config

Parameters

name the name of a previously declared subsignaturehex the pattern for this subsignature

7.4.1.2.4. #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short ___FuncMax = (m); Define the maximum engine functionality level required for this bytecode/logical signature. Engines newer than this will skip loading the bytecode. You can use the 'enum FunctionalityLevels' constants here.

7.4.1.2.5. #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short ___FuncMin = (m); Define the minimum engine functionality level required for this bytecode/logical signature. Engines older than this will skip loading the bytecode. You can

config

7.4.1.2.6. #define ICONGROUP1(group) const char *const __-_IconGroup1 = (group); Define IconGroup1 for logical signature.

See logical signature documentation for what it is

use the 'enum FunctionalityLevels' constants here.

config

7.4.1.2.7. #define ICONGROUP2(group) const char *const ___IconGroup2 = (group); Define IconGroup2 for logical signature. See logical signature documentation for what it is.

config

7.4.1.2.8. #define PDF_HOOK_DECLARE const uint16_t ___-clambc_kind = BC_PDF; Make the current bytecode a PDF hook. Having a logical signature doesn't make sense here, since logical signature is evaluated AFTER these hooks run.

config

This hook is called several times, use pdf_get_phase() to find out in which phase you got called.

config

7.4.1.2.10. #define SIGNATURES_DECL_BEGIN struct ___-Signatures { Marks the beginning of the subsignature name declaration section.

config

7.4.1.2.11. #define SIGNATURES_DECL_END }; Marks the end of the subsignature name declaration section.

config

7.4.1.2.12. #define SIGNATURES_DEF_BEGIN

Value:

```
static const unsigned __signature_bias = __COUNTER__+1;\
const struct __Signatures Signatures = {\
```

Marks the beginning of subsignature pattern definitions.

config

See also

SIGNATURES_DECL_BEGIN

7.4.1.2.13. #define SIGNATURES_END \};\ Marks the end of the subsignature pattern definitions.

config

7.4.1.2.14. #define TARGET(
$$tgt$$
) const unsigned short _____ Target = (tgt); Defines the ClamAV file target.

config

Parameters

tgt ClamAV signature type (0 - raw, 1 - PE, etc.)

7.4.1.2.15. #define VIRUSNAME_PREFIX(name) const char __clambc_virusname_prefix[] = name; Declares the virusname prefix.

config

Parameters

name the prefix common to all viruses reported by this bytecode

7.4.1.2.16. #define VIRUSNAMES(...) const char *const ___clambc_virusnames[] = {___VA_ARGS___}; Declares all the virusnames that this bytecode can report.

Parameters

... a comma-separated list of strings interpreted as virusnames

7.4.1.3. Function Documentation

7.4.1.3.1. bool ___is_bigendian (void) const Returns true if the bytecode is executing on a big-endian CPU.

Returns

true if executing on bigendian CPU, false otherwise

Environment

This will be optimized away in libclamav, but it must be used when dealing with endianess for portability reasons. For example whenever you read a 32-bit integer from a file, it can be written in little-endian convention (x86 CPU for example), or big-endian convention (PowerPC CPU for example). If the file always contains little-endian integers, then conversion might be needed. ClamAV bytecodes by their nature must only handle known-endian integers, if endianness can change, then both situations must be taken into account (based on a 1-byte field for example).

7.4.1.3.2. static uint16_t force_inline cli_readint16 (const void * buff) [static] Reads from the specified buffer a 16-bit of little-endian integer.

Data structure

Parameters

[in] **buff** pointer to buffer

Returns

16-bit little-endian integer converted to host endianness

7.4.1.3.3. static uint32_t force_inline cli_readint32 (const void * buff) [static] Reads from the specified buffer a 32-bit of little-endian integer.

Data structure

Parameters

[in] **buff** pointer to buffer

Returns

32-bit little-endian integer converted to host endianness

7.4.1.3.4. static void force_inline cli_writeint32 (void * offset, uint32_t v) [static] Writes the specified value into the specified buffer in little-endian order

Data structure

Parameters

[out] offset pointer to buffer to write to [in] v value to write

7.4.1.3.5. static force_inline uint32_t count_match (___-Signature sig) [static] Returns how many times the specified signature matched.

Parameters

sig name of subsignature queried

Returns

number of times this subsignature matched in the entire file

Engine query

This is a constant-time operation, the counts for all subsignatures are already computed.

7.4.1.3.6. static force_inline uint32_t DisassembleAt (struct DIS_fixed * result, uint32_t offset, uint32_t len) [static] Disassembles one X86 instruction starting at the specified offset.

Disassemble

Parameters

[out] result disassembly result

[in] offset start disassembling from this offset, in the current file

[in] *len* max amount of bytes to disassemble

Returns

offset where disassembly ended

7.4.1.3.7. static force_inline overloadable void foundVirus (const char * virusname) [static] Sets the specified virusname as the virus detected by this bytecode.

Scan

Parameters

virusname the name of the virus, excluding the prefix, must be one of the virusnames declared in VIRUSNAMES.

See also

VIRUSNAMES

7.4.1.3.8. static force_inline uint32_t getEntryPoint (void) [static] Returns the offset of the EntryPoint in the executable file.

\mathbf{PE}

Returns

offset of EP as 32-bit unsigned integer

7.4.1.3.9. static force_inline uint32_t getExeOffset (void) [static] Returns the offset of the executable in the file.

PE

Returns

offset of embedded executable inside file.

7.4.1.3.10. static force_inline uint32_t getFilesize (void) [static] Returns the currently scanned file's size.

File operation

Returns

file size as 32-bit unsigned integer

7.4.1.3.11. static force_inline uint32_t getImageBase (void) [static] Returns the ImageBase with the correct endian conversion. Only works if the bytecode is a PE hook (i.e. you invoked PE_UNPACKER_DECLARE)

 \mathbf{PE}

Returns

ImageBase of PE file, 0 - for non-PE hook

7.4.1.3.12. static force_inline uint16_t getNumberOfSections (void) [static] Returns the number of sections in this executable file.

 \mathbf{PE}

Returns

number of sections as 16-bit unsigned integer

7.4.1.3.13. static force_inline uint32_t getPEBaseOfCode (void) [static] Return the PE BaseOfCode.

 \mathbf{PE}

Returns

PE BaseOfCode, or 0 if not in PE hook.

7.4.1.3.14. static force_inline uint32_t getPEBaseOfData (void) [static] Return the PE BaseOfData.

 \mathbf{PE}

Returns

PE BaseOfData, or 0 if not in PE hook.

7.4.1.3.15. static force_inline uint16_t getPECharacteristics () [static] Returns PE characteristics. For example you can use this to check whether it is a DLL (0x2000).

 \mathbf{PE}

Returns

characteristic of PE file, or 0 if not in PE hook

7.4.1.3.16. static force_inline uint32_t getPECheckSum (void) [static] Return the PE CheckSum.

 \mathbf{PE}

Returns

PE CheckSum, or 0 if not in PE hook

7.4.1.3.17. static force_inline uint32_t getPEDataDirRVA (unsigned n) [static] Gets the virtual address of specified image data directory.

PE

Parameters

n image directory requested

Returns

Virtual Address of requested image directory

7.4.1.3.18. static force_inline uint32_t getPEDataDirSize (unsigned n) [static] Gets the size of the specified image data directory.

PE

Parameters

n image directory requested

Returns

Size of requested image directory

7.4.1.3.19. static force_inline uint 16_t getPEDllCharacteristics (void) [static]

Return the PE DllCharacteristics.

 \mathbf{PE}

Returns

PE DllCharacteristics, or 0 if not in PE hook

7.4.1.3.20. static force_inline uint32_t getPEFileAlignment (void) [static] Return the PE FileAlignment.

PE

Returns

PE FileAlignment, or 0 if not in PE hook

7.4.1.3.21. static force_inline uint64_t getPEImageBase (void) [static] Return the PE ImageBase as 64-bit integer.

PE

Returns

PE ImageBase as 64-bit int, or 0 if not in PE hook

7.4.1.3.22. static force_inline bool getPEisDLL () [static] Returns whether this is a DLL. Use this only in a PE hook!

PE

Returns

true - the file is a DLL false - file is not a DLL

7.4.1.3.23. static uint32_t getPELFANew (void) [static] Gets the offset to the PE header.

PE

Returns

offset to the PE header, or 0 if not in PE hook

7.4.1.3.24. static force_inline uint32_t getPELoaderFlags (void) [static] Return the PE LoaderFlags.

PE

Returns

PE LoaderFlags or 0 if not in PE hook

7.4.1.3.25. static force_inline uint16_t getPEMachine () [static] Returns the CPU this executable runs on, see libclamav/pe.c for possible values.

PE

Returns

PE Machine or 0 if not in PE hook

 $\begin{array}{lll} \textbf{7.4.1.3.26.} & \textbf{static force_inline uint16_t getPEMajorImageVersion} \\ \textbf{(void) [static]} & \textbf{Return the PE MajorImageVersion}. \end{array}$

PE

Returns

PE MajorImageVersion, or 0 if not in PE hook

7.4.1.3.27. static static force__inline force__inline uint8__t getPEMa-jorLinkerVersion (void) [static] Returns MajorLinkerVersion for this PE file.

 \mathbf{PE}

Returns

PE MajorLinkerVersion or 0 if not in PE hook

7.4.1.3.28. static force_inline uint16_t getPEMajorOperatingSystemVersion (void) [static] Return the PE MajorOperatingSystemVersion.

 \mathbf{PE}

Returns

PE MajorOperatingSystemVersion, or 0 if not in PE hook

7.4.1.3.29. static force_inline uint 16_t getPEMajorSubsystemVersion (void) [static] Return the PE MajorSubsystem Version.

PE

Returns

PE MajorSubsystemVersion or 0 if not in PE hook

PE

Returns

PE MinorrImageVersion, or 0 if not in PE hook

7.4.1.3.31. static force_inline uint8_t getPEMinorLinkerVersion (void) [static] Returns MinorLinkerVersion for this PE file.

PE

Returns

PE MinorLinkerVersion or 0 if not in PE hook

7.4.1.3.32. static force_inline uint16_t getPEMinorOperatingSystemVersion (void) [static] Return the PE MinorOperatingSystemVersion.

 \mathbf{PE}

Returns

PE MinorOperatingSystemVersion, or 0 if not in PE hook

7.4.1.3.33. static force_inline uint16_t getPEMinorSubsystemVersion (void) [static] Return the PE MinorSubsystemVersion.

 \mathbf{PE}

Returns

PE MinorSubsystemVersion, or 0 if not in PE hook

```
7.4.1.3.34. static force_inline uint32_t getPENumberOfSymbols () [static] Returns the PE number of debug symbolsPE
```

Returns

PE NumberOfSymbols or 0 if not in PE hook

```
7.4.1.3.35. static force_inline uint32_t getPEPointerToSymbol-Table ( ) [static] Returns pointer to the PE debug symbol table

PE
```

Returns

PE PointerToSymbolTable or 0 if not in PE hook

```
7.4.1.3.36. static force_inline uint32_t getPESectionAlignment (void ) [static] Return the PE SectionAlignment.

PE
```

Returns

PE SectionAlignment, or 0 if not in PE hook

```
7.4.1.3.37. static force_inline uint32_t getPESizeOfCode ( void ) [static] Return the PE SizeOfCode.

PE
```

Returns

PE SizeOfCode or 0 if not in PE hook

```
7.4.1.3.38. static force_inline uint32_t getPESizeOfHeaders (void ) [static] Return the PE SizeOfHeaders.

PE
```

Returns

PE SizeOfHeaders, or 0 if not in PE hook

```
7.4.1.3.39. static force_inline uint32_t getPESizeOfHeapCommit ( void ) [static] Return the PE SizeOfHeapCommit.

PE
```

Returns

PE SizeOfHeapCommit, or 0 if not in PE hook

```
7.4.1.3.40. static force_inline uint32_t getPESizeOfHeapReserve (void ) [static] Return the PE SizeOfHeapReserve.

PE
```

Returns

PE SizeOfHeapReserve, or 0 if not in PE hook

```
7.4.1.3.41. static force_inline uint32_t getPESizeOfImage ( void ) [static] Return the PE SizeOfImage.

PE
```

Returns

PE SizeOfImage, or 0 if not in PE hook

```
7.4.1.3.42. static force_inline uint32_t getPESizeOfInitialized-Data ( void ) [static] Return the PE SizeofInitializedData.

PE
```

Returns

PE SizeOfInitializeData or 0 if not in PE hook

7.4.1.3.43. static force_inline uint16_t getPESizeOfOptional-Header () [static] Returns the size of PE optional header.

PE

Returns

size of PE optional header, or 0 if not in PE hook

7.4.1.3.44. static force_inline uint32_t getPESizeOfStackCommit (void) [static] Return the PE SizeOfStackCommit.

 \mathbf{PE}

Returns

PE SizeOfStackCommit, or 0 if not in PE hook

7.4.1.3.45. static force_inline uint32_t getPESizeOfStackReserve (void) [static] Return the PE SizeOfStackReserve.

Returns

PE

PE SizeOfStackReserver, or 0 if not in PE hook

7.4.1.3.46. static force_inline uint32_t getPESizeOfUninitialized-Data (void) [static] Return the PE SizeofUninitializedData.

 \mathbf{PE}

Returns

PE SizeofUninitializedData or 0 if not in PE hook

118 7.4. High level API 7.4.1.3.47. static force_inline uint16_t getPESubsystem (void) Return the PE Subsystem. [static] \mathbf{PE} Returns PE subsystem, or 0 if not in PE hook 7.4.1.3.48. static force_inline uint32_t getPETimeDateStamp (Returns the PE TimeDateStamp from headers [static] \mathbf{PE} Returns PE TimeDateStamp or 0 if not in PE hook 7.4.1.3.49. static force_inline uint32_t getPEWin32VersionValue (void) [static] Return the PE Win32VersionValue. \mathbf{PE} Returns PE Win32VersionValue, or 0 if not in PE hook 7.4.1.3.50. static uint32_t getSectionRVA (unsigned) Return the RVA of the specified section [static] \mathbf{PE} **Parameters** i section index (from 0) Returns RVA of section, or -1 if invalid

7.4.1.3.51. static uint32_t getSectionVirtualSize (unsigned i) [static] Return the virtual size of the specified section.

PE

Parameters

i section index (from 0)

Returns

VSZ of section, or -1 if invalid

7.4.1.3.52. static uint32_t getVirtualEntryPoint (void) [static] The address of the EntryPoint. Use this for matching EP against sections.

PE

Returns

virtual address of EntryPoint, or 0 if not in PE hook

7.4.1.3.53. static force_inline bool hasExeInfo (void) [static] Returns whether the current file has executable information.

PE

Returns

true if the file has exe info, false otherwise

7.4.1.3.54. static int32_t ilog2_compat (uint32_t a, uint32_t b) [inline, static] ilog2_compat for 0.96 compatibility, you should use ilog2() 0.96.1 API instead of this one!

7.4.1.3.55. static force_inline bool isPE64 (void) [static] Returns whether this is a PE32+ executable.

PE

Returns

true if this is a PE32+ executable

7.4.1.3.56. static uint16_t force_inline le16_to_host (uint16_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Data structure

Parameters

[in] v 16-bit integer as read from a file

Returns

integer converted to host's endianess

7.4.1.3.57. static uint32_t force_inline le32_to_host (uint32_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Data structure

Parameters

[in] v 32-bit integer as read from a file

Returns

integer converted to host's endianess

7.4.1.3.58. static uint64_t force_inline le64_to_host (uint64_t v) [static] Converts the specified value if needed, knowing it is in little endian order.

Data structure

Parameters

[in] v 64-bit integer as read from a file

Returns

integer converted to host's endianess

7.4.1.3.59. static force_inline uint32_t match_location (____-Signature sig, uint32_t goback) [static] Returns the offset of the match.

Engine query

Parameters

sig - Signaturegoback - max length of signature

Returns

offset of match

7.4.1.3.60. static force_inline int32_t match_location_check (_-Signature sig, uint32_t goback, const char * static_start, uint32_t static_len) [static] Like match_location(), but also checks that the match starts with the specified hex string.

Engine query

It is recommended to use this for safety and compatibility with 0.96.1

Parameters

sig - signature
 goback - maximum length of signature (till start of last subsig)
 static_start - static string that sig must begin with
 static_len - static string that sig must begin with - length

Returns

>=0 - offset of match -1 - no match

7.4.1.3.61. static force_inline uint32_t matches (___Signature sig) [static] Returns whether the specified subsignature has matched at least once.

Engine query

Parameters

sig name of subsignature queried

Returns

1 if subsignature one or more times, 0 otherwise

7.4.1.3.62. static void* memchr (const void * s, int c, size_t n) [static] Scan the first n bytes of the buffer s, for the character c.

String operation

Parameters

```
[in] s buffer to scan c character to look for n size of buffer
```

Returns

a pointer to the first byte to match, or NULL if not found.

```
7.4.1.3.63. void* void* int memcmp ( const void * s1, const void * s2, uint32_t n ) Compares two memory buffers.
```

String operation

Parameters

```
[in] s1 buffer one
[in] s2 buffer two
[in] n amount of bytes to copy
```

Returns

an integer less than, equal to, or greater than zero if the first n bytes of $\mathtt{s1}$ are found, respectively, to be less than, to match, or be greater than the first n bytes of $\mathtt{s2}$.

7.4.1.3.64. void* void* memcpy (void *restrict dst, const void *restrict src, uintptr_t n) Copies data between two non-overlapping buffers.

String operation

Parameters

[out] dst destination buffer

```
[in] src source buffer [in] n amount of bytes to copy
```

Returns

dst

7.4.1.3.65. void* memmove (void * dst, const void * src, uintptr_t n) Copies data between two possibly overlapping buffers.

String operation

Parameters

```
[out] dst destination buffer
[in] src source buffer
[in] n amount of bytes to copy
```

Returns

dst

7.4.1.3.66. void* memset (void * src, int c, uintptr_t n) Fills the specified buffer to the specified value.

String operation

Parameters

```
[out] src pointer to buffer [in] c character to fill buffer with [in] n length of buffer
```

Returns

src

7.4.1.3.67. static force_inline int readPESectionName (unsigned char name[8], unsigned n) [static] Read name of requested PE section.

PE

Parameters

[out] name name of PE section

[in] n PE section requested

Returns

0 if successful, <0 otherwise

7.4.1.3.68. static force_inline bool readRVA (uint32_t rva, void * buf, size_t bufsize) [static] read the specified amount of bytes from the PE file, starting at the address specified by RVA.

PE

Parameters

rva the Relative Virtual Address you want to read from (will be converted to file offset)

[out] buf destination buffer

bufsize size of buffer

Returns

true on success (full read), false on any failure

7.4.1.4. Variable Documentation

 $7.4.1.4.1. \ union \ unaligned_16 \ __attribute__ \qquad disassembled \\ memory \ operand: \ scale_reg*scale + add_reg + displacement$

Disassemble

CHAPTER 8 Copyright and License

8.1. The ClamAV Bytecode Compiler

The ClamAV Bytecode Compiler is released under the GNU General Public License version 2.

The following directories are under the GNU General Public License version 2: ClamBC, docs, driver, editor, examples, ifacegen.

Copyright (C) 2009 Sourcefire, Inc.

This program is free software; you can redistribute it and/or modify it under the terms of the GNU General Public License version 2 as published by the Free Software Foundation.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE. See the GNU General Public License for more details.

You should have received a copy of the GNU General Public License along with this program; if not, write to the Free Software Foundation, Inc., 51 Franklin Street, Fifth Floor, Boston, MA 02110-1301, USA.

It uses the LLVM compiler framework, contained in the following directories: llvm, clang. They have this copyright:

LLVM Release License

University of Illinois/NCSA Open Source License

Copyright (c) 2003-2009 University of Illinois at Urbana-Champaign. All rights reserved.

Developed by:

LLVM Team

University of Illinois at Urbana-Champaign

http://llvm.org

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal with the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

- * Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimers.
- * Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimers in the documentation and/or other materials provided with the distribution.
- * Neither the names of the LLVM Team, University of Illinois at Urbana-Champaign, nor the names of its contributors may be used to endorse or promote products derived from this Software without specific prior written permission.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE CONTRIBUTORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS WITH THE SOFTWARE.

Copyrights and Licenses for Third Party Software Distributed with LLVM:

The LLVM software contains code written by third parties. Such software will have its own individual LICENSE.TXT file in the directory in which it appears. This file will describe the copyrights, license, and restrictions which apply to that code.

The disclaimer of warranty in the University of Illinois Open Source License applies to all code in the LLVM Distribution, and nothing in any of the other licenses gives permission to use the names of the LLVM Team or the University of Illinois to endorse or promote products derived from this Software.

The following pieces of software have additional or alternate copyrights, licenses, and/or restrictions:

Program Directory
-----Autoconf Directory
-----1lvm/autoconf

llvm/projects/ModuleMaker/autoconf

llvm/projects/sample/autoconf

CellSPU backend llvm/lib/Target/CellSPU/README.txt
Google Test llvm/utils/unittest/googletest

It also uses re2c, contained in driver/clamdriver/re2c. This code is public domain:

Originally written by Peter Bumbulis (peter@csg.uwaterloo.ca)

Currently maintained by:

- * Dan Nuffer <nuffer@users.sourceforge.net>
- * Marcus Boerger <helly@users.sourceforge.net>
- * Hartmut Kaiser <hkaiser@users.sourceforge.net>

The re2c distribution can be found at:

http://sourceforge.net/projects/re2c/

re2c is distributed with no warranty whatever. The code is certain to contain errors. Neither the author nor any contributor takes responsibility for any consequences of its use.

re2c is in the public domain. The data structures and algorithms used in re2c are all either taken from documents available to the general public or are inventions of the author. Programs generated by re2c may be distributed freely. re2c itself may be distributed freely, in source or binary, unchanged or modified. Distributors may charge whatever fees they can obtain for re2c.

If you do make use of re2c, or incorporate it into a larger project an acknowledgement somewhere (documentation, research report, etc.) would be appreciated.

8.2. Bytecode

The headers used when compiling bytecode have these license (clang/lib/Headers/{bcfeatures,bytecode*}.h):

128 8.2. Bytecode

Copyright (C) 2009 Sourcefire, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE REGENTS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE REGENTS OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

The other header files in clang/lib/Headers/ are from clang with this license (see individual files for copyright owner):

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

When using the ClamAV bytecode compiler to compile your own bytecode programs, you can release it under the license of your choice, provided that you comply with the license of the above header files.

APPENDIX A Predefined macros

```
1 \ \# define \ \_\_llvm \_\_ 1
                                                                                                                                                     clang 1
GNUC MINOR 2
GNUC PATCHLEVEL
                                        #define
                   3 #define
                                          #define
#define GNUC_4
#define GXX_ABL_VERSION 1002
7 #define VERSION_ "4.2.1 Compatible Clang Compiler
#define STIDC_I
9 #define STIDC_I
9 #define STIDC_HOSTED_0
11 #define STIDC_HOSTED_0
12 #define STIDC_HOSTED_0
13 #define SCHAR_MAX_ 127
#define SHRT_MAX_ 32767
15 #define INT_MAX_ 2147483647
#define INT_MAX_ 2147483647
#define LONG_MAX_ 9223372036854775807L
#define LONG_MAX_ 9223372036854775807L
#define INT_MAX_MAX_ 9223372036854775807L
#define INT_MAX_TYPE_long_int
#define INT_MAX_TYPE_ long int
#define INT_MAX_WIDTH_ 64
23 #define PIRDIFF_WIDTH_ 32
25 #define INT_PR_WIDTH_ 32
26 #define SIZE_TYPE_ unsigned int
#define SIZE_WIDTH_ 32
3 #define WCHAR_WIDTH_ 32
4 #define WCHAR_WIDTH_ 32
4 #define WCHAR_WIDTH_ 32
4 #define WCHAR_WIDTH_ 32
4 #define FIT_DENORM_MIN_ 1.40129846e-45F
4 #define FIT_DENORM_MIN_ 1.40129846e-45F
4 #define FIT_HAS_DENORM_ 1
#define FIT_HAS_DENORM_ 1
#define FIT_HAS_DENORM_ 1
#define FIT_HAS_DENORM_ 1
#define FIT_MAX_ 10_EXP_ 38
#define FIT_MAX_ 10_EXP_ 38
#define FIT_MAX_ 10_EXP_ 38
#define FIT_MAX_ 3.40282347e+38F
#define DBL_HAS_DENORM_ 1
#define D
                   5 #define _
                                                                                                                                                     GNUC 4
GXX_ABI_VERSION 1002
                                          #define
                                                                                                                                                        VERSION___ "4.2.1 Compatible Clang Compiler"
```

```
2.2204460492503131e-16
         63 #define
         65
         69 #define
         73
                                                              IN 164 TYPE long in INT64 C SUFFIX LUSER LABEL PREFIX FINITE MATH ONLY GNUC STDC INLINE NO INLINE 1 FLT EVAL METHOD 0 FLT RADIX ?
                      #define
#define
                         ..
#define
         81
                      #define
                         ..
#define
                       #define
                                                               FLT_RADIX__2
DECIMAL_DIG__ 17
        #define
85 #define
                      #define __CLAMBC__ 1
#define BYTECODE_API_H
                        #define _EXECS_H
#define BC_FEATURES_H
#define EBOUNDS(x)
                      #define
#define
        #define DISASM_BC_H
93 #define BYTECODE_DETECT_H
                      #define STDBOOL_H
#define bool Bool
#define true 1
#define false 0
#define true I

97 #define false 0

#define false 0

#define _bool_true_false_are_defined 1

99 #define force_inline inline _attribute__((always_inline))

#define VirrusNAME_PREFIX(name) const char _clambc_virusname_prefix[] = name;

101 #define VIRUSNAME_PREFIX(name) const char _clambc_virusnames[] = {_VA_ARGS_};

#define VIRUSNAMES(...) const char *const _clambc_virusnames[] = {_VA_ARGS_};

#define VIRUSNAMES_DECL_BEGIN struct _Signatures {

#define SIGNATURES_DECL_BEGIN struct _Signatures {

#define DECLARE_SIGNATURES_DECL_END_};

#define SIGNATURES_DECL_END_};

#define IONGROUPY(group) const char *const __lconGroup1 = (group);

#define (CONGROUPY(group) const char *const __lconGroup2 = (group);

#define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short _FuncMin = (m);

101 #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short _FuncMax = (m);

#define SIGNATURES_DES_BEGIN static const unsigned short _FuncMax = (m);

#define SIGNATURES_DES_BEGIN static const unsigned short _FuncMax = (m);

#define SIGNATURES_DES_BEGIN static const unsigned _signature_bias =

___COUNTER__+1; const struct __Signatures Signatures = {

113 #define PEPINE_SIGNATURE[name, hex) .name##_sig = (hex), .name = {_COUNTER_} -

___signature_bias},

#define RECC_BSIZE 128

#define YYCTYPE unsigned char

117 #define YYCTYPE unsigned char

118 #define YYCTYPE unsigned char

#define YYCTYPE unsigned char

#define YYCONTEXT re2c_sctx

#define YYCONTEXT re2c_sctx

#define YYCONTEXT re2c_sctx

#define REGEX_SCANNER unsigned char *re2c_scur, *re2c_stok, *re2c_smrk, *re2c_sctx, *re2c_slim; int re2c_sres; int32_t re2c_sctokstart; unsigned char

re2c_sbuffer [RECZ_BSIZE]; re2c_scur = re2c_slim = re2c_smrk = re2c_sctx =

&re2c_sbuffer [RECZ_BSIZE]; re2c_scur = re2c_scur; re2c_stokstart = REGEX_POS;} while

(0);

125 #define RECEX_RESULT (re2c_sres)

#define RECEX_RESULT (re2c_sres)
 (0);
```