Reference Manual

Generated by Doxygen 1.8.6

Wed May 7 2014 14:19:22

ii CONTENTS

Contents

1	Modu	ule Doc	umentation	1
	1.1	Abstrac	ct Data Types	1
		1.1.1	Detailed Description	2
		1.1.2	Function Documentation	2
	1.2	Byteco	de Configuration	9
		1.2.1	Detailed Description	9
		1.2.2	Macro Definition Documentation	9
		1.2.3	Enumeration Type Documentation	11
	1.3	Debugg	ging	13
		1.3.1	Detailed Description	13
		1.3.2	Function Documentation	13
	1.4	Disasse	embly	16
		1.4.1	Detailed Description	16
		1.4.2	Function Documentation	16
	1.5	Engine	Queries	17
		1.5.1	Detailed Description	17
		1.5.2	Function Documentation	17
	1.6	Environ	nment	19
		1.6.1	Detailed Description	19
		1.6.2	Function Documentation	19
	1.7	File Op	erations	23
		1.7.1	Detailed Description	23
		1.7.2	Enumeration Type Documentation	23
		1.7.3	Function Documentation	23
	1.8	Global	Variables	27
		1.8.1	Detailed Description	27
		1.8.2	Variable Documentation	27
	1.9	JavaSc	ript Normalization	28
		1.9.1	Detailed Description	28
		1.9.2	Function Documentation	28
	1.10	JSON (Querying	29
		1.10.1	Detailed Description	29
		1.10.2	Enumeration Type Documentation	29
		1.10.3	Function Documentation	29
	1.11	Icon Ma	atcher	32
		1.11.1	Detailed Description	32
		1.11.2	Function Documentation	32
	1.12	Math O	peration	33

1.13 PDF Handling 1.13.1 Detailed Description 1.13.2 Enumeration Type Documentation 1.13.3 Function Documentation 1.14.1 PE Operations 1.14.1 Detailed Description 1.14.2 Function Documentation 1.15 Scan Control 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 2.1 cli_exe_into Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.3.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.5.3 Detailed Description 2.6.5 Field Documentation 2.7 DISASM RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.12.1 Deta	iled Description		 	 	 	 33
1.13.1 Detailed Description 1.13.2 Enumeration Type Documentation 1.13.3 Function Documentation 1.14.1 Pet Operations 1.14.1 Detailed Description 1.14.2 Function Documentation 1.15 Scan Control 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 1.16.2 Field Documentation 1.1			1.12.2 Fund	tion Documentation	on	 	 	 	 33
1.13.2 Enumeration Type Documentation 1.13.3 Function Documentation 1.14 PE Operations . 1.14.1 Detailed Description 1.14.2 Function Documentation 1.15 Scan Control . 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 1.16.2 Function Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.1 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.1.2 Field Documentation 2.2 di_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 di_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.5.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		1.13	PDF Handlin	g		 	 	 	 35
1.13.3 Function Documentation 1.14 PE Operations 1.14.1 Detailed Description 1.14.2 Function Documentation 1.15 Scan Control. 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 2 Data Structure Documentation 2.1 di_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 di_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 di_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation			1.13.1 Deta	iled Description		 	 	 	 35
1.14 PE Operations 1.14.1 Detailed Description 1.14.2 Function Documentation 1.15 Scan Control 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 1.16.2 Function Documentation 1.16.3 Punction Documentation 2 Data Structure Documentation 2 Data Structure Documentation 2 Disex_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 ci_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 di pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.13.2 Enur	neration Type Doc	umentation	 	 	 	 35
1.14.1 Detailed Description 1.14.2 Function Documentation 1.15 Scan Control 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 2.1 di_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 di_exe_section Struct Reference 2.2.1.1 Detailed Description 2.2.2 Field Documentation 2.3 di_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.13.3 Fund	tion Documentation	on	 	 	 	 35
1.14.2 Function Documentation 1.15 Scan Control 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 2.1 dil exe into Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cil exe section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 dil_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation		1.14	PE Operation	ns		 	 	 	 40
1.15 Scan Control 1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 2 Data Structure Documentation 2.1 cil_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cil_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cil_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.14.1 Deta	iled Description		 	 	 	 41
1.15.1 Detailed Description 1.15.2 Function Documentation 1.16 String Operations 1.16.1 Detailed Description 1.16.2 Function Documentation 2 Data Structure Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.14.2 Fund	tion Documentation	on	 	 	 	 41
1.15.2 Function Documentation 1.16.1 Detailed Description 1.16.2 Function Documentation 2 Data Structure Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		1.15	Scan Control			 	 	 	 49
1.16.1 Detailed Description 1.16.2 Function Documentation 2 Data Structure Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.15.1 Deta	iled Description		 	 	 	 49
1.16.1 Detailed Description 1.16.2 Function Documentation 2 Data Structure Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.15.2 Fund	tion Documentation	on	 	 	 	 49
1.16.2 Function Documentation 2 Data Structure Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		1.16	String Opera	tions		 	 	 	 51
2 Data Structure Documentation 2.1 cli_exe_info Struct Reference 2.1.1 Detailed Description 2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.16.1 Deta	iled Description		 	 	 	 51
2.1.1 Detailed Description 2.1.2 Field Documentation 2.1.2 Field Documentation 2.2 di_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			1.16.2 Fund	tion Documentation	on	 	 	 	 51
2.1.1 Detailed Description 2.1.2 Field Documentation 2.1.2 Field Documentation 2.2 di_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description	2	Data	Structure Do	ocumentation					54
2.1.2 Field Documentation 2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description						 	 	 	 54
2.2 cli_exe_section Struct Reference 2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.1.1 Deta	iled Description		 	 	 	 54
2.2.1 Detailed Description 2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.1.2 Field	Documentation		 	 	 	 54
2.2.2 Field Documentation 2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		2.2	cli_exe_secti	on Struct Referen	ce	 	 	 	 54
2.3 cli_pe_hook_data Struct Reference 2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.2.1 Deta	iled Description		 	 	 	 55
2.3.1 Detailed Description 2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.2.2 Field	Documentation		 	 	 	 55
2.3.2 Field Documentation 2.4 DIS_arg Struct Reference 2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		2.3	cli_pe_hook_	_data Struct Refere	ence	 	 	 	 55
2.4 DIS_arg Struct Reference . 2.4.1 Detailed Description . 2.4.2 Field Documentation . 2.5 DIS_fixed Struct Reference . 2.5.1 Detailed Description . 2.5.2 Field Documentation . 2.6 DIS_mem_arg Struct Reference . 2.6.1 Detailed Description . 2.6.2 Field Documentation . 2.7 DISASM_RESULT Struct Reference . 2.7.1 Detailed Description . 2.8 pe_image_data_dir Struct Reference . 2.8.1 Detailed Description .			2.3.1 Deta	iled Description		 	 	 	 56
2.4.1 Detailed Description 2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.3.2 Field	Documentation		 	 	 	 56
2.4.2 Field Documentation 2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		2.4	DIS_arg Stru	ct Reference		 	 	 	 56
2.5 DIS_fixed Struct Reference 2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.4.1 Deta	iled Description		 	 	 	 56
2.5.1 Detailed Description 2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.4.2 Field	Documentation		 	 	 	 57
2.5.2 Field Documentation 2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		2.5	DIS_fixed Str	ruct Reference .		 	 	 	 57
2.6 DIS_mem_arg Struct Reference 2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.5.1 Deta	iled Description		 	 	 	 57
2.6.1 Detailed Description 2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.5.2 Field	Documentation		 	 	 	 57
2.6.2 Field Documentation 2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description		2.6	DIS_mem_a	rg Struct Referenc	e	 	 	 	 58
2.7 DISASM_RESULT Struct Reference 2.7.1 Detailed Description 2.8 pe_image_data_dir Struct Reference 2.8.1 Detailed Description			2.6.1 Deta	iled Description		 	 	 	 58
2.7.1 Detailed Description			2.6.2 Field	Documentation		 	 	 	 58
2.8 pe_image_data_dir Struct Reference		2.7	DISASM_RE	SULT Struct Refe	rence	 	 	 	 58
2.8.1 Detailed Description			2.7.1 Deta	iled Description		 	 	 	 58
·		2.8	pe_image_da	ata_dir Struct Refe	erence	 	 	 	 58
2.9 pe_image_file_hdr Struct Reference			2.8.1 Deta	iled Description		 	 	 	 58
		2.9	pe_image_fil	e_hdr Struct Refe	rence	 	 	 	 58

1 Module Documentation

		2.9.1	Detailed Description	59
		2.9.2	Field Documentation	59
	2.10	pe_ima	age_optional_hdr32 Struct Reference	59
		2.10.1	Detailed Description	60
		2.10.2	Field Documentation	60
	2.11	pe_ima	age_optional_hdr64 Struct Reference	61
		2.11.1	Detailed Description	61
		2.11.2	Field Documentation	61
	2.12	pe_ima	age_section_hdr Struct Reference	62
		2.12.1	Detailed Description	62
		2.12.2	Field Documentation	62
3	File I	Docume	entation	63
9				
	3.1	byteco	de_api.h File Reference	63
		3.1.1	Enumeration Type Documentation	65
		3.1.2	Function Documentation	65
	3.2	byteco	de_disasm.h File Reference	66
		3.2.1	Enumeration Type Documentation	68
	3.3	byteco	de_execs.h File Reference	75
	3.4	byteco	de_local.h File Reference	75
		3.4.1	Macro Definition Documentation	77
		3.4.2	Function Documentation	77
	3.5	byteco	de_pe.h File Reference	77
Ind	dex			78

1 Module Documentation

1.1 Abstract Data Types

Functions

- void * malloc (uint32_t size)
- int32_t hashset_new (void)
- int32_t hashset_add (int32_t hs, uint32_t key)
- int32_t hashset_remove (int32_t hs, uint32_t key)
- int32_t hashset_contains (int32_t hs, uint32_t key)
- int32_t hashset_done (int32_t id)
- int32_t hashset_empty (int32_t id)
- int32_t buffer_pipe_new (uint32_t size)
- int32_t buffer_pipe_new_fromfile (uint32_t pos)
- uint32_t buffer_pipe_read_avail (int32_t id)
- const uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)
- int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)
- uint32_t buffer_pipe_write_avail (int32_t id)

- uint8_t * buffer_pipe_write_get (int32_t id, uint32_t size)
- int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)
- int32_t buffer_pipe_done (int32_t id)
- int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)
- int32_t inflate_process (int32_t id)
- int32 t inflate done (int32 t id)
- int32_t map_new (int32_t keysize, int32_t valuesize)
- int32_t map_addkey (const uint8_t *key, int32_t ksize, int32_t id)
- int32_t map_setvalue (const uint8_t *value, int32_t vsize, int32_t id)
- int32_t map_remove (const uint8_t *key, int32_t ksize, int32_t id)
- int32 t map find (const uint8 t *key, int32 t ksize, int32 t id)
- int32 t map getvaluesize (int32 t id)
- uint8_t * map_getvalue (int32_t id, int32_t size)
- int32_t map_done (int32_t id)

1.1.1 Detailed Description

1.1.2 Function Documentation

1.1.2.1 int32_t buffer_pipe_done (int32_t id)

Deallocate memory used by buffer. After this all attempts to use this buffer will result in error. All buffer_pipes are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of buffer_pipe
----	----	-------------------

Returns

0 on success

1.1.2.2 int32_t buffer_pipe_new (uint32_t size)

Creates a new pipe with the specified buffer size

Parameters

in	size	size of buffer

Returns

ID of newly created buffer_pipe

1.1.2.3 int32_t buffer_pipe_new_fromfile (uint32_t pos)

Creates a new pipe with the specified buffer size w/ tied input to the current file, at the specified position.

Parameters

in	pos	starting position of pipe input in current file
----	-----	---

Returns

ID of newly created buffer_pipe

1.1.2.4 uint32_t buffer_pipe_read_avail (int32_t id)

Returns the amount of bytes available to read.

Parameters

in	id	ID of buffer_pipe
----	----	-------------------

Returns

amount of bytes available to read

1.1.2.5 const uint8_t* buffer_pipe_read_get (int32_t id, uint32_t amount)

Returns a pointer to the buffer for reading. The 'amount' parameter should be obtained by a call to buffer_pipe_read_avail().

Parameters

in	id	ID of buffer_pipe
in	amount	to read

Returns

pointer to buffer, or NULL if buffer has less than specified amount

1.1.2.6 int32_t buffer_pipe_read_stopped (int32_t id, uint32_t amount)

Updates read cursor in buffer_pipe.

Parameters

in	id	ID of buffer_pipe
in	amount	amount of bytes to move read cursor

Returns

0 on success

1.1.2.7 uint32_t buffer_pipe_write_avail (int32_t id)

Returns the amount of bytes available for writing.

Parameters

in	id	ID of buffer_pipe

Returns

amount of bytes available for writing

1.1.2.8 uint8_t* buffer_pipe_write_get (int32_t id, uint32_t size)

Returns pointer to writable buffer. The 'size' parameter should be obtained by a call to buffer_pipe_write_avail().

Parameters

in	id	ID of buffer_pipe
in	size	amount of bytes to write

Returns

pointer to write buffer, or NULL if requested amount is more than what is available in the buffer

1.1.2.9 int32_t buffer_pipe_write_stopped (int32_t id, uint32_t amount)

Updates the write cursor in buffer_pipe.

Parameters

in	id	ID of buffer_pipe
in	amount	amount of bytes to move write cursor

Returns

0 on success

1.1.2.10 int32_t hashset_add (int32_t hs, uint32_t key)

Add a new 32-bit key to the hashset.

Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to add

Returns

0 on success

1.1.2.11 int32_t hashset_contains (int32_t hs, uint32_t key)

Returns whether the hashset contains the specified key.

Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to lookup

Returns

1 if found

0 if not found

<0 on invalid hashset ID

1.1.2.12 int32_t hashset_done (int32_t id)

Deallocates the memory used by the specified hashset. Trying to use the hashset after this will result in an error. The hashset may not be used after this. All hashsets are automatically deallocated when bytecode finishes execution.

Parameters

in	id	ID of hashset (from hashset_new)

Returns

0 on success

1.1.2.13 int32_t hashset_empty (int32_t id)

Returns whether the hashset is empty.

Parameters

in	id	of hashset (from hashset_new)
T11	iu	of flashiset (flotti flashiset_flew)

Returns

0 on success

1.1.2.14 int32_t hashset_new (void)

Creates a new hashset and returns its id.

Returns

ID for new hashset

1.1.2.15 int32_t hashset_remove (int32_t hs, uint32_t key)

Remove a 32-bit key from the hashset.

Parameters

in	hs	ID of hashset (from hashset_new)
in	key	the key to add

Returns

0 on success

1.1.2.16 int32_t inflate_done (int32_t id)

Deallocates inflate data structure. Using the inflate data structure after this will result in an error. All inflate data structures are automatically deallocated when bytecode finishes execution.

Parameters

in	id ID of inflate	data structure
----	------------------	----------------

Returns

0 on success.

1.1.2.17 int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)

Initializes inflate data structures for decompressing data 'from_buffer' and writing uncompressed uncompressed data 'to_buffer'.

Parameters

in	from_buffer	ID of buffer_pipe to read compressed data from
in	to_buffer	ID of buffer_pipe to write decompressed data to
in	windowBits	(see zlib documentation)

Returns

ID of newly created inflate data structure, <0 on failure

1.1.2.18 int32_t inflate_process (int32_t id)

Inflate all available data in the input buffer, and write to output buffer. Stops when the input buffer becomes empty, or write buffer becomes full. Also attempts to recover from corrupted inflate stream (via inflateSync). This function can be called repeatedly on success after filling the input buffer, and flushing the output buffer. The inflate stream is done processing when 0 bytes are available from output buffer, and input buffer is not empty.

Parameters

in	id	ID of inflate data structure
----	----	------------------------------

Returns

0 on success, zlib error code otherwise

1.1.2.19 void* malloc (uint32_t size)

Allocates memory. Currently this memory is freed automatically on exit from the bytecode, and there is no way to free it sooner.

Parameters

in	size	amount of memory to allocate in bytes
----	------	---------------------------------------

Returns

pointer to allocated memory

1.1.2.20 int32_t map_addkey (const uint8_t * key, int32_t ksize, int32_t id)

Inserts the specified key/value pair into the map.

Parameters

in	id	id of table
in	key	key
in	ksize	size of key

Returns

- 0 if key existed before
- 1 if key didn't exist before
- <0 if ksize doesn't match keysize specified at table creation

1.1.2.21 int32_t map_done (int32_t id)

Deallocates the memory used by the specified map. Trying to use the map after this will result in an error. All maps are automatically deallocated when the bytecode finishes execution.

Parameters

in	id	id of map

Returns

- 0 success
- -1 invalid map

1.1.2.22 int32_t map_find (const uint8_t * key, int32_t ksize, int32_t id)

Looks up key in map. The map remember the last looked up key (so you can retrieve the value).

Parameters

in	id	id of map
in	key	key
in	ksize	size of key

Returns

- 0 if not found
- 1 if found
- <0 if ksize doesn't match the size specified at table creation
- 1.1.2.23 uint8_t* map_getvalue (int32_t id, int32_t size)

Returns the value obtained during last map_find.

Parameters

in	id	id of map.
in	size	size of value (obtained from map_getvaluesize)

Returns

value

1.1.2.24 int32_t map_getvaluesize (int32_t id)

Returns the size of value obtained during last map_find.

Parameters

in	id	id of map.

Returns

size of value

1.1.2.25 int32_t map_new (int32_t keysize, int32_t valuesize)

Creates a new map and returns its id.

Parameters

in	keysize	size of key
in	valuesize	size of value, if 0 then value is allocated separately

Returns

ID of new map

1.1.2.26 int32_t map_remove (const uint8_t * key, int32_t ksize, int32_t id)

Remove an element from the map.

Parameters

B CONTENTS

in	id	id of map
in	key	key
in	ksize	size of key

Returns

0 on success, key was present

- 1 if key was not present
- <0 if ksize doesn't match keysize specified at table creation

1.1.2.27 int32_t map_setvalue (const uint8_t * value, int32_t vsize, int32_t id)

Sets the value for the last inserted key with map_addkey.

Parameters

in	id	id of table
in	value	value
in	vsize	size of value

Returns

0 - if update was successful

<0 - if there is no last key

1.2 Bytecode Configuration

Macros

```
#define VIRUSNAME_PREFIX(name) const char __clambc_virusname_prefix[] = name;
#define VIRUSNAMES(...) const char *const __clambc_virusnames[] = {__VA_ARGS__};
#define PE_UNPACKER_DECLARE const uint16_t __clambc_kind = BC_PE_UNPACKER;
#define PDF_HOOK_DECLARE const uint16_t __clambc_kind = BC_PDF;
#define PE_HOOK_DECLARE const uint16_t __clambc_kind = BC_PE_ALL;
#define SIGNATURES_DECL_BEGIN struct __Signatures {
#define DECLARE_SIGNATURE(name)
#define SIGNATURES_DECL_END };
#define TARGET(tgt) const unsigned short __Target = (tgt);
#define COPYRIGHT(c) const char *const __Copyright = (c);
#define ICONGROUP1(group) const char *const __lconGroup1 = (group);
#define FUNCTIONALITY LEVEL MIN(m) const unsigned short FuncMin = (m);
```

#define FUNCTIONALITY LEVEL MAX(m) const unsigned short FuncMax = (m);

Enumerations

```
enum BytecodeKind {
    BC_GENERIC =0, BC_STARTUP =1 , BC_LOGICAL =256, BC_PE_UNPACKER,
    BC_PDF, BC_PE_ALL }
enum FunctionalityLevels {
    FUNC_LEVEL_096 = 51 , FUNC_LEVEL_096_1 = 53 , FUNC_LEVEL_096_2 = 54 , FUNC_LEVEL_096_3 = 55,
    FUNC_LEVEL_096_4 = 56, FUNC_LEVEL_096_5 = 58, FUNC_LEVEL_097 = 60, FUNC_LEVEL_097_1 = 61,
    FUNC_LEVEL_097_2 = 62, FUNC_LEVEL_097_3 = 63, FUNC_LEVEL_097_4 = 64, FUNC_LEVEL_097_5 = 65,
    FUNC_LEVEL_097_6 = 67, FUNC_LEVEL_097_7 = 68, FUNC_LEVEL_097_8 = 69, FUNC_LEVEL_098_1 = 76,
    FUNC_LEVEL_098_2 = 77, FUNC_LEVEL_098_3 = 77, FUNC_LEVEL_098_4 = 78 }
```

1.2.1 Detailed Description

1.2.2 Macro Definition Documentation

```
1.2.2.1 #define COPYRIGHT( c ) const char *const __Copyright = (c);
```

Defines an alternative copyright for this bytecode.

#define SIGNATURES_DEF_BEGIN#define SIGNATURES_DEF_END };

This will also prevent the sourcecode from being embedded into the bytecode.

```
1.2.2.2 #define DECLARE_SIGNATURE( name )
```

Value:

```
const char *name##_sig;\
    __Signature name;
```

Declares a name for a subsignature.

```
1.2.2.3 #define FUNCTIONALITY_LEVEL_MAX( m ) const unsigned short __FuncMax = (m);
```

Define the maximum engine functionality level required for this bytecode/logical signature.

Engines newer than this will skip loading the bytecode. You can use the FunctionalityLevels enumeration here.

```
1.2.2.4 #define FUNCTIONALITY LEVEL MIN( m) const unsigned short FuncMin = (m);
```

Define the minimum engine functionality level required for this bytecode/logical signature.

Engines older than this will skip loading the bytecode. You can use the FunctionalityLevels enumeration here.

```
1.2.2.5 #define ICONGROUP1( group ) const char *const __lconGroup1 = (group);
```

Define IconGroup1 for logical signature.

See logical signature documentation for what it is.

```
1.2.2.6 #define ICONGROUP2( group ) const char *const __lconGroup2 = (group);
```

Define IconGroup2 for logical signature.

See logical signature documentation for what it is.

```
1.2.2.7 #define PDF_HOOK_DECLARE const uint16_t __clambc_kind = BC_PDF;
```

Make the current bytecode a PDF hook.

Having a logical signature doesn't make sense here, since the logical signature is evaluated AFTER these hooks run.

This hook is called several times, use pdf_get_phase() to find out in which phase you got called.

```
1.2.2.8 #define PE_HOOK_DECLARE const uint16_t __clambc_kind = BC_PE_ALL;
```

Make the current bytecode a PE hook.

Bytecode will be called once the logical signature trigger matches (or always if there is none), and if you have access to all the PE information. By default you only have access to execs.h information, and not to PE field information (even for PE files).

```
1.2.2.9 #define PE_UNPACKER_DECLARE const uint16_t clambc kind = BC_PE_UNPACKER;
```

Like PE_HOOK_DECLARE, but it is not run for packed files that pe.c can unpack (only on the unpacked file).

```
1.2.2.10 #define SIGNATURES_DECL_BEGIN struct __Signatures {
```

Marks the beginning of the subsignature name declaration section.

```
1.2.2.11 #define SIGNATURES_DECL_END };
```

Marks the end of the subsignature name declaration section.

```
1.2.2.12 #define SIGNATURES_DEF_BEGIN
```

Value:

```
static const unsigned __signature_bias = __COUNTER__+1;\ const struct __Signatures Signatures = {\
```

Marks the beginning of subsignature pattern definitions.

See Also

SIGNATURES_DECL_BEGIN

1.2.2.13 #define SIGNATURES_DEF_END };

Marks the end of the subsignature pattern definitions.

Alternative: SIGNATURES_END

1.2.2.14 #define TARGET(tgt) const unsigned short __Target = (tgt);

Defines the ClamAV file target.

Parameters

in	tgt	ClamAV signature type (0 - raw, 1 - PE, etc.)

1.2.2.15 #define VIRUSNAME_PREFIX(name) const char __clambc_virusname_prefix[] = name;

Declares the virusname prefix.

Parameters

in	name	the prefix common to all viruses reported by this bytecode
----	------	--

1.2.2.16 #define VIRUSNAMES(...) const char *const __clambc_virusnames[] = {__VA_ARGS__};

Declares all the virusnames that this bytecode can report.

Parameters

in		a comma-separated list of strings interpreted as virusnames
----	--	---

1.2.3 Enumeration Type Documentation

1.2.3.1 enum BytecodeKind

Specifies the bytecode type and how ClamAV executes it

Enumerator

BC_GENERIC generic bytecode, not tied a specific hook

BC_STARTUP triggered at startup, only one is allowed per ClamAV startup

BC_LOGICAL executed on a logical trigger

BC_PE_UNPACKER specifies a PE unpacker, executed on PE files on a logical trigger

BC_PDF specifies a PDF hook, executes at a predetermined point of PDF parsing for PDF files

BC_PE_ALL specifies a PE hook, executes at a predetermined point in PE parsing for PE files, both packed and unpacked files

1.2.3.2 enum FunctionalityLevels

LibClamAV functionality level constants

Enumerator

FUNC_LEVEL_096 LibClamAV release 0.96.0: bytecode engine released

FUNC_LEVEL_096_1 LibClamAV release 0.96.1: logical signature use of VI/macros requires this minimum functionality level

FUNC_LEVEL_096_2 LibClamAV release 0.96.2: PDF Hooks require this minimum level

FUNC LEVEL 096 3 LibClamAV release 0.96.3: BC PE ALL bytecodes require this minimum level

FUNC_LEVEL_096_4 LibClamAV release 0.96.4: minimum recommended engine version, older versions have quadratic load time

```
FUNC_LEVEL_097 LibClamAV release 0.96.5

FUNC_LEVEL_097 LibClamAV release 0.97.0: older bytecodes may incorrectly use 57

FUNC_LEVEL_097_1 LibClamAV release 0.97.1

FUNC_LEVEL_097_2 LibClamAV release 0.97.2

FUNC_LEVEL_097_3 LibClamAV release 0.97.3

FUNC_LEVEL_097_4 LibClamAV release 0.97.4

FUNC_LEVEL_097_5 LibClamAV release 0.97.5

FUNC_LEVEL_097_6 LibClamAV release 0.97.6

FUNC_LEVEL_097_7 LibClamAV release 0.97.7

FUNC_LEVEL_097_8 LibClamAV release 0.97.8

FUNC_LEVEL_098_1 LibClamAV release 0.98.2

FUNC_LEVEL_098_2 LibClamAV release 0.98.2

FUNC_LEVEL_098_3 LibClamAV release 0.98.3

FUNC_LEVEL_098_4 LibClamAV release 0.98.4: JSON reading API requires this minimum level
```

1.3 Debugging 13

1.3 Debugging

Functions

- uint32_t debug_print_str (const uint8_t *str, uint32_t len)
- uint32_t debug_print_uint (uint32_t a)
- uint32_t debug_print_str_start (const uint8_t *str, uint32_t len)
- uint32_t debug_print_str_nonl (const uint8_t *str, uint32_t len)
- void debug (...) __attribute__((overloadable
- static force_inline void overloadable_func debug (const char *str)
- static force_inline void overloadable_func debug (const uint8_t *str)
- static force_inline void overloadable_func debug (uint32_t a)

1.3.1 Detailed Description

1.3.2 Function Documentation

```
1.3.2.1 debug (const char * str ) [static]
```

Prints str to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in	str	null terminated string
----	-----	------------------------

```
1.3.2.2 debug (const uint8_t * str ) [static]
```

Prints str to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in	str	null terminated string
----	-----	------------------------

```
1.3.2.3 debug(uint32_t a) [static]
```

Prints a integer to clamscan's –debug output. This is an overloaded member function, provided for convenience. It differs from the above function only in what argument(s) it accepts.

Parameters

in a	integer
------	---------

1.3.2.4 void debug (...)

debug is an overloaded function (yes clang supports that in C!), but it only works on strings, and integers. Give an error on any other type.

See Also

```
debug(const char * str),
debug(const uint8_t* str),
debug(uint32 t a)
```

1.3.2.5 uint32_t debug_print_str (const uint8_t * str, uint32_t len)

Prints a debug message string.

1.3 Debugging 15

Parameters

in	str	Message to print
in	len	length of message to print

Returns

0

1.3.2.6 uint32_t debug_print_str_nonl (const uint8_t * str, uint32_t len)

Prints a debug message with a trailing newline, and not preceded by 'LibClamAV debug'.

Parameters

in	str	the string
in	len	length of str

Returns

0

1.3.2.7 uint32_t debug_print_str_start (const uint8_t * str, uint32_t len)

Prints a debug message with a trailing newline, but preceded by 'LibClamAV debug'.

Parameters

in	str	the string
in	len	length of str

Returns

0

1.3.2.8 uint32_t debug_print_uint (uint32_t a)

Prints a number as a debug message. This is similar to debug_print_str_nonl.

Parameters

in	а	number to print

Returns

0

1.4 Disassembly

Data Structures

- struct DIS_mem_arg
- struct DIS_arg
- struct DIS_fixed

Functions

- uint32 t disasm x86 (struct DISASM RESULT *result, uint32 t len)
- static force_inline uint32_t DisassembleAt (struct DIS_fixed *result, uint32_t offset, uint32_t len)

1.4.1 Detailed Description

1.4.2 Function Documentation

1.4.2.1 uint32_t disasm_x86 (struct DISASM_RESULT * result, uint32_t len)

Disassembles starting from current file position, the specified amount of bytes.

Parameters

out	result	pointer to struct holding result
in	len	how many bytes to disassemble

Returns

0 for success

You can use Iseek to disassemble starting from a different location. This is a low-level API, the result is in ClamAV type-8 signature format (64 bytes/instruction).

See Also

DisassembleAt

1.4.2.2 static force_inline uint32_t DisassembleAt (struct DIS_fixed * result, uint32_t offset, uint32_t len) [static]

Disassembles one X86 instruction starting at the specified offset.

Parameters

out	result	disassembly result
in	offset	start disassembling from this offset, in the current file
in	len	max amount of bytes to disassemble

Returns

offset where disassembly ended

1.5 Engine Queries 17

1.5 Engine Queries

Functions

- uint32_t engine_functionality_level (void)
- uint32 t engine dconf level (void)
- uint32_t engine_scan_options (void)
- uint32_t engine_db_options (void)
- int32 t running on jit (void)
- static force_inline uint32_t count_match (__Signature sig)
- static force_inline uint32_t matches (__Signature sig)
- static force_inline uint32_t match_location (__Signature sig, uint32_t goback)
- static force_inline int32_t match_location_check (__Signature sig, uint32_t goback, const char *static_start, uint32_t static_len)

1.5.1 Detailed Description

1.5.2 Function Documentation

1.5.2.1 static force_inline uint32_t count_match (__Signature sig) [static]

Returns how many times the specified signature matched.

Parameters

in	sig	name of subsignature queried
----	-----	------------------------------

Returns

number of times this subsignature matched in the entire file

This is a constant-time operation, the counts for all subsignatures are already computed.

```
1.5.2.2 uint32_t engine_db_options (void )
```

Returns the current engine's db options.

Returns

```
CL_DB_* flags
```

1.5.2.3 uint32_t engine_dconf_level (void)

Returns the current engine (dconf) functionality level. Usually identical to engine_functionality_level(), unless distrobackported patches. Compare with FunctionalityLevels.

Returns

an integer representing the DCONF (security fixes) level.

1.5.2.4 uint32_t engine_functionality_level (void)

Returns the current engine (feature) functionality level. To map these to ClamAV releases, compare it with FunctionalityLevels.

Returns

an integer representing current engine functionality level.

```
1.5.2.5 uint32_t engine_scan_options (void)
```

Returns the current engine's scan options.

Returns

```
CL_SCAN* flags
```

1.5.2.6 static force_inline uint32_t match_location (__Signature sig, uint32_t goback) [static]

Returns the offset of the match.

Parameters

in	sig	- Signature
in	goback	- max length of signature

Returns

offset of match

1.5.2.7 static force_inline int32_t match_location_check (__Signature sig, uint32_t goback, const char * static_start, uint32_t static_len) [static]

Like match_location(), but also checks that the match starts with the specified hex string.

It is recommended to use this for safety and compatibility with 0.96.1

Parameters

in	sig	- signature
in	goback	- maximum length of signature (till start of last subsig)
in	static_start	- static string that sig must begin with
in	static_len	- static string that sig must begin with - length

Returns

```
>=0 - offset of match
```

-1 - no match

1.5.2.8 static force_inline uint32_t matches (__Signature sig) [static]

Returns whether the specified subsignature has matched at least once.

Parameters

in	sig	name of subsignature queried

Returns

1 if subsignature one or more times, 0 otherwise

1.5.2.9 int32_t running_on_jit (void)

Returns whether running on JIT. As side-effect it disables interp / JIT comparisons in test mode (errors are still checked)

Returns

- 1 running on JIT
- 0 running on ClamAV interpreter

1.6 Environment 19

1.6 Environment

Functions

- uint32_t get_environment (struct cli_environment *env, uint32_t len)
- uint32_t disable_bytecode_if (const int8_t *reason, uint32_t len, uint32_t cond)
- uint32 t disable jit if (const int8 t *reason, uint32 t len, uint32 t cond)
- int32_t version_compare (const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_t rhs_len)
- uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c)
- bool <u>__is_bigendian</u> (void) <u>__attribute__((const))</u> <u>__attribute__((nothrow))</u>
- static uint32_t force_inline le32_to_host (uint32_t v)
- static uint32 t force inline be32 to host (uint32 t v)
- static uint64 t force inline le64 to host (uint64 t v)
- static uint64_t force_inline be64_to_host (uint64_t v)
- static uint16_t force_inline le16_to_host (uint16_t v)
- static uint16_t force_inline be16_to_host (uint16_t v)
- static uint32 t force inline cli readint32 (const void *buff)
- static uint16_t force_inline cli_readint16 (const void *buff)
- static void force_inline cli_writeint32 (void *offset, uint32_t v)

1.6.1 Detailed Description

1.6.2 Function Documentation

1.6.2.1 bool __is_bigendian (void) const

Returns true if the bytecode is executing on a big-endian CPU.

Returns

true if executing on bigendian CPU, false otherwise

This will be optimized away in libclamav, but it must be used when dealing with endianess for portability reasons.

For example whenever you read a 32-bit integer from a file, it can be written in little-endian convention (x86 CPU for example), or big-endian convention (PowerPC CPU for example).

If the file always contains little-endian integers, then conversion might be needed.

ClamAV bytecodes by their nature must only handle known-endian integers, if endianness can change, then both situations must be taken into account (based on a 1-byte field for example).

```
1.6.2.2 static uint16_t force_inline be16_to_host ( uint16_t \nu ) [static]
```

Converts the specified value if needed, knowing it is in big endian order.

Parameters

in	V	16-bit integer as read from a file
----	---	------------------------------------

Returns

integer converted to host's endianess

1.6.2.3 static uint32_t force_inline be32_to_host (uint32_t ν) [static]

Converts the specified value if needed, knowing it is in big endian order.

Parameters

in	V	32-bit integer as read from a file
----	---	------------------------------------

Returns

integer converted to host's endianess

1.6.2.4 static uint64_t force_inline be64_to_host(uint64_t v) [static]

Converts the specified value if needed, knowing it is in big endian order.

Parameters

	*	
in	V	64-bit integer as read from a file

Returns

integer converted to host's endianess

1.6.2.5 uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c)

Disables the JIT if the platform id matches. 0xff can be used instead of a field to mark ANY.

Parameters

in	а	- os_category << 24 arch << 20 compiler << 16 flevel << 8 dconf
in	b	- big_endian << 28 sizeof_ptr << 24 cpp_version
in	С	- os_features << 24 c_version

Returns

- 0 no match
- 1 match

1.6.2.6 static uint16_t force_inline cli_readint16 (const void * buff) [static]

Reads from the specified buffer a 16-bit of little-endian integer.

Parameters

in	buff	pointer to buffer

Returns

16-bit little-endian integer converted to host endianness

1.6.2.7 static uint32_t force_inline cli_readint32 (const void * buff) [static]

Reads from the specified buffer a 32-bit of little-endian integer.

Parameters

in	buff	pointer to buffer

Returns

32-bit little-endian integer converted to host endianness

1.6.2.8 static void force_inline cli_writeint32 (void * offset, uint32_t v) [static]

Writes the specified value into the specified buffer in little-endian order

1.6 Environment 21

Parameters

out	offset	pointer to buffer to write to
in	V	value to write

1.6.2.9 uint32_t disable_bytecode_if (const int8_t * reason, uint32_t len, uint32_t cond)

Disables the bytecode completely if condition is true. Can only be called from the BC_STARTUP bytecode.

Parameters

in	reason	- why the bytecode had to be disabled
in	len	- length of reason
in	cond	- condition

Returns

- 0 auto mode
- 1 JIT disabled
- 2 fully disabled

1.6.2.10 uint32_t disable_jit_if (const int8_t * reason, uint32_t len, uint32_t cond)

Disables the JIT completely if condition is true. Can only be called from the BC_STARTUP bytecode.

Parameters

in	reason	- why the JIT had to be disabled
in	len	- length of reason
in	cond	- condition

Returns

- 0 auto mode
- 1 JIT disabled
- 2 fully disabled

1.6.2.11 uint32_t get_environment (struct cli_environment * env, uint32_t len)

Queries the environment this bytecode runs in. Used by BC_STARTUP to disable bytecode when bugs are known for the current platform.

Parameters

out	env	- the full environment
in	len	- size of env

Returns

0

1.6.2.12 static uint16_t force_inline le16_to_host (uint16_t ν) [static]

Converts the specified value if needed, knowing it is in little endian order.

Parameters

in	V	16-bit integer as read from a file
----	---	------------------------------------

Returns

integer converted to host's endianess

1.6.2.13 static uint32_t force_inline le32_to_host (uint32_t ν) [static]

Converts the specified value if needed, knowing it is in little endian order.

Parameters

in	V	32-bit integer as read from a file

Returns

integer converted to host's endianess

1.6.2.14 static uint64_t force_inline le64_to_host(uint64_t v) [static]

Converts the specified value if needed, knowing it is in little endian order.

Parameters

in	V	64-bit integer as read from a file
----	---	------------------------------------

Returns

integer converted to host's endianess

1.6.2.15 int32_t version_compare (const uint8_t * Ihs, uint32_t Ihs_len, const uint8_t * rhs, uint32_t rhs_len)

Compares two version numbers.

Parameters

[in	lhs	- left hand side of comparison
			'
	ın	lhs_len	- length of lhs
	in	rhs	- right hand side of comparison
	in	rhs_len	- length of rhs

Returns

- -1 lhs < rhs
- 0 lhs == rhs
- 1 lhs > rhs

1.7 File Operations 23

1.7 File Operations

Enumerations

enum { SEEK_SET =0, SEEK_CUR, SEEK_END }

Functions

- int32_t read (uint8_t *data, int32_t size)
- int32 t write (uint8 t *data, int32 t size)
- int32_t seek (int32_t pos, uint32_t whence)
- int32 t file find (const uint8 t *data, uint32 t len)
- int32_t file_byteat (uint32_t offset)
- int32_t fill_buffer (uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)
- int32_t read_number (uint32_t radix)
- int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)
- int32_t get_file_reliability (void)
- static force_inline uint32_t getFilesize (void)

1.7.1 Detailed Description

1.7.2 Enumeration Type Documentation

1.7.2.1 anonymous enum

Enumerator

SEEK_SET set file position to specified absolute position

SEEK_CUR set file position relative to current position

SEEK_END set file position relative to file end

1.7.3 Function Documentation

1.7.3.1 int32_t file_byteat (uint32_t offset)

Read a single byte from current file

Parameters

in	offset	file offset

Returns

byte at offset off in the current file, or -1 if offset is invalid

1.7.3.2 int32_t file_find (const uint8_t * data, uint32_t len)

Looks for the specified sequence of bytes in the current file.

Parameters

in	data	the sequence of bytes to look for
in	len	length of data, cannot be more than 1024

Returns

offset in the current file if match is found, -1 otherwise

1.7.3.3 int32_t file_find_limit (const uint8_t * data, uint32_t len, int32_t maxpos)

Looks for the specified sequence of bytes in the current file, up to the specified position.

1.7 File Operations 25

Parameters

in	data	the sequence of bytes to look for
in	len	length of data, cannot be more than 1024
in	maxpos	maximum position to look for a match, note that this is 1 byte after the end of
		last possible match: match_pos + len < maxpos

Returns

offset in the current file if match is found, -1 otherwise

1.7.3.4 int32_t fill_buffer (uint8_t * buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)

Fills the specified buffer with at least fill bytes.

Parameters

out	buffer	the buffer to fill
in	len	length of buffer
in	filled	how much of the buffer is currently filled
in	cursor	position of cursor in buffer
in	fill	amount of bytes to fill in (0 is valid)

Returns

<0 on error

0 on EOF

number bytes available in buffer (starting from 0)

The character at the cursor will be at position 0 after this call.

1.7.3.5 int32_t get_file_reliability (void)

Get file reliability flag, higher value means less reliable. When >0 import tables and such are not reliable

Returns

0 - normal

1 - embedded PE

2 - unpacker created file (not impl. yet)

1.7.3.6 static force_inline uint32_t getFilesize (void) [static]

Returns the currently scanned file's size.

Returns

file size as 32-bit unsigned integer

1.7.3.7 int32_t read (uint8_t * data, int32_t size)

Reads specified amount of bytes from the current file into a buffer. Also moves current position in the file.

Parameters

in	size	amount of bytes to read

out	data	pointer to buffer where data is read into
-----	------	---

Returns

amount read.

1.7.3.8 int32_t read_number (uint32_t radix)

Reads a number in the specified radix starting from the current position. Non-numeric characters are ignored.

Parameters

in	radix	10 or 16

Returns

the number read

1.7.3.9 int32_t seek (int32_t pos, uint32_t whence)

Changes the current file position to the specified one.

See Also

SEEK_SET, SEEK_CUR, SEEK_END

Parameters

in	pos	offset (absolute or relative depending on whence param)
in	whence	one of SEEK_SET, SEEK_CUR, SEEK_END

Returns

absolute position in file

1.7.3.10 int32_t write (uint8_t * data, int32_t size)

Writes the specified amount of bytes from a buffer to the current temporary file.

Parameters

in	data	pointer to buffer of data to write
in	size	amount of bytes to write $\ensuremath{\mathtt{size}}$ bytes to temporary file, from the buffer pointed
		to byte

Returns

amount of bytes successfully written

1.8 Global Variables 27

1.8 Global Variables

Variables

const uint32_t __clambc_match_counts [64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

const uint32_t __clambc_match_offsets [64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

- const struct cli_pe_hook_data __clambc_pedata
- const uint32_t __clambc_filesize [1]
- const uint16_t __clambc_kind
- 1.8.1 Detailed Description
- 1.8.2 Variable Documentation
- 1.8.2.1 const uint32_t __clambc_filesize[1]

File size (max 4G).

1.8.2.2 const uint16_t __clambc_kind

Kind of the bytecode, affects LibClamAV usage

1.8.2.3 const uint32_t __clambc_match_counts[64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Logical signature match counts

1.8.2.4 const uint32_t __clambc_match_offsets[64]

This is a low-level variable, use the Macros in bytecode_local.h instead to access it.

Logical signature match offsets

1.8.2.5 const struct cli_pe_hook_data __clambc_pedata

PE data, if this is a PE hook.

1.9 JavaScript Normalization

Functions

- int32_t jsnorm_init (int32_t from_buffer)
- int32_t jsnorm_process (int32_t id)
- int32_t jsnorm_done (int32_t id)
- 1.9.1 Detailed Description
- 1.9.2 Function Documentation
- 1.9.2.1 int32_t jsnorm_done (int32_t id)

Flushes JS normalizer.

Parameters

in	id	ID of js normalizer to flush
----	----	------------------------------

Returns

0 on success, <0 on failure

1.9.2.2 int32_t jsnorm_init (int32_t from_buffer)

Initializes JS normalizer for reading 'from_buffer'. Normalized JS will be written to a single tempfile, one normalized JS per line, and automatically scanned when the bytecode finishes execution.

Parameters

in	from_buffer	ID of buffer_pipe to read javascript from
----	-------------	---

Returns

ID of JS normalizer, <0 on failure

1.9.2.3 int32_t jsnorm_process (int32_t id)

Normalize all javascript from the input buffer, and write to tempfile. You can call this function repeatedly on success, if you (re)fill the input buffer.

Parameters

in	id	ID of JS normalizer

Returns

0 on success, <0 on failure

1.10 JSON Querying 29

1.10 JSON Querying

Enumerations

• enum bc_json_type

Functions

- int32_t json_is_active (void)
- int32_t json_get_object (const int8_t *name, int32_t name_len, int32_t objid)
- int32_t json_get_type (int32_t objid)
- int32 t json get array length (int32 t objid)
- int32_t json_get_array_idx (int32_t idx, int32_t objid)
- int32_t json_get_string_length (int32_t objid)
- int32 t json get string (int8 t *str, int32 t str len, int32 t objid)
- int32_t json_get_boolean (int32_t objid)
- int32_t json_get_int (int32_t objid)
- 1.10.1 Detailed Description
- 1.10.2 Enumeration Type Documentation
- 1.10.2.1 enum bc_json_type

JSON types

- 1.10.3 Function Documentation
- 1.10.3.1 int32_t json_get_array_idx (int32_t idx, int32_t objid)

Returns

objid of json object at idx of json array of objid 0 if invalid idx

- -1 if an error has occurred
- -2 if object is not JSON TYPE ARRAY

Parameters

in	idx	- index of array to query, must be >= 0 and less than array length
in	objid	- id value of json object (should be JSON_TYPE_ARRAY) to query

1.10.3.2 int32_t json_get_array_length (int32_t objid)

Returns

number of elements in the json array of objid

- -1 if an error has occurred
- -2 if object is not JSON_TYPE_ARRAY

Parameters

in	objid	 id value of json object (should be JSON_TYPE_ARRAY) to query

1.10.3.3 int32_t json_get_boolean (int32_t objid)

Returns

boolean value of queried objid; will force other types to boolean

Parameters

in	objid	- id value of json object to query

1.10.3.4 int32_t json_get_int (int32_t objid)

Returns

integer value of queried objid; will force other types to integer

Parameters

in	objid	- id value of json object to query

1.10.3.5 int32_t json_get_object (const int8_t * name, int32_t name_len, int32_t objid)

Returns

objid of json object with specified name

0 if json object of specified name cannot be found

-1 if an error has occurred

Parameters

in	name	- name of object in ASCII
in	name_len	- length of specified name (not including terminating NULL), must be \geq = 0
in	objid	- id value of json object to query

1.10.3.6 int32_t json_get_string (int8_t * str, int32_t str_len, int32_t objid)

Returns

number of characters transferred (capped by str_len), including terminating null-character

- -1 if an error has occurred
- -2 if object is not JSON_TYPE_STRING

Parameters

out	str	- user location to store string data; will be null-terminated
in	str_len	- length of str or limit of string data to read, including terminating null-character
in	objid	- id value of json object (should be JSON_TYPE_STRING) to query

1.10.3.7 int32_t json_get_string_length (int32_t objid)

Returns

length of json string of objid, not including terminating null-character

- -1 if an error has occurred
- -2 if object is not JSON_TYPE_STRING

1.10 JSON Querying 31

Parameters

in	objid	- id value of json object (should be JSON_TYPE_STRING) to query

1.10.3.8 int32_t json_get_type (int32_t objid)

Returns

type (json_type) of json object specified -1 if type unknown or invalid id

Parameters

_			
	in	objid	- id value of json object to query

1.10.3.9 int32_t json_is_active (void)

Returns

- 0 json is disabled or option not specified
- 1 json is active and properties are available

1.11 Icon Matcher

Functions

• int32_t matchicon (const uint8_t *group1, int32_t group1_len, const uint8_t *group2, int32_t group2_len)

1.11.1 Detailed Description

1.11.2 Function Documentation

1.11.2.1 int32_t matchicon (const uint8_t * group1, int32_t group1_len, const uint8_t * group2, int32_t group2_len)

Attempts to match current executable's icon against the specified icon groups.

Parameters

in	group1	- same as GROUP1 in LDB signatures
in	group1_len	- length of group1
in	group2	- same as GROUP2 in LDB signatures
in	group2_len	- length of group2

Returns

- -1 invalid call, or sizes (only valid for PE hooks)
- 0 not a match
- 1 match

1.12 Math Operation 33

1.12 Math Operation

Functions

- int32_t ilog2 (uint32_t a, uint32_t b)
- int32_t ipow (int32_t a, int32_t b, int32_t c)
- uint32_t iexp (int32_t a, int32_t b, int32_t c)
- int32_t isin (int32_t a, int32_t b, int32_t c)
- int32_t icos (int32_t a, int32_t b, int32_t c)

1.12.1 Detailed Description

1.12.2 Function Documentation

1.12.2.1 int32_t icos (int32_t a, int32_t b, int32_t c)

Returns c*cos(a/b).

Parameters

in	а	integer
in	b	integer
in	С	integer

Returns

c*sin(a/b)

1.12.2.2 uint32_t iexp (int32_t a, int32_t b, int32_t c)

Returns exp(a/b)*c

Parameters

in	а	integer
in	b	integer
in	С	integer

Returns

c*exp(a/b)

1.12.2.3 int32_t ilog2 (uint32_t a, uint32_t b)

Returns 2^{\(\)}26*log2(a/b)

Parameters

in	а	input
in	b	input

Returns

 2^{2} 4 log2(a/b)

1.12.2.4 int32_t ipow (int32_t a, int32_t b, int32_t c)

Returns c*a^b.

Parameters

in	а	integer
in	b	integer
in	С	integer

Returns

c*pow(a,b)

1.12.2.5 int32_t isin (int32_t a, int32_t b, int32_t c)

Returns c*sin(a/b).

Parameters

in	а	integer
in	b	integer
in	С	integer

Returns

c*sin(a/b)

1.13 PDF Handling 35

1.13 PDF Handling

Enumerations

```
enum pdf_phase { , PDF_PHASE_PARSED, PDF_PHASE_POSTDUMP, PDF_PHASE_END, PDF_PHASE_EPRE }
```

- enum pdf_flag
- · enum pdf_objflags

Functions

- int32_t pdf_get_obj_num (void)
- int32_t pdf_get_flags (void)
- int32_t pdf_set_flags (int32_t flags)
- int32_t pdf_lookupobj (uint32_t id)
- uint32_t pdf_getobjsize (int32_t objidx)
- const uint8_t * pdf_getobj (int32_t objidx, uint32_t amount)
- int32_t pdf_getobjid (int32_t objidx)
- int32_t pdf_getobjflags (int32_t objidx)
- int32_t pdf_setobjflags (int32_t objidx, int32_t flags)
- int32_t pdf_get_offset (int32_t objidx)
- int32_t pdf_get_phase (void)
- int32_t pdf_get_dumpedobjid (void)

1.13.1 Detailed Description

1.13.2 Enumeration Type Documentation

1.13.2.1 enum pdf_flag

PDF flags

1.13.2.2 enum pdf_objflags

PDF obj flags

1.13.2.3 enum pdf_phase

Phase of PDF parsing used for PDF Hooks

Enumerator

```
PDF_PHASE_PARSED after parsing a PDF, object flags can be set etc.
PDF_PHASE_POSTDUMP after an obj was dumped and scanned
PDF_PHASE_END after the pdf scan finished
PDF_PHASE_PRE before pdf is parsed at all
```

1.13.3 Function Documentation

1.13.3.1 int32_t pdf_get_dumpedobjid (void)

Return the currently dumped obj index. Valid only in PDF PHASE POSTDUMP.

Returns

```
>=0 - object index
```

-1 - invalid phase

```
1.13.3.2 int32_t pdf_get_flags ( void )
```

Return the flags for the entire PDF (as set so far).

Returns

```
-1 - if not called from PDF hook
>=0 - pdf flags
```

1.13.3.3 int32_t pdf_get_obj_num (void)

Return number of pdf objects

Returns

-1 - if not called from PDF hook>=0 - number of PDF objects

1.13.3.4 int32_t pdf_get_offset (int32_t objidx)

Return the object's offset in the PDF.

Parameters

in	objidx	- object index (from 0)
----	--------	-------------------------

Returns

-1 - object index invalid >=0 - offset

1.13.3.5 int32_t pdf_get_phase (void)

Return an 'enum pdf_phase'. Identifies at which phase this bytecode was called.

Returns

the current pdf_phase

1.13.3.6 const uint8_t* pdf_getobj (int32_t objidx, uint32_t amount)

Return the undecoded object. Meant only for reading, write modifies the fmap buffer, so avoid!

Parameters

in	objidx	- object index (from 0), not object id!
in	amount	- size returned by pdf_getobjsize (or smaller)

Returns

NULL - invalid objidx/amount pointer - pointer to original object

1.13.3.7 int32_t pdf_getobjflags (int32_t objidx)

Return the object flags for the specified object index.

1.13 PDF Handling 37

Parameters

in	objidx	- object index (from 0)
----	--------	-------------------------

Returns

-1 - object index invalid

>=0 - object flags

1.13.3.8 int32_t pdf_getobjid (int32_t objidx)

Return the object id for the specified object index.

Parameters

	- I- " -I	
ın	objidx	- object index (from 0)

Returns

-1 - object index invalid

>=0 - object id (obj id << 8 | generation id)

1.13.3.9 uint32_t pdf_getobjsize (int32_t objidx)

Return the size of the specified PDF obj.

Parameters

in	objidx	- object index (from 0), not object id!
----	--------	---

Returns

0 - if not called from PDF hook, or invalid objnum

>=0 - size of object

1.13.3.10 int32_t pdf_lookupobj (uint32_t id)

Lookup pdf object with specified id.

Parameters

in	id	- pdf id (objnumber << 8 generationid)
----	----	--

Returns

-1 - if object id doesn't exist

>=0 - object index

1.13.3.11 int32_t pdf_set_flags (int32_t flags)

Sets the flags for the entire PDF. It is recommended that you retrieve old flags, and just add new ones.

Parameters

in	flags	- flags to set.

Returns

0 - success -1 - invalid phase

1.13.3.12 int32_t pdf_setobjflags (int32_t objidx, int32_t flags)

Sets the object flags for the specified object index. This can be used to force dumping of a certain obj, by setting the OBJ_FORCEDUMP flag for example.

1.13 PDF Handling 39

Parameters

in	objidx	- object index (from 0)
in	flags	- value to set flags

Returns

-1 - object index invalid

>=0 - flags set

1.14 PE Operations

Data Structures

- · struct cli exe section
- · struct cli exe info
- · struct pe image file hdr
- · struct pe image data dir
- struct pe_image_optional_hdr32
- · struct pe image optional hdr64
- · struct pe image section hdr
- · struct cli pe hook data

Functions

- uint32 t pe rawaddr (uint32 t rva)
- int32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
- static force_inline bool hasExeInfo (void)
- static force_inline bool hasPEInfo (void)
- static force inline bool isPE64 (void)
- static force_inline uint8_t getPEMajorLinkerVersion (void)
- static force inline uint8 t getPEMinorLinkerVersion (void)
- static force_inline uint32_t getPESizeOfCode (void)
- static force_inline uint32_t getPESizeOfInitializedData (void)
- static force inline uint32 t getPESizeOfUninitializedData (void)
- static force inline uint32 t getPEBaseOfCode (void)
- static force inline uint32 t getPEBaseOfData (void)
- static force inline uint64 t getPEImageBase (void)
- static force_inline uint32_t getPESectionAlignment (void)
- static force inline uint32 t getPEFileAlignment (void)
- static force inline uint16 t getPEMajorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
- static force inline uint16 t getPEMajorImageVersion (void)
- static force_inline uint16_t getPEMinorImageVersion (void)
- static force inline uint16 t getPEMajorSubsystemVersion (void)
- static force_inline uint16_t getPEMinorSubsystemVersion (void)
- static force_inline uint32_t getPEWin32VersionValue (void)
- static force_inline uint32_t getPESizeOfImage (void)
- static force inline uint32 t getPESizeOfHeaders (void)
- static force_inline uint32_t getPECheckSum (void)
- static force inline uint16 t getPESubsystem (void)
- static force inline uint16 t getPEDIICharacteristics (void)
- static force_inline uint32_t getPESizeOfStackReserve (void)
- static force_inline uint32_t getPESizeOfStackCommit (void)
- static force_inline uint32_t getPESizeOfHeapReserve (void)
- static force_inline uint32_t getPESizeOfHeapCommit (void)
- static force_inline uint32_t getPELoaderFlags (void)
- static force_inline uint16_t getPEMachine ()
- static force_inline uint32_t getPETimeDateStamp ()
- static force_inline uint32_t getPEPointerToSymbolTable ()
- static force inline uint32_t getPENumberOfSymbols ()
- static force inline uint16 t getPESizeOfOptionalHeader ()
- static force inline uint16 t getPECharacteristics ()
- static force inline bool getPEisDLL ()

1.14 PE Operations 41

- static force_inline uint32_t getPEDataDirRVA (unsigned n)
- static force_inline uint32_t getPEDataDirSize (unsigned n)
- static force_inline uint16_t getNumberOfSections (void)
- static uint32 t getPELFANew (void)
- static force inline int readPESectionName (unsigned char name[8], unsigned n)
- static force_inline uint32_t getEntryPoint (void)
- static force_inline uint32_t getExeOffset (void)
- static force_inline uint32_t getImageBase (void)
- static uint32_t getVirtualEntryPoint (void)
- static uint32 t getSectionRVA (unsigned i)
- static uint32_t getSectionVirtualSize (unsigned i)
- static force_inline bool readRVA (uint32_t rva, void *buf, size_t bufsize)

1.14.1 Detailed Description

1.14.2 Function Documentation

1.14.2.1 int32_t get_pe_section (struct cli_exe_section * section, uint32_t num)

Gets information about the specified PE section.

Parameters

out	section	PE section information will be stored here
in	num	PE section number

Returns

- 0 success
- -1 failure

1.14.2.2 static force_inline uint32_t getEntryPoint(void) [static]

Returns the offset of the EntryPoint in the executable file.

Returns

offset of EP as 32-bit unsigned integer

1.14.2.3 static force_inline uint32_t getExeOffset (void) [static]

Returns the offset of the executable in the file.

Returns

offset of embedded executable inside file

1.14.2.4 static force_inline uint32_t getImageBase (void) [static]

Returns the ImageBase with the correct endian conversion.

Only works if the bytecode is a PE hook (i.e. you invoked PE_UNPACKER_DECLARE).

Returns

ImageBase of PE file, 0 - for non-PE hook

```
1.14.2.5 static force_inline uint16_t getNumberOfSections ( void ) [static]
Returns the number of sections in this executable file.
Returns
      number of sections as 16-bit unsigned integer
1.14.2.6 static force_inline uint32_t getPEBaseOfCode ( void ) [static]
Return the PE BaseOfCode.
Returns
      PE BaseOfCode, or 0 if not in PE hook
1.14.2.7 static force_inline uint32_t getPEBaseOfData (void ) [static]
Return the PE BaseOfData.
Returns
      PE BaseOfData, or 0 if not in PE hook
1.14.2.8 static force_inline uint16_t getPECharacteristics() [static]
Returns PE characteristics.
For example you can use this to check whether it is a DLL (0x2000).
Returns
      characteristic of PE file, or 0 if not in PE hook
1.14.2.9 static force_inline uint32_t getPECheckSum ( void ) [static]
Return the PE CheckSum.
Returns
      PE CheckSum, or 0 if not in PE hook
1.14.2.10 static force_inline uint32_t getPEDataDirRVA ( unsigned n ) [static]
Gets the virtual address of specified image data directory.
Parameters
      in
                                    image directory requested
```

Returns

Virtual Address of requested image directory

1.14.2.11 static force_inline uint32_t getPEDataDirSize (unsigned n) [static]

Gets the size of the specified image data directory.

1.14 PE Operations 43

Parameters

in	n	image directory requested
----	---	---------------------------

Returns

Size of requested image directory

1.14.2.12 static force_inline uint16_t getPEDIICharacteristics (void) [static]

Return the PE DIICharacteristics.

Returns

PE DIICharacteristics, or 0 if not in PE hook

1.14.2.13 static force_inline uint32_t getPEFileAlignment (void) [static]

Return the PE FileAlignment.

Returns

PE FileAlignment, or 0 if not in PE hook

1.14.2.14 static force_inline uint64_t getPEImageBase (void) [static]

Return the PE ImageBase as 64-bit integer.

Returns

PE ImageBase as 64-bit int, or 0 if not in PE hook

1.14.2.15 static force_inline bool getPEisDLL() [static]

Returns whether this is a DLL. Use this only in a PE hook!

Returns

true - the file is a DLL false - file is not a DLL

1.14.2.16 static uint32_t getPELFANew(void) [static]

Gets the offset to the PE header.

Returns

offset to the PE header, or 0 if not in PE hook

1.14.2.17 static force_inline uint32_t getPELoaderFlags (void) [static]

Return the PE LoaderFlags.

Returns

PE LoaderFlags or 0 if not in PE hook

```
1.14.2.18 static force_inline uint16_t getPEMachine( ) [static]
Returns the CPU this executable runs on, see libclamav/pe.c for possible values.
Returns
      PE Machine or 0 if not in PE hook
1.14.2.19 static force_inline uint16_t getPEMajorImageVersion ( void ) [static]
Return the PE MajorImageVersion.
Returns
      PE MajorImageVersion, or 0 if not in PE hook
1.14.2.20 static force_inline uint8_t getPEMajorLinkerVersion ( void ) [static]
Returns MajorLinkerVersion for this PE file.
Returns
      PE MajorLinkerVersion or 0 if not in PE hook
1.14.2.21 static force_inline uint16_t getPEMajorOperatingSystemVersion ( void ) [static]
Return the PE MajorOperatingSystemVersion.
Returns
      PE MajorOperatingSystemVersion, or 0 if not in PE hook
1.14.2.22 static force_inline uint16_t getPEMajorSubsystemVersion ( void ) [static]
Return the PE MajorSubsystemVersion.
Returns
      PE MajorSubsystemVersion or 0 if not in PE hook
1.14.2.23 static force_inline uint16_t getPEMinorImageVersion ( void ) [static]
Return the PE MinorImageVersion.
Returns
      PE MinorrImageVersion, or 0 if not in PE hook
1.14.2.24 static force_inline uint8_t getPEMinorLinkerVersion(void) [static]
Returns MinorLinkerVersion for this PE file.
Returns
      PE MinorLinkerVersion or 0 if not in PE hook
```

1.14 PE Operations 45

```
1.14.2.25 static force_inline uint16_t getPEMinorOperatingSystemVersion ( void ) [static]
Return the PE MinorOperatingSystemVersion.
Returns
     PE MinorOperatingSystemVersion, or 0 if not in PE hook
1.14.2.26 static force_inline uint16_t getPEMinorSubsystemVersion ( void ) [static]
Return the PE MinorSubsystemVersion.
Returns
     PE MinorSubsystemVersion, or 0 if not in PE hook
1.14.2.27 static force_inline uint32_t getPENumberOfSymbols() [static]
Returns the PE number of debug symbols
Returns
     PE NumberOfSymbols or 0 if not in PE hook
1.14.2.28 static force_inline uint32_t getPEPointerToSymbolTable() [static]
Returns pointer to the PE debug symbol table
Returns
     PE PointerToSymbolTable or 0 if not in PE hook
1.14.2.29 static force_inline uint32_t getPESectionAlignment(void) [static]
Return the PE SectionAlignment.
Returns
     PE SectionAlignment, or 0 if not in PE hook
1.14.2.30 static force_inline uint32_t getPESizeOfCode(void) [static]
Return the PE SizeOfCode.
Returns
     PE SizeOfCode or 0 if not in PE hook
1.14.2.31 static force_inline uint32_t getPESizeOfHeaders ( void ) [static]
Return the PE SizeOfHeaders.
Returns
     PE SizeOfHeaders, or 0 if not in PE hook
```

```
1.14.2.32 static force_inline uint32_t getPESizeOfHeapCommit(void) [static]
Return the PE SizeOfHeapCommit.
Returns
      PE SizeOfHeapCommit, or 0 if not in PE hook
1.14.2.33 static force_inline uint32_t getPESizeOfHeapReserve ( void ) [static]
Return the PE SizeOfHeapReserve.
Returns
      PE SizeOfHeapReserve, or 0 if not in PE hook
1.14.2.34 static force_inline uint32_t getPESizeOflmage ( void ) [static]
Return the PE SizeOfImage.
Returns
      PE SizeOfImage, or 0 if not in PE hook
1.14.2.35 static force_inline uint32_t getPESizeOfInitializedData ( void ) [static]
Return the PE SizeofInitializedData.
Returns
      PE SizeOfInitializeData or 0 if not in PE hook
1.14.2.36 static force_inline uint16_t getPESizeOfOptionalHeader( ) [static]
Returns the size of PE optional header.
Returns
      size of PE optional header, or 0 if not in PE hook
1.14.2.37 static force_inline uint32_t getPESizeOfStackCommit(void) [static]
Return the PE SizeOfStackCommit.
Returns
      PE SizeOfStackCommit, or 0 if not in PE hook
1.14.2.38 static force_inline uint32_t getPESizeOfStackReserve ( void ) [static]
Return the PE SizeOfStackReserve.
Returns
      PE SizeOfStackReserver, or 0 if not in PE hook
1.14.2.39 static force_inline uint32_t getPESizeOfUninitializedData ( void ) [static]
Return the PE SizeofUninitializedData.
Returns
      PE SizeofUninitializedData or 0 if not in PE hook
```

1.14 PE Operations 47

```
1.14.2.40 static force_inline uint16_t getPESubsystem ( void ) [static]
Return the PE Subsystem.
Returns
      PE subsystem, or 0 if not in PE hook
1.14.2.41 static force_inline uint32_t getPETimeDateStamp( ) [static]
Returns the PE TimeDateStamp from headers
Returns
      PE TimeDateStamp or 0 if not in PE hook
1.14.2.42 static force_inline uint32_t getPEWin32VersionValue ( void ) [static]
Return the PE Win32VersionValue.
Returns
      PE Win32VersionValue, or 0 if not in PE hook
1.14.2.43 static uint32_t getSectionRVA (unsigned i) [static]
Return the RVA of the specified section.
Parameters
                  i section index (from 0)
Returns
      RVA of section, or -1 if invalid
1.14.2.44 static uint32_t getSectionVirtualSize (unsigned i) [static]
Return the virtual size of the specified section.
Parameters
                  i section index (from 0)
Returns
      VSZ of section, or -1 if invalid
1.14.2.45 static uint32_t getVirtualEntryPoint(void) [static]
The address of the EntryPoint. Use this for matching EP against sections.
Returns
      virtual address of EntryPoint, or 0 if not in PE hook
1.14.2.46 static force_inline bool hasExeInfo ( void ) [static]
Returns whether the current file has executable information.
Returns
      true if the file has exe info, false otherwise
```

1.14.2.47 static force_inline bool hasPEInfo (void) [static]

Returns whether PE information is available

Returns

true if PE information is available (in PE hooks)

1.14.2.48 static force_inline bool isPE64 (void) [static]

Returns whether this is a PE32+ executable.

Returns

true if this is a PE32+ executable

1.14.2.49 uint32_t pe_rawaddr (uint32_t rva)

Converts a RVA (Relative Virtual Address) to an absolute PE file offset.

Parameters

in	rva	a rva address from the PE file
----	-----	--------------------------------

Returns

absolute file offset mapped to the rva, or PE_INVALID_RVA if the rva is invalid.

1.14.2.50 static force_inline int readPESectionName (unsigned char name[8], unsigned n) [static]

Read name of requested PE section.

Parameters

out	name	name of PE section
in	n	PE section requested

Returns

0 if successful,

<0 otherwise

1.14.2.51 static force_inline bool readRVA (uint32_t rva, void * buf, size_t bufsize) [static]

read the specified amount of bytes from the PE file, starting at the address specified by RVA.

Parameters

in	rva	the Relative Virtual Address you want to read from (will be converted to file offset)
out	buf	destination buffer
in	bufsize	size of buffer

Returns

true on success (full read) false on any failure

1.15 Scan Control 49

1.15 Scan Control

Functions

- uint32_t setvirusname (const uint8_t *name, uint32_t len)
- int32_t extract_new (int32_t id)
- int32_t bytecode_rt_error (int32_t locationid)
- int32_t extract_set_container (uint32_t container)
- int32_t input_switch (int32_t extracted_file)
- static force_inline overloadable_func void foundVirus (const char *virusname)

1.15.1 Detailed Description

1.15.2 Function Documentation

1.15.2.1 int32_t bytecode_rt_error (int32_t locationid)

Report a runtime error at the specified locationID.

Parameters

in	locationid	(line << 8) (column&0xff)
----	------------	-----------------------------

Returns

0

1.15.2.2 int32_t extract_new (int32_t id)

Prepares for extracting a new file, if we've already extracted one it scans it.

Parameters

in	id	an id for the new file (for example position in container)

Returns

1 if previous extracted file was infected

1.15.2.3 int32_t extract_set_container (uint32_t container)

Sets the container type for the currently extracted file.

Parameters

in	container	container type (CL_TYPE_*)
----	-----------	----------------------------

Returns

current setting for container (CL_TYPE_ANY default)

1.15.2.4 static force_inline overloadable_func void foundVirus (const char * virusname) [static]

Sets the specified virusname as the virus detected by this bytecode.

Parameters

in	virusname	the name of the virus, excluding the prefix, must be one of the virusnames
		declared in VIRUSNAMES.

See Also

VIRUSNAMES

1.15.2.5 int32_t input_switch (int32_t extracted_file)

Toggles the read/seek API to read from the currently extracted file, and back. You must call seek after switching inputs to position the cursor to a valid position.

Parameters

in	extracted_file	1 - switch to reading from extracted file
		0 - switch back to original input

Returns

-1 on error (if no extracted file exists)

0 on success

1.15.2.6 uint32_t setvirusname (const uint8_t * name, uint32_t len)

Sets the name of the virus found.

Parameters

in	name	the name of the virus
in	len	length of the virusname

Returns

0

1.16 String Operations

Functions

- int32_t memstr (const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needlesize)
- int32_t hex2ui (uint32_t hex1, uint32_t hex2)
- int32 t atoi (const uint8 t *str, int32 t size)
- uint32_t entropy_buffer (uint8_t *buffer, int32_t size)
- static force_inline void * memchr (const void *s, int c, size_t n)
- void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__((__nonnull__((1))))
- void * memmove (void *dst, const void *src, uintptr_t n) __attribute__((__nothrow__)) __attribute__((__-nothrow__))
- void void * memcpy (void *restrict dst, const void *restrict src, uintptr_t n) __attribute__((__nothrow__)) __ attribute__((__nonnull__(1
- void void int memcmp (const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow__)) __attribute__(__nonnull__(1

1.16.1 Detailed Description

1.16.2 Function Documentation

1.16.2.1 int32_t atoi (const uint8_t * str, int32_t size)

Converts string to positive number.

Parameters

	in	str	buffer
Ī	in	size	size of str

Returns

>0 string converted to number if possible, -1 on error

1.16.2.2 uint32_t entropy_buffer (uint8_t * buffer, int32_t size)

Returns an approximation for the entropy of buffer.

Parameters

in	buffer	input buffer
in	size	size of buffer

Returns

entropy estimation $*2^{\wedge}26$

1.16.2.3 int32_t hex2ui (uint32_t hex1, uint32_t hex2)

Returns hexadecimal characters <code>hex1</code> and <code>hex2</code> converted to 8-bit number.

Parameters

in	hex1	hexadecimal character
----	------	-----------------------

in	hex2	hexadecimal character
111	TICAL	nexadedinar diaracter

Returns

hex1 hex2 converted to 8-bit integer, -1 on error

1.16.2.4 static force_inline void* memchr (const void * s, int c, size_t n) [static]

Scan the first n bytes of the buffer s, for the character c.

Parameters

in	s	buffer to scan
in	С	character to look for
in	n	size of buffer

Returns

a pointer to the first byte to match, or NULL if not found.

1.16.2.5 void void int memcmp (const void * s1, const void * s2, uint32_t n)

[LLVM Intrinsic] Compares two memory buffers, s1 and s2 to length n.

Parameters

in	s1	buffer one
in	s2	buffer two
in	n	amount of bytes to copy

Returns

an integer less than, equal to, or greater than zero if the first n bytes of s1 are found, respectively, to be less than, to match, or be greater than the first n bytes of s2.

1.16.2.6 void void* memcpy (void *restrict dst, const void *restrict src, uintptr_t n)

[LLVM Intrinsic] Copies data between two non-overlapping buffers, from $\verb"src"$ to $\verb"dst"$ to length n.

Parameters

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

Returns

dst

1.16.2.7 void* memmove (void * dst, const void * src, uintptr_t n)

[LLVM Intrinsic] Copies data between overlapping buffers, from src to dst to length n.

Parameters

Generated on Wed May 7 2014 14:19:22 by Doxygen

out	dst	destination buffer
in	src	source buffer
in	n	amount of bytes to copy

Returns

dst

1.16.2.8 void* memset (void * src, int c, uintptr_t n)

[LLVM Intrinsic] Fills src location with c up to length n.

Parameters

	out	src	pointer to buffer
ſ	in	С	character to fill buffer with
	in	n	length of buffer

Returns

src

1.16.2.9 int32_t memstr (const uint8_t * haystack, int32_t haysize, const uint8_t * needle, int32_t needlesize)

Return position of match, -1 otherwise.

Parameters

in	haystack	buffer to search
in	haysize	size of haystack
in	needle	substring to search
in	needlesize	size of needle

Returns

location of match, -1 otherwise

2 Data Structure Documentation

2.1 cli_exe_info Struct Reference

Data Fields

- struct cli_exe_section * section
- uint32_t offset
- uint32 t ep
- uint16_t nsections
- · uint32_t res_addr
- uint32_t hdr_size

2.1.1 Detailed Description

Executable file information

2.1.2 Field Documentation

2.1.2.1 uint32_t ep

Entrypoint of executable

2.1.2.2 uint32_t hdr_size

Address size - PE ONLY

2.1.2.3 uint16_t nsections

Number of sections

2.1.2.4 uint32_t offset

Offset where this executable start in file (nonzero if embedded)

2.1.2.5 uint32_t res_addr

Resrources RVA - PE ONLY

2.1.2.6 struct cli_exe_section* section

Information about all the sections of this file. This array has nsection elements

2.2 cli_exe_section Struct Reference

Data Fields

- uint32_t rva
- uint32_t vsz
- uint32_t raw
- uint32_t rsz
- uint32_t chr
- uint32_t urva
- uint32_t uvsz
- · uint32_t uraw
- uint32_t ursz

2.2.1 Detailed Description

Section of executable file.

2.2.2 Field Documentation

2.2.2.1 uint32_t chr

Section characteristics

2.2.2.2 uint32_t raw

Raw offset (in file)

2.2.2.3 uint32_t rsz

Raw size (in file)

2.2.2.4 uint32_t rva

Relative VirtualAddress

2.2.2.5 uint32_t uraw

PE - unaligned PointerToRawData

2.2.2.6 uint32_t ursz

PE - unaligned SizeOfRawData

2.2.2.7 uint32_t urva

PE - unaligned VirtualAddress

2.2.2.8 uint32_t uvsz

PE - unaligned VirtualSize

2.2.2.9 uint32_t vsz

VirtualSize

2.3 cli_pe_hook_data Struct Reference

Data Fields

- uint32_t ep
- uint16_t nsections
- struct pe_image_file_hdr file_hdr
- struct pe_image_optional_hdr32 opt32
- struct pe_image_optional_hdr64 opt64
- struct pe_image_data_dir dirs [16]
- uint32_t e_lfanew
- uint32_t overlays
- · int32_t overlays_sz
- uint32_t hdr_size

2.3.1 Detailed Description

Data for the bytecode PE hook

2.3.2 Field Documentation

2.3.2.1 struct pe_image_data_dir dirs[16]

PE data directory header

2.3.2.2 uint32_t e_lfanew

address of new exe header

2.3.2.3 uint32_t ep

EntryPoint as file offset

2.3.2.4 struct pe_image_file_hdr file_hdr

Header for this PE file

2.3.2.5 uint32_t hdr_size

internally needed by rawaddr

2.3.2.6 uint16_t nsections

Number of sections

2.3.2.7 struct pe_image_optional_hdr32 opt32

32-bit PE optional header

2.3.2.8 struct pe_image_optional_hdr64 opt64

64-bit PE optional header

2.3.2.9 uint32_t overlays

number of overlays

2.3.2.10 int32_t overlays_sz

size of overlays

2.4 DIS_arg Struct Reference

Data Fields

- enum DIS_ACCESS access_type
- enum DIS_SIZE access_size
- struct DIS_mem_arg mem
- enum X86REGS reg
- uint64_t other

2.4.1 Detailed Description

Disassembled operand.

2.4.2 Field Documentation

2.4.2.1 enum DIS_SIZE access_size

size of access

2.4.2.2 enum DIS_ACCESS access_type

type of access

2.4.2.3 struct DIS_mem_arg mem

memory operand

2.4.2.4 uint64_t other

other operand

2.4.2.5 enum X86REGS reg

register operand

2.5 DIS_fixed Struct Reference

Data Fields

- enum X86OPS x86_opcode
- enum DIS_SIZE operation_size
- enum DIS_SIZE address_size
- uint8_t segment
- struct DIS_arg arg [3]

2.5.1 Detailed Description

Disassembled instruction.

2.5.2 Field Documentation

2.5.2.1 enum DIS_SIZE address_size

size of address

2.5.2.2 struct DIS_arg arg[3]

arguments

2.5.2.3 enum DIS_SIZE operation_size

size of operation

2.5.2.4 uint8_t segment

segment

2.5.2.5 enum X86OPS x86_opcode

opcode of X86 instruction

2.6 DIS_mem_arg Struct Reference

Data Fields

- enum DIS_SIZE access_size
- enum X86REGS scale_reg
- · enum X86REGS add reg
- uint8_t scale
- · int32_t displacement

2.6.1 Detailed Description

Disassembled memory operand: scale_reg*scale + add_reg + displacement.

- 2.6.2 Field Documentation
- 2.6.2.1 enum DIS SIZE access_size

size of access

2.6.2.2 enum X86REGS add_reg

register used as displacemenet

2.6.2.3 int32_t displacement

displacement as immediate number

2.6.2.4 uint8_t scale

scale as immediate number

2.6.2.5 enum X86REGS scale_reg

register used as scale

2.7 DISASM_RESULT Struct Reference

2.7.1 Detailed Description

disassembly result, 64-byte, matched by type-8 signatures

- 2.8 pe_image_data_dir Struct Reference
- 2.8.1 Detailed Description

PE data directory header

2.9 pe_image_file_hdr Struct Reference

Data Fields

- uint32_t Magic
- uint16_t Machine
- uint16_t NumberOfSections

- uint32_t TimeDateStamp
- uint32_t PointerToSymbolTable
- uint32_t NumberOfSymbols
- uint16_t SizeOfOptionalHeader

2.9.1 Detailed Description

Header for this PE file

2.9.2 Field Documentation

2.9.2.1 uint16_t Machine

CPU this executable runs on, see libclamav/pe.c for possible values

2.9.2.2 uint32_t Magic

PE magic header: PE\0\0

2.9.2.3 uint16_t NumberOfSections

Number of sections in this executable

2.9.2.4 uint32_t NumberOfSymbols

debug

2.9.2.5 uint32_t PointerToSymbolTable

debug

2.9.2.6 uint16_t SizeOfOptionalHeader

== 224

2.9.2.7 uint32_t TimeDateStamp

Unreliable

2.10 pe_image_optional_hdr32 Struct Reference

Data Fields

- uint8_t MajorLinkerVersion
- uint8_t MinorLinkerVersion
- uint32_t SizeOfCode
- uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- uint32_t ImageBase
- uint32_t SectionAlignment
- uint32_t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32_t NumberOfRvaAndSizes

2.10.1 Detailed Description

32-bit PE optional header

2.10.2 Field Documentation

2.10.2.1 uint32_t CheckSum

NT drivers only

2.10.2.2 uint32_t FileAlignment

usually 32 or 512

2.10.2.3 uint32_t ImageBase

multiple of 64 KB

2.10.2.4 uint16_t MajorlmageVersion

unreliable

2.10.2.5 uint8_t MajorLinkerVersion

unreliable

2.10.2.6 uint16_t MajorOperatingSystemVersion

not used

2.10.2.7 uint16_t MinorImageVersion

unreliable

2.10.2.8 uint8 t MinorLinkerVersion

unreliable

2.10.2.9 uint16_t MinorOperatingSystemVersion

not used

2.10.2.10 uint32_t NumberOfRvaAndSizes

unreliable

2.10.2.11 uint32_t SectionAlignment

usually 32 or 4096

2.10.2.12 uint32_t SizeOfCode

unreliable

2.10.2.13 uint32_t SizeOfInitializedData

unreliable

2.10.2.14 uint32_t SizeOfUninitializedData

unreliable

2.11 pe_image_optional_hdr64 Struct Reference

Data Fields

- uint8_t MajorLinkerVersion
- uint8_t MinorLinkerVersion
- uint32_t SizeOfCode
- uint32_t SizeOfInitializedData
- uint32_t SizeOfUninitializedData
- uint64_t ImageBase
- uint32_t SectionAlignment
- uint32 t FileAlignment
- uint16_t MajorOperatingSystemVersion
- uint16_t MinorOperatingSystemVersion
- uint16_t MajorImageVersion
- uint16_t MinorImageVersion
- uint32_t CheckSum
- uint32_t NumberOfRvaAndSizes

2.11.1 Detailed Description

PE 64-bit optional header

2.11.2 Field Documentation

2.11.2.1 uint32_t CheckSum

NT drivers only

2.11.2.2 uint32_t FileAlignment

usually 32 or 512

2.11.2.3 uint64_t ImageBase

multiple of 64 KB

2.11.2.4 uint16_t MajorlmageVersion

unreliable

2.11.2.5 uint8_t MajorLinkerVersion

unreliable

2.11.2.6 uint16_t MajorOperatingSystemVersion

not used

2.11.2.7 uint16_t MinorImageVersion

unreliable

2.11.2.8 uint8_t MinorLinkerVersion

unreliable

2.11.2.9 uint16_t MinorOperatingSystemVersion
not used
2.11.2.10 uint32_t NumberOfRvaAndSizes
unreliable
2.11.2.11 uint32_t SectionAlignment
usually 32 or 4096
2.11.2.12 uint32_t SizeOfCode
unreliable
2.11.2.13 uint32_t SizeOfInitializedData

2.11.2.14 uint32_t SizeOfUninitializedData

unreliable

unreliable

2.12 pe_image_section_hdr Struct Reference

Data Fields

- uint8_t Name [8]
- uint32_t SizeOfRawData
- uint32_t PointerToRawData
- uint32_t PointerToRelocations
- uint32_t PointerToLinenumbers
- uint16_t NumberOfRelocations
- uint16_t NumberOfLinenumbers

2.12.1 Detailed Description

PE section header

2.12.2 Field Documentation

2.12.2.1 uint8_t Name[8]

may not end with NULL

2.12.2.2 uint16_t NumberOfLinenumbers

object files only

2.12.2.3 uint16_t NumberOfRelocations

object files only

2.12.2.4 uint32_t PointerToLinenumbers

object files only

3 File Documentation 63

```
2.12.2.5 uint32_t PointerToRawData
offset to the section's data
2.12.2.6 uint32_t PointerToRelocations
object files only
2.12.2.7 uint32_t SizeOfRawData
multiple of FileAlignment
```

3 File Documentation

3.1 bytecode api.h File Reference

Enumerations

```
    enum BytecodeKind {

 BC GENERIC =0, BC STARTUP =1, BC LOGICAL =256, BC PE UNPACKER,
 BC_PDF, BC_PE_ALL }
enum { PE_INVALID_RVA = 0xFFFFFFFF }
enum FunctionalityLevels {
 FUNC_LEVEL_096 = 51 , FUNC_LEVEL_096_1 = 53 , FUNC_LEVEL_096_2 = 54 , FUNC_LEVEL_096_3
 = 55,
 FUNC_LEVEL_096_4 = 56, FUNC_LEVEL_096_5 = 58, FUNC_LEVEL_097 = 60, FUNC_LEVEL_097_1 =
 FUNC_LEVEL_097_2 = 62, FUNC_LEVEL_097_3 = 63, FUNC_LEVEL_097_4 = 64, FUNC_LEVEL_097_5
 FUNC_LEVEL_097_6 = 67, FUNC_LEVEL_097_7 = 68, FUNC_LEVEL_097_8 = 69, FUNC_LEVEL_098_1
 = 76,
 FUNC_LEVEL_098_2 = 77, FUNC_LEVEL_098_3 = 77, FUNC_LEVEL_098_4 = 78 }
• enum pdf_phase { , PDF_PHASE_PARSED, PDF_PHASE_POSTDUMP, PDF_PHASE_END, PDF_PHAS-
 E PRE }

    enum pdf_flag

    enum pdf_objflags

enum bc_json_type
• enum { SEEK SET =0, SEEK CUR, SEEK END }
```

Functions

```
uint32_t test1 (uint32_t a, uint32_t b)
int32_t read (uint8_t *data, int32_t size)
int32_t write (uint8_t *data, int32_t size)
int32_t seek (int32_t pos, uint32_t whence)
uint32_t setvirusname (const uint8_t *name, uint32_t len)
uint32_t debug_print_str (const uint8_t *str, uint32_t len)
uint32_t debug_print_uint (uint32_t a)
uint32_t disasm_x86 (struct DISASM_RESULT *result, uint32_t len)
uint32_t pe_rawaddr (uint32_t rva)
int32_t file_find (const uint8_t *data, uint32_t len)
int32_t file_byteat (uint32_t offset)
void * malloc (uint32_t size)
uint32_t get_pe_section (struct cli_exe_section *section, uint32_t num)
```

```
    int32_t fill_buffer (uint8_t *buffer, uint32_t len, uint32_t filled, uint32_t cursor, uint32_t fill)

• int32 t extract new (int32 t id)
int32_t read_number (uint32_t radix)
• int32 t hashset new (void)

    int32 t hashset add (int32 t hs, uint32 t key)

int32_t hashset_remove (int32_t hs, uint32_t key)

    int32 t hashset contains (int32 t hs, uint32 t key)

    int32_t hashset_done (int32_t id)

    int32_t hashset_empty (int32_t id)

    int32 t buffer pipe new (uint32 t size)

• int32 t buffer pipe new fromfile (uint32 t pos)

    uint32 t buffer pipe read avail (int32 t id)

    const uint8_t * buffer_pipe_read_get (int32_t id, uint32_t amount)

    int32 t buffer pipe read stopped (int32 t id, uint32 t amount)

• uint32_t buffer_pipe_write_avail (int32_t id)

    uint8 t * buffer pipe write get (int32 t id, uint32 t size)

    int32 t buffer pipe write stopped (int32 t id, uint32 t amount)

    int32 t buffer pipe done (int32 t id)

• int32_t inflate_init (int32_t from_buffer, int32_t to_buffer, int32_t windowBits)

    int32_t inflate_process (int32_t id)

• int32_t inflate_done (int32_t id)

    int32_t bytecode_rt_error (int32_t locationid)

• int32 t jsnorm init (int32 t from buffer)

    int32_t jsnorm_process (int32_t id)

• int32 t isnorm done (int32 t id)

    int32_t ilog2 (uint32_t a, uint32_t b)

    int32_t ipow (int32_t a, int32_t b, int32_t c)

    uint32 t iexp (int32 t a, int32 t b, int32 t c)

    int32 t isin (int32 t a, int32 t b, int32 t c)

    int32_t icos (int32_t a, int32_t b, int32_t c)

    int32_t memstr (const uint8_t *haystack, int32_t haysize, const uint8_t *needle, int32_t needlesize)

    int32 t hex2ui (uint32 t hex1, uint32 t hex2)

    int32_t atoi (const uint8_t *str, int32_t size)

• uint32_t debug_print_str_start (const uint8_t *str, uint32_t len)

    uint32 t debug print str nonl (const uint8 t *str, uint32 t len)

    uint32 t entropy buffer (uint8 t *buffer, int32 t size)

    int32 t map new (int32 t keysize, int32 t valuesize)

    int32_t map_addkey (const uint8_t *key, int32_t ksize, int32_t id)

    int32_t map_setvalue (const uint8_t *value, int32_t vsize, int32_t id)

• int32 t map remove (const uint8 t *key, int32 t ksize, int32 t id)
• int32 t map find (const uint8 t *key, int32 t ksize, int32 t id)

    int32_t map_getvaluesize (int32_t id)

    uint8 t * map getvalue (int32 t id, int32 t size)

• int32_t map_done (int32_t id)

    int32_t file_find_limit (const uint8_t *data, uint32_t len, int32_t maxpos)

· uint32 t engine functionality level (void)

    uint32 t engine dconf level (void)

    uint32_t engine_scan_options (void)

    uint32_t engine_db_options (void)

    int32_t extract_set_container (uint32_t container)

• int32 t input switch (int32 t extracted file)

    uint32 t get environment (struct cli environment *env, uint32 t len)

    uint32 t disable bytecode if (const int8 t *reason, uint32 t len, uint32 t cond)

    uint32 t disable jit if (const int8 t *reason, uint32 t len, uint32 t cond)
```

int32_t version_compare (const uint8_t *lhs, uint32_t lhs_len, const uint8_t *rhs, uint32_t rhs_len)

 uint32_t check_platform (uint32_t a, uint32_t b, uint32_t c) • int32_t pdf_get_obj_num (void) • int32 t pdf get flags (void) int32_t pdf_set_flags (int32_t flags) int32_t pdf_lookupobj (uint32_t id) uint32_t pdf_getobjsize (int32_t objidx) const uint8_t * pdf_getobj (int32_t objidx, uint32_t amount) • int32_t pdf_getobjid (int32_t objidx) int32_t pdf_getobjflags (int32_t objidx) • int32 t pdf setobiflags (int32 t objidx, int32 t flags) int32 t pdf get offset (int32 t objidx) • int32_t pdf_get_phase (void) int32_t pdf_get_dumpedobjid (void) int32_t matchicon (const uint8_t *group1, int32_t group1_len, const uint8_t *group2, int32_t group2_len) int32 t running on jit (void) • int32 t get file reliability (void) int32_t json_is_active (void) int32_t json_get_object (const int8_t *name, int32_t name_len, int32_t objid) int32_t json_get_type (int32_t objid) int32_t json_get_array_length (int32_t objid) • int32 t json get array idx (int32 t idx, int32 t objid) int32_t json_get_string_length (int32_t objid) • int32_t json_get_string (int8_t *str, int32_t str_len, int32_t objid) int32_t json_get_boolean (int32_t objid) • int32_t json_get_int (int32_t objid) Variables const uint32_t __clambc_match_counts [64] This is a low-level variable, use the Macros in bytecode_local.h instead to access it. const uint32_t __clambc_match_offsets [64] This is a low-level variable, use the Macros in bytecode_local.h instead to access it. • const struct cli_pe_hook_data __clambc_pedata const uint32 t clambc filesize [1] • const uint16_t __clambc_kind 3.1.1 Enumeration Type Documentation 3.1.1.1 anonymous enum

Enumerator

PE_INVALID_RVA Invalid RVA specified

```
3.1.2 Function Documentation
```

3.1.2.1 uint32_t test1 (uint32_t a, uint32_t b)

Test api.

Parameters

in	а	0xf00dbeef
in	b	0xbeeff00d

Returns

0x12345678 if parameters match, 0x55 otherwise

3.1.2.2 uint32_t test2 (uint32_t a)

Test api2.

Parameters

in	a	0xf00d
111	u	Oxiood

Returns

0xd00f if parameter matches, 0x5555 otherwise

3.2 bytecode_disasm.h File Reference

Data Structures

• struct DISASM_RESULT

Enumerations

```
    enum X86OPS { ,

     OP_AAA, OP_AAD, OP_AAM, OP_AAS,
     OP_ADD, OP_ADC, OP_AND, OP_ARPL,
     OP_BOUND, OP_BSF, OP_BSR, OP_BSWAP,
     OP_BT, OP_BTC, OP_BTR, OP_BTS,
     OP CALL, OP CDQ, OP CWDE, OP CBW,
     OP CLC, OP CLD, OP CLI, OP CLTS,
     OP_CMC, OP_CMOVO, OP_CMOVNO, OP_CMOVC,
     OP CMOVNC, OP CMOVZ, OP CMOVNZ, OP CMOVBE,
     OP CMOVA, OP CMOVS, OP CMOVNS, OP CMOVP,
     OP_CMOVNP, OP_CMOVL, OP_CMOVGE, OP_CMOVLE,
     OP_CMOVG, OP_CMP, OP_CMPSD, OP_CMPSW,
     OP CMPSB, OP CMPXCHG, OP CMPXCHG8B, OP CPUID,
     OP DAA, OP DAS, OP DEC, OP DIV,
     OP_ENTER, OP_FWAIT, OP_HLT, OP_IDIV,
     OP_IMUL, OP_INC, OP_IN, OP_INSD,
     OP INSW, OP INSB, OP INT, OP INT3,
     OP INTO, OP INVD, OP INVLPG, OP IRET,
     OP_JO, OP_JNO, OP_JC, OP_JNC,
     OP_JZ, OP_JNZ, OP_JBE, OP_JA,
     OP_JS, OP_JNS, OP_JP, OP_JNP,
     OP JL, OP JGE, OP JLE, OP JG,
     OP_JMP, OP_LAHF, OP_LAR, OP_LDS,
     OP_LES, OP_LFS, OP_LGS, OP_LEA,
     OP_LEAVE, OP_LGDT, OP_LIDT, OP_LLDT,
     OP_PREFIX_LOCK, OP_LODSD, OP_LODSW, OP_LODSB,
     OP_LOOP, OP_LOOPE, OP_LOOPNE, OP_JECXZ,
     OP LSL, OP LSS, OP LTR, OP MOV,
     OP MOVSD, OP MOVSW, OP MOVSB, OP MOVSX,
     OP MOVZX, OP MUL, OP NEG, OP NOP,
     OP_NOT, OP_OR, OP_OUT, OP_OUTSD,
     OP_OUTSW, OP_OUTSB, OP_PUSH, OP_PUSHAD,
     OP PUSHFD, OP POP, OP POPAD, OP POPFD,
     OP_RCL, OP_RCR, OP_RDMSR, OP_RDPMC,
     OP_RDTSC, OP_PREFIX_REPE, OP_PREFIX_REPNE, OP_RETF,
     OP_RETN, OP_ROL, OP_ROR, OP_RSM,
     OP_SAHF, OP_SAR, OP_SBB, OP_SCASD,
     OP_SCASW, OP_SCASB, OP_SETO, OP_SETNO,
     OP_SETC, OP_SETNC, OP_SETZ, OP_SETNZ,
     OP_SETBE, OP_SETA, OP_SETS, OP_SETNS,
     OP_SETP, OP_SETNP, OP_SETL, OP_SETGE,
     OP_SETLE, OP_SETG, OP_SGDT, OP_SIDT,
     OP_SHL, OP_SHLD, OP_SHR, OP_SHRD,
     OP_SLDT, OP_STOSD, OP_STOSW, OP_STOSB,
     OP_STR, OP_STC, OP_STD, OP_STI,
     OP_SUB, OP_SYSCALL, OP_SYSENTER, OP_SYSEXIT,
     OP_SYSRET, OP_TEST, OP_UD2, OP_VERR,
     OP_VERRW, OP_WBINVD, OP_WRMSR, OP_XADD,
     OP XCHG, OP XLAT, OP XOR, OP FPU,
     OP_F2XM1, OP_FABS, OP_FADD, OP_FADDP,
     OP FBLD, OP FBSTP, OP FCHS, OP FCLEX,
     OP FCMOVB, OP FCMOVBE, OP FCMOVE, OP FCMOVNB,
     OP FCMOVNBE, OP FCMOVNE, OP FCMOVNU, OP FCMOVU,
     OP_FCOM, OP_FCOMI, OP_FCOMIP, OP_FCOMP,
     OP FCOMPP, OP FCOS, OP FDECSTP, OP FDIV,
     OP_FDIVP, OP_FDIVR, OP_FDIVRP, OP_FFREE,
     OP_FIADD, OP_FICOM, OP_FICOMP, OP_FIDIV,
     OP_FIDIVR, OP_FILD, OP_FIMUL, OP_FINCSTP,
OP_FINIT, OP_FIST_OP_FISTP, OP_FISTTP,
Generated on Wed May 7 2014 14:19:22 by Doxygen
OP_FISUB, OP_FISUBR, OP_FLD, OP_FLD1,
```

OP_FLDLG2, OP_FLDLN2, OP_FLDPI, OP_FLDLAR,

OP_FLDLG2, OP_FLDLN2, OP_FLDPI, OP_FLDZ,

OP_FLDLG2, OP_FLDLN2, OP_FLDPI, OP_FLDZ,

OP_FLDLG2, OP_FLDLN2, OP_FLDPI, OP_FLDZ,

```
OP_FYL2XP1 }
    enum DIS_ACCESS {
      ACCESS_NOARG, ACCESS_IMM, ACCESS_REL, ACCESS_REG,
      ACCESS_MEM }
    • enum DIS_SIZE {
      SIZEB, SIZEW, SIZED, SIZEF,
      SIZEQ, SIZET, SIZEPTR }
    • enum X86REGS
3.2.1 Enumeration Type Documentation
3.2.1.1 enum DIS ACCESS
Access type
Enumerator
    ACCESS_NOARG arg not present
    ACCESS_IMM immediate
    ACCESS_REL +/- immediate
    ACCESS_REG register
    ACCESS_MEM [memory]
3.2.1.2 enum DIS_SIZE
for mem access, immediate and relative
Enumerator
    SIZEB Byte size access
    SIZEW Word size access
    SIZED Doubleword size access
    SIZEF 6-byte access (seg+reg pair)
    SIZEQ Quadword access
    SIZET 10-byte access
    SIZEPTR ptr
3.2.1.3 enum X86OPS
X86 opcode
Enumerator
    OP_AAA Ascii Adjust after Addition
    OP_AAD Ascii Adjust AX before Division
     OP_AAM Ascii Adjust AX after Multiply
     OP_AAS Ascii Adjust AL after Subtraction
     OP_ADD Add
    OP_ADC Add with Carry
     OP_AND Logical And
    OP_ARPL Adjust Requested Privilege Level
     OP_BOUND Check Array Index Against Bounds
     OP_BSF Bit Scan Forward
```

- OP_BSR Bit Scan Reverse
- OP_BSWAP Byte Swap
- OP_BT Bit Test
- OP_BTC Bit Test and Complement
- OP BTR Bit Test and Reset
- OP_BTS Bit Test and Set
- OP CALL Call
- OP_CDQ Convert DoubleWord to QuadWord
- OP_CWDE Convert Word to DoubleWord
- OP_CBW Convert Byte to Word
- OP_CLC Clear Carry Flag
- OP_CLD Clear Direction Flag
- OP_CLI Clear Interrupt Flag
- OP_CLTS Clear Task-Switched Flag in CR0
- OP_CMC Complement Carry Flag
- OP_CMOVO Conditional Move if Overflow
- OP_CMOVNO Conditional Move if Not Overflow
- OP_CMOVC Conditional Move if Carry
- **OP_CMOVNC** Conditional Move if Not Carry
- OP_CMOVZ Conditional Move if Zero
- OP_CMOVNZ Conditional Move if Non-Zero
- OP_CMOVBE Conditional Move if Below or Equal
- OP_CMOVA Conditional Move if Above
- OP_CMOVS Conditional Move if Sign
- OP_CMOVNS Conditional Move if Not Sign
- OP_CMOVP Conditional Move if Parity
- OP_CMOVNP Conditional Move if Not Parity
- OP_CMOVL Conditional Move if Less
- OP_CMOVGE Conditional Move if Greater or Equal
- OP_CMOVLE Conditional Move if Less than or Equal
- OP_CMOVG Conditional Move if Greater
- **OP_CMP** Compare
- OP_CMPSD Compare String DoubleWord
- OP_CMPSW Compare String Word
- OP_CMPSB Compare String Byte
- OP_CMPXCHG Compare and Exchange
- OP_CMPXCHG8B Compare and Exchange Bytes
- OP_CPUID CPU Identification
- OP_DAA Decimal Adjust AL after Addition
- OP_DAS Decimal Adjust AL after Subtraction
- OP_DEC Decrement by 1
- OP_DIV Unsigned Divide
- **OP_ENTER** Make Stack Frame for Procedure Parameters
- **OP FWAIT** Wait
- OP_HLT Halt

- OP_IDIV Signed Divide
- OP_IMUL Signed Multiply
- OP_INC Increment by 1
- **OP_IN** INput from port
- OP_INSD INput from port to String Doubleword
- OP_INSW INput from port to String Word
- OP_INSB INput from port to String Byte
- **OP_INT** INTerrupt
- **OP_INT3** INTerrupt 3 (breakpoint)
- OP_INTO INTerrupt 4 if Overflow
- OP_INVD Invalidate Internal Caches
- OP_INVLPG Invalidate TLB Entry
- OP_IRET Interrupt Return
- **OP_JO** Jump if Overflow
- OP_JNO Jump if Not Overflow
- OP_JC Jump if Carry
- OP_JNC Jump if Not Carry
- OP_JZ Jump if Zero
- OP_JNZ Jump if Not Zero
- OP_JBE Jump if Below or Equal
- OP_JA Jump if Above
- OP_JS Jump if Sign
- *OP_JNS* Jump if Not Sign
- OP_JP Jump if Parity
- OP_JNP Jump if Not Parity
- OP_JL Jump if Less
- OP_JGE Jump if Greater or Equal
- OP_JLE Jump if Less or Equal
- OP_JG Jump if Greater
- **OP_JMP** Jump (unconditional)
- OP_LAHF Load Status Flags into AH Register
- OP_LAR load Access Rights Byte
- OP_LDS Load Far Pointer into DS
- OP_LES Load Far Pointer into ES
- OP_LFS Load Far Pointer into FS
- OP_LGS Load Far Pointer into GS
- OP_LEA Load Effective Address
- OP_LEAVE High Level Procedure Exit
- OP_LGDT Load Global Descript Table Register
- OP_LIDT Load Interrupt Descriptor Table Register
- OP_LLDT Load Local Descriptor Table Register
- OP_PREFIX_LOCK Assert LOCK# Signal Prefix
- OP_LODSD Load String Dword
- OP_LODSW Load String Word
- OP_LODSB Load String Byte

- OP_LOOP Loop According to ECX Counter
- OP_LOOPE Loop According to ECX Counter and ZF=1
- **OP_LOOPNE** Looop According to ECX Counter and ZF=0
- OP_JECXZ Jump if ECX is Zero
- OP_LSL Load Segment Limit
- OP_LSS Load Far Pointer into SS
- OP_LTR Load Task Register
- **OP_MOV** Move
- OP_MOVSD Move Data from String to String Doubleword
- OP_MOVSW Move Data from String to String Word
- OP_MOVSB Move Data from String to String Byte
- OP_MOVSX Move with Sign-Extension
- **OP_MOVZX** Move with Zero-Extension
- **OP_MUL** Unsigned Multiply
- OP_NEG Two's Complement Negation
- **OP_NOP** No Operation
- **OP_NOT** One's Complement Negation
- OP_OR Logical Inclusive OR
- **OP_OUT** Output to Port
- OP_OUTSD Output String to Port Doubleword
- OP_OUTSW Output String to Port Word
- OP_OUTSB Output String to Port Bytes
- OP_PUSH Push Onto the Stack
- OP_PUSHAD Push All Double General Purpose Registers
- OP_PUSHFD Push EFLAGS Register onto the Stack
- **OP_POP** Pop a Value from the Stack
- OP_POPAD Pop All Double General Purpose Registers from the Stack
- OP_POPFD Pop Stack into EFLAGS Register
- **OP_RCL** Rotate Carry Left
- OP_RCR Rotate Carry Right
- OP_RDMSR Read from Model Specific Register
- **OP_RDPMC** Read Performance Monitoring Counters
- OP_RDTSC Read Time-Stamp Coutner
- OP_PREFIX_REPE Repeat String Operation Prefix while Equal
- OP_PREFIX_REPNE Repeat String Operation Prefix while Not Equal
- OP_RETF Return from Far Procedure
- OP_RETN Return from Near Procedure
- OP_ROL Rotate Left
- OP_ROR Rotate Right
- OP_RSM Resumse from System Management Mode
- OP_SAHF Store AH into Flags
- OP_SAR Shift Arithmetic Right
- OP_SBB Subtract with Borrow
- OP_SCASD Scan String Doubleword
- OP_SCASW Scan String Word

- OP_SCASB Scan String Byte
- OP_SETO Set Byte on Overflow
- OP_SETNO Set Byte on Not Overflow
- OP_SETC Set Byte on Carry
- OP_SETNC Set Byte on Not Carry
- OP_SETZ Set Byte on Zero
- OP_SETNZ Set Byte on Not Zero
- OP_SETBE Set Byte on Below or Equal
- OP_SETA Set Byte on Above
- OP_SETS Set Byte on Sign
- OP_SETNS Set Byte on Not Sign
- OP_SETP Set Byte on Parity
- OP_SETNP Set Byte on Not Parity
- OP_SETL Set Byte on Less
- OP_SETGE Set Byte on Greater or Equal
- OP_SETLE Set Byte on Less or Equal
- OP_SETG Set Byte on Greater
- OP_SGDT Store Global Descriptor Table Register
- **OP_SIDT** Store Interrupt Descriptor Table Register
- OP_SHL Shift Left
- OP_SHLD Double Precision Shift Left
- OP_SHR Shift Right
- OP_SHRD Double Precision Shift Right
- OP_SLDT Store Local Descriptor Table Register
- OP_STOSD Store String Doubleword
- OP_STOSW Store String Word
- OP_STOSB Store String Byte
- OP_STR Store Task Register
- OP_STC Set Carry Flag
- OP_STD Set Direction Flag
- OP_STI Set Interrupt Flag
- OP_SUB Subtract
- OP_SYSCALL Fast System Call
- OP_SYSENTER Fast System Call
- OP_SYSEXIT Fast Return from Fast System Call
- OP_SYSRET Return from Fast System Call
- **OP_TEST** Logical Compare
- **OP_UD2** Undefined Instruction
- OP_VERR Verify a Segment for Reading
- OP_VERRW Verify a Segment for Writing
- OP_WBINVD Write Back and Invalidate Cache
- OP_WRMSR Write to Model Specific Register
- **OP_XADD** Exchange and Add
- OP_XCHG Exchange Register/Memory with Register
- OP_XLAT Table Look-up Translation

- OP_XOR Logical Exclusive OR
- OP_FPU FPU operation
- OP_F2XM1 Compute 2x-1
- OP_FABS Absolute Value
- **OP_FADD** Floating Point Add
- OP_FADDP Floating Point Add, Pop
- OP_FBLD Load Binary Coded Decimal
- **OP_FBSTP** Store BCD Integer and Pop
- OP_FCHS Change Sign
- OP_FCLEX Clear Exceptions
- OP_FCMOVB Floating Point Move on Below
- OP_FCMOVBE Floating Point Move on Below or Equal
- OP_FCMOVE Floating Point Move on Equal
- OP_FCMOVNB Floating Point Move on Not Below
- OP_FCMOVNBE Floating Point Move on Not Below or Equal
- OP_FCMOVNE Floating Point Move on Not Equal
- OP_FCMOVNU Floating Point Move on Not Unordered
- OP_FCMOVU Floating Point Move on Unordered
- **OP_FCOM** Compare Floating Pointer Values and Set FPU Flags
- OP_FCOMI Compare Floating Pointer Values and Set EFLAGS
- OP_FCOMIP Compare Floating Pointer Values and Set EFLAGS, Pop
- OP_FCOMP Compare Floating Pointer Values and Set FPU Flags, Pop
- OP_FCOMPP Compare Floating Pointer Values and Set FPU Flags, Pop Twice
- OP_FCOS Cosine
- OP_FDECSTP Decrement Stack Top Pointer
- OP_FDIV Floating Point Divide
- OP_FDIVP Floating Point Divide, Pop
- OP_FDIVR Floating Point Reverse Divide
- OP_FDIVRP Floating Point Reverse Divide, Pop
- OP_FFREE Free Floating Point Register
- OP_FIADD Floating Point Add
- **OP_FICOM** Compare Integer
- OP_FICOMP Compare Integer, Pop
- OP_FIDIV Floating Point Divide by Integer
- OP_FIDIVR Floating Point Reverse Divide by Integer
- OP_FILD Load Integer
- OP_FIMUL Floating Point Multiply with Integer
- **OP_FINCSTP** Increment Stack-Top Pointer
- **OP_FINIT** Initialize Floating-Point Unit
- OP_FIST Store Integer
- OP_FISTP Store Integer, Pop
- **OP_FISTTP** Store Integer with Truncation
- OP_FISUB Floating Point Integer Subtract
- OP_FISUBR Floating Point Reverse Integer Subtract
- OP_FLD Load Floating Point Value

OP_FLD1 Load Constant 1

OP_FLDCW Load x87 FPU Control Word

OP_FLDENV Load x87 FPU Environment

OP_FLDL2E Load Constant log_2(e)

OP_FLDL2T Load Constant log 2(10)

OP_FLDLG2 Load Constant log_10(2)

OP_FLDLN2 Load Constant log e(2)

OP_FLDPI Load Constant PI

OP_FLDZ Load Constant Zero

OP_FMUL Floating Point Multiply

OP_FMULP Floating Point Multiply, Pop

OP_FNOP No Operation

OP_FPATAN Partial Arctangent

OP_FPREM Partial Remainder

OP_FPREM1 Partial Remainder

OP_FPTAN Partial Tangent

OP_FRNDINT Round to Integer

OP_FRSTOR Restore x86 FPU State

OP_FSCALE Scale

OP_FSINCOS Sine and Cosine

OP_FSQRT Square Root

OP_FSAVE Store x87 FPU State

OP_FST Store Floating Point Value

OP FSTCW Store x87 FPU Control Word

OP_FSTENV Store x87 FPU Environment

OP_FSTP Store Floating Point Value, Pop

OP_FSTSW Store x87 FPU Status Word

OP_FSUB Floating Point Subtract

OP_FSUBP Floating Point Subtract, Pop

OP_FSUBR Floating Point Reverse Subtract

OP_FSUBRP Floating Point Reverse Subtract, Pop

OP_FTST Floating Point Test

OP_FUCOM Floating Point Unordered Compare

OP_FUCOMI Floating Point Unordered Compare with Integer

OP_FUCOMIP Floating Point Unorder Compare with Integer, Pop

OP_FUCOMP Floating Point Unorder Compare, Pop

OP_FUCOMPP Floating Point Unorder Compare, Pop Twice

OP_FXAM Examine ModR/M

OP_FXCH Exchange Register Contents

OP_FXTRACT Extract Exponent and Significand

OP_FYL2X Compute y*log2x

 $OP_FYL2XP1$ Compute y*log2(x+1)

3.2.1.4 enum X86REGS

X86 registers

3.3 bytecode_execs.h File Reference

Data Structures

- struct cli_exe_section
- · struct cli exe info

3.4 bytecode_local.h File Reference

Data Structures

- struct DIS_mem_arg
- struct DIS_arg
- · struct DIS fixed

Macros

- #define VIRUSNAME PREFIX(name) const char clambc virusname prefix[] = name;
- #define VIRUSNAMES(...) const char *const clambc virusnames[] = { VA ARGS };
- #define PE_UNPACKER_DECLARE const uint16_t __clambc_kind = BC_PE_UNPACKER;
- #define PDF_HOOK_DECLARE const uint16_t __clambc_kind = BC_PDF;
- #define BYTECODE_ABORT_HOOK 0xcea5e
- #define PE_HOOK_DECLARE const uint16_t __clambc_kind = BC_PE_ALL;
- #define SIGNATURES_DECL_BEGIN struct __Signatures {
- #define DECLARE SIGNATURE(name)
- #define SIGNATURES DECL END };
- #define TARGET(tgt) const unsigned short ___Target = (tgt);
- #define COPYRIGHT(c) const char *const __Copyright = (c);
- #define ICONGROUP2(group) const char *const __lconGroup2 = (group);
- #define FUNCTIONALITY_LEVEL_MIN(m) const unsigned short __FuncMin = (m);
- #define FUNCTIONALITY_LEVEL_MAX(m) const unsigned short __FuncMax = (m);
- #define SIGNATURES_DEF_BEGIN
- #define SIGNATURES END };
- #define SIGNATURES_DEF_END };

Functions

- static force_inline void overloadable_func debug (const char *str)
- static force_inline void overloadable_func debug (const uint8_t *str)
- static force_inline void overloadable_func debug (uint32_t a)
- void debug (...) __attribute__((overloadable
- static force_inline uint32_t count_match (__Signature sig)
- static force_inline uint32_t matches (__Signature sig)
- static force_inline uint32_t match_location (__Signature sig, uint32_t goback)
- static force_inline int32_t match_location_check (__Signature sig, uint32_t goback, const char *static_start, uint32_t static_len)
- static force_inline overloadable_func void foundVirus (const char *virusname)
- static force_inline void overloadable_func foundVirus (void)

- static force_inline uint32_t getFilesize (void)
- bool <u>is_bigendian</u> (void) <u>__attribute__((const)) __attribute__((nothrow))</u>
- static uint32_t force_inline le32_to_host (uint32_t v)
- static uint32_t force_inline be32_to_host (uint32_t v)
- static uint64 t force inline le64 to host (uint64 t v)
- static uint64_t force_inline be64_to_host (uint64_t v)
- static uint16 t force inline le16 to host (uint16 t v)
- static uint16_t force_inline be16_to_host (uint16_t v)
- static uint32_t force_inline cli_readint32 (const void *buff)
- static uint16 t force inline cli readint16 (const void *buff)
- static void force inline cli_writeint32 (void *offset, uint32_t v)
- static force inline bool hasExeInfo (void)
- static force inline bool hasPEInfo (void)
- static force inline bool isPE64 (void)
- static force_inline uint8_t getPEMajorLinkerVersion (void)
- static force inline uint8 t getPEMinorLinkerVersion (void)
- static force inline uint32 t getPESizeOfCode (void)
- static force inline uint32 t getPESizeOfInitializedData (void)
- static force inline uint32 t getPESizeOfUninitializedData (void)
- static force inline uint32 t getPEBaseOfCode (void)
- static force_inline uint32_t getPEBaseOfData (void)
- static force inline uint64 t getPEImageBase (void)
- static force inline uint32 t getPESectionAlignment (void)
- static force_inline uint32_t getPEFileAlignment (void)
- static force inline uint16 t getPEMajorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMinorOperatingSystemVersion (void)
- static force_inline uint16_t getPEMajorImageVersion (void)
- static force inline uint16 t getPEMinorImageVersion (void)
- static force inline uint16 t getPEMajorSubsystemVersion (void)
- static force_inline uint16_t getPEMinorSubsystemVersion (void)
- static force inline uint32 t getPEWin32VersionValue (void)
- static force inline uint32 t getPESizeOfImage (void)
- static force_inline uint32_t getPESizeOfHeaders (void)
- static force_inline uint32_t getPECheckSum (void)
- static force_inline uint16_t getPESubsystem (void)
- static force_inline uint16_t getPEDIICharacteristics (void)
- static force_inline uint32_t getPESizeOfStackReserve (void)
- static force_inline uint32_t getPESizeOfStackCommit (void)
- static force inline uint32 t getPESizeOfHeapReserve (void)
- static force inline uint32 t getPESizeOfHeapCommit (void)
- static force inline uint32 t getPELoaderFlags (void)
- static force_inline uint16_t getPEMachine ()
- static force_inline uint32_t getPETimeDateStamp ()
- static force_inline uint32_t getPEPointerToSymbolTable ()
- static force inline uint32 t getPENumberOfSymbols ()
- static force inline uint16 t getPESizeOfOptionalHeader ()
- static force inline uint16 t getPECharacteristics ()
- static force inline bool getPEisDLL ()
- static force inline uint32 t getPEDataDirRVA (unsigned n)
- static force_inline uint32_t getPEDataDirSize (unsigned n)
- static force inline uint16 t getNumberOfSections (void)
- static uint32_t getPELFANew (void)
- static force_inline int readPESectionName (unsigned char name[8], unsigned n)
- static force inline uint32 t getEntryPoint (void)
- static force_inline uint32_t getExeOffset (void)

- static force_inline uint32_t getImageBase (void)
- static uint32_t getVirtualEntryPoint (void)
- static uint32 t getSectionRVA (unsigned i)
- static uint32 t getSectionVirtualSize (unsigned i)
- static force inline bool readRVA (uint32 t rva, void *buf, size t bufsize)
- static force_inline void * memchr (const void *s, int c, size_t n)
- void * memset (void *src, int c, uintptr_t n) __attribute__((nothrow)) __attribute__((__nonnull__((1))))
- void * memmove (void *dst, const void *src, uintptr_t n) __attribute__((__nothrow__)) __attribute__((__-nothrow__))
- void void * memcpy (void *restrict dst, const void *restrict src, uintptr_t n) __attribute__((__nothrow__)) __ attribute__((__nonnull__(1
- void void int memcmp (const void *s1, const void *s2, uint32_t n) __attribute__((__nothrow__)) __attribute__(
 _ ((__pure__)) __attribute__((__nonnull__(1
- static force_inline uint32_t DisassembleAt (struct DIS_fixed *result, uint32_t offset, uint32_t len)
- static int32_t ilog2_compat (uint32_t a, uint32_t b)

3.4.1 Macro Definition Documentation

3.4.1.1 #define BYTECODE ABORT HOOK 0xcea5e

entrypoint() return code that tells hook invoker that it should skip executing, probably because it'd trigger a bug in it

3.4.1.2 #define SIGNATURES_END };

Old macro used to mark the end of the subsignature pattern definitions.

3.4.2 Function Documentation

3.4.2.1 static force_inline void overloadable_func foundVirus (void) [static]

Like foundVirus() but just use the prefix as virusname

3.4.2.2 static int32_t ilog2_compat (uint32_t a, uint32_t b) [inline], [static]

ilog2 compat for 0.96 compatibility, you should use ilog2() 0.96.1 API instead of this one!

Parameters

а	input
b	input

Returns

2²6*log2(a/b)

3.5 bytecode_pe.h File Reference

Data Structures

- · struct pe image file hdr
- · struct pe image data dir
- struct pe_image_optional_hdr32
- · struct pe_image_optional_hdr64
- · struct pe_image_section_hdr
- struct cli_pe_hook_data

Index

clambc_filesize	DIS_arg, 57
Global Variables, 27	add_reg
clambc_kind	DIS_mem_arg, 58
Global Variables, 27	address_size
clambc_match_counts	DIS_fixed, 57
Global Variables, 27	arg
clambc_match_offsets	DIS_fixed, 57
Global Variables, 27	atoi
clambc_pedata	String Operations, 51
Global Variables, 27	
is_bigendian	BC_GENERIC
Environment, 19	Bytecode Configuration, 11
	BC_LOGICAL
ACCESS_IMM	Bytecode Configuration, 11
bytecode_disasm.h, 68	BC_PDF
ACCESS_MEM	Bytecode Configuration, 11
bytecode_disasm.h, 68	BC_PE_ALL
ACCESS_NOARG	Bytecode Configuration, 11
bytecode_disasm.h, 68	BC_PE_UNPACKER
ACCESS_REG	Bytecode Configuration, 11
bytecode_disasm.h, 68	BC_STARTUP
ACCESS_REL	Bytecode Configuration, 11
bytecode_disasm.h, 68	bc_json_type
Abstract Data Types, 1	JSON Querying, 29
buffer_pipe_done, 2	be16_to_host
buffer_pipe_new, 2	Environment, 19
buffer_pipe_new_fromfile, 2	be32_to_host
buffer_pipe_read_avail, 2	Environment, 19
buffer_pipe_read_get, 3	be64_to_host
buffer_pipe_read_stopped, 3	Environment, 20
buffer_pipe_write_avail, 3	buffer_pipe_done
buffer_pipe_write_get, 3	Abstract Data Types, 2
buffer_pipe_write_stopped, 3	buffer_pipe_new
hashset_add, 4	Abstract Data Types, 2
hashset_contains, 4	buffer_pipe_new_fromfile
hashset_done, 4	Abstract Data Types, 2
hashset_empty, 4	buffer_pipe_read_avail
hashset_new, 5	Abstract Data Types, 2
hashset_remove, 5	buffer_pipe_read_get
inflate_done, 5	Abstract Data Types, 3
inflate_init, 5	buffer_pipe_read_stopped
inflate_process, 5	Abstract Data Types, 3
malloc, 6	buffer_pipe_write_avail
map_addkey, 6	Abstract Data Types, 3
map_done, 6	buffer_pipe_write_get
map_find, 6	Abstract Data Types, 3
map_getvalue, 7	buffer_pipe_write_stopped
map_getvaluesize, 7	Abstract Data Types, 3
map_new, 7	Bytecode Configuration, 9
map_remove, 7	BC_GENERIC, 11
map_setvalue, 8	BC_LOGICAL, 11
access_size	BC_PDF, 11
DIS_arg, 57	BC_PE_ALL, 11
DIS_mem_arg, 58	BC_PE_UNPACKER, 11
access_type	BC_STARTUP, 11

BytecodeKind, 11	OP_CBW, 69
COPYRIGHT, 9	OP_CDQ, 69
DECLARE_SIGNATURE, 9	OP_CLC, 69
FUNC_LEVEL_096, 11	OP_CLD, 69
FUNC_LEVEL_096_1, 11	OP_CLI, 69
FUNC_LEVEL_096_2, 11	OP CLTS, 69
FUNC_LEVEL_096_3, 11	OP_CMC, 69
FUNC_LEVEL_096_4, 11	OP CMOVA, 69
FUNC_LEVEL_096_5, 11	OP_CMOVBE, 69
FUNC_LEVEL_097, 12	OP_CMOVC, 69
FUNC_LEVEL_097_1, 12	OP CMOVG, 69
FUNC_LEVEL_097_2, 12	OP CMOVGE, 69
FUNC_LEVEL_097_3, 12	OP CMOVL, 69
FUNC LEVEL 097 4, 12	OP CMOVLE, 69
FUNC LEVEL 097 5, 12	OP CMOVNC, 69
FUNC_LEVEL_097_5, 12	OP CMOVNO, 69
	-
FUNC_LEVEL_097_7, 12	OP_CMOVNP, 69
FUNC_LEVEL_097_8, 12	OP_CMOVNS, 69
FUNC_LEVEL_098_1, 12	OP_CMOVNZ, 69
FUNC_LEVEL_098_2, 12	OP_CMOVO, 69
FUNC_LEVEL_098_3, 12	OP_CMOVP, 69
FUNC_LEVEL_098_4, 12	OP_CMOVS, 69
FunctionalityLevels, 11	OP_CMOVZ, 69
ICONGROUP1, 10	OP_CMP, 69
ICONGROUP2, 10	OP_CMPSB, 69
PDF_HOOK_DECLARE, 10	OP_CMPSD, 69
PE_HOOK_DECLARE, 10	OP_CMPSW, 69
PE_UNPACKER_DECLARE, 10	OP_CMPXCHG, 69
SIGNATURES_DECL_END, 10	OP_CMPXCHG8B, 69
SIGNATURES_DEF_END, 10	OP_CPUID, 69
TARGET, 11	OP CWDE, 69
VIRUSNAME_PREFIX, 11	OP DAA, 69
VIRUSNAMES, 11	OP DAS, 69
bytecode_api.h	OP DEC, 69
PE_INVALID_RVA, 65	OP DIV, 69
bytecode_disasm.h	OP ENTER, 69
ACCESS IMM, 68	OP F2XM1, 73
ACCESS MEM, 68	OP FABS, 73
ACCESS NOARG, 68	OP FADD, 73
ACCESS_REG, 68	OP FADDP, 73
ACCESS REL, 68	OP FBLD, 73
OP AAA, 68	OP FBSTP, 73
_ <i>′</i>	-
OP_AAM_68	OP_FCHS, 73
OP_AAN, 68	OP_FCLEX, 73
OP_AAS, 68	OP_FCMOVB, 73
OP_ADC, 68	OP_FCMOVBE, 73
OP_ADD, 68	OP_FCMOVE, 73
OP_AND, 68	OP_FCMOVNB, 73
OP_ARPL, 68	OP_FCMOVNBE, 73
OP_BOUND, 68	OP_FCMOVNE, 73
OP_BSF, 68	OP_FCMOVNU, 73
OP_BSR, 68	OP_FCMOVU, 73
OP_BSWAP, 69	OP_FCOM, 73
OP_BT, 69	OP_FCOMI, 73
OP_BTC, 69	OP_FCOMIP, 73
OP_BTR, 69	OP_FCOMP, 73
OP_BTS, 69	OP_FCOMPP, 73
OP_CALL, 69	OP_FCOS, 73
- ·	<i>=</i> '

OP FDECSTP, 73	OP FUCOMPP, 74
OP FDIV, 73	OP FWAIT, 69
OP FDIVP, 73	OP FXAM, 74
_	_
OP_FDIVR, 73	OP_FXCH, 74
OP_FDIVRP, 73	OP_FXTRACT, 74
OP_FFREE, 73	OP_FYL2X, 74
OP_FIADD, 73	OP FYL2XP1, 74
OP FICOM, 73	OP HLT, 69
OP FICOMP, 73	OP IDIV, 69
_	OP_IMUL, 70
OP_FIDIV, 73	
OP_FIDIVR, 73	OP_IN, 70
OP_FILD, 73	OP_INC, 70
OP_FIMUL, 73	OP_INSB, 70
OP_FINCSTP, 73	OP_INSD, 70
OP_FINIT, 73	OP_INSW, 70
OP_FIST, 73	OP_INT, 70
OP_FISTP, 73	OP_INT3, 70
OP_FISTTP, 73	OP_INTO, 70
OP_FISUB, 73	OP_INVD, 70
OP_FISUBR, 73	OP_INVLPG, 70
OP_FLD, 73	OP_IRET, 70
OP_FLD1, 73	OP_JA, 70
OP_FLDCW, 74	OP_JBE, 70
OP FLDENV, 74	OP_JC, 70
OP FLDL2E, 74	OP_JECXZ, 71
OP FLDL2T, 74	OP_JG, 70
OP FLDLG2, 74	OP_JGE, 70
_	
OP_FLDLN2, 74	OP_JL, 70
OP_FLDPI, 74	OP_JLE, 70
OP_FLDZ, 74	OP_JMP, 70
OP_FMUL, 74	OP_JNC, 70
OP_FMULP, 74	OP_JNO, 70
OP_FNOP, 74	OP_JNP, 70
OP FPATAN, 74	OP JNS, 70
OP FPREM, 74	OP JNZ, 70
OP FPREM1, 74	OP_JO, 70
OP FPTAN, 74	OP_JP, 70
-	
OP_FPU, 73	OP_JS, 70
OP_FRNDINT, 74	OP_JZ, 70
OP_FRSTOR, 74	OP_LAHF, 70
OP_FSAVE, 74	OP_LAR, 70
OP_FSCALE, 74	OP_LDS, 70
OP_FSINCOS, 74	OP_LEA, 70
OP FSQRT, 74	OP LEAVE, 70
OP_FST, 74	OP LES, 70
OP FSTCW, 74	OP LFS, 70
OP FSTENV, 74	OP LGDT, 70
_	<u> </u>
OP_FSTP, 74	OP_LGS, 70
OP_FSTSW, 74	OP_LIDT, 70
OP_FSUB, 74	OP_LLDT, 70
OP_FSUBP, 74	OP_LODSB, 70
OP_FSUBR, 74	OP_LODSD, 70
OP_FSUBRP, 74	OP_LODSW, 70
OP_FTST, 74	OP_LOOP, 70
OP FUCOM, 74	OP LOOPE, 71
OP FUCOMI, 74	OP LOOPNE, 71
OP FUCOMIP, 74	OP LSL, 71
OP_FUCOMP, 74	OP_LSS, 71
51 _1 000Wii , / T	OI _LOO, / I

OP_LTR, 71	OP SHL, 72
	_ ·
OP_MOV, 71	OP_SHLD, 72
OP_MOVSB, 71	OP_SHR, 72
OP_MOVSD, 71	OP_SHRD, 72
OP MOVSW, 71	OP_SIDT, 72
-	OP_SLDT, 72
OP_MOVSX, 71	
OP_MOVZX, 71	OP_STC, 72
OP MUL, 71	OP_STD, 72
OP NEG, 71	OP_STI, 72
<u> </u>	OP_STOSB, 72
OP_NOP, 71	
OP_NOT, 71	OP_STOSD, 72
OP OR, 71	OP_STOSW, 72
OP OUT, 71	OP_STR, 72
_ :	OP_SUB, 72
OP_OUTSB, 71	
OP_OUTSD, 71	OP_SYSCALL, 72
OP OUTSW, 71	OP_SYSENTER, 72
OP POP, 71	OP SYSEXIT, 72
<i>_ ′</i>	OP_SYSRET, 72
OP_POPAD, 71	
OP_POPFD, 71	OP_TEST, 72
OP_PREFIX_LOCK, 70	OP_UD2, <mark>72</mark>
OP PREFIX REPE, 71	OP VERR, 72
,	OP VERRW, 72
OP_PREFIX_REPNE, 71	
OP_PUSH, 71	OP_WBINVD, 72
OP PUSHAD, 71	OP_WRMSR, 72
OP PUSHFD, 71	OP_XADD, 72
-	OP_XCHG, 72
OP_RCL, 71	OP_XLAT, 72
OP_RCR, 71	
OP RDMSR, 71	OP_XOR, 72
OP RDPMC, 71	SIZEB, 68
OP RDTSC, 71	SIZED, 68
_	SIZEF, 68
OP_RETF, 71	SIZEPTR, 68
OP_RETN, 71	•
OP ROL, 71	SIZEQ, 68
OP ROR, 71	SIZET, 68
- · · · ·	SIZEW, 68
OP_RSM, 71	bytecode api.h, 63
OP_SAHF, 71	
OP_SAR, 71	test1, 65
OP_SBB, 71	test2, 66
	bytecode_disasm.h, 66
OP_SCASB, 71	DIS ACCESS, 68
OP_SCASD, 71	DIS_SIZE, 68
OP_SCASW, 71	
OP_SETA, 72	X86OPS, 68
OP_SETBE, 72	X86REGS, 74
	bytecode_execs.h, 75
OP_SETC, 72	bytecode_local.h, 75
OP_SETG, 72	foundVirus, 77
OP_SETGE, 72	
OP_SETL, 72	ilog2_compat, 77
	SIGNATURES_END, 77
OP_SETLE, 72	bytecode_pe.h, 77
OP_SETNC, 72	bytecode_rt_error
OP SETNO, 72	
OP_SETNP, 72	Scan Control, 49
	BytecodeKind
OP_SETNS, 72	Bytecode Configuration, 11
OP_SETNZ, 72	, ,
OP SETO, 72	COPYRIGHT
OP_SETP, 72	Bytecode Configuration, 9
	-
OP_SETS, 72	check_platform
OP_SETZ, 72	Environment, 20
OP SGDT, 72	CheckSum
_	

pe_image_optional_hdr32, 60	DIS_mem_arg, 58
pe_image_optional_hdr64, 61	access_size, 58
chr	add_reg, 58
cli_exe_section, 55	displacement, 58
cli_exe_info, 54	scale, 58
ep, 54	scale_reg, 58
hdr_size, 54	DISASM_RESULT, 58
nsections, 54	debug
offset, 54	Debugging, 13
res_addr, 54	debug_print_str
section, 54	Debugging, 13
cli_exe_section, 54	debug_print_str_nonl
chr, 55	Debugging, 15
raw, 55	debug_print_str_start
rsz, 5 5	Debugging, 15
rva, 55	debug_print_uint
uraw, 55	Debugging, 15
ursz, 55	Debugging, 13
urva, 55	debug, 13
uvsz, <u>55</u>	debug_print_str, 13
vsz, 55	debug_print_str_nonl, 15
cli_pe_hook_data, 55	debug_print_str_start, 15
dirs, 56	debug_print_uint, 15
e_lfanew, 56	dirs
ep, 56	cli_pe_hook_data, 56
file_hdr, 56	disable_bytecode_if
hdr_size, 56	Environment, 21
nsections, 56	disable_jit_if
opt32, 56	Environment, 21
opt64, 56	disasm_x86
overlays, 56	Disassembly, 16
overlays_sz, 56	DisassembleAt
cli_readint16	Disassembly, 16
Environment, 20	Disassembly, 16
cli_readint32	disasm_x86, 16
Environment, 20	DisassembleAt, 16
cli_writeint32	displacement
Environment, 20	DIS_mem_arg, 58
count_match	e Ifanew
Engine Queries, 17	-
DECLARE SIGNATURE	cli_pe_hook_data, 56 Engine Queries, 17
—	count match, 17
Bytecode Configuration, 9 DIS ACCESS	-
bytecode_disasm.h, 68	engine_db_options, 17 engine_dconf_level, 17
DIS SIZE	engine_dconi_level, 17 engine functionality level, 17
bytecode_disasm.h, 68	engine_scan_options, 17
DIS arg, 56	·
_ •	match_location, 18
access_size, 57	match_location_check, 18
access_type, 57	matches, 18
mem, 57	running_on_jit, 18
other, 57	engine_db_options
reg, 57	Engine Queries, 17
DIS_fixed, 57	engine_dconf_level
address_size, 57	Engine Queries, 17
arg, 57	engine_functionality_level
operation_size, 57	Engine Queries, 17
segment, 57	engine_scan_options
x86_opcode, 57	Engine Queries, 17

entropy_buffer	Bytecode Configuration, 12
String Operations, 51	FUNC_LEVEL_098_3
Environment, 19	Bytecode Configuration, 12
is_bigendian, 19	FUNC_LEVEL_098_4
be16 to host, 19	Bytecode Configuration, 12
be32_to_host, 19	File Operations, 23
be64_to_host, 20	file_byteat, 23
check_platform, 20	file_find, 23
_	file find limit, 23
cli_readint16, 20	
cli_readint32, 20	fill_buffer, 25
cli_writeint32, 20	get_file_reliability, 25
disable_bytecode_if, 21	getFilesize, 25
disable_jit_if, 21	read, 25
get_environment, 21	read_number, 26
le16_to_host, 21	SEEK_CUR, 23
le32_to_host, 22	SEEK_END, 23
le64_to_host, 22	SEEK_SET, 23
version_compare, 22	seek, 26
ер	write, 26
cli exe info, 54	file_byteat
cli pe hook data, 56	File Operations, 23
extract_new	file find
Scan Control, 49	File Operations, 23
extract_set_container	file find limit
Scan Control, 49	File Operations, 23
Scari Control, 49	•
FUNC_LEVEL_096	file_hdr
Bytecode Configuration, 11	cli_pe_hook_data, 56
FUNC_LEVEL_096_1	FileAlignment
Bytecode Configuration, 11	pe_image_optional_hdr32, 60
	pe_image_optional_hdr64, 61
FUNC_LEVEL_096_2	fill_buffer
Bytecode Configuration, 11	File Operations, 25
FUNC_LEVEL_096_3	foundVirus
Bytecode Configuration, 11	bytecode_local.h, 77
FUNC_LEVEL_096_4	Scan Control, 49
Bytecode Configuration, 11	FunctionalityLevels
FUNC_LEVEL_096_5	Bytecode Configuration, 11
Bytecode Configuration, 11	-
FUNC_LEVEL_097	get_environment
Bytecode Configuration, 12	Environment, 21
FUNC_LEVEL_097_1	get_file_reliability
Bytecode Configuration, 12	File Operations, 25
FUNC_LEVEL_097_2	get pe section
Bytecode Configuration, 12	PE Operations, 41
FUNC LEVEL 097 3	getEntryPoint
Bytecode Configuration, 12	PE Operations, 41
FUNC LEVEL 097 4	getExeOffset
Bytecode Configuration, 12	PE Operations, 41
FUNC_LEVEL_097_5	getFilesize
	_
Bytecode Configuration, 12	File Operations, 25
FUNC_LEVEL_097_6	getImageBase
Bytecode Configuration, 12	PE Operations, 41
FUNC_LEVEL_097_7	getNumberOfSections
Bytecode Configuration, 12	PE Operations, 41
FUNC_LEVEL_097_8	getPEBaseOfCode
Bytecode Configuration, 12	PE Operations, 42
FUNC_LEVEL_098_1	getPEBaseOfData
Bytecode Configuration, 12	PE Operations, 42
FUNC_LEVEL_098_2	getPECharacteristics

PE Operations, 42	PE Operations, 46
getPECheckSum	getPESizeOfUninitializedData
PE Operations, 42	PE Operations, 46
getPEDataDirRVA	getPESubsystem
PE Operations, 42	PE Operations, 46
getPEDataDirSize	getPETimeDateStamp
PE Operations, 42	PE Operations, 47
getPEDIICharacteristics	getPEWin32VersionValue
PE Operations, 43	PE Operations, 47
getPEFileAlignment	getPEisDLL
PE Operations, 43	PE Operations, 43
getPEImageBase	getSectionRVA
PE Operations, 43	PE Operations, 47
getPELFANew	getSectionVirtualSize
PE Operations, 43	PE Operations, 47
getPELoaderFlags	getVirtualEntryPoint
PE Operations, 43	PE Operations, 47
getPEMachine	Global Variables, 27
PE Operations, 43	clambc_filesize, 27
getPEMajorImageVersion	clambc_kind, 27
PE Operations, 44	clambc_match_counts, 27
getPEMajorLinkerVersion	clambc_match_offsets, 27
PE Operations, 44	clambc_pedata, 27
getPEMajorOperatingSystemVersion	<u> </u>
PE Operations, 44	hasExeInfo
getPEMajorSubsystemVersion	PE Operations, 47
PE Operations, 44	hasPEInfo
getPEMinorImageVersion	PE Operations, 47
PE Operations, 44	hashset_add
getPEMinorLinkerVersion	Abstract Data Types, 4
PE Operations, 44	hashset_contains
•	Abstract Data Types, 4
getPEMinorOperatingSystemVersion	hashset_done
PE Operations, 44	Abstract Data Types, 4
getPEMinorSubsystemVersion	hashset_empty
PE Operations, 45	Abstract Data Types, 4
getPENumberOfSymbols	hashset_new
PE Operations, 45	Abstract Data Types, 5
getPEPointerToSymbolTable	hashset_remove
PE Operations, 45	Abstract Data Types, 5
getPESectionAlignment	hdr_size
PE Operations, 45	cli_exe_info, 54
getPESizeOfCode	cli_pe_hook_data, 56
PE Operations, 45	hex2ui
getPESizeOfHeaders	String Operations, 51
PE Operations, 45	
getPESizeOfHeapCommit	ICONGROUP1
PE Operations, 45	Bytecode Configuration, 10
getPESizeOfHeapReserve	ICONGROUP2
PE Operations, 46	Bytecode Configuration, 10
getPESizeOfImage	Icon Matcher, 32
PE Operations, 46	matchicon, 32
getPESizeOfInitializedData	icos
PE Operations, 46	Math Operation, 33
getPESizeOfOptionalHeader	iexp
PE Operations, 46	Math Operation, 33
getPESizeOfStackCommit	ilog2
PE Operations, 46	Math Operation, 33
getPESizeOfStackReserve	ilog2_compat
-	

bytecode_local.h, 77	le16_to_host
ImageBase	Environment, 21
pe_image_optional_hdr32, 60	le32_to_host
pe_image_optional_hdr64, 61	Environment, 22
inflate_done	le64_to_host
Abstract Data Types, 5	Environment, 22
inflate_init	Machine
Abstract Data Types, 5	pe_image_file_hdr, 59
inflate_process	Magic
Abstract Data Types, 5	pe image file hdr, 59
input_switch	MajorImageVersion
Scan Control, 50	pe_image_optional_hdr32, 60
ipow	pe_image_optional_hdr64, 61
Math Operation, 33	MajorLinkerVersion
isPE64	pe_image_optional_hdr32, 60
PE Operations, 48	pe_image_optional_hdr64, 61
isin	MajorOperatingSystemVersion
Math Operation, 34	pe_image_optional_hdr32, 60
	pe_image_optional_hdr64, 61
JSON Querying, 29	malloc
bc_json_type, 29	Abstract Data Types, 6
json_get_array_idx, 29	map addkey
json_get_array_length, 29	Abstract Data Types, 6
json_get_boolean, 29	map_done
json_get_int, 30	Abstract Data Types, 6
json_get_object, 30	
json_get_string, 30	map_find
json_get_string_length, 30	Abstract Data Types, 6
json_get_type, 31	map_getvalue
json_is_active, 31	Abstract Data Types, 7
JavaScript Normalization, 28	map_getvaluesize
jsnorm_done, 28	Abstract Data Types, 7
jsnorm init, 28	map_new
jsnorm_process, 28	Abstract Data Types, 7
jsnorm_done	map_remove
JavaScript Normalization, 28	Abstract Data Types, 7
jsnorm_init	map_setvalue
JavaScript Normalization, 28	Abstract Data Types, 8
•	match_location
jsnorm_process	Engine Queries, 18
JavaScript Normalization, 28	match_location_check
json_get_array_idx	Engine Queries, 18
JSON Querying, 29	matches
json_get_array_length	Engine Queries, 18
JSON Querying, 29	matchicon
json_get_boolean	Icon Matcher, 32
JSON Querying, 29	Math Operation, 33
json_get_int	icos, <mark>33</mark>
JSON Querying, 30	iexp, <mark>33</mark>
json_get_object	ilog2, 33
JSON Querying, 30	ipow, 33
json_get_string	isin, 34
JSON Querying, 30	mem
json_get_string_length	DIS_arg, 57
JSON Querying, 30	memchr
json_get_type	String Operations, 52
JSON Querying, 31	memcmp
json_is_active	String Operations, 52
JSON Querying, 31	memcpy
, g, -	• •

0.1.0	
String Operations, 52	bytecode_disasm.h, 69
memmove	OP_BTC
String Operations, 52 memset	bytecode_disasm.h, 69 OP BTR
String Operations, 53	_
memstr	bytecode_disasm.h, 69 OP BTS
String Operations, 53	_
MinorImageVersion	bytecode_disasm.h, 69 OP CALL
pe_image_optional_hdr32, 60	bytecode_disasm.h, 69
pe_image_optional_hdr64, 61	OP CBW
MinorLinkerVersion	-
pe_image_optional_hdr32, 60	bytecode_disasm.h, 69 OP CDQ
pe_image_optional_hdr64, 61	bytecode_disasm.h, 69
MinorOperatingSystemVersion	OP_CLC
pe_image_optional_hdr32, 60	bytecode_disasm.h, 69
pe_image_optional_hdr64, 61	OP CLD
poago_opnoao.o., o.	bytecode_disasm.h, 69
Name	OP CLI
pe_image_section_hdr, 62	bytecode_disasm.h, 69
nsections	OP_CLTS
cli_exe_info, 54	bytecode_disasm.h, 69
cli_pe_hook_data, 56	OP_CMC
NumberOfLinenumbers	bytecode_disasm.h, 69
pe_image_section_hdr, 62	OP CMOVA
NumberOfRelocations	bytecode_disasm.h, 69
pe_image_section_hdr, 62	OP CMOVBE
NumberOfRvaAndSizes	bytecode_disasm.h, 69
pe_image_optional_hdr32, 60	OP CMOVC
pe_image_optional_hdr64, 62	_
1 = 0 = 1 = 7	
NumberOfSections	bytecode_disasm.h, 69
	OP_CMOVG
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols	OP_CMOVG bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAM OP_AAS	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNO OP_CMOVNO
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNP OP_CMOVNS
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNS
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVO
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BSF	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVP
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68 OP_BSR	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68 OP_BSR bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVZ bytecode_disasm.h, 69
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68 OP_BSR bytecode_disasm.h, 68 OP_BSR bytecode_disasm.h, 68 OP_BSR bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVZ
NumberOfSections pe_image_file_hdr, 59 NumberOfSymbols pe_image_file_hdr, 59 OP_AAA bytecode_disasm.h, 68 OP_AAD bytecode_disasm.h, 68 OP_AAM bytecode_disasm.h, 68 OP_AAS bytecode_disasm.h, 68 OP_ADC bytecode_disasm.h, 68 OP_ADD bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_AND bytecode_disasm.h, 68 OP_ARPL bytecode_disasm.h, 68 OP_BOUND bytecode_disasm.h, 68 OP_BSF bytecode_disasm.h, 68 OP_BSR bytecode_disasm.h, 68	OP_CMOVG bytecode_disasm.h, 69 OP_CMOVGE bytecode_disasm.h, 69 OP_CMOVL bytecode_disasm.h, 69 OP_CMOVLE bytecode_disasm.h, 69 OP_CMOVNC bytecode_disasm.h, 69 OP_CMOVNO bytecode_disasm.h, 69 OP_CMOVNP bytecode_disasm.h, 69 OP_CMOVNS bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVNZ bytecode_disasm.h, 69 OP_CMOVO bytecode_disasm.h, 69 OP_CMOVP bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVS bytecode_disasm.h, 69 OP_CMOVZ bytecode_disasm.h, 69

bytecode_disasm.h, 69 OP CMPSD	bytecode_disasm.h, 73 OP FCOMIP
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_CMPSW	OP_FCOMP
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_CMPXCHG bytecode_disasm.h, 69	OP_FCOMPP bytecode_disasm.h, 73
OP_CMPXCHG8B	OP FCOS
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_CPUID	OP_FDECSTP
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_CWDE bytecode_disasm.h, 69	OP_FDIV bytecode_disasm.h, 73
OP_DAA	OP_FDIVP
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_DAS	OP_FDIVR
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_DEC bytecode_disasm.h, 69	OP_FDIVRP bytecode_disasm.h, 73
OP DIV	OP FFREE
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_ENTER	OP_FIADD
bytecode_disasm.h, 69	bytecode_disasm.h, 73
OP_F2XM1	OP_FICOM
bytecode_disasm.h, 73 OP FABS	bytecode_disasm.h, 73 OP FICOMP
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FADD	OP_FIDIV
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FADDP	OP_FIDIVR
bytecode_disasm.h, 73 OP FBLD	bytecode_disasm.h, 73 OP_FILD
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FBSTP	OP_FIMUL
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCHS	OP_FINCSTP
bytecode_disasm.h, 73 OP FCLEX	bytecode_disasm.h, 73 OP_FINIT
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCMOVB	OP_FIST
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCMOVBE	OP_FISTP
bytecode_disasm.h, 73 OP FCMOVE	bytecode_disasm.h, 73 OP FISTTP
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCMOVNB	OP_FISUB
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCMOVNBE	OP_FISUBR
bytecode_disasm.h, 73 OP FCMOVNE	bytecode_disasm.h, 73 OP FLD
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCMOVNU	OP_FLD1
bytecode_disasm.h, 73	bytecode_disasm.h, 73
OP_FCMOVU	OP_FLDCW
bytecode_disasm.h, 73 OP FCOM	bytecode_disasm.h, 74
	(AD ELLIENIA)
-	OP_FLDENV bytecode_disasm.h. 74
bytecode_disasm.h, 73 OP_FCOMI	OP_FLDENV bytecode_disasm.h, 74 OP_FLDL2E

bytecode_disasm.h, 74 OP_FLDL2T	bytecode_disasm.h, 74 OP_FUCOM
bytecode_disasm.h, 74 OP_FLDLG2	bytecode_disasm.h, 74 OP_FUCOMI
bytecode_disasm.h, 74 OP FLDLN2	bytecode_disasm.h, 74 OP FUCOMIP
bytecode_disasm.h, 74 OP_FLDPI	bytecode_disasm.h, 74 OP_FUCOMP
bytecode_disasm.h, 74 OP_FLDZ	bytecode_disasm.h, 74 OP_FUCOMPP
bytecode_disasm.h, 74 OP_FMUL	bytecode_disasm.h, 74 OP_FWAIT
bytecode_disasm.h, 74	bytecode_disasm.h, 69 OP_FXAM
OP_FMULP bytecode_disasm.h, 74	bytecode_disasm.h, 74
OP_FNOP bytecode_disasm.h, 74	OP_FXCH bytecode_disasm.h, 74
OP_FPATAN bytecode_disasm.h, 74	OP_FXTRACT bytecode_disasm.h, 74
OP_FPREM bytecode_disasm.h, 74	OP_FYL2X bytecode_disasm.h, 74
OP_FPREM1 bytecode_disasm.h, 74	OP_FYL2XP1 bytecode_disasm.h, 74
OP_FPTAN bytecode_disasm.h, 74	OP_HLT bytecode_disasm.h, 69
OP_FPU	OP_IDIV
bytecode_disasm.h, 73 OP_FRNDINT	bytecode_disasm.h, 69 OP_IMUL
bytecode_disasm.h, 74 OP_FRSTOR	bytecode_disasm.h, 70 OP_IN
bytecode_disasm.h, 74 OP_FSAVE	bytecode_disasm.h, 70 OP_INC
bytecode_disasm.h, 74 OP_FSCALE	bytecode_disasm.h, 70 OP_INSB
bytecode_disasm.h, 74 OP_FSINCOS	bytecode_disasm.h, 70 OP_INSD
bytecode_disasm.h, 74 OP_FSQRT	bytecode_disasm.h, 70 OP_INSW
bytecode_disasm.h, 74 OP FST	bytecode_disasm.h, 70 OP_INT
bytecode_disasm.h, 74 OP FSTCW	bytecode_disasm.h, 70 OP_INT3
bytecode_disasm.h, 74 OP_FSTENV	bytecode_disasm.h, 70 OP_INTO
bytecode_disasm.h, 74 OP_FSTP	bytecode_disasm.h, 70
OP F51P	
bytecode_disasm.h, 74	OP_INVD bytecode_disasm.h, 70
bytecode_disasm.h, 74 OP_FSTSW bytecode_disasm.h, 74	bytecode_disasm.h, 70 OP_INVLPG bytecode_disasm.h, 70
bytecode_disasm.h, 74 OP_FSTSW	bytecode_disasm.h, 70 OP_INVLPG
bytecode_disasm.h, 74 OP_FSTSW bytecode_disasm.h, 74 OP_FSUB	bytecode_disasm.h, 70 OP_INVLPG bytecode_disasm.h, 70 OP_IRET
bytecode_disasm.h, 74 OP_FSTSW bytecode_disasm.h, 74 OP_FSUB bytecode_disasm.h, 74 OP_FSUBP bytecode_disasm.h, 74 OP_FSUBR	bytecode_disasm.h, 70 OP_INVLPG bytecode_disasm.h, 70 OP_IRET bytecode_disasm.h, 70 OP_JA bytecode_disasm.h, 70 OP_JBE
bytecode_disasm.h, 74 OP_FSTSW bytecode_disasm.h, 74 OP_FSUB bytecode_disasm.h, 74 OP_FSUBP bytecode_disasm.h, 74	bytecode_disasm.h, 70 OP_INVLPG bytecode_disasm.h, 70 OP_IRET bytecode_disasm.h, 70 OP_JA bytecode_disasm.h, 70

bytecode_disasm.h, 71 OP_JG	bytecode_disasm.h, 70 OP LOOPE
bytecode_disasm.h, 70 OP_JGE	bytecode_disasm.h, 71 OP LOOPNE
bytecode_disasm.h, 70 OP_JL	bytecode_disasm.h, 71 OP LSL
bytecode_disasm.h, 70 OP_JLE	bytecode_disasm.h, 71 OP LSS
bytecode_disasm.h, 70	bytecode_disasm.h, 71
OP_JMP bytecode_disasm.h, 70	OP_LTR bytecode_disasm.h, 71
OP_JNC bytecode_disasm.h, 70	OP_MOV
OP_JNO	bytecode_disasm.h, 71 OP_MOVSB
bytecode_disasm.h, 70 OP_JNP	bytecode_disasm.h, 71 OP_MOVSD
bytecode_disasm.h, 70 OP_JNS	bytecode_disasm.h, 71 OP MOVSW
bytecode_disasm.h, 70	bytecode_disasm.h, 71
OP_JNZ bytecode_disasm.h, 70	OP_MOVSX bytecode_disasm.h, 71
OP_JO bytecode_disasm.h, 70	OP_MOVZX bytecode_disasm.h, 71
OP_JP	OP_MUL
bytecode_disasm.h, 70 OP_JS	bytecode_disasm.h, 71 OP_NEG
bytecode_disasm.h, 70 OP_JZ	bytecode_disasm.h, 71 OP_NOP
bytecode_disasm.h, 70 OP_LAHF	bytecode_disasm.h, 71 OP_NOT
bytecode_disasm.h, 70 OP_LAR	bytecode_disasm.h, 71 OP_OR
bytecode_disasm.h, 70 OP LDS	bytecode_disasm.h, 71 OP_OUT
bytecode_disasm.h, 70	bytecode_disasm.h, 71
OP_LEA bytecode_disasm.h, 70	OP_OUTSB bytecode_disasm.h, 71
OP_LEAVE bytecode disasm.h, 70	OP_OUTSD bytecode disasm.h, 71
OP_LES	OP_OUTSW bytecode disasm.h, 71
bytecode_disasm.h, 70 OP_LFS	OP_POP
bytecode_disasm.h, 70 OP LGDT	bytecode_disasm.h, 71 OP POPAD
bytecode_disasm.h, 70 OP LGS	bytecode_disasm.h, 71 OP POPFD
bytecode_disasm.h, 70 OP_LIDT	bytecode_disasm.h, 71 OP_PREFIX_LOCK
bytecode_disasm.h, 70	bytecode_disasm.h, 70
OP_LLDT bytecode_disasm.h, 70	OP_PREFIX_REPE bytecode_disasm.h, 71
OP_LODSB bytecode_disasm.h, 70	OP_PREFIX_REPNE bytecode_disasm.h, 71
OP_LODSD	OP_PUSH
bytecode_disasm.h, 70 OP_LODSW	bytecode_disasm.h, 71 OP_PUSHAD
bytecode_disasm.h, 70 OP LOOP	bytecode_disasm.h, 71 OP PUSHFD
	•• b

OP_RCL bytecode_disasm.h, 71 OP_RCR bytecode_disasm.h, 71 OP_RDMSR bytecode_disasm.h, 71 OP_RDPMC bytecode_disasm.h, 71 OP_RETT bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_SHR bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_RON bytecode_disasm.h, 71 OP_SAHP bytecode_disasm.h, 71 OP_SAHP bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SBB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 72 OP_STOSD bytecode_disasm.h, 72 OP_STOSD bytecode_disasm.h, 72 OP_SETA bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETRE bytecode_disasm.h, 72 OP_SETRNO bytecode_disasm.h, 72 OP_VERRN bytecode_disasm.h, 72 OP_VERRN bytecode_disasm.h, 72 OP_VERRN bytecode_disasm.h, 72 OP_VERRN bytecode_disasm.h, 72 OP_VERRN		
OP_RCR bytecode_disasm.h, 71 OP_RDMSR bytecode_disasm.h, 71 OP_RDPMC bytecode_disasm.h, 71 OP_RDPMC bytecode_disasm.h, 71 OP_RDTSC bytecode_disasm.h, 71 OP_RETF bytecode_disasm.h, 71 OP_RETF bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_RCD bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_RSM bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 72 OP_SETA bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_WERNS bytecode_disasm.h, 72 OP_WERNS	bytecode_disasm.h, 71 OP_RCL	bytecode_disasm.h, 72 OP_SETP
OP_RDMSR OP_SETZ bytecode_disasm.h, 72 OP_RDPMC OP_SGDT bytecode_disasm.h, 72 OP_RDTSC OP_SHL bytecode_disasm.h, 72 OP_RETF OP_SHLD bytecode_disasm.h, 72 OP_RETN OP_SHR bytecode_disasm.h, 72 OP_ROL OP_SHRD bytecode_disasm.h, 72 OP_ROR OP_SHRD bytecode_disasm.h, 72 OP_ROR OP_SIDT bytecode_disasm.h, 72 OP_RSM OP_SIDT bytecode_disasm.h, 72 OP_SAHF OP_SIDT bytecode_disasm.h, 72 OP_SAHF OP_STC bytecode_disasm.h, 72 OP_SAR OP_STC bytecode_disasm.h, 72 OP_SAB OP_STD bytecode_disasm.h, 72 OP_STB bytecode_disasm.h, 72 OP_STOSB OP_SCASB OP_STOSB bytecode_disasm.h, 72 OP_SCASD OP_STOSB bytecode_disasm.h, 72 OP_SETA OP_STOSW bytecode_disasm.h, 72 OP_SETA OP_STOSW bytecode_disasm.h, 72 OP_SETBE OP_SYSENTER bytecode_disasm.h, 72	· —	bytecode_disasm.h, 72 OP_SETS
OP_RDPMC bytecode_disasm.h, 71 OP_RETF Dytecode_disasm.h, 71 OP_RETF Dytecode_disasm.h, 71 OP_RETN Dytecode_disasm.h, 71 OP_RETN Dytecode_disasm.h, 71 OP_RETN Dytecode_disasm.h, 71 OP_ROR Dytecode_disasm.h, 71 OP_ROR Dytecode_disasm.h, 71 OP_RSM Dytecode_disasm.h, 71 OP_SAH Dytecode_disasm.h, 71 OP_SAH Dytecode_disasm.h, 71 OP_SAR Dytecode_disasm.h, 71 OP_SBB Dytecode_disasm.h, 71 OP_SCASB Dytecode_disasm.h, 71 OP_SCASB Dytecode_disasm.h, 71 OP_SCASD Dytecode_disasm.h, 72 OP_SETC Dytecode_disasm.h, 72 OP_SETG Dytecode_disasm.h, 72 OP_SETC Dytecode_disasm.h, 72 OP_SETG Dytecode_disasm.h, 72 OP_SETG Dytecode_disasm.h, 72 OP_SETC Dytecode_disasm.h, 72 OP_SETRC Dytecode_disasm.h, 72 OP_SETRN Dytecode_disasm.h, 72 OP_SETNC Dytecode_disasm.h, 72 OP_VERR Dytecode_disasm.h, 72 OP_VERR Dytecode_disasm.h, 72 OP_VERR Dytecode_disasm.h, 72 OP_VERRN Dytecode_disasm.h, 72 OP_VERRN Dytecode_disasm.h, 72 OP_WBMSH		
OP_RDTSC bytecode_disasm.h, 71 OP_RETF bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_RON bytecode_disasm.h, 71 OP_RSM OP_SHR bytecode_disasm.h, 71 OP_RSM OP_SLDT bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAR OP_STD bytecode_disasm.h, 71 OP_SAR OP_STD bytecode_disasm.h, 71 OP_SAR OP_STD bytecode_disasm.h, 72 OP_STD bytecode_disasm.h, 72 OP_SCASB OP_STOSD bytecode_disasm.h, 71 OP_SCASB OP_SCASB OP_STOSD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 72 OP_SETA bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETB Dytecode_disasm.h, 72 OP_SETG OP_SYSCALL bytecode_disasm.h, 72 OP_SETG OP_SYSCALL bytecode_disasm.h, 72 OP_SETG OP_SYSCALL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_WERRW bytecode_disasm.h, 72 OP_WERRW bytecode_disasm.h, 72 OP_WERND bytecode_disasm.h,		
OP_RETF bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_ROR bytecode_disasm.h, 71 OP_ROR OP_SIBT bytecode_disasm.h, 71 OP_RSM OP_SLDT bytecode_disasm.h, 72 OP_SAR OP_STC bytecode_disasm.h, 71 OP_SAR OP_STC bytecode_disasm.h, 71 OP_SBB OP_STD bytecode_disasm.h, 71 OP_SBB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SETA OP_STOSD bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_WENRW bytecode_disasm.h, 72 OP_WENRW bytecode_disasm.h, 72 OP_WENRN bytecode_disasm.h, 72 OP_WENRN bytecode_disasm.h, 72 OP_WENNS bytecode_disasm.h, 72 DP_WENNS bytecode_		
bytecode_disasm.h, 71 OP_RETN bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_ROR bytecode_disasm.h, 71 OP_ROR bytecode_disasm.h, 71 OP_ROR bytecode_disasm.h, 71 OP_RSM bytecode_disasm.h, 71 OP_RSM bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAR bytecode_disasm.h, 71 OP_SCASR bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 72 OP_SETA bytecode_disasm.h, 72 OP_SETBE bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_WRMSR		
bytecode_disasm.h, 71 OP_ROL bytecode_disasm.h, 71 OP_ROR bytecode_disasm.h, 71 OP_ROR OP_SIDT bytecode_disasm.h, 71 OP_RSM OP_SLDT bytecode_disasm.h, 72 OP_SAR OP_STD bytecode_disasm.h, 71 OP_SAR OP_STD bytecode_disasm.h, 71 OP_SAR OP_STD bytecode_disasm.h, 71 OP_SAR OP_STD bytecode_disasm.h, 71 OP_SCASB OP_STOSB bytecode_disasm.h, 71 OP_SCASB OP_SCOSB OP_STOSB bytecode_disasm.h, 71 OP_SCASB OP_STOSB bytecode_disasm.h, 71 OP_SCASB OP_STOSB bytecode_disasm.h, 71 OP_SCASB OP_STOSB OP_STOB OP_STO OP_STOSB OP_STOB OP_STO OP_STOSB OP_STO OP_STOSB OP_STO OP_STOSB OP_STO OP_STOB OP_STO OP_STOB OP_STO OP_STOSB OP_STO OP_STOB OP_STO OP_STOB OP_STO OP		
bytecode_disasm.h, 71 OP_ROR		bytecode_disasm.h, 72
bytecode_disasm.h, 71 OP_RSM bytecode_disasm.h, 71 OP_SAHF bytecode_disasm.h, 71 OP_SAR bytecode_disasm.h, 71 OP_SAR bytecode_disasm.h, 71 OP_SBB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SETA OP_STOSW bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETC OP_SETC OP_SYSCASW bytecode_disasm.h, 72 OP_SETC OP_SETC OP_SUB bytecode_disasm.h, 72 OP_SETC OP_SYSCALL bytecode_disasm.h, 72 OP_SETC OP_SYSCALL bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_VERR bytecode_disasm.h, 72 OP_VERR bytecode_disasm.h, 72 OP_VERR bytecode_disasm.h, 72 OP_VERR bytecode_disasm.h, 72 OP_VERRW bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WBINND bytecode_disasm.h, 72 OP_WBINND bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 DP_WRMSR	bytecode_disasm.h, 71	
bytecode_disasm.h, 71 OP_SAHF	bytecode_disasm.h, 71	bytecode_disasm.h, 72
bytecode_disasm.h, 71 OP_SAR	bytecode_disasm.h, 71	bytecode_disasm.h, 72
bytecode_disasm.h, 71 OP_SBB		bytecode_disasm.h, 72
bytecode_disasm.h, 71 OP_SCASB bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SETA Dytecode_disasm.h, 72 OP_SETB bytecode_disasm.h, 72 OP_SETBE bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72	bytecode_disasm.h, 71	bytecode_disasm.h, 72
bytecode_disasm.h, 71 OP_SCASD bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SCASW bytecode_disasm.h, 71 OP_SETA bytecode_disasm.h, 72 OP_SETA bytecode_disasm.h, 72 OP_SETBE bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WBMSR bytecode_disasm.h, 72 OP_WBMSR bytecode_disasm.h, 72		bytecode_disasm.h, 72 OP STOSB
OP_SCASW bytecode_disasm.h, 71 OP_SETA bytecode_disasm.h, 72 OP_SETBE bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72		bytecode_disasm.h, 72 OP_STOSD
OP_SETA bytecode_disasm.h, 72 OP_SETBE bytecode_disasm.h, 72 OP_SETC OP_SETC bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72		bytecode_disasm.h, 72 OP_STOSW
OP_SETBE bytecode_disasm.h, 72 OP_SETC bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETG bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72		bytecode_disasm.h, 72 OP_STR
OP_SETC bytecode_disasm.h, 72 OP_SETG OP_SETG bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72		bytecode_disasm.h, 72 OP_SUB
OP_SETG bytecode_disasm.h, 72 OP_SETGE OP_SYSEXIT bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72		
OP_SETGE bytecode_disasm.h, 72 OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72	· —	bytecode_disasm.h, 72 OP_SYSENTER
OP_SETL bytecode_disasm.h, 72 OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72	. —	
OP_SETLE bytecode_disasm.h, 72 OP_SETNC bytecode_disasm.h, 72 OP_SETNO OP_UD2 bytecode_disasm.h, 72 OP_SETNO OP_VERR bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72	· —	
OP_SETNC bytecode_disasm.h, 72 OP_SETNO bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNP bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNS bytecode_disasm.h, 72 OP_SETNZ bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WBINVD bytecode_disasm.h, 72 OP_WRMSR bytecode_disasm.h, 72 DP_WRMSR bytecode_disasm.h, 72	OP_SETLE	OP_TEST
OP_SETNO	OP_SETNC	OP_UD2
OP_SETNP	OP_SETNO	OP_VERR
OP_SETNS	OP_SETNP	OP_VERRW
OP_SETNZ OP_WRMSR bytecode_disasm.h, 72 bytecode_disasm.h, 72	OP_SETNS	—
	OP_SETNZ	_
		bytecode_disasm.h, 72 OP_XADD

bytecode_disasm.h, 72	getImageBase, 41
OP_XCHG	getNumberOfSections, 41
bytecode_disasm.h, 72	getPEBaseOfCode, 42
OP_XLAT	getPEBaseOfData, 42
bytecode_disasm.h, 72	getPECharacteristics, 42
OP_XOR	getPECheckSum, 42
bytecode_disasm.h, 72	getPEDataDirRVA, 42
offset	getPEDataDirSize, 42
cli_exe_info, 54	getPEDIICharacteristics, 43
operation_size	getPEFileAlignment, 43
DIS_fixed, 57	getPEImageBase, 43
opt32	getPELFANew, 43
cli_pe_hook_data, 56	getPELoaderFlags, 43
opt64	getPEMachine, 43
cli_pe_hook_data, 56	getPEMajorImageVersion, 44
other	getPEMajorLinkerVersion, 44
DIS_arg, 57	getPEMajorOperatingSystemVersion, 44
overlays	getPEMajorSubsystemVersion, 44
cli_pe_hook_data, 56	getPEMinorImageVersion, 44
overlays_sz	
cli_pe_hook_data, 56	getPEMinorLinkerVersion, 44
on_po_noon_data, oo	getPEMinorOperatingSystemVersion, 44
PDF Handling	getPEMinorSubsystemVersion, 45
PDF PHASE END, 35	getPENumberOfSymbols, 45
PDF PHASE PARSED, 35	getPEPointerToSymbolTable, 45
PDF_PHASE_POSTDUMP, 35	getPESectionAlignment, 45
PDF PHASE PRE, 35	getPESizeOfCode, 45
PDF PHASE END	getPESizeOfHeaders, 45
PDF Handling, 35	getPESizeOfHeapCommit, 45
PDF PHASE PARSED	getPESizeOfHeapReserve, 46
PDF Handling, 35	getPESizeOfImage, 46
PDF PHASE POSTDUMP	getPESizeOfInitializedData, 46
PDF Handling, 35	getPESizeOfOptionalHeader, 46
PDF PHASE PRE	getPESizeOfStackCommit, 46
	getPESizeOfStackReserve, 46
PDF Handling, 35	getPESizeOfUninitializedData, 46
PE_INVALID_RVA	getPESubsystem, 46
bytecode_api.h, 65	getPETimeDateStamp, 47
PDF Handling, 35	getPEWin32VersionValue, 47
pdf_flag, 35	getPEisDLL, 43
pdf_get_dumpedobjid, 35	getSectionRVA, 47
pdf_get_flags, 35	getSectionVirtualSize, 47
pdf_get_obj_num, 36	•
pdf_get_offset, 36	getVirtualEntryPoint, 47
pdf_get_phase, 36	hasExeInfo, 47
pdf_getobj, 36	hasPEInfo, 47
pdf_getobjflags, 36	isPE64, 48
pdf_getobjid, 37	pe_rawaddr, 48
pdf_getobjsize, 37	readPESectionName, 48
pdf_lookupobj, 37	readRVA, 48
pdf_objflags, 35	PE_HOOK_DECLARE
pdf_phase, 35	Bytecode Configuration, 10
pdf_set_flags, 37	PE_UNPACKER_DECLARE
pdf_setobjflags, 37	Bytecode Configuration, 10
PDF_HOOK_DECLARE	pdf_flag
Bytecode Configuration, 10	PDF Handling, 35
PE Operations, 40	pdf_get_dumpedobjid
get_pe_section, 41	PDF Handling, 35
getEntryPoint, 41	pdf_get_flags
getExeOffset, 41	PDF Handling, 35
- ·	.

pdf_get_obj_num PDF Handling, 36	NumberOfRvaAndSizes, 62 SectionAlignment, 62
pdf_get_offset	SizeOfCode, 62
PDF Handling, 36	SizeOfInitializedData, 62
pdf_get_phase	SizeOfUninitializedData, 62
PDF Handling, 36	pe image section hdr, 62
pdf getobj	Name, 62
PDF Handling, 36	NumberOfLinenumbers, 62
pdf_getobjflags	NumberOfRelocations, 62
PDF Handling, 36	PointerToLinenumbers, 62
pdf_getobjid	PointerToRawData, 62
PDF Handling, 37	PointerToRelocations, 63
pdf_getobjsize	SizeOfRawData, 63
PDF Handling, 37	pe_rawaddr
pdf_lookupobj	PE Operations, 48
PDF Handling, 37	PointerToLinenumbers
pdf_objflags	pe_image_section_hdr, 62
PDF Handling, 35	PointerToRawData
pdf_phase	pe_image_section_hdr, 62
PDF Handling, 35	PointerToRelocations
pdf_set_flags	pe_image_section_hdr, 63
PDF Handling, 37	PointerToSymbolTable
pdf_setobjflags	pe_image_file_hdr, 59
PDF Handling, 37	
pe_image_data_dir, 58	raw
pe_image_file_hdr, 58	cli_exe_section, 55
Machine, 59	read
Magic, 59	File Operations, 25
NumberOfSections, 59	read_number
NumberOfSymbols, 59	File Operations, 26
PointerToSymbolTable, 59	readPESectionName
SizeOfOptionalHeader, 59	PE Operations, 48
TimeDateStamp, 59	readRVA
pe_image_optional_hdr32, 59	PE Operations, 48
CheckSum, 60	reg
FileAlignment, 60	DIS_arg, 57
ImageBase, 60	res_addr
MajorImageVersion, 60	cli_exe_info, 54
MajorLinkerVersion, 60	rsz
MajorOperatingSystemVersion, 60	cli_exe_section, 55
MinorImageVersion, 60	running_on_jit
MinorLinkerVersion, 60	Engine Queries, 18
MinorOperatingSystemVersion, 60	rva
NumberOfRvaAndSizes, 60	cli_exe_section, 55
SectionAlignment, 60	SEEK CUR
SizeOfCode, 60	File Operations, 23
SizeOfInitializedData, 60	SEEK END
SizeOfUninitializedData, 60	File Operations, 23
pe_image_optional_hdr64, 61	SEEK SET
CheckSum, 61	File Operations, 23
FileAlignment, 61	SIZEB
ImageBase, 61	bytecode_disasm.h, 68
MajorImageVersion, 61	SIZED
MajorLinkerVersion, 61	bytecode_disasm.h, 68
MajorOperatingSystemVersion, 61	SIZEF
MinorImageVersion, 61	bytecode_disasm.h, 68
MinorLinkerVersion, 61	SIZEPTR
MinorOperatingSystemVersion, 61	bytecode_disasm.h, 68
	2,100000_diodoi11111,00

SIZEQ	Bytecode Configuration, 1
bytecode_disasm.h, 68	test1
SIZET	bytecode_api.h, 65
bytecode_disasm.h, 68	test2
SIZEW	bytecode_api.h, 66
bytecode_disasm.h, 68	TimeDateStamp
SIGNATURES_DECL_END	pe_image_file_hdr, 59
Bytecode Configuration, 10	uraw
SIGNATURES_DEF_END	cli_exe_section, 55
Bytecode Configuration, 10	ursz
SIGNATURES_END	cli_exe_section, 55
bytecode_local.h, 77	urva
scale	cli_exe_section, 55
DIS_mem_arg, 58	uvsz
scale_reg	cli_exe_section, 55
DIS_mem_arg, 58	on_cxc_scotion, so
Scan Control, 49	VIRUSNAME PREFIX
bytecode_rt_error, 49	Bytecode Configuration, 1
extract_new, 49	VIRUSNAMES
extract_set_container, 49	Bytecode Configuration, 1
foundVirus, 49	version_compare
input_switch, 50	Environment, 22
setvirusname, 50	VSZ
section	cli_exe_section, 55
cli_exe_info, 54 SectionAlignment	,
pe_image_optional_hdr32, 60	write
pe_image_optional_hdr64, 62	File Operations, 26
seek	
File Operations, 26	x86_opcode
segment	DIS_fixed, 57
DIS_fixed, 57	X86OPS
setvirusname	bytecode_disasm.h, 68
Scan Control, 50	X86REGS
SizeOfCode	bytecode_disasm.h, 74
pe_image_optional_hdr32, 60	
pe_image_optional_hdr64, 62	
SizeOfInitializedData	
pe image optional hdr32, 60	
pe_image_optional_hdr64, 62	
SizeOfOptionalHeader	
pe_image_file_hdr, 59	
SizeOfRawData	
pe image section hdr, 63	
SizeOfUninitializedData	
pe_image_optional_hdr32, 60	
pe_image_optional_hdr64, 62	
String Operations, 51	
atoi, 51	
entropy_buffer, 51	
hex2ui, 51	
memchr, 52	
memcmp, 52	
memcpy, 52	
memmove, 52	
memset, 53	
memstr, 53	
TARGET	
T/ II GET	