Survey on Android Memory Management System

May 29, 2012

Garza Matteo

Matr. 755295, (matteo.garza@mail.polimi.it)

Tania Suarez Legra

Matr 748927 (tania.suarez@mail.polimi.it)

Report for the master course of Real Time Operative System (RTOS) Reviser: PhD. Patrick Bellasi (bellasi@elet.polimi.it)

Received: April, 01 2011

Abstract


Android Operative System[4] is the most diffuse OS in mobile devices. In this paper we will analyze how Android manages memory. We discuss in particular about application memory and some of the most used MMUs used by Android OS.

Analyze and document how the Android specific memory management systems work and integrate with hardware resources. In particular, describe how application and hardware resources are managed (OOM killer, PMEM and HWMEM drivers). Project Goals: Understanding the Android memory management Required skills: Linux kernel and UNIX process management basics Peoples: This project is suited for one student or a group with maximum two people. Project Status: Working on: anyone NOTE: still available for other students/groups

1 Kernel Memory Management


1.1 Introduction

Android[2, 4] is a Linux-based operative system, written in C and C++. Android application software runs on a framework which includes Java-compatible libraries. Android uses the Dalvik virtual machine with just-in-time compilation to run Dalvik dex-code (Dalvik Executable), which is usually translated from Java bytecode. Figure 1.1 shows the actual[2] distribution of Android version between devices with this kernel:



We can notice that now the common kernel distributions still use Linux 2.6.x kernel.

Figure 1.1 shows Android System Architecture schema [2].



Android [4] provides some modification to main Linux kernel, such as an improved power management, ASH-MEM virtual memory, some specific-component drivers, and a low memory killer. The latter's mission is to free memory when the system run Out of Memory (OOM).

1.2 Low level management and integration with HW resources

In this part, we discuss about how the memory has managed in Android devices. For most of the releases in Android, it was used PMEM and ASHMEM. These kind of libraries was too simple, and was patched with some SoC patches, such as NVMAP for nVidia Tegra devices and CMEM for TI OMAP ones. The most important patch was CMA (Contiguous Memory Access), expecially with DMABUF patch. With the release of Android 4.0 (Ice Cream Sandwich) a brand new driver has released, ION. We discuss about differences between ION and CMA approach, and, in the state-of-art, we discuss of a future integration between them.

1.3 PMEM and ASHMEM

PMEM (Process MEMory)[1] is the first memory driver implemented on Android devices (since G1). It is used to manage shared memory regions sufficiently large (from 1 to 16MB).

This regions must be physically contiguous between user space and kernel drivers (such as GPU, or DSP). It was written specifically to be used in a very limited hardware platform, and it could be disabled on x86 architectures.

ASHMEM[13] (Android SHared MEMory) is a shared memory allocator subsystem, similar to POSIX, but with a different behavior. It also gives to the developer an easier and file-based API. It used named memory, releasable by the kernel. Apparently, ASHMEM supports low memory devices better than PMEM, because it could free shared memory units when it is needed.

inclinity units when it	is needed.
PMEM	ASHMEM
Uses physically	Uses virtual memory
contiguous	
addresses	
The first process	Memory is handled by
who instantiate a	instances (object
memory heap must	oriented like). It is
keep that till the	managed by a
last one of the	reference counter
users won't free	
the file descriptor.	
Thus to preserve	
contiguity	

1.4 CMA and DMABUF

CMA (Contiguous Memory Allocator)[7] is a well known framework, which allows setting up a machine-specific configuration for physically-contiguous memory management. Memory for devices is then allocated according to that configuration. Differently from similar framework, it let regions of system-reserved memory to be reused in a transparent way, letting memory not to be wasted. When

an alloc is instantiated, this framework migrates all the system page. Thus to build a big chunk of physically contiguous memory.

Why do an OS have to use chunks of memory?[14, 8] Because virtual memory tends to fragment pages. An intensive use of memory let the system not able to find contiguous memory in a very short time after boot. Recently, the requirement of huge pages in applications raises, especially for transparent huge pages. Another question is devices (such as cameras) that needs DMA over areas physically contiguous. CMA reserve an huge area of memory at boot time, only for huge request of memory. For every region, block of pages can be flaggable as three type.

- movable: typically, cache pages or anonymous pages, accessed by page table or page cache radix tree
- kernel recallable: they can be given back to the kernel by request.
- immovable : these are typically pointer referred pages (such as pages invoked by a kmalloc())

The memory manager subsystem try to keep movable pages as near as possible. Grouping these pages, kernel try to ensure more and more contiguous free space available for further request. CMA extends this mechanism. It adds a new type of migration (CMA). Pages flagged as cma behave like the movable ones, with some differences:

- they are "sticky"
- Their migration type can't be modified by the kernel
- In CMA Area, the kernel cannot instantiate pages not movable.

In other words, memory flagged as CMA keep available for the rest of the system with the only restriction to be movable.

When a driver ask for a huge contiguous allocation of memory, CMA allocator can try to free in his own area some contiguous pages to create a buffer large as needed. When the buffer is no longer requested, memory can be used for other needs. CMA can just take only the needed amount of memory without worrying about strictly request of alignment.

DMA buffers has different request despise of huge pages.

DMABUF	Transparent Huge Pages
Normally larger	Almost 2Mb large
than Transparent	
Huge Pages. 10	
Mb.	
It could be needed	
specific memory	
area, if underlying	
hardware is	
sufficiently	
"strange"	
	2MB of THP
DMA requires less	needs 2Mb of
alignment than	Alignment
THP	

CMA patches provides a set of function that can prepare regions of memory and the creation of contest area of a well known size using function cm_alloc and cm_free to keep and release buffers. CMA must not be invoked by the driver, but from DMA support functions. When a driver call a function like dma_alloc_coherent(), CMA should be invoked automatically to satisfying the request. This should work in normal condition.

One of the issue about CMA is how to initially alloc this area of memory. Current scheme needs that some of special calls should be done by the board file system, with a very arm-like approach. The idea is to do that without board files. The ending result is that it should be at least one iteration of that patch set before it will be executed by the mainline.

1.5 ION

In december 2011, PMEM is marked as deprecated, and then replaced by ION memory allocator[15]. ION is a memory manager that Google has developed from the 4.0 release of Android (Ice Cream Sandwich), mainly to resolve the interface issue between different memory management between different Android device. In fact, some SoC developer implemented different memory manager. We can cite some of them:

- NVMAP, implemented on nVidia Tegra
- CMEM[3], implemented on TI OMAP
- HWMEM[11], implemented on ST-Ericsonn devices

All this vendor will pass to ION soon

Besides ION being a memory pool manager, it also enables his clients to share buffers (so, it works like DMABUF, the DMA buffer sharing framework). Like PMEM, ION manages one or more pools of memory, some of them instantiated at boot time or from hardware blocks with specific memory needs. Some devices like that are GPU, display controllers and cameras. ION let his pools to be available

as heap ION. Every kind of android device can have different ION heaps, depending on device memory. Phisical address and heap dimension can be returned to the programmer only if the buffer is physically contiguous. Buffer can be prepared or deallocated to be used with DMA, or with virtual kernel addressing. Using a file descriptor, it can be also mapped in the user-space. There are three kind of allocable ION heap. Other ones can be defined by SoC producers (like ION_HEAP_TYPE_SYSTEM_IOMMU for hardware blocks equipped with IOMMU driver).

- ION_HEAP_TYPE_SYSTEM
- ION_HEAP_TYPE_SYSTEM_CONTIG
- ION_HEAP_TYPE_CARVEOUT: in this case, carveout memory is physically contiguous and set as boot.

Typically, in the user-space case, libraries uses ION to alloc large continuous buffers. For instance, camera library can alloc a capture buffer to be used from the camera device. Once the buffer is fulfilled with video data, the library gives the buffer to kernel to be processed by jpeg encoder block. A c/c++ program must have access to '/dev/ion' before it can alloc memory thanks to ION. He can alloc data using file descriptors (fd). It can be maximum one client for user process.

Clients interacts from user-space with ION using ioctl() system interface. Android processes can share memory using their fd. To obtain shared buffer, the second user process must obtain a client handle through a system call open('/dev/ion', O_RDONLY). ION manage user space client through process PID (in particular, the 'group leader ' one). Fd will be instantiated pointing at the same client structure in the kernel. To free a buffer, the second client must invalidate the mmap() effect, with an explicit call at munmap(), and the first client must close the fd, calling ION IOC FREE. This function decrements the reference counter of the handle. When it reaches zero, the ion_handle is destroyed, and the data structure that manages ION is updated. While managing client calls, ION validates input from fd, from client and from handler arguments. This validation mechanism reduce the probability of undesired access and memory leaks. Ion_buffers is somewhere similar to DMABUF. Both uses anonymous fd, reference counted, as shareable objects.

	ION buffers	DMABUF
Applicat	ioAlloc and free	It focus on import,
level	memory from	export and
MMU	memory pools in a	syncronization in a
	shareable and	consisten way with
	trackable way	buffer sharing solution
		for non arm
		architectures
Role	ION replace PMEM	DMABUF is a buffer
of	as memory pools	sharing framework,
Mem-	manager. ION heap	designed to be
ory	lists can be	integrated with
man-	extended by the	memory allocator in
ager	device.	contiguous DMA
		mapping framewors,
		such as CMA.
		DMABUF exporters
		can implement custom
	IONI - CC /1 - /'	allocator.
User	ION offers /dev/ion	DMABUF offers only
Space	interface to user	kernel API. Access control is a
access	space program, letting them to alloc	function of the
con- trol	and share buffers.	permissions on device
uoi	Every user process	that uses DMABUF
	with ION access	feature
	can suspend the	Teature
	system overlapping	
	ION heap. Android	
	chech user and	
	groupID blocking	
	non authorized	
	access to ION heap	
Global	ION has a driver	The debub structure of
Client	associated to	DMA implements a
and	/dev/ion. The	global hashtable,
Buffer	device structure has	dma_entry_hash,
Database	a database that	tracking DMA buffers,
	keeps ION buffers	but only when kernel is
	allocated, handlers	build with
	and fd, grouped by	CONFIG_DMA_API_
	user client and	DEBUG option.
	kernel client. ION validates all the	
	client calls to be	
	valid for database	
	rules. For instance,	
	an handle can't have	
	two buffers	
	associated.	
Cross-	ION usage now is	DMABUF usage is
archi-	limited on	cross architecture.
tecture	architectures that	DMA mapping
usage	runs kernel Android	redesign let his
		implementation in 9
		architectures beside
		the ARM one.

	ION_buffer	DMABUF
Buffer	Ion consider the	DMABUF gives a
Syn-	syncronization	pair of API for
croniza-	problem as an	synchronization.
tion	orthogonal	Buffer user invokes
	problem	dma_buf_map_
	-	attachment()
		everywhere he
		desires to use buffer
		for DMA. Once he
		finished using that,
		signals
		"endOfDMA" to
		exporter using
		dma_buf_unmap_
		attachment()
Buffer	ION allocs	DMABUF can
delayed	physical memory	delay allocation till
allocation	before the buffer	the first call of
ano cauton	is shared	dma_buf_map_
	15 Sharea	attachment(). DMA
		buffer exporter has
		the opportunity of
		scans every client
		attachment,
		collecting all the
		constraints and
		choose the most
		efficient storage
Integration	Processes that	DMABUF
with	uses these API	integration with
Video4	tends to use	Video4Linux is
Linux2	PMEM. So, the	hard and asked for
API	migration from	lots of modifies in
	PMEM to ION	DMABUF. But in a
	has a relatively	long time that will
	small impact.	be a smart choice,
		because DMABUF
		sharing mechanism
		is fitted for DMA,
		so it is well written
		for CMA and
		IOMMU. Both of
		them reduces
		carveout memory
		needs to build an
		Android
		smartphone.
		Jimar epitotic.

2 OOM Killer

2.1 Introduction

Mobile devices become more and more rich of memory over time, due to Moore's Law. However, there's always

a limit over wich memory isn't available, and a well form kernel needs some politics to free bunch of memory when needed. Android provides an OOM killer, who kills processes with some heuristics, letting memory to be used from someone else. OOM killer mechanism are implemented in most of Linux kernel.

Major distribution kernels set the default value of /proc/sys/vm/overcommit_memory to zero, which means that processes can request more memory than is currently free in the system. This is done based on the heuristics that allocated memory is not used immediately, and that processes, over their lifetime, also do not use all of the memory they allocate. Without overcommit, a system will not fully utilize its memory, thus wasting some of it. Overcommiting memory allows the system to use the memory in a more efficient way, but at the risk of OOM situations. Programs who need lots of memory can consume all the system's memory, stopping the whole system. In such a situation, the OOM-killer kicks in and identifies the process to be terminated.

2.2 OOM Killer parameters

The process to be killed in an out-of-memory situation is selected based on its badness score. The badness score is reflected in /proc/<pid>/oom_score. This value is determined on the basis of four characteristics:

- the system loses the minimum amount of work done,
- recovers a large amount of memory,
- doesn't kill any innocent process,
- and kills the minimum number of processes (if possible limited to one).

The badness score is computed using

- the original memory size of the process,
- its CPU time (utime + stime),
- the run time (uptime start time)
- and its oom_adj value.

The more memory the process uses, the higher the score. The longer a process is alive in the system, the smaller the score.

Any process unlucky enough to be in the swapoff() system call (which removes a swap file from the system) will be selected to be killed first. For the rest, the initial memory size becomes the original badness score of the process. Half of each child's memory size is added to the parent's score if they do not share the same memory. Thus forking servers are the prime candidates to be killed. Having only one "hungry" child will make the parent less preferable than the child. Finally, the following heuristics are applied to save important processes:

- if the task has nice value above zero, its score doubles
- superuser or direct hardware access tasks (CAP_SYS_ADMIN, CAP_SYS_RESOURCE or CAP_SYS_RAWIO) have their score divided by 4. This is cumulative, i.e., a super-user task with hardware access would have its score divided by 16.
- if OOM condition happened in one cpuset and checked task does not belong to that set, its score is divided by 8.
- the resulting score is multiplied by two to the power of oom_adj (i.e. points <<= oom_adj when it is positive and points >>= -(oom_adj) otherwise).

The task with the highest badness score is then selected and its children are killed. The process itself will be killed in an OOM situation when it does not have children.

2.3 lowmemory driver in Android

The Android developers required a greater degree of control over the low memory situation because the OOM killer does not interfere till late in the low memory situation, i.e. till all the cache is emptied. Android wanted a solution which would start early while the free memory is being depleted. So they introduced the "lowmemory" driver, which has multiple thresholds of low memory.

In a low-memory situation, when the first thresholds are met, background processes are notified of the problem. They do not exit, but, instead, save their state. This affects the latency when switching applications, because the application has to reload on activation. On further pressure, the lowmemory killer kills the non-critical background processes whose state had been saved in the previous threshold and, finally, the foreground applications.

Keeping multiple low memory triggers gives the processes enough time to free memory from their caches because in an OOM situation, user-space processes may not be able to run at all. All it takes is a single allocation from the kernel's internal structures, or a page fault to make the system run out of memory. An earlier notification of a low-memory situation could avoid the OOM situation with a little help from the user space applications which respond to low memory notifications.

Killing processes based on kernel heuristics is not an optimal solution, and these new initiatives of offering better control to the user in selecting the process to be the chosen one to terminate are steps to a robust design to give more control to the user.

2.4 User space OOM control

/proc/<pid>/oom_score is a dynamic value, not so much controllable and checkable i by the administrator. It is difficult to determine which process will be killed in case of an OOM condition. The system must let the administrator to modify the score for every process created, and for every process which exits. In an attempt to make OOM-killer policy implementation easier, a name-based solution was proposed. With his patch, the process to die first is the one running the program whose name is found in /proc/sys/vm/oom_victim. A name based solution has its limitations:

- task name is not a reliable indicator of true name and is truncated in the process name fields. Moreover, symlinks to executing binaries, but with different names will not work with this approach
- This approach can specify only one name at a time, ruling out the possibility of a hierarchy
- There could be multiple processes of the same name but from different binaries.
- The behavior boils down to the default current implementation if there is no process by the name defined by /proc/sys/vm/oom_victim. This increases the number of scans required to find the victim process.

possible solution is using containers. The patch introduces an OOM control group (cgroup) with an oom.priority field. The process to be killed is selected from the processes having the highest oom.priority value.

If you want to create a special control group containing the list of processes which should be the first to receive the OOM killer's attention, create a directory under /mnt/oom-killer to represent it: Add the PID of the process to be added to the list of tasks:

This approach could have some trouble, in presence of multiple cpuset. Consider two cpusets, A and B. If a process in cpuset A has a high oom.priority value, it will be killed if cpuset B runs out of memory, even though there is enough memory in cpuset A.

An interesting outcome of the discussion has been handling OOM situations in user space. The kernel sends notification to user space, and applications respond by dropping their user-space caches. In case the user-space processes are not able to free enough memory, or the processes ignore the kernel's requests to free memory, the kernel will kill them.

- the cgroup OOM notifier allows you to attach a task to wait on an OOM condition for a collection of tasks. This allows userspace to respond to the condition by dropping caches, adding nodes to a cpuset, elevating memory controller limits, sending a signal, etc. It can also defer to the kernel OOM killer as a last resort.
- /dev/mem_notify allows you to poll() on a device file
 and be informed of low memory events. This can include the cgroup oom notifier behavior when a collection of tasks is completely out of memory, but can
 also warn when such a condition may be imminent.

[9]

References

- [1] Android kernel features.
- [2] Android (operating system), from wikipedia, the free encyclopedia.
- [3] Cmem overview.
- [4] Android overview, 2011.
- [5] J. Corbet. Arm, dma and memory access, 2011.
- [6] —. Cma and arm, 2011.
- [7] —. Cma documentation file, 2011.
- [8] —. A reworked contiguous memory allocator, 2011.
- [9] W. L. E. J. J. K. Joongjin Kook, Sukil Hong. Optimization of out of memory killer for embedded linux environments. 2011.
- [10] K. P. Marek Szyprowski. Arm dma-mapping framework redesign and iommu integration. October 2011.
- [11] J. Mossberg. hwmem: Hardware memory driver, 2010.
- [12] G. Rodrigues. Taming the oom killer, 2009.
- [13] B. Rosenkraenzer. Ashmem.
- [14] M. Szyprowski. Contiguous memory access, 2011.
- [15] T. M. Zeng. The android ion memory allocator, 2012.