Memo: UVCal FITS Format (.calfits)

Zaki Ali, Bryna Hazelton, Adam Beardsley, Paul La Plante, and the pyuvdata team

July 3, 2017 Revised May 8, 2020

1 Introduction

This memo introduces a new FITS-based file format for storing calibration solutions to use with pyuvdata¹, a python package which provides a software interface for interferometry. We describe the required and optional parameters of a UVCal FITS—hereafter *calfits*—file and pyuvdata's interface for reading and writing these files. For usage examples please refer to the pyuvdata tutorial: http://pyuvdata.readthedocs.io/en/latest/tutorial.html.

2 Overview

Calfits is an adaptation of the FITS file format to enable the storage of calibration information for radio interferometric arrays. Because it builds on the existing FITS file format, all calfits files should be properly formatted according to the FITS standard, which is widely available².

Any valid *calfits* file corresponds directly to a UVCal object within pyuvdata. As such, every new HDU keyword introduced here has a one-to-one correspondence with UVCal object parameters. In this memo, each new keyword is followed by its corresponding UVCal parameter, in parentheses. For more information about the UVCal class and its parameters, please refer to pyuvdata's documentation: http://pyuvdata.readthedocs.io/en/latest/uvcal.html.

2.1 The FITS file

A UVCal object stores calibration solutions as either a "gain" type solution, or as a "delay" type solution. These types represent two distinct but mathematically equivalent conventions, both widely used in radio astronomy. Depending on the calibration type (gain or

https://github.com/RadioAstronomySoftwareGroup/pyuvdata

 $^{^2}$ https://fits.gsfc.nasa.gov/fits_documentation.html

delay), the *calfits* format may consist of up to 4 HDUs. In either case, the primary header is the same and consists of relevant meta-information for a UVCal object to be instantiated. The second HDU is also the same in either case and is the ANTENNAS HDU. This HDU is a BinaryTable and consists of ANTNAME, ANTINDEX, and ANTARR, corresponding to antenna_names, antenna_numbers, and ant_array in the above list, respectively.

When the calibration type is "gain", the essential data contains only these 2 HDUs. In this case, the image data in the primary HDU consists is a 6 dimensional array, where each dimension corresponds to (Nants, Nspws, Nfreqs, Ntimes, Njones, Number of arrays in image array), respectively. In other words, the primary data HDU contains the 5 axes of the data given in the list above, and then a sixth axis corresponding to the individual quantities being saved. For instance, if there is an input_flag_array the image array consists of [real(gain_array), imag(gain_array), flag_array, input_flag_array, quality_array], which is concatenated along the last axis and so the last dimension is equal to 5. However, if no input_flag_array is given, the input_flag_array is left out of the above array and a the last dimension is equal to 4.

When the calibration type is "delay", there are 3 data HDUs. The image data in the primary HDU is still a 5 dimensional array as before (dimensions are Nants, Nfreqs, Ntimes, Njones, number of arrays in image array), but with Nfreqs = 1 as a placeholder axis. This axis is added to keep the data arrays the same size between the delay-type and gains-type formats. In this case the image data is [delay_array, quality_array], concatenated along the last axis. The flag arrays are stored in the third HDU (ImageHDU) which has the flag_array and may have an input_flag_array.

For both delay-types, there is also an optional total_quality_array HDU, which contains information about the overall χ^2 value of the whole array. The size of the array is (Nspws, Nfreqs, Ntimes, Njones). For delay-type calibrations, Nfreqs = 1 as above. If present, there will be 3 total HDUs for gain-type files, and 4 total HDUs for delay-type. Note that self-consistency checks are run when reading and writing calfits files to ensure that arrays have the proper size across different HDUs.

3 Primary Header

The primary HDU of a *calfits* file is an image-type HDU with six axes. These axes, in order, represent

- 1. Number of image arrays
- 2. Integer representing polarization values
- 3. Time
- 4. Frequency
- 5. The spectral window number (currently only a single spectral window is supported)

6. Antenna number

The following are required keywords in the primary header of a *calfits* file. For a more detailed explanation of what these keywords mean, see the descriptions on pyuvdata's ReadTheDocs uvcal_parameters page. The uvcal parameter corresponding to each keyword is noted in parentheses.

3.1 Standard FITS Keywords

Some text descriptions in this subsection are adapted from the official FITS 4.0 Standard, which is available at https://fits.gsfc.nasa.gov/fits_standard.html. Only FITS standard keywords which are required by the format, and those with corresponding uvcal object parameters will be listed here.

3.1.1 Mandatory standard FITS keywords

- **BITPIX**: *integer* Bits per data value, with sign indicating data type. Possible values and their corresponding data types are: -64, double-precision floating point number; -32, single-precision floating point number; 8, character or unsigned 8-bit binary integer; 16, 16-bit two's complement binary integer; 32, 32-bit two's complement binary integer.
- CTYPEm, CUNITm, CDELTm, CRPIXm, CRVALm: string, string, float, float, float Information about the mth axis. In order, describing coordinate type, coordinate unit, step size (delta) between coordinate values on that axis, coordinate reference pixel, and the coordinate's physical value at that reference pixel. Axes are assumed to be linear.
- **EXTEND**: boolean May this FITS file contain extensions? Always *True* in valid calfits files.
- **SIMPLE**: boolean Does file conform to the Standard? The SIMPLE keyword is required to be the first keyword in the primary header of all FITS files. The value field shall contain a logical constant with the value *True* if the file conforms to the standard. This keyword is mandatory for the primary header and is not permitted in extension headers. A value of *False* signifies that the file does not conform to this standard.
- **NAXIS:** *integer* Number of axes in the current HDU. A valid *calfits* file always has NAXIS = 6 in its primary HDU.
- NAXISn: integer The length of the nth axis.
- **TELESCOP**: *string* Observing telescope. Although this keyword is optional in standard FITS files, it is required for *calfits*. (telescope_name)

3.1.2 Optional, but commonly included standard FITS keywords

- **COMMENT**: *string* Descriptive comment. Any number of COMMENT card images may appear in a header.
- **HISTORY**: *string* Processing history of the data. Any number of HISTORY card images may appear in a header.
- **OBSERVER**: *string* The name of the observer. (observer)

3.2 Mandatory *calfits* Keywords

- GNCONVEN: string Gain convention. The convention for applying the calibration solutions to data. Values are "divide" or "multiply", indicating whether one should divide or multiply uncalibrated data by gains. Mathematically this indicates the alpha exponent in the equation: (calibrated data) = $(gain^{\alpha}) \times (uncalibrated data)$. A value of "divide" represents $\alpha = -1$ and "multiply" represents $\alpha = 1$. (gain_convention)
- **CALTYPE**: *string* Calibration type parameter. Possible values are "delay", "gain", or "unknown". (cal_type)
- CALSTYLE: *string* Style of calibration. Possible values are "sky" or "redundant". (cal_style)
- INTTIME: float Integration time of a time bin, in units of seconds. (integration_time)
- **CHWIDTH:** *float* Channel width of of a frequency bin, in units of Hz. (channel_width)
- **XORIENT:** string Orientation of the physical dipole corresponding to what is labeled as the x polarization. Possible values are are "east" (indicating east/west orientation) or "north" (indicating north/south orientation). (x_orientation)
- **TMERANGE:** (minimum: *float*, maximum: *float*) Time range (in JD) that cal solutions are valid for. (time_range)

3.2.1 Required if CALSTYLE = "sky"

- **CATALOG**: *string* (Required if CALSTYLE = "sky".) Name of the calibration catalog. (sky_catalog)
- **FIELD**: *string* (Required if CALSTYLE = "sky".) A short string describing the field center or dominant source. (sky_field)

• **REFANT**: *string* (Required if CALSTYLE = "sky".) Phase reference antenna. (ref_antenna_name)

3.2.2 Required if CALTYPE = "delay"

• **FRQRANGE:** *float* Required if CALTYPE = "delay". Frequency range that solutions are valid for, in Hz. (freq_range)

3.3 Optional Keywords

- BL_RANGE: float Range of baselines used for calibration. (baseline_range)
- **DIFFUSE:** string Name of diffuse model used for sky model. (diffuse_model)
- **GNSCALE:** *string* The gain scale of the calibration, which indicates the units of the calibrated visibilities. For example, Jy or K. (gain_scale)
- **HASHCAL:** *string* Commit hash of calibration software (from ORIGCAL) used to generate solutions. (git_hash_cal)
- **NSOURCES:** *integer* Number of sources used in sky model. (Nsources)
- **ORIGCAL:** *string* Origin (on github for e.g) of calibration software. Url and branch. (git_origin_cal)

There are also some optionally required parameters that depend on the calibration type. These parameters include.

- **delay_array**: Required if cal_type = "delay". Array of delays with units of seconds. Shape: (Nants_data, Nspws, 1, Ntimes, Njones), type = float. (delay_array)
- gain_array: Required if cal_type = "gain". Array of gains, shape: (Nants_data, Nspws, Nfreqs, Ntimes, Njones), type = complex float. (gain_array)
- **freq_range**: Required if cal_type = "delay". Frequency range that solutions are valid for. list: [start_frequency, end_frequency] in Hz. (freq_range)

In addition to the required parameters, there are a number of truly optional parameters that may be passed in. These include:

- git_origin_cal: Origin (on github for e.g) of calibration software. Url and branch. (git_origin_cal)
- git_hash_cal: Commit hash of calibration software (from git_origin_cal) used to generate solutions. (git_hash_cal)

- input_flag_array: Array of input flags, True is flagged. shape: (Nants_data, Nspws, Nfreqs, Ntimes, Njones), type = bool. (input_flag_array)
- total_quality_array: Array of qualities of the calibration solution for the entire array. The shape depends on cal_type, if the cal_type is "gain" or "unknown", the shape is: (Nspws, Nfreqs, Ntimes, Njones), if the cal_type is "delay", the shape is (Nspws, 1, Ntimes, Njones), type = float. (total_quality_array)

Once these parameters are set in the UVCal object, a calfits file may be written out.

4 Reading and Writing a *calfits* File

Writing out the UVCal object to a file is very simple: just run UVCal.write_calfits(filename). That will write a fits file called "filename". Note that a filename check will be done and a new file will not be written with the same name. You can override this functionality with the clobber key word.

Reading in a calfits file is also straightforward. First instantiate the UVCal object and then run UVCal.read_calfits(filename). This updates the UVCal object with all the parameters from the fits file.

There are examples of working with pyuvdata UVCal objects and *calfits* files in the tutorial (http://pyuvdata.readthedocs.io/en/latest/tutorial.html).