Dynace

User Manual Version 5.08 November 23, 2004 Copyright © 1996 Blake McBride All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

MS-DOS, Windows and Microsoft are registered trademarks of Microsoft Corporation. WATCOM is a trademark of WATCOM Systems, Inc. All Borland products are trademarks or registered trademarks of Borland International, Inc. TeX is a trademark of the American Mathematical Society. Other brand and product names are trademarks or registered trademarks of their respective holders.

This manual was typeset with the TEX typesetting system developed by Donald Knuth.

Short Contents

1	Introduction
2	Concepts
3	Mechanics
4	Kernel Reference
5	Class Library Reference
Met	hod, Macro, Function And Variable Index

Table of Contents

1	Introduction	1
	1.1 Features	. 1
	1.2 Reasons to use Dynace	. 3
	1.3 Dynace vs. Other Languages	. 4
	1.3.1 A comparison of Dynace and C++	. 4
	1.3.1.1 Code In Header Files	
	1.3.1.2 Frequency Of Re-compiles	. 4
	1.3.1.3 Application Maintainability / Object Encapsulation	. 5
	1.3.1.4 C++ Templates	. 5
	1.3.1.5 Virtual Functions	. 5
	1.3.1.6 Learning Curve / Code Complexity	. 6
	1.3.1.7 Code Re-usability	
	1.3.1.8 Strong vs. Weakly Typed Languages	
	1.3.1.9 Generic Container Classes	. 8
	1.3.1.10 Runtime class representation	. 8
	1.3.1.11 Efficiency	. 9
	1.3.1.12 Compatibility With C	. 9
	1.3.1.13 Garbage Collection	
	1.3.1.14 Class Library	
	1.3.1.15 Conclusion	
	1.3.2 A comparison of Dynace and Smalltalk	
	1.4 Installation	
	1.5 Contents	
	1.6 Learning The System	
	1.7 Quick Start & Tutorial	
	1.8 Manual Organization	
	1.9 Contact Information	
	1.10 Use, Copyrights & Trademarks	
	1.11 Credits	11
		10
2	Concepts	
	2.1 Object Oriented	
	2.1.1 Encapsulation	
	2.1.2 Polymorphism And Overloading	
	2.1.2.1 Early vs. Late Binding	
	2.1.3 Inheritance	
	2.2 Dynace	
	2.2.1 Object	
	2.2.2 Classes & Instances	
	2.2.2.1 Superclasses	
	2.2.2.2 Instance Variables	
	2.2.2.3 Class Variables	26 26
	Z Z 5 IVIELACIASSES	ZD

iv Dynace Manual

	2.2.4 Methods	$\dots 27$
	2.2.4.1 Instance Methods	27
	2.2.4.2 Class Methods	27
	2.2.5 Generic Functions	27
	2.2.5.1 Method Lookup	
	2.2.6 Memory Management and Garbage Collection	29
	2.2.7 Threads	29
	2.2.8 Pipes	30
	2.2.9 Semaphores	
	2.2.10 Dynace Kernel & Class Library	30
3	8 Mechanics	33
•	3.1 Setup, Configuration & Build Procedures	
	3.1.1 Build Utilities	
	3.1.2 DMAKE Build Setup	
	3.1.3 Building Dynace From Scratch	
	3.1.4 Examples Setup	
	3.1.5 Example Files	
	3.1.6 Building The Examples	
	3.1.7 Debugging	
	3.1.8 Building Your Own Application	
	3.1.9 DMAKE	
	3.2 Using Dynace Classes	
	3.2.1 External Naming Conventions	
	3.2.2 Internal Naming Conventions	
	3.2.3 Class Hierarchy	
	3.2.4 Example Code	
	3.2.5 Include File	
	3.2.6 Declarations	
	3.2.7 Initializing Dynace	
	3.2.8 Generic Functions	
	3.2.9 Creating Objects	40
	3.2.10 Using Objects	
	3.2.11 Disposing of Objects	
	3.2.11.1 Disposal Generics	
	3.2.11.2 Garbage Collection	42
	3.2.12 Generics Files	
	3.2.13 Compiling & Linking	43
	3.2.13.1 Files	43
	3.2.13.2 Compiling & Linking	43
	3.2.14 Learning Dynace Classes	43
	3.3 Defining Dynace Classes	
	3.3.1 Class Definition File Syntax	
	3.3.1.1 Class Definition	47
	3.3.1.2 Public Method Definition	49
	3.3.1.3 Private Method Definition	51
	3.3.1.4 Super Messages	51
	3.3.1.5 Comments	

3.3.2	Example Code	
3.3.3	Class Definition54	
3.3.4	Defining Methods54	
3.3	3.4.1 Accessing Instance And Class Variables	
3.3	3.4.2 Determining the Class of an Object	
3.3	3.4.3 Sending Super Messages	
3.3.5	Class Initialization	
3.3	3.5.1 Class Initialization Function	
3.3	3.5.2 An Example	
3.3.6	What Gets Linked 60	
3.3.7	The gNew Class Method 61	
3.3.8	The Dispose Instance Method 61	
3.3.9	Creating Generic Files	
3.4 Dyn	nace Pre-Processor (DPP)	
3.4.1	Controlling DPP	
3.4.2	DPP Status Messages64	
3.4.3	Input Options (-g & -G)	
3.4	4.3.1 Generic Declaration Input	
3.4	1.3.2 Source File Input (-s & -p)	
3.4.4	Output Options	
3.4	4.4.1 Generic Declaration File Creation (-h)	
3.4	4.4.2 Generic Source File Creation (-c)	
3.4	4.4.3 Processing Class Definition Files (-p)	
3.4	1.4.4 Java Interface Files (-j)	
=	1.4.5 Scheme Interface Files (-L1 & -L2)	
	Misc. Options	
	1.5.1 Preventing Unnecessary Compiles (-t)	
	1.5.2 Removing Classes or Generics (-r)	
	1.5.3 Splitting the Generics File (-M)	
	4.5.4 Including Additional	
	Header Files (-Isc, -Iac, -Ish & -Iah)	
3.4	4.5.5 Ignoring Errors (-i)	
3.4	4.5.6 Quiet Operation (-q)	
	1.5.7 Return Code (-z)	
	4.5.8 Compile Time Argument Checking (-N)	
	1.5.9 Disabling #line directives (-nld)	
	4.5.10 Extra #line directives (-eld)	
	4.5.11 Preprocessing Strategies (-S)	
	1.5.12 Generic Overloading (-X)	
	1.5.13 Force Generics.h File Generation (-f)	
	1.5.14 Generating External Structures (-iv & -cv)	
	1.5.15 Class Initialization (-ni)	
	4.5.16 Auto Include Generation (-nai)	
	1.5.17 Macro Guard Typedefs (-mg)	
	nace Customization & Special Techniques	
3.5.1	,	
	5.1.1 Adding New Classes	
3.5	5.1.2 Removal Of Classes	

vi Dynace Manual

3.5.1.3 Adding New Generics	72
3.5.1.4 Generic Removal	
3.5.1.5 Generic Argument Or Return Type Changes	
3.5.2 Compile Time Argument Checking	
3.5.2.1 Compile Time vs. Runtime Argument Checking	
3.5.2.2 Sharing Methods	
3.5.3 Runtime Argument Validation	
3.5.3.1 Additional Argument Validation	
3.5.4 Methods With A Variable Number Of Arguments	
3.5.5 Tracing Facility	
3.5.6 Memory Management and Object Disposal	
3.5.7 Speeding Up IsObj	
3.5.8 Garbage Collection	
3.5.9 Global or Static Variables	
3.5.10 Boehm Garbage Collector	
3.5.11 Native Thread Support	
3.5.12 Method Cache	
3.5.13 Memory Compaction	
3.5.14 Avoiding Runtime Method Lookup Costs	
3.5.15 Generic Functions As First Class C Objects	
3.5.16 Static Binding	80
3.5.17 Allocating Objects From The Stack	80
3.6 Notes On Compilers, Rebuilding And Porting Dynace	
3.6.1 DMAKE	. 82
3.6.2 MS-DOS	82
3.6.2.1 Microsoft Visual C++	82
3.6.2.2 WATCOM Compilers	83
3.6.2.3 Borland C++	83
3.6.2.4 Symantec C++	83
3.6.3 UNIX	. 83
3.6.4 Using A Debugger	
3.6.5 Porting To Other Compilers, Memory Models or OSs	84
3.6.5.1 JumpTo Assembler Code	
3.6.5.2 GC & CPU Registers	85
3.6.5.3 Memory Alignment	
3.6.5.4 Linear vs. Segmented Memory	
3.6.5.5 Thread Timer	
3.6.5.6 Setjmp/longjmp Functionality	. 86
4 Kernel Reference	. 87
4.1 Kernel Class Hierarchy	
4.2 Object Class	
4.2.1 Object Class Methods	
4.2.2 Object Instance Methods	
4.3 Behavior Class	
4.3.1 Behavior Class Methods	
4.3.2 Behavior Instance Methods	
4.4 Class Class	

	4.4.1 Class Class Methods	106
	4.4.2 Class Instance Methods	108
	4.5 MetaClass Class	109
	4.6 Method Class	110
	4.6.1 Method Class Methods	110
	4.6.2 Method Instance Methods	110
	4.7 GenericFunction Class	113
	4.7.1 GenericFunction Class Methods	113
	4.7.2 GenericFunction Instance Methods	114
	4.8 Dynace Class	117
	4.8.1 Dynace Class Methods	117
	4.8.2 Dynace Instance Methods	126
	4.9 Kernel Macros	127
	4.10 Kernel Functions	153
	4.11 Kernel Data Types	157
5	Class Library Reference	159
	5.1 Class Library Hierarchy	
	5.2 Array Class	
	5.2.1 Array Class Methods	
	5.2.2 Array Instance Methods	
	5.3 Association Class	
	5.3.1 Association Class Methods.	
	5.3.2 Association Instance Methods	
	5.4 BitArray Class	
	· · · · · · · · · · · · · · · · · · ·	
	5.4.1 BitArray Class Methods	
	5.4.2 BitArray instance Methods	
	5.5.1 BTree Class Methods	
	5.5.2 BTree Instance Methods	
	5.6 BTreeNode Class	
	5.7 Character Class	
	5.7.1 Character Class Methods	
	5.7.2 Character Instance Methods	
	and the same of th	
	5.9 Constant Class	
	5.9.2 Constant Instance Methods	
	5.10.1 Date Class Methods	
	5.10.2 Date Instance Methods	
	5.11 DateTime Class	
	5.11.1 DateTime Class Methods	
	5.11.2 DateTime Instance Methods	
	5.12 Dictionary Class	
	5.12.1 Dictionary Class Methods	
	5.12.2 Dictionary Instance Methods	
	5.13 DoubleFloat Class	$\dots 205$

viii Dynace Manual

5.13.1	DoubleFloat Class Methods	. 205
5.13.2	DoubleFloat Instance Methods	. 205
5.14 Dou	bleFloatArray Class	. 207
5.15 File	Class	. 208
5.15.1	File Class Methods	. 208
5.15.2	File Instance Methods	. 210
5.16 Fine	dFile Class	
5.16.1		
5.16.2	FindFile Instance Methods	
	atArray Class	
	gerArray Class	
	gerAssociation Class	
5.19.1	9	
5.19.2	IntegerAssociation Instance Methods	
00	gerDictionary Class	
5.20.1	Integer Dictionary Class Methods	
5.20.1 $5.20.2$		
	Class	
	Link Class Methods	
5.21.1 $5.21.2$		
0	Link Instance Methods	
	kList Class	
	LinkList Class Methods	
	LinkList Instance Methods	
	Object Class	
5.23.1	LinkObject Class Methods	
5.23.2	LinkObject Instance Methods	
	ObjectSequence Class	
5.24.1	9 1	
5.24.2	LinkObjectSequence Instance Methods	
5.25 Link	Sequence Class	
5.25.1	1	
5.25.2	1	
	«Value Class	
	LinkValue Class Methods	
5.26.2	LinkValue Instance Methods	. 253
	gArray Class	
5.28 Lon	gInteger Class	. 257
5.28.1	LongInteger Class Methods	. 257
5.28.2	LongInteger Instance Methods	. 257
5.29 Loo	kupKey Class	. 258
5.29.1	LookupKey Class Methods	
5.29.2	LookupKey Instance Methods	
	File Class	
5.30.1	LowFile Class Methods	
5.30.2	LowFile Instance Methods	
	nber Class	
5.31.1	Number Class Methods	
5.31.2	Number Instance Methods	
J.J.		00

5.32 Nun	aberArray Class	271
5.32.1	NumberArray Class Methods	271
5.32.2	NumberArray Instance Methods	271
5.33 Obj	ectArray Class	280
5.33.1	ObjectArray Class Methods	
5.33.2	ObjectArray Instance Methods	280
5.34 Obj	ectAssociation Class	
	ObjectAssociation Class Methods	
5.34.2	ObjectAssociation Instance Methods	
	ectPool Class	
5.35.1	ObjectPool Class Methods	
	e Class	
5.36.1		
5.36.2	Pipe Instance Methods	
	ater Class	
5.37 - 1.01 $5.37.1$	Pointer Class Methods	
	Pointer Instance Methods	
	nterArray Class	
	PointerArray Class Methods	
5.38.2		
	pertyList Class	
	PropertyList Class Methods	
	PropertyList Instance Methods	
5.40 Sem	aphore Class	
5.40.1	Semaphore Class Methods	
5.40.2	Semaphore Instance Methods	
_	ience Class	
	Class	
5.42.1	Set Class Methods	303
5.42.2	Set Instance Methods	304
5.43 SetS	Sequence Class	313
5.43.1	SetSequence Class Methods	313
5.43.2	SetSequence Instance Methods	313
5.44 Shor	rtArray Class	314
5.44.1	ShortArray Class Methods	314
	rtInteger Class	
5.45.1	ShortInteger Class Methods	315
5.45.2	ShortInteger Instance Methods	
5.46 Soci	xet Class	
5.46.1	Socket Class Methods	
5.46.2	Socket Instance Methods	
5.47 Stre	am Class	
5.47.1	Stream Class Methods	
5.47.2	Stream Instance Methods	
5.47.2 $5.47.3$	Stream Global Variables	
00	ng Class	
5.48.1	String Class Methods	
5.48.2	String Instance Methods	
0.40.4	NOTHING THOUGHOU INTOUTIONS	550

5.49 Stri	ngAssociation Class
5.49.1	StringAssociation Class Methods
5.49.2	StringAssociation Instance Methods
5.50 Stri	ngDictionary Class
5.50.1	StringDictionary Class Methods
5.50.2	StringDictionary Instance Methods
5.51 Three	ead Class
5.51.1	Thread Class Methods
5.51.2	Thread Instance Methods
5.51.3	Thread Macros
5.52 Tim	e Class
5.52.1	Time Class Methods
5.52.2	Time Instance Methods
5.53 Uns	ignedShortArray Class
5.54 Uns	ignedShortInteger Class
5.54.1	UnsignedShortInteger Class Methods
5.54.2	UnsignedShortInteger Instance Methods
Method,	Macro, Function And Variable Index 383

1 Introduction

Dynace (pronounced $d\bar{i}$ -ne- $s\bar{e}$) stands for a "DYNAmic C language Extension". It is an object oriented extension to the C or C++ languages.

Dynace is written in the C language, designed to be as portable as possible and achieve its goals without changing or adding much to the standard C syntax.

Dynace is a preprocessor, include files and a library which extends the C or C++ languages with advanced object oriented capabilities, automatic garbage collection and multiple threads. Dynace is designed to solve many of the problems associated with C++ while being easier to learn and containing more flexible object oriented facilities. Dynace is able to add facilities previously only available in languages such as Smalltalk and CLOS without all the overhead normally associated with those environments.

This manual is designed for a programmer who is proficient in the C language, but has little or no knowledge of object oriented concepts. We will start with some object oriented concepts, and then discuss how these concepts are realized with Dynace. We will then continue with a detailed description of Dynace usage. Finally, we will discuss the various classes which are built on top of the Dynace kernel.

1.1 Features

The following table lists some of the key features of Dynace:

- Written in C and designed to maximize portability (currently tested on 16 & 32 bit DOS, Windows 3.1, Windows 95, Windows NT, Linux, Nextstep, SunOS & various other Unix, Plan 9, VMS and Macintosh.)
- Very little added to the standard C syntax (very easy to learn for anyone familiar with C)
- May be intermixed and linked with regular C or C++ code (easy to incrementally add OO features to pre-existing apps)
- Multiple Inheritance
- True Dynamic Binding (polymorphism) Using Generic Functions
- Fast, Cached, Method Lookup
- Full Metaclass System (runtime class representation)
- Enforced Encapsulation very important for large applications! (No longer place 50\% of your code in include files, as in C++. If something changes no need to recompile everything in Dynace. If a class needs to be changed you don't need to worry who is looking under the hood, as in C++)
- Modeled after CLOS providing the most flexible solution without the overhead and runtime penalty, and large memory requirements of an interpreter (as in CLOS and Smalltalk).
- Compiles with a regular C or C++ compiler not an interpreter runs FAST! (Doesn't have the runtime overhead and performance penalty experienced with CLOS and Smalltalk)

• Automatic Garbage Collection (system automatically frees unused objects – you no longer have to keep track of what and when things must be freed)

- Multiple Threads
- Named & Unnamed Pipes
- Named & Unnamed Counting Semaphores
- Any Class located anywhere in the class hierarchy may be changed without necessitating the re-compilation of any other module so long as the pre-existing method protocols remain unchanged. (No need to re-compile the world because your not sure who is using or subclassing it A major problem with C++!!)
- Uniform representation of all objects including Classes, Instances, Methods, and Generics. This allows easy construction of generic container classes.
- Powerful base class library including fundamental data types and collection classes such as Dictionary and Double Linked Lists.

1.2 Reasons to use Dynace

The following lists several reasons to use Dynace:

- 1. Drastically reduce application complexity and increase its maintainability by enforcing strong encapsulation no more need to wonder which other modules are modifying your instance variables or what effect changes in one module will have on other modules.
- 2. Drastically reduce the need for recompilation since all class information is defined in the source file (*.c) instead of header files (*.h). Most changes to a class, including its place in the class hierarchy, instance or class variable declarations, new or changed methods (member functions), have no compile time effect on modules which use, subclass or inherit from the changed class.
- 3. Easily build generic functionality (like generic container classes) which translates into increased use of existing code since Dynace treats all objects, including classes, in a uniform manner and supports weak and runtime object typing.
- 4. Dynace is the easiest OO language to learn since it's almost entirely normal C syntax, yet offers features far surpassing all the alternatives such as true dynamic binding using generic functions, multiple inheritance, fully metaclass based (runtime class representation) from the ground up (like CLOS or Smalltalk), garbage collector (system automatically frees unused objects), threader, and a powerful class library. Defining classes in Dynace is simple, all of the complexity and house cleaning chores are handled by the Dynace pre-processor (dpp).
- 5. Dynace applications run fast because they are compiled by your normal C compiler into fast machine code (no interpreter or p-code). Dynace includes a pre-processor which converts Dynace class definition files (which contain mostly straight C code) into plain C source files.
- 6. It's easy to incrementally add OO facilities into pre-existing C code because Dynace is just more C code.
- 7. No longer be the victim of a vendor Dynace comes with full, portable source code.
- 8. You no longer have to distribute header files containing your proprietary class structure in order for third parties to be able to use and subclass your class. Dynace doesn't need any of this information.
- 9. Dynace OO model is much more flexible due to its metaobject base. Now you can actually have greater control over classes as well as instances.
- 10. Dynace applications are royalty free (with the appropriate license).

1.3 Dynace vs. Other Languages

1.3.1 A comparison of Dynace and C++

The Dynace object oriented extension to the C language was created in order to solve many of the problems associated with C++ while retaining more backward compatibility with C than C++ and offering stronger object oriented facilities. This section discusses many of the shortcomings of C++ and how Dynace address them, as well as other important facts regarding Dynace.

1.3.1.1 Code In Header Files

C++ greatly encourages the movement of code and class definitions from source files (.c) to header files (.h). Because of its design, C++ requires this in order to support many of its compile time facilities. However, while enabling many compile time facilities, it is also the source of many of C++'s shortcomings. Dynace is able to offer similar compile time facilities (argument checking, ability to subclass a pre-existing class, etc.) while greatly encouraging movement of code from header files (.h) to source files (.c). In fact, all Dynace class definitions are entirely contained within source files. The consequences of these fundamental design differences will ripple throughout this comparison.

C++ requires class definitions to be placed in header files and included by other source files for three main reasons. The first reason is so that when other files need to declare or create new instances of a given class, C++ needs to know the size of the instance at compile time.

The second reason is that C++ needs to know the entire structure of classes at compile time in order to create a new subclasses of them. The third reason is that C++ needs to know at compile time the names and locations of all externally accessible instance members (through public, protected and friend members).

Dynace is able to perform these facilities with an increased level of abstraction and code protection without any class definitions in header files.

1.3.1.2 Frequency Of Re-compiles

One very important consequence of placing class definitions in header files is that even very small changes in a class's definition necessitates the re-compilation of source files which implement the class, files which use the class and files which subclass that class. On large, real-life applications this can amount to several hours of time. And for applications in which a lot of development is being done, this may be required every thirty minutes. The net effect of this problem is that compile time quickly becomes the place where most of the development time is spent.

Dynace, on the other hand, places all class definition code in source (.c) files. With Dynace, you can have a massive application, take a class out of the middle of the class hierarchy and totally modify it, and so long as the pre-existing member functions (methods) retain their interface protocol (take the same arguments), only the one source file which implements that class would have to be re-compiled. Even if the member function's syntax changed, the only thing that would have to be modified and re-compiled were those modules who used the changed member function – something which would have to be done in any

environment. The net effect of Dynace's approach is that only the absolute minimum amount of time is wasted on compiles.

1.3.1.3 Application Maintainability / Object Encapsulation

One of the principal features of the object oriented paradigm is encapsulation. Encapsulation is the ability to combine code and data into a package such that the only external access provided is through a well defined interface. There are several important benefits associated with strong encapsulation.

At development time, strong encapsulation helps organize the design and breaks up the code into manageable size chunks. At debug time, strong encapsulation significantly limits the amount of code a programmer has to look at in order to locate the problem. After development, strong encapsulation makes code easier to understand by new programmers and limits the amount of code which must be checked and modified when a given module is changed. Strong encapsulation can have a major effect on the development, debug, and enhancement times associated with a project, not to mention reliability of the code.

C++ supports four types of encapsulation (protection) associated with members of a class: private, protected, public and friends. Of the four types, three of them (public, protected and friends) are ways to circumvent C++'s encapsulation features. And private members are only private from a narrow standpoint since it is declared in a publicly accessible header file.

Note that from a technical standpoint, there is never a reason for protected, public or friend members. Anything you could ever need to do can be done with private members and access functions. The net effect is that C++, for no apparent technical reason, does not encourage strong encapsulation, nor does it even have the facilities to support it.

Dynace, on the other hand, enforces strong encapsulation (private members) and places all member definitions in a source (.c) file. With this approach, all the benefits of strong encapsulation may be maximally achieved.

1.3.1.4 C++ Templates

In order to write similar code for many classes C++ provides templates. Templates are an extremely poor attempt to patch some of the blatant shortcomings of C++. There are two principal problems with templates. First, it suffers from the same compile-time limitations as all the rest of C++, namely, templates only work on classes which were set up at compile-time. Any time you want to add a new class, rebuild time. The second problem is unnecessary duplication of code. If you compile a template for five classes, you get five copies of the same code!

Dynace has no templates and no need for them. Dynace methods support any class at runtime. No need to re-compile the existing ones or to duplicate any code. The existing code adapts to new classes at runtime!

1.3.1.5 Virtual Functions

Virtual functions give C++ a great deal of flexibility. However, there is a major problem associated with them. If you purchase a third party library and the vendor chooses not

to implement a particular function as a virtual function and you later need to use it as a virtual function, it can't be done without the source code.

In Dynace all methods operate like C++ virtual member functions. There is never a one you can't use like a virtual function. Dynace implements these methods in a memory efficient manner so it's not prohibitive.

1.3.1.6 Learning Curve / Code Complexity

C++ is a large and complex language from a syntactical standpoint, especially when compared to the minimalist C language. There are two problems associated with this complexity. The first is that the learning curve associated with going from a proficient C programmer to a proficient C++ programmer is at least six months for most programmers. The second problem is that code written in C++ tends to be more complex and therefore harder for new programmers to understand and maintain. The bottom line is that C++ development tends to be much more expensive than C and employers end up being much more dependent on a few "experts".

Dynace, on the other hand, uses straight C syntax and only adds a few, easy to learn, constructs. The learning curve associated with Dynace is about one week (although you can actually use it the first day). Pre-existing C code can co-exist with Dynace code better than C++. And due to the simpler syntax and strong encapsulation features of Dynace, it is much easier for new programmers to pick up Dynace and the new application. This translates into real dollars saved.

Dynace adds powerful capabilities of object oriented technology in a simple, idealistic, theoretically pure way. Dynace has taken the best attributes of CLOS, Smalltalk and Objective—C and implemented it in a way which is natural to a C programmer. A Dynace program looks just like any other C program. Dynace is, therefore, much simpler and easier to master than C++ and the resulting tool is more powerful and expressive.

1.3.1.7 Code Re-usability

C++ is a strongly typed language. This means that all type information associated with variables and function arguments must be completely specified at compile time. While attempting to create reusable code a programmer must create routines which are general purpose and can therefore be used in a variety of situations. The problem is that these two points are at odds with each other.

When creating general purpose (reusable) software components it is often desirable to have the routine handle a variety of data types, as is often needed in container classes. Strongly typed languages require that the potential data types be known at the compile time of the routine. This means that every time a new data type is used the "general purpose" routine would have to be modified and recompiled. How many books and articles have you seen which attempt to trick C++ into handling data in a generic fashion? This important feature of good software development (creating reusable software) is an up hill battle with C++.

Dynace, on the other hand, is a weakly typed language. This means that Dynace treats all objects (including classes) in a generic fashion. Creating generic (reusable) routines like

container classes are trivial in Dynace. Dynace is also able to validate an object or its type at runtime.

1.3.1.8 Strong vs. Weakly Typed Languages

Strongly typed languages (such as C++) require that the programmer specify exactly what data types a particular routine may handle. Whereas, weakly typed languages (such as Dynace, CLOS and Smalltalk) allow a programmer to define a process in abstract terms without specifying any particular data types. It's kind of like the difference between speaking literally and speaking abstractly.

If teaching a child were anything like programming a computer and you could only teach him literally you would have to explain to him that if he had two dogs and someone gave him another, he would then have three dogs. If he has two apples and someone gives him another he'll have three apples. If he has two trains and someone gives him another he'll have three trains, and so on. However, if you could teach your child in abstract terms you could simply tell him that if he has two of something and he receives another, he'll then have three of them.

The advocates of strongly typed languages like to point out that their language can uncover an incorrect argument to a function at compile time, before the program is even run. The reality of it is that passing the incorrect data type to a function is just one of many, many possible types of errors a given program may contain. Why restrict a language's capabilities so severely to uncover just one type of error.

In fact when programming in C++ it is quite easy to create a situation where the correct type is being passed (a pointer to some structure) but when the code gets run it hangs the system because it wasn't initialized and the compiler can't check for that. So C++, as well as other strongly typed languages, are quite good at performing static, compile time, type checking at the expense of a flexible language. And then when it comes to dynamic (runtime) checking you're on your own.

While Dynace does check arguments at compile time, it does not attempt to validate each argument beyond whether it's an object or a particular C data type. In other words, all Dynace objects are treated opaquely. Not only can Dynace verify the type at runtime (essentially the same test C++ performs at compile time), but it will also validate an uninitialized pointer! If there is an attempt to use an uninitialized object or an incorrect type of object Dynace prints an error message. No hung system.

Weakly typed languages, such as Dynace, provide an extremely more flexible and powerful means of expressing computer algorithms, and they do this with an increase in error detection and handling as compared to strongly typed languages such as C++.

Weak typing is a much stronger approach to implementing the object oriented model. Weak typing allows much more powerful, flexible, and general purpose solutions to be developed. Since strong typing requires the types of data a routine handles be known at compile time, at the very least, the module will have to be recompiled if it is to handle a new type of object, if not entirely re-coded. Weak typing allows the development of truly general purpose, reusable software components.

1.3.1.9 Generic Container Classes

The tremendous difficulty involved in tricking C++ into implementing generic container classes, such as dictionary, linked list and bags, typifies the biggest problem with C++, lack of runtime flexibility. How many books and computer magazine articles have to be written in order to show how to trick C++ into accomplishing something which should be fundamental and trivial. It lies at the heart of the value of object oriented concepts.

The properties of C++ which make is so inflexible are it's strong data typing and lack of runtime class representation.

Creating generic container classes is fundamental and trivial in Dynace. This is a very important difference.

1.3.1.10 Runtime class representation

C++ has no runtime representation of classes and no metaclasses. In fact, a C++ class is not an object at all. In short, C++ is a half hearted attempt to add object oriented capabilities to the C language. Dynace implements all object oriented concepts in a pure, flexible fashion. In fact, in Dynace, classes are objects just like any other.

Since C++ has no runtime class representation its compiler must know the entire (supposed to be private) structure of every class the module might use. This causes two very significant problems. First of all, it encourages the programmer to put a great deal of code in the header files. The more code put in the header the greater the chance that something in the header will have to be changed when modifying a class. If a header file changes all programs which are dependent on this header file must be re-compiled. This is because the "new" operator must know the class size at compile time (even if all the elements are private!). What this ends up causing, in a real life application where there are many classes in a complex hierarchy, is that the entire application must be totally re-compiled every time there is the smallest modification (in order to play it safe). This one factor can multiply the time it takes to develop an application.

The second problem with not having a runtime class representation is a lack of flexibility and a lack of the ability to create truly general purpose routines. Since C++ does all its type checking at compile time it makes sense that at runtime it can only handle the types it was compiled for. Therefore, if you compile some general purpose routines into a library (or worse yet, buy a third party's library without source) and later wish to use its existing functionality, but for a class it was not compiled for, you would have to make some sort of code changes and re-compile the library (if you have source).

Since Dynace has a runtime class representation it doesn't have any of these problems. All code and structure definitions for a class reside in the .c file. There is no need to put anything in a header. If a class changes it has no compile-time effect on any other modules. As long as its original interface remains the same (although at can be added to) not a single line of code in any other module would have to be changed, no other modules would have to be re-compiled, and no libraries rebuilt.

Again, since Dynace has a runtime representation truly general purpose routines can be build without requiring the old code to be re-compiled. You can build a general purpose routine, put it in a library, and then two years later create a totally new class, and run

an instance of the new class against the old code in the library without ever having to re-compile the old code.

1.3.1.11 Efficiency

Dynace is not an interpretive language. Dynace programs are compiled with a standard C compiler. The majority of the code is just standard compiled C code with no performance penalty. The only place Dynace incurs a runtime cost is at the point of method dispatch. Since C++ also incurs a runtime cost when using virtual functions, there is not much of a difference between the performance of Dynace programs when compared to C++. In addition, Dynace gives the ability to locally cache a method pointer in tight loops so as to totally dispense with the runtime overhead.

1.3.1.12 Compatibility With C

C++ is somewhat compatible with C, however, Dynace is entirely compatible with C. Code which uses Dynace classes is just plain C code. Code which defines new Dynace classes consists of standard C with a few added constructs to define classes and methods. This then goes through a Dynace preprocessor which emits straight C.

The two main points about this is that Dynace is more compatible with C than C++, and it's easier to incrementally add object oriented facilities to a pre-existing C application with Dynace.

1.3.1.13 Garbage Collection

While C++ will automatically dispose of some types of objects (automatic variables), it can not automatically dispose of those objects allocated from the heap. In a complex application most objects would be allocated from the heap, requiring explicit disposal in C++. Dynace's garbage collector handles all object reclamation automatically.

1.3.1.14 Class Library

C++ environments come with an absolute bare minimum of fundamental classes. Of course there are many C++ class libraries available, however, given the fundamental architecture of C++, these libraries are typically incompatible and difficult to understand, use and extend.

Dynace comes with a complete set of fundamental classes including classes to represent all the basic C types, a variety of container classes (sets, dictionaries, linked lists, associations, etc.), multi-dimensional dynamic arrays, threads, pipes and semaphores.

1.3.1.15 Conclusion

Dynace adds powerful object oriented capabilities in a simple, idealistic, theoretically pure way. Dynace has taken the best attributes of CLOS, Smalltalk and Objective–C and implemented it in a way which is natural to a C programmer. Dynace has no special syntax and is easy to learn. A Dynace program looks just like any other C program.

Dynace offers effective solutions to a variety of problems associated with software development, including reducing development time by segregating and organizing various application components, providing a powerful class library, making pre-written components maximally reusable, reducing language and application learning curves for new programmers, and making an application easy to debug, maintain and enhance.

1.3.2 A comparison of Dynace and Smalltalk

Dynace is a very dynamic and flexible language just like Smalltalk. Dynace and Smalltalk share the following features:

- Both are weakly typed languages and therefore allow for the development of powerful routines which provide truly generic and re-usable software components.
- Both provide true dynamic binding on all messages.
- Both provide tight encapsulation of objects for easy program maintenance.
- Both provide a similar class hierarchy including the Object, Behavior, Class and Meta-Class classes.
- Both provide a complete metaclass system which allows all objects in the system to be treated uniformly.
- Both provide the ability to perform automatic reclamation of unneeded objects (garbage collection).
- Both provide the ability to create, synchronize and pass information between multiple independent processes (threads).

The following lists some of the differences between Dynace and Smalltalk:

- Dynace uses a standard C syntax which is easy for C programmers to learn.
- Dynace may be freely mixed with regular C code and may also link with pre-existing C libraries.
- Dynace uses a standard C compiler and generates stand alone native executable code. Smalltalk typically generates code for a virtual machine which must be included or bound with an application.
- Since Dynace generates native code it runs many times faster than Smalltalk and requires much, much less RAM (just a little more than a typical C program).
- Dynace is written in standard C and comes with full source code. It is therefore very portable and drastically reduces your dependence on a vendor.
- Dynace supports multiple inheritance.

1.4 Installation

The diskette(s) distributed with Dynace are standard DOS formatted diskette(s). The files on the diskette(s) have been compressed in order to reduce the quantity of diskettes.

See the file README, located on the first disk, for installation instructions.

1.5 Contents

Once the system has been installed there will exist a series of directories under the **dynace** directory. The system will contain the following directories:

\DYNACE

This is the root of the Dynace system.

\DYNACE\LIB

This is the location of all the Dynace libraries. You may wish to add this directory to the list of paths your linker searches.

\DYNACE\INCLUDE

This is the location of the include files necessary to compile Dynace applications. You may need to add this directory to the path your compiler uses to search include files.

\DYNACE\BIN

Executable files necessary for development with the Dynace system. This directory should be added to your normal search path for executable programs.

\DYNACE\EXAMPLES

Example programs used to learn & demonstrate the Dynace object oriented extension to C.

\DYNACE\WINEXAM

Example programs used to learn & demonstrate WDS.

\DYNACE\DOCS

Misc. documentation files.

\DYNACE\MANUAL

The Dynace and WDS manuals.

\DYNACE\KERNAL

Complete source to the Dynace kernel.

\DYNACE\CLASS

Source to all of the Dynace base classes.

\DYNACE\THREADS

Complete source to the multi-threader, pipes and semaphores.

\DYNACE\GENERICS

Files necessary to build the system generics files from scratch.

\DYNACE\DPP

Complete source to the dpp utility.

\DYNACE\WINDOWS

Complete source to the Dynace WDS library.

\DYNACE\UTILS

Complete source to the utility programs.

The only files that are absolutely necessary for a developer are those located in the \DYNACE\LIB, \DYNACE\INCLUDE and \DYNACE\BIN directories and \DYNACE\UTILS\STARTUP.MK.

1.6 Learning The System

This manual contains a description and rationale of object oriented concepts, a detailed description of the Dynace system and complete reference to all Dynace classes including examples. The example programs included with Dynace provide a step-by-step tutorial to getting started.

A user of the Dynace system will need to know the C language. However, no previous experience with object oriented concepts is necessary.

The best approach to learning Dynace would be to start by reading chapters 1 (Introduction) and 2 (Concepts). Then read sections 3.1 and 3.2 (Using Dynace Classes, including its sub-sections) while working through the example programs. When the example programs start creating their own classes follow with section 3.3 (Defining Dynace Classes, including its sub-sections). Ultimately it is best to read the entire manual.

If you are somewhat familiar with object oriented concepts and wish to dive right in and get a feel for the system you may go directly to the example programs after reading this chapter.

While working through the examples you may refer to the index (located in the back of the manual) to locate information on all Dynace methods, macros, variables, functions and data types.

It is highly recommended that a programmer already familiar with object oriented concepts still read the entire *Concepts* chapter because of its particular relevance to the approach taken in the Dynace system.

1.7 Quick Start & Tutorial

The Dynace system includes a series of examples which serve both as a Quick Start and a Tutorial. Each example is contained in its entirety in an independent directory. This is done in order to illustrate the exact files and steps necessary to create a single application.

The example programs are contained in sub-directories under the EXAMPLES directory and are named EXAMnn (where the nn is a two digit number). These numbers are significant in that they describe the correct order that the examples should be followed. Each example depends on knowledge built up in previous examples which is not repeated.

Each example contains a *readme* file which describes information relating to the purpose of the example and build instructions. These files should be read first. Each example also includes makefiles which are used by the included <code>dmake</code> make utility. The source to the examples is also included.

The example programs are not intended as a substitute for the manual. They are simply meant to augment the manual and accelerate the initial learning curve.

The following is a list of the enclosed examples:

	1
01	Illustrates the steps necessary to compile and link a program which incorporates and correctly initializes Dynace.
02	Illustrates the creation, use and disposal of a simple object.
03	Illustrates the creation, use and disposal of more simple objects.
04	Illustrates the creation, use and disposal of an instance of the LinkObject class.
05	Illustrates the use of the LinkObjectSequence class to enumerate through the elements of a linked list.
06	Illustrates the creation, use and disposal of an instance of the StringDictionary class.
07	Illustrates the process of enumerating through the elements of a set or dictionary using the SetSequence class.
08	Illustrates how Dynace handles errors.
09	Illustrates the value of and initialization procedure for the automatic garbage collector.
10	Illustrates the creation and initialization of a new class.
11	Illustrates the creation of a new method and generic function.
12	Illustrates additional points about methods and generics.

15 Illustrates initialization of instance variables with gNew.

Another illustration of initialization of instance variables with gNew.

Illustrates the independence one instance has from another.

Illustrates use of class variables / methods using gNew / gDispose.

17 Illustrates subclassing.

1314

20	Illustrates the use of threads.
21	Illustrates the use of the BTree classes.
30	Illustrates the process of getting information from the system.
31	Illustrates how generic functions are first class C objects.
32	Illustrates how to locally cache a method lookup and avoid the runtime cost.
33	Illustrates most of the methods associated with the String class.
34	Illustrates some of the numeric and date formatting abilities.

See the file $\DYNACE\EXAMPLES\LIST$ for the most up-to-date list of example programs.

1.8 Manual Organization

This manual serves as both a user manual and a complete reference manual to the Dynace system. It makes no assumptions about the users knowledge of object oriented programming. It does, however, assume a working knowledge of the C language.

Chapter 1 (Introduction) covers background material needed to orient a new user.

Chapter 2 (Concepts) covers object oriented concepts both in an abstract sense and as it relates to the Dynace system. It does this without introducing very much syntax or other mechanics.

A full understanding of these concepts is crucial to the effective use of the Dynace system. Even if you have experience with other object oriented languages it is important to understand these concepts as they are implemented within Dynace. Note, however, that it is not necessary to know everything before effective use of Dynace can be accomplished. Full understanding will come with use of the system.

Chapter 3 (Mechanics) introduces the exact syntax and procedures necessary to use the Dynace system. It does much of this with examples. Although this chapter does not make explicit reference to the Dynace example programs, they should be reviewed while reading this chapter.

Chapter 4 (Kernel Reference) provides a detailed reference to all classes, methods, macros, functions and data types associated with the Dynace kernel.

Chapter 5 (Class Reference) provides a detailed reference to all classes and methods associated with the class library included with the Dynace system.

The index (located in the back) provides a complete alphabetical listing of all classes, methods, macros, functions and data types described in chapters 4 and 5.

1.9 Contact Information

Internet blake@mcbride.name

Discussion There is a Dynace discussion group at

http://groups.yahoo.com/group/Dynace/

1.10 Use, Copyrights & Trademarks

Copyright © 1996 Blake McBride All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- 1. Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.
- 2. Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

1.11 Credits

The Dynace Object Oriented Extension to C, Windows Development System and their associated documentation were written by Blake McBride (blake@mcbride.name).

Credit and great appreciation is given to several sources for the ideas and inspiration behind many of Dynace's facilities as follows.

John Wainwright for the development and sharing of ideas concerning early releases of his Objects In C (OIC) system. He is an extremely talented individual with many unique and innovative approaches to software development issues. I am proud to call him my friend.

Gregor Kiczales, Jim des Rivières, and Daniel G. Bobrow for their book "The Art of the Metaobject Protocol" and their CLOS system.

Adele Goldberg and David Robson for their books on Smalltalk-80 and the Xerox Palo Alto Research Center for providing access to much powerful and innovative technology.

And finally, Dr. Brad Cox for pioneering object oriented extensions to C with his Objective–C system.

2 Concepts

Over time, the methods used in the development of computer software has evolved from a Goto model, to a Structured Programming model, and finally the Object Oriented model. In the beginning, the goto model was able to accommodate all the needs of the programmers. However, as the size of programs became larger and more complex, the goto code began to look like spaghetti. No one, except perhaps the original author, was able to understand, and therefore maintain, a complex program which was jumping all over the place. The solution to this problem was the Structured Programming model.

The Structured Programming model got rid of goto statements and replaced them with the more structured for and while statements. With this model, the programmer knows the beginning and ending location of the loop or conditional, as well as what the specific conditions are for executing the contained code. No more spaghetti.

Structured Programming also stressed the use of subroutines. This allowed blocks of code to be packaged in a form which could be easier understood as a small, well defined, unit. It also enabled, to some degree, the ability to create reusable code. It should be noted that while packaging blocks of code as subroutines greatly increased the programmers ability to manage large programs, it also comes at a cost. Calling blocks of code as subroutines is substantially more expensive, in terms of computer cycles, than a goto statement. As time has progressed, however, it has generally been accepted that the benefits of subroutines far exceed the costs.

The Structured Programming model worked well for many years. However, as computer programs became still larger, the programmers ability to manage larger, more complex projects became increasingly difficult. The ability to use common subroutines across varying applications was very limited. It became very difficult to manage the relationship between all the varying data structures and various subroutines.

Three things were needed to solve the problems of the Structured Programming model. First, there needed to be a way of isolating or packaging related groups of code and data, so that if a modification had to be made, or a bug fixed, only a specific group of code and data had to be understood and modified. This would allow a programmer to change a system, or add new functionality, without first having to understand all the intricacies of the entire system.

Second, any changes made to the related group of code and data should have minimal effect on any other code or data. This way, if a programmer changes a module, he shouldn't then have to search every place it's used to see what additional changes had to be made in order to accommodate the module change.

The third problem is that of maximizing reusability. For years programmers have been writing the same linked list routines, the same sort routines, and the same hash table routines over and over. The ability to create general purpose routines, which could be used in many places, over and over, is of immense value. After the creation of a good general purpose library, applications development time would be reduced considerably, and code reliability increased considerably. In addition, any enhancements made to the general purpose library would have an automatic benefit to all applications which use the library.

All three of the above issues are addressed in the Object Oriented model. The first two are addressed by the *encapsulation*, *data abstraction*, and *loose coupling* attributes of the Object Oriented model. The third issue is addressed by the *inheritance* and *dynamic binding* aspects of the Object Oriented model. All these issues, as well as others, will be addressed by the remainder of this manual.

2.1 Object Oriented

The Object Oriented model of programming is embodied by three fundamental concepts, a bit of new terminology, and a few new programming mechanisms used to implement the new concepts. The three fundamental concepts are *encapsulation*, *polymorphism*, *and inheritance*. These concepts will be introduced first, followed by the mechanisms. The terminology will be introduced as it is encountered.

2.1.1 Encapsulation

Encapsulation allows the programmer to tightly bind a data structure with the routines which access it, into an item called an *object*. Encapsulation reduces the ways in which outside data or procedures may effect a given object. Outside elements may only effect a given object by a limited number of well defined methods. Using a limited number of ways to effect an object causes *loose coupling*. A well defined method of effecting an object is a *protocol*.

A limited example of this idea can be achieved, for example, by creating a unique structure declaration inside a particular C source file, or module, as opposed to inside an include file. By doing this, only the functions in the same source file as the structure declaration may access elements of the structure, since those are the only routines which have any knowledge of its structure. Anything outside the defining module must call a non-static function, located within the module, in order to effect the data structure. These non-static functions would, in effect, comprise the modules protocol. The module would have loose coupling because the only way outside routines may effect the internal data structure, or state of the object, is, again, through the non-static functions. External routines have no access to the static, or local, routines, and have no direct access to the data structure itself.

Further, a very important form of data abstraction is achieved through encapsulation. Data abstraction refers to the ability to change the structure of data without having to change any external routines which, indirectly, use the data structure. As in the previous example, the data structure, as well as the entire implementation of the module may be changed entirely, and so long as the pre-existing protocol and module functionality remains intact, all other modules which use this module will continue to work without any modifications. Major implementation details may change and be made more efficient, and major additions to the module's functionality may be added, without any effect to external, pre-existing, code.

As opposed to the above example, the form of encapsulation implemented in most of the more advanced object oriented models, as well as Dynace, is much tighter. External routines not only have no access to the elements of the data structure, but also have no direct access to any of the routines which may effect the data structure! The data structure and associated routines are tightly packaged into a unique object. The only way to effect the object is to request the object itself to make any modifications to itself, or perform any operation. The meaning and methods to achieve this will become increasingly clear as we progress.

2.1.2 Polymorphism And Overloading

In a normal C program, you may only have one function with any particular name. For example, if you had a non-static function fun1() in one module, you couldn't have another

non-static function fun1() in another module. The two modules wouldn't link. If the program did link, and a third module called fun1(), the system wouldn't know which one you wanted to execute.

Polymorphism or overloading refers to the ability of the system to determine, based on context, which particular routine to execute. The context normally refers to the arguments to the routine. So, for example, in our previous example, you would be able to link two modules, each with non-local fun1()s. If a third module called fun1() the system would know which fun1() to execute based on the types of the arguments passed to fun1(). This ability to determine which specific routine to execute, among several possible, is called dynamic binding.

At first, it may seem unclear what value polymorphism may have. The following example will show that polymorphism is an extremely valuable tool, when trying to create general purpose, reusable, software components.

Lets say you had a *box* object. That is, a data structure representing a box (height and width), and a group of routines which can create, modify, draw, and destroy a particular box data structure. Now we want to create a routine to draw an arbitrary number of a particular box. We would probably write the routine as follows:

If you later wanted to modify draw_n() to work with circles, as well as boxes, you would normally have to modify draw_n() as follows:

The first problem with the draw_n2() solution is that draw_n() had to be changed to handle the additional type. The second problem is that the syntax has also been changed. This means that everywhere draw_n() is called the syntax would have to be adjusted. The third problem, is that now the programmer has to keep track of which type b really is. All this work is necessary just to add a little additional functionality. You can imagine what would be involved in making these types of changes to real, complex, applications.

The facility of polymorphism alleviates the need for *any* of these changes. As an example, in Dynace, the code could have originally been written as follows:

```
void draw_n3(object b, int n)
{
      while (n-- > 0)
      draw(b);
}
```

If you then created a circle object, with all the appropriate supporting functions, and passed it to draw_n3() it would work fine! No code changes anywhere! You wouldn't even have to recompile draw_n3()! You could later pass draw_n3() a triangle or a rectangle and again, no code changes, and no re-compilation of draw_n3().

2.1.2.1 Early vs. Late Binding

In the previous example of draw_n3() one should understand that there is a draw() function defined for the square, one for the circle, one for the triangle, and so on. What's going on is that the system is automatically determining which draw() to call based on the type of b, which is kept automatically.

Some object oriented implementations have what's called *early binding*. Early binding is when the relationship between the function call, and what's actually called is determined when the program is being compiled. The advantage of early binding is speed. Since the determination is being performed at compile time, there is no runtime cost. It is just as fast as a normal function call.

There are, however, some serious disadvantages of early binding. First of all, in order for the compiler to make the determination it must know the type of the argument at compile time. This means that the procedure could only work for *one* type of object. This is entirely inadequate for the above example. Using early binding, one would define a function as in draw_n(). This would allow multiple definitions for draw(), however, it would only work for a box. Therefore, early binding provides only a partial solution to the problems polymorphism can solve.

Late binding refers to a system which determines which function to call at runtime. Late binding requires that the system knows, at runtime, the type of any object. This information is typically kept automatically by the system, as it is in Dynace. Late binding has the advantage that it gives all the benefits of polymorphism. Therefore, one could define a very general purpose <code>draw_n3()</code> type of function within a system that supports late binding. The only disadvantage normally associated with late binding is speed. The system must determine which <code>draw()</code> function, for example, to execute at runtime.

Dynace normally uses late binding, and has a caching facility which minimizes the runtime overhead associated with late binding. Dynace also contains a method for reducing the runtime overhead to virtually zero. This method may be used in tight loops. Dynace can also use early binding, however, this is discouraged.

2.1.3 Inheritance

Inheritance allows you to create objects which are like other objects, or group of objects, but has some differences. Inheritance is an extremely powerful tool. It enables a programmer to

create a new module by using pre-existing modules. The only parts the programmer has to write are the parts which make the new module unique. In Dynace, all this can be achieved without any access to implementation details or source code to the pre-existing modules.

Inheritance operates in a hierarchical form. Thus, if object B inherits from object A, and a new object C is created which inherits from object B, you will have the following graphical relationship:



This diagram shows that object C has all the data and functionality locally defined as part of object C, as well as all the data and functionality of object C as well as all the data and functionality locally defined as part of object C as well as all the data and functionality of object C and C but not object C object C has only the immediate data and functionality which are locally defined.

This idea may be extended in a multiple inheritance form pictured below:



In this example object A has only its locally defined data and functionality. Object B, also, has only its locally defined data and functionality. Object C, however, contains its locally defined data and functionality, as well as the data and functionality of both object A and B.

This idea of single and multiple inheritance may be extended arbitrarily in both depth and width, whatever makes sense.

2.2 Dynace

Dynace is an object oriented extension to the C language. It implements all of the features discussed in this manual. Dynace is written in the C language, and designed to be portable, efficient, powerful, and simple to use. Dynace was designed after an in depth study of Smalltalk–80, the Common Lisp Object System (CLOS), Objective–C, C++, as well as object oriented principles in general. Dynace was designed with the following goals:

- Implement as much power and flexibility, available in languages such as CLOS and Smalltalk–80, as possible.
- Create a language which was as simple to use as possible, like Objective–C.
- Create a language which stuck as close as possible to the standard C syntax.
- Create a language which was as efficient as possible, such as C++ and Objective-C.

Dynace succeeds in the satisfaction of these specific goals better than any of the other languages above.

The remainder of this manual will deal with more specifics aspects of Dynace, although the vast majority of these concepts are very closely related to most of the above languages.

2.2.1 Object

Dynace adds to the C language only one new data type, the object. An object is a package consisting of data and the procedures necessary to create, destroy, modify, and otherwise effect the data. An object always knows what type it is. Dynace operates on objects. An object can be thought of as a fundamental data type. In fact, object, much like int or long, is a fundamental type which may be used in declarations. All other elements of Dynace, such as classes, metaclasses, instances, methods, and generic functions, are regular objects, just like any other object you may create in an application. In this respect, all objects are treated exactly the same throughout Dynace. The exact same code which processes the pre-defined Dynace objects, which allow Dynace to operate, process the user added objects.

Variables containing objects may be declared as follows:

In this example three variables, a, b and c, which may refer to objects, have been defined.

2.2.2 Classes & Instances

In Dynace, each and every object refers to an object, called a class, which defines that object. One class object may define any number of objects. Each object which is defined by a particular class object has the same data structure and performs the same functions as all the other objects which are directly defined by that class object. The only thing which differentiates one object from another, when they are both defined by the same class object, is the values contained within their similar data structures.

The objects which are defined by a particular class object are called *instance* objects of that class object. Class objects have names. For simplicity sake, we will call a class object with a name X, X class. An instance object of X class is called an instance of class X. In general terms, we can speak directly about classes and instances.

Now that we have some terminology under our belt, I can restate exactly what classes and instances are, and what their relationship to each other is. One very important thing to keep in mind, and the main reason all these terminology gyrations were necessary, is that classes and instances are both objects. There is nothing more special about one than the other. There is no code in Dynace which treats classes any different from instances.

A class keeps track of the structure of the data located in its instances. A class also keeps track of the functions the instances are able to perform. Each instance has only a single class which defines it, and it always knows which class it is. There may be an arbitrary number of instances of a class, however.

2.2.2.1 Superclasses

Each class may have zero or more superclasses. Classes normally have at least one superclass, though. The data contained in an instance will be the sum of the data defined directly in the instance's class, and the data defined in all the superclasses of the instance's class. In addition, the instance will also contain the data defined in it's superclasses. This continues till there are no more superclasses.

The instance's functionality follows the same path as it's data.

If class A is a superclass of class B then, class B is called a subclass of class A.

2.2.2.2 Instance Variables

The data contained within a particular instance are called its *instance variables*. The values contained within an instance's instance variables are unique to that individual instance. Of course every instance of one class will always have the same instance variable structure, though. You can think of instance variables as a C structure definition. Each instance of a particular class contains the same structure. It just contains different data within that structure.

When dealing with an instance, only the procedures which are part of the instance's class are able to access the instance variables. This ensures encapsulation and data abstraction.

2.2.2.3 Class Variables

Each class may also contain data. This data, which is located in the class, are called *class variables*. The data in class variables is always unique to a particular class. Class variables often serve as data which is common among all the instances of the class. With class variables you can keep track of how many instances of the class there are, or sums of their instance variables. You can even keep a linked list of a class's instances if you like.

Like instances variables, class variables may only be accessed by specific procedures which are bound to the class.

2.2.3 Metaclasses

As was discussed before, all things in Dynace are *objects*, and are treated the same. If this is true, you may be wondering why we are discussing classes and instances like they are two different things. The fact is, they are not! In fact, it so happens, that like instances, classes are also instances, instances of another class. The classes whose instances are themselves

classes, are called *metaclasses*. And as you might imagine, metaclasses are also instances of other classes. This is a circular process which goes on without beginning or end.

In this sense Dynace is quite interesting. Every part of Dynace, and all of its functionality, is defined by some other class. Fortunately, though, Dynace hides much of its complexity. You will rarely, if ever, have to concern yourself with any metaclasses or any aspects of its recursive design and operation. There is one important thing to remember, though, every class is an instance of exactly one class (the metaclass) and has zero or more superclasses.

2.2.4 Methods

As was discussed earlier, the only procedures which may access instance variables are the procedures associated with the class of the instance. These procedures are called *methods*. Methods are used to effect all aspects of an instance's variables. In fact, methods are the only thing which can create or destroy instances.

There is one interesting thing about methods, though. Like instance variables, there is not, normally, a way to evoke a method. Methods, like instance variables, are tightly bound to the class, and there is no easy, external access to the method. Thus, methods, like instance variables, are encapsulated and abstracted.

After reading about instance variables and methods being so tightly bound and inaccessible, external to the object, one may begin to wonder how one could ever effect an object. Be patient. The next few sections will wrap up all the ideas.

These features are very important. They are among the key elements which allow the object oriented model to be such a powerful tool.

2.2.4.1 Instance Methods

Instance methods are methods which typically operate on instance variables. Instance methods are conceptually located in the class of an instance.

2.2.4.2 Class Methods

Class methods are methods which typically operate on class variables. Class methods are conceptually located in the class of the class, or the metaclass.

2.2.5 Generic Functions

Given how tightly bound and inaccessible instance (or class) variables and methods are bound to an object, one might wonder just how anything external to the object can cause any change in an object. The answer to this is *generic functions*.

Generic functions act as special C functions which take one or more arguments. What a generic function does is check the class of the first argument to the generic function, for a method which has been associated to this generic function. If one is found, it is evoked. If one is not found, the generic will search all the superclasses of the class of the first argument. This superclass search will continue until a method is found, or there are no more superclasses to check. If no method is found an error is signaled.

Although this search process sounds quite involved and time consuming, it really is not. Dynace employs a caching scheme, so there is almost never an actual search.

As you can see, this generic function mechanism gives Dynace quite a bit of its power and flexibility. Through generic functions, most of the dynamic binding and method inheritance facilities are implemented.

Dynamic binding is achieved, for example, through the fact that class A could have a method called M1, as can class B. The generic function will evoke the correct method, based on the class of its first argument. If the first argument to the generic is an instance of class A then class A's M1 method will be evoked. Likewise, if the first argument to the generic is an instance of class B then class B's M1 method will be evoked. The two methods could perform entirely different functions.

The method inheritance facility of Dynace are realized by the fact that generic functions search the superclasses until an appropriate method is found. It will keep searching up the tree until a class which implements the necessary operation is found.

All the arguments passed to a generic function are passed directly to the appropriate method, just as if the method was called directly. Therefore, since one implementation of an M1 method may take a different number of arguments (or different types) as another M1 method, generic functions take different arguments (or different types) depending on the method which will eventually be evoked. In addition, the return value of a generic is whatever the method returns.

The process of evoking a generic function may also be referred to as sending a *message* to the object which is the first argument to the generic function.

2.2.5.1 Method Lookup

The order with which generic functions search for an appropriate method is important to understand. The first place searched is always the class of the object in the first argument to the generic function. If the method is not found, the first superclass (the one listed first when the class was created) is searched and then its superclasses. After checking the entire branch the method is still not found then the next superclass to the first class will be searched. This process will continue until a method is found or there are no more superclasses. If no method is found, an error is signaled. The search method, therefore, is a depth-first search. For example the following class structure:



would be searched in the following order E--C--A--D--B. Note that the order of C and D is determined by the order they are listed when class E is created.

One important point. If the first argument to the generic function is an instance, the class of the instance will be searched first. And since instance methods are kept in classes, an *instance* method will be evoked. However, if the first argument to the generic function is a class, the class of the class, or the *metaclass*, will be searched first. And since class methods are kept in metaclasses, a *class* method will be evoked.

So to summarize, if the first argument to a generic function is an instance, then an instance method will be evoked. Likewise, if the first argument to a generic function is a class, then a class method will be found.

2.2.6 Memory Management and Garbage Collection

All objects in Dynace are dynamic entities which are allocated from the C heap. When a new object is created, it is allocated from the heap, but when an object is no longer needed, it must be returned to the heap, lest we use up all the memory. This can be done in Dynace explicitly via one of the disposal generics. However, as an application gets larger and more complex, it becomes more and more difficult to know exactly when an object is no longer needed. Also, there is often a larger than desired level of complexity added to an application when trying to keep track of when an object should be disposed of, and being sure it is.

Garbage collection is a system used to free the programmer of most all concern of when an object should be freed, and making sure it is done. The garbage collector works by marking all the objects which your program is using, and then going through memory and freeing any object which is not marked. This process happens automatically, and without any programmer intervention. The algorithms used in Dynace assure smooth, reliable, and efficient operation of an application without ever having to worry about freeing any objects.

2.2.7 Threads

In a normal C program when one function calls another the first function waits until the second function completes before it may continue. The program follows a single line, or thread, of execution. In a multi-threading language a function may call a second function, and while the second function executes the first function is able to continue running. Thus two threads would be running. Either thread could even start more threads.

Threads share the same global variables and opened files just like the functions of a normal single threading system. Each thread, however, has its own stack space for local variables and function calls.

The advantage of having multiple threads is that it adds the ability to create applications which make more efficient use of user and computer CPU time. While a user is updating information in an application, the same application program could be printing a report. Any time an application has to perform an operation which the user would normally have to wait for, such as report printing or other processing of information, it could continue in a thread while the user is able to perform other data entry/query operations in another thread.

Dynace supports multiple threads in a semi-preemptive, round robin, priority based system. Dynace uses the system timer to assure that each thread gets equal access to CPU time. Semi-preemptive operation is achieved by the fact that Dynace performs automatic thread switching whenever a generic function is called (if the thread's time is up). Each

thread has a priority associated with it. Higher priority threads get first access to CPU time, while threads of equal priority share CPU time equally.

Dynace supports threads being put on hold, released, priority changed, waiting for other threads, getting thread return values, and a blocking getkey function. Threads on hold or otherwise not running require no CPU time.

In addition to Dynace's thread facility, Dynace also supports true native threads provided by the underlying system.

2.2.8 Pipes

Once there are multiple threads running there arises a need to coordinate and communicate among the multiple threads. *Pipes* are a streams based facility which allows one thread to pass information to another using a puts/gets type of interface. *Named pipes* allows one thread to create a pipe and give it a name. Later, if another thread wants to use the pipe all it needs to know is the name. It can get access to the pipe object via the name.

Dynace supports named and anonymous pipes with blocking and non-blocking io.

2.2.9 Semaphores

Thread coordination is achieved with *semaphores*. Semaphores allow the programmer to control the number of threads which may have simultaneous access to arbitrary system resources or blocks of code.

Semaphores may be thought of as a global variable which is initialized to zero. When one thread wants access to a resource it first increments the global variable. Later, if a different thread wants access to the same resource it first checks the value of the global variable. If it is greater than zero it means that another thread is utilizing the resource and that the second thread should wait till the first thread is done. When the first thread is done with the resource it decrements the global variable. This allows the second thread to start up and use the resource.

Real semaphores, as opposed to global variables, automate the creation and destruction of semaphores, the maintenance of the semaphore count, and the holding and automatic release of threads.

Dynace supports named and anonymous counting semaphores. Dynace semaphores are implemented in such a fashion so that threads which are waiting for a semaphore require no CPU time!

2.2.10 Dynace Kernel & Class Library

Dynace consists of two separable parts. One part is called the *kernel*, and the other is the *class library*. The kernel contains all the raw functionality of Dynace. It contains all the features which allow the creation and functionality of classes, instances, methods, generics, and garbage collection.

The class library provides a set of general purpose classes which are built on top of the Dynace kernel. These classes provide basic facilities to create object representations of all the basic C language data types. It also provides other general use classes to handle object collection and ordering.

The Dynace kernel is entirely functional without the class library.

3 Mechanics

This chapter describes the actual steps necessary to use build and use Dynace. First the steps necessary to configure, compile and link Dynace and Dynace applications is described, then the steps necessary to use existing classes is described. Once this is understood, the creation of new classes is described. Finally, Dynace customization and special techniques are discussed.

3.1 Setup, Configuration & Build Procedures

This section, in concert with the examples, describes the tools and actual steps necessary to build Dynace and create Dynace application programs. The best method of learning is to go through the example programs located under the \DYNACE\EXAMPLES directory in the order in which they appear.

3.1.1 Build Utilities

All the utilities used to build Dynace applications are contained within the Dynace package and the command line utilities (compiler, linker, etc.) which come with your compiler. Dynace utilizes special utilities and build procedures designed to intelligently minimize the need for re-compilation. These procedures are too complex for IDEs which come with the various compilers. For this reason the IDE environments which come with your compiler are not used. Instead, the included dmake make utility is used.

Having said that, however, you may still use the IDE for editing and debugging. You may also be able to find a way of integrating the supplied make files and procedures into your favorite IDE.

3.1.2 DMAKE Build Setup

This section lists environment variables which must be set for the DMAKE build.

The \DYANCE\BIN directory should be part of the search path used by your system for executable programs (the PATH environment variable).

The following environment variables should be set as follows (modify as appropriate):

```
set MAKESTARTUP=c:\dynace\utils\startup.mk
set TMPDIR=c:\tmp
set DOS4G=quiet
set DOS16M=:4M
```

The DOS4G and DOS16M environment variables are only necessary when running the 32 bit DOS version of dpp.exe which has been compiled with the WATCOM compiler. Win32 or other versions of dpp do not require these variables.

Although not required by the example programs, Microsoft users may find it convenient to add \DYNACE\INCLUDE and \DYNACE\LIB to your compiler's include and library search paths respectively.

Borland users will need to adjust the BORLAND_HOME path setting in the B16.DM and B32.DM makefiles located in all the example and Dynace source code directories.

3.1.3 Building Dynace From Scratch

The procedure used to build Dynace from scratch is fully described in \DYNACE\DOCS\BUILD.txt. See that file for build instructions.

New users will want to read all the files in the docs directory.

3.1.4 Examples Setup

All examples are buildable under all supported environments and build procedures including 16 and 32 bit environments. The only difference is the makefile used.

3.1.5 Example Files

This section documents the files which are contained in each example program.

README This file describes the object of the example. It should be read first.

MAIN.C This file is the complete source code to the example program. It is fully commented and describes all aspects of the current example which are unique.

In addition to the above, the following build/system specific make files are used.

M32.DM DMAKE makefile for Microsoft Visual C 32 bit

MAKEFILE.UNX

GNU MAKE makefile for Unix or Linux systems

MKFILE Makefile for the Plan 9 operating system

M16.DM DMAKE makefile for Microsoft Visual C 16 bit

B16.DM DMAKE makefile for Borland C 16 bit

B32.DM DMAKE makefile for Borland C 32 bit

W32.DM DMAKE makefile for WATCOM C 32 bit

S32.DM DMAKE makefile for Symantec C 32 bit

Once an application is built, the only file needed to run it is MAIN.EXE.

3.1.6 Building The Examples

In order to build with the DMAKE command line utility execute the following command.

```
dmake -f MAKEFILE.DM
```

where MAKEFILE.DM is one of the DMAKE makefiles listed above.

Alternatively, you can use the following command to create a debug version of the example:

dmake -f MAKEFILE.DM DEBUG=1

3.1.7 Debugging

When dpp strategy 1 is selected Dynace uses a small amount of assembler. This is not true for the default strategy of 2, however, when strategy 1 is used there are a couple of procedures which, when followed, will easy the debugging process.

First compile your application with debugging information. Then when you wish to debug the application, set a break point at the beginning of any methods you wish to debug. You may then step through your program as normal and when you enter a generic, the system will stop at the methods in which you placed the break points.

Once you are fully into the method, you may access the instances variables through the "iv" structure pointer and the class variables through the "cv" structure pointer.

3.1.8 Building Your Own Application

The best method of building your own application would be to start with one of the example programs and proceed from there. This way all the compiler, linker and other options will be preset. The best examples to start with would be one of the ones which define a new class. Their makefiles are designed to handle class files in a very convenient and automated way.

3.1.9 **DMAKE**

DMAKE is a very powerful, portable and enhanced make utility developed by Dennis Vadura. It is freely distributable and not owned by Algorithms Corporation or Blake McBride. Complete documentation for this utility is contained in \DYNACE\DOCS\DMAKE.MAN

3.2 Using Dynace Classes

Dynace usage can be divided into two categories: class user or class creation. All a class user has to do to use Dynace classes is include a single file in the source code and call a function to initialize the system. After these two easy steps the class user has full access to the entire set of existing classes. A class user need not learn any special syntax or procedures. Learning to use the existing classes is the same as learning to use any other library of routines.

A class creator will have to understand all aspects of being a class user first. In addition, a class creator will have to understand the steps necessary to define classes, methods and generics. These steps are well defined and simple to use.

This section describes the actual steps necessary to *use* a pre-existing class. The next section will discuss the steps necessary to create new classes.

3.2.1 External Naming Conventions

External naming conventions refers to those names that the programmer defines such as a new class name, an instance variable name or a method or generic name. By contrast, internal naming conventions refers to those names which are generated by the Dynace preprocessor (dpp). These internal names are often made up from modifications or concatenations of the external names.

In Dynace, generic function names, by convention only, always begin with a lower case "g" or "v", followed by an upper case letter, and then optionally followed by other letters (of any case), numbers, or underscores. This convention allows a user to immediately know which functions may be used polymorphically or overloaded.

Generics which begin with "g", by convention only, have compile time (as well as runtime) argument checking turned on and often, but not always, have a fixed number of arguments.

Generics which begin with "v", by convention only, have compile time argument checking turned off and are often, but not always, associated with generics which take a variable number of arguments. Use of generics with argument checking turned off allows them to be associated with methods with arbitrary argument signatures. It is up to the system and the programmer to assure that the correct arguments are passed. Dynace provides ample tools necessary to assure correct arguments at runtime. In fact, the runtime checking facilities are much more reliable and fool proof than compile time argument checking. The only disadvantage is that you don't know a problem exists until you run the system. If, however, an error is discovered it can be handled many different ways and never crashes the system.

Dynace uses the "g" type of generic as much as possible. However, some methods, such as indexing into a variable dimension array or printf like functionality, are implemented as "v" generics.

It's all right if several methods (associated with different classes) have the same name because methods are implemented as static C functions. So there is no name conflict.

Classes normally begin with a capital letter. Instance variables, by convention only, begin with "i" and are followed by an upper case letter. Likewise, class variables, by convention only, begin with "c" and are followed by an upper case letter.

In the index the notation will specify a generic (minus the normal leading "g" or "v"), two colons and its associated class. For example ChangeValue::Number specifies a generic called gChangeValue which is associated with the Number class.

The above naming scheme is used by the Dynace system, however, it is not enforced. You may use any naming scheme you wish.

3.2.2 Internal Naming Conventions

External naming conventions refers to those names that the programmer defines such as a new class name, an instance variable name or a method or generic name. By contrast, internal naming conventions refers to those names which are generated by the Dynace preprocessor (dpp). These internal names are often made up from modifications or concatenations of the external names.

The following table lists the internal name structure used by Dynace. The associated source external names for example purposes are the class String and the generic gNew.

String a macro which evaluates to the class object but also automatically initializes the class if it hasn't already been initialized

String_c the actual variable which contains the class object (NULL if the class hasn't been initialized yet

String_t a typedef defining a String class (always object), used for documentation purposes only

String_cv

pointer to the actual locally defined class variable structure

String_cv_t

a typedef which defines the locally defined class variable structure

String_iv_t

a typedef which defines the locally defined instance variable structure

String_initialize

the name of the class initialization function generated by dpp

gNew_t a typedef defining a pointer to a function with the return type and argument signature of the generic

gNew_g a Dynace object representing the generic

String_im_gNew

default instance method name for methods with argument checking turned on (imeth)

String_cm_gNew

default class method name for methods with argument checking turned on (cmeth)

String_ivm_gNew

default instance method name for methods with argument checking turned off (ivmeth)

String_cvm_gNew

default class method name for methods with argument checking turned off (cvmeth)

3.2.3 Class Hierarchy

The only class in Dynace which has no superclasses is called Object. All classes in Dynace eventually inherit from the class Object. The Object class defines those features that are common to all objects. The class Behavior inherits from Object and defines the functionality common to classes and metaclasses. The class Class inherits from Behavior, and describes the functionality particular to all classes. The class MetaClass also inherits from Behavior, and defines the operations particular to metaclasses. There is a class called Dynace which inherits from Object, and is used to effect various aspects of the Dynace kernel. There are also classes called Method and GenericFunction, which both inherit from Object, and perform the expected functions.

The above class hierarchy can be depicted as follows:

```
Object
Behavior
Class
MetaClass
Dynace
Method
GenericFunction
```

These classes comprise the entire Dynace kernel. Other facilities of Dynace, such as threads, pipes, dictionaries, are supplied as Dynace classes. Although an in depth understanding of each of the above classes is unnecessary, it is important to fully understand the relationship between the inheritance of the above classes, and the indentation of the diagram.

3.2.4 Example Code

The following example illustrates a complete program which uses Dynace. Each line is explained in the following sub-sections.

```
#include "generics.h"
main(int argc, char *argv[])
       /* declare some variables which will hold objects */
       object name, pi, age;
       /* initialize the Dynace kernel and class library */
       InitDynace(&argc);
       /* optional: start automatic garbage collector */
       gSetMemoryBufferArea(Dynace, 40000L);
       /* set name to an instance of the String class */
       name = gNewWithStr(String, "Tom Swift");
       /* set pi to an instance of the DoubleFloat class */
            = gNewWithDouble(DoubleFloat, 3.14159265358979);
       рi
       /* set age to an instance of the ShortInteger class */
       age = gNewWithInt(ShortInteger, 32);
       /* tell some objects to print themselves */
       gPrint(name, stdoutStream);
       gPrint(age, stdoutStream);
       /* change the age */
       gChangeShortValue(age, 33);
       /* manually dispose of the objects (not necessary if the
           garbage collector is enabled) */
       gDispose(name);
       gDispose(pi);
       gDispose(age);
}
```

3.2.5 Include File

Any source module which uses any Dynace objects must include generics.h. This may be accomplished with the following line:

```
#include "generics.h"
```

3.2.6 Declarations

All objects (classes, instances, methods...) in Dynace are *objects*. The declaration used in Dynace is **object**. Therefore, if you wanted to declare three objects in Dynace you could use the following:

This declaration may be used anywhere you can define any other type of variable in the C language.

3.2.7 Initializing Dynace

The first thing which must be done prior to using any classes in Dynace is to initialize the Dynace kernel and system classes.

This initialization *must* be called from the main() function. The initialization function *must* also be passed the address of the argc argument to the main() function. This information is required by the Dynace garbage collector.

Use of the following is required to initialize the Dynace system:

InitDynace(&argc);

3.2.8 Generic Functions

In Dynace, generic function names, by convention only, always begin with a lower case "g" or "v", followed by an upper case letter, and then optionally followed by other letters (of any case), numbers, or underscores. This convention allows a user to immediately know which functions may be used polymorphically or overloaded.

Generic functions are used like any other C language function. However, generic functions always have at least one argument. This first argument, is the object which will be performing the requested method. Any remaining arguments will be passed to the appropriate method.

When using variable argument generics (those beginning with "v") the number and types of arguments may be different from one call to a particular generic function call to another. This is because different methods, with different argument requirements, may be called.

3.2.9 Creating Objects

By convention, the generic function used to create new objects is called <code>gNew()</code> or <code>vNew()</code>. The first argument to either should be the class of the new object (or instance) to be created. Any, possible, remaining arguments (in the case of <code>vNew</code>) will be the ones required by a particular class.

If compile time argument checking is used then the gNew function will possibly be renamed to avoid argument conflicts.

The following are examples of some instances being created:

```
object name, pi, age;
name = gNewWithStr(String, "Tom Swift");
pi = gNewWithDouble(DoubleFloat, 3.14159265358979);
age = gNewWithInt(ShortInteger, 32);
```

There are a number of interesting things about this example. First of all, the syntax is normal C language syntax. Second, the three objects created, each of a different type, had the same declaration. Note also, the standard naming of the generic function gNewXXXX().

3.2.10 Using Objects

Once an object is created it may be used as arguments to generic functions. For example:

```
object myInt;
myInt = gNewWithInt(ShortInteger, 42);
gPrint(myInt, stdoutStream);
gChangeShortValue(myInt, 68);
gPrint(myInt, stdoutStream);
```

When the <code>gPrint()</code> generic function is called, as in the above example, Dynace checks the class of <code>myInt</code>, and finds that it is of type <code>ShortInteger</code>. It then finds a method which is associated with the <code>gPrint()</code> generic function / <code>ShortInteger</code> class combination, and evokes it. This association is defined by the person who wrote the <code>ShortInteger</code> class.

3.2.11 Disposing of Objects

All objects in Dynace are allocated from the heap. Therefore, when an object is no longer needed, it must be returned to the heap. If this is not done you would eventually run out of heap space. Dynace has two methods of accomplishing this task, disposal generics and the garbage collector.

3.2.11.1 Disposal Generics

One method Dynace uses to release unused objects is through an explicit call to a disposal generic. There are two common disposal generics. One is called gDispose and the other is gDeepDispose.

gDispose is typically used to dispose of a single object and any associated allocated space it may reference.

The gDeepDispose generic, in addition to performing the same functions as the gDispose generic, is typically used to dispose of whole group of related objects at the same time. This method will typically recursively call the gDeepDispose generic on all objects being referenced within the object being disposed.

Both gDispose and gDeepDispose always return NULL. This is done in order to allow the disposal generic to null out the variable which holds the object in the same expression which disposes of it.

The following is an example of the gDispose() generic:

```
object age;
age = gNewWithInt(ShortInteger, 32);
gPrint(age, stdoutStream);
age = gDispose(age);
```

3.2.11.2 Garbage Collection

The second, and preferred, method Dynace has for disposing of objects is through a garbage collector. The garbage collector is an integral part of Dynace which constantly monitors the applications memory use. Whenever certain conditions arise, such as low memory conditions, the garbage collector automatically, and transparently kicks in. The garbage collector marks all objects which are directly or indirectly accessible via the automatic variables in the program. It also marks any objects which are referenced by global or static variables which have been registered with Dynace. Dynace also automatically marks all classes, methods, and generic function objects. After this marking phase, the Dynace garbage collector goes through all objects and frees those that are not marked.

The simple explanation is that by using the Dynace garbage collector, you never have to worry about freeing any objects which are no longer needed. The garbage collection process requires no additional coding on the developers part. It runs entirely automatically and transparently to the application program.

A few things to remember, though, the Dynace garbage collector may be used with the gDispose generic function. The garbage collector is off by default, and must be turned on (as shown below). Only those objects which are referenced by automatic variables, and those globals and statics which have been registered with the garbage collector (via the gRegisterMemory generic), will be marked. Therefore, any objects which are only referenced by unregistered globals or statics will be disposed of by the garbage collector.

Note that under Win32, Dynace has special code and can automatically detect and mark unregistered globals or statics. Therefore manual registration of these memory locations is not needed under Win32.

The garbage collector may be turned on with the following line (after the Dynace system has been initialized):

```
gSetMemoryBufferArea(Dynace, 40000L);
```

Dynace offers an alternative garbage collection scheme which has important tradeoffs. See the sub-section on the Boehm Garbage Collector under the Dynace Customization & Special Techniques section.

3.2.12 Generics Files

In any given program, only a single source file should contain all the generic functions used throughout the entire application. This includes the generics used by the Dynace kernel, the class library, and any application specific generics. The file used to define all the generics is called <code>generics.c</code>. There is also a file called <code>generics.h</code> which provides for the external declarations for all the classes and generics. Both of these files are automatically generated by a program called <code>dpp</code>.

See the section documenting the dpp program for further details.

3.2.13 Compiling & Linking

This section describes the necessary tools and steps necessary to create an application which uses the Dynace system.

3.2.13.1 Files

In order to compile and link programs which use the Dynace kernel and class library you will need the following files:

dynl.h This file is included with the Dynace system and located in the include directory. generics.h

If your application creates its own classes, you will need a custom <code>generics.h</code> file located in your application directory. This file is automatically generated by the <code>dpp</code> program. Otherwise, the <code>generics.h</code> file included with Dynace may be used.

generics.c

This is a file generated by dpp from the application specific generics.h file. It should be created and kept in the applications source directory. It is only needed if your application creates its own classes.

- dpp.exe This program is used to generate the generics.c and generics.h files in the applications source directory. dpp.exe should be kept somewhere in your normal path for executable programs.
- *.lib The Dynace library files are located under the lib directory. These libraries are specific to each supported compiler and whether they are for 16 or 32 bit versions of the compiler. For 16 bit compilers, only the large memory model is supported.

3.2.13.2 Compiling & Linking

The best way to compile and link your application is to start with one of the makefiles included with the example programs included with Dynace. There are specific make files for each supported compiler.

3.2.14 Learning Dynace Classes

Once the basics of using Dynace objects, and the mechanics of creating a program are understood, a study of the Dynace library, including what facilities it has to offer, and how to use it, are strongly recommended. Nothing will get you up and running with the system faster. The true value of Dynace cannot be appreciated until a full understanding of the Dynace class library, and what facilities it has to offer, as well as the understanding of the simplicity and power offered by creating your own classes has been achieved.

3.3 Defining Dynace Classes

This section describes the syntax and procedure necessary to create Dynace classes. It is recommended that all the information in the previous sections be understood prior to continuing in this section. It is also recommended that some experience with the class library be accomplished.

Each new class in Dynace is defined in its own unique source file. Multiple classes should never be defined in a single source file. However, it is possible to define a large class by several source files. This process is illustrated in one of the example programs.

Dynace uses the static function ability of the C language to encapsulate the methods. This is why it is best to define a class in a single source file.

Classes are defined in class definition files which have a ".d" file extension instead of the normal ".c" file extension. These class definition files may contain normal C code as well as the additional syntax elements described in the next subsection.

When building the application, class definition files are processed by the Dynace preprocessor (dpp) which produces corresponding C source files (with a ".c" file extension) which may be compiled with your normal C compiler. At the same time dpp also performs argument checking by comparing arguments to methods and their associated generics. dpp also uses this information to produce the appropriate generic files.

The following sub-sections describe the exact syntax necessary to define your own Dynace classes.

3.3.1 Class Definition File Syntax

Class definition files may contain normal C code without restriction. In addition, the following syntax elements may be used to define a class, methods and generics.

Legend:

```
Items between [ ] are optional
... indicates any number (including 0) of the preceding
| indicates a choice
Identifiers in caps should be replaced by the appropriate name
Lines beginning with // are comments
Lower case identifiers and other symbols are typed as-is
```

```
// Public method definition
[public] METHOD-TYPE [RETURN-TYPE] GENERIC [,GENERIC]...
        [, < GENERIC >] ... [: METHOD-NAME] ( ARGUMENT-LIST )
        METHOD-BODY
}
METHOD-TYPE = imeth | cmeth | ivmeth | cvmeth
RETURN-TYPE defaults to object
Undeclared method names default to CLASS_Xm_GENERIC
ARGUMENT-LIST - types default to object,
                first arg (object self) defaults
// Private method definition
private METHOD-TYPE [RETURN-TYPE] METHOD-NAME
        ( ARGUMENT-LIST )
        METHOD-BODY
}
METHOD-TYPE = imeth | cmeth | ivmeth | cvmeth
RETURN-TYPE defaults to object
ARGUMENT-LIST - types default to object,
                first arg (object self) defaults
// Super syntax
GENERIC(super [ARG] [, ARGN]...)
// Comments
/* COMMENT */
```

```
// COMMENT-TO-END-OF-LINE
```

3.3.1.1 Class Definition

This syntax element allows for a central location for all elements associated with the new class. The new class's name, an optional list of superclasses, instance variables, class variables, and class initialization function are all defined by this structure.

All variables default to type object if not otherwise declared.

Since most elements of a class definition are optional, the minimum that is requires is as follows:

```
defclass MyClass;
```

This defines a class called MyClass which has no specific class or instance variables and has a single superclass (Object).

The next example defines a class which is a subclass of SomeClass.

```
defclass MyClass: SomeClass;
```

The next example defines a class which is a subclass of SomeClass and SomeOtherClass.

The next example defines a class which has a couple of specific instance variables associated with it. This class defaults to the single Object superclass.

```
defclass MyClass {
    int iAge;
    object iName;
};
```

The next example is the same as the previous except that since variables default to the object type, this type declaration may be omitted.

```
defclass MyClass {
    int iAge;
    iName;
};
```

The next example adds to the previous example by adding a class variable. Note that since there is no type explicitly declared it defaults to object.

```
defclass MyClass {
        int iAge;
        iName;
    class:
        cPeople;
};
```

The next example adds to the previous example with the addition of a specific superclass (as shown above).

```
defclass MyClass : SomeClass {
        int iAge;
        iName;
    class:
        cPeople;
};
```

The next example adds to the previous example with the addition of a class initialization function. This feature is rarely needed but allows a specific function to be executed by Dynace when the class is being initialized. This is typically used to initialize class variables.

```
defclass MyClass : SomeClass {
        int iAge;
        iName;
class:
        cPeople;
init: my_init_function;
};
```

The next example illustrates the fact that the various sections may be in any order, however, if the instance section is not first, it must be explicitly declared.

The default scope of class definitions is **private**. Therefore the previous example could just as well have been written as follows.

Use of the private keyword is strongly discouraged. It was only added to complement the public scoping which is also strongly discouraged but needed in certain circumstances.

The public defclass declaration is used to cause the Dynace preprocessor (dpp) to create additional files which contain the class and instance variable structures. This is the same as the <code>-iv</code> and <code>-cv</code> dpp options. See the dpp section for further explanation of this feature.

3.3.1.2 Public Method Definition

Public methods are only accessible through generic functions. The body of public methods is identical with normal C functions. The main difference between a C function definition and a public method is that a method of associating a method with generics and determining the method type is required.

The following table lists the available method types:

This indicates an instance method with compile time argument checking enabled. Use of this option requires that all methods associated with a specific generic function all have the exact same argument signature.

This indicates a class method with compile time argument checking enabled.

Use of this option requires that all methods associated with a specific generic function all have the exact same argument signature.

ivmeth This indicates an instance method with compile time argument checking turned off. Use of this feature allows methods with totally arbitrary argument signatures to be associated with the same generic function.

This indicates a class method with compile time argument checking turned off.

Use of this feature allows methods with totally arbitrary argument signatures to be associated with the same generic function.

The following example illustrates a minimum method declaration. Note that a generic name is specified instead of the method's name. This is done since all external access to a method is through its associated generic, the actual method name is rarely important. Dynace will default a method's name to be the associated generic name prefixed with the class name, a code indicating the method type and the generic name. Each part is separated with an underscore. So in the following example the actual method name will be MyClass_im_gMyGeneric. You can, however, explicitly name a generic. This will be shown in other examples.

```
public imeth object gMyGeneric(object self)
{
    return self;
}
```

Since all methods take object self as their first argument, Dynace defaults this information. Therefore, the above example may also be written as follows.

```
public imeth object gMyGeneric()
{
    return self;
}
```

If the method took an additional arguments, the first argument may, optionally, be skipped. For example:

```
public imeth object gSomeGeneric(object self, int age, char *name)
may also be written as:
```

```
public imeth object gSomeGeneric(int age, char *name)
```

In addition, all argument types default to object, therefore, any arguments which are of type object may exclude their type declaration. For example:

```
public imeth object gSomeGeneric(object self, int age, object name) may also be written as:
```

```
public imeth object gSomeGeneric(int age, name)
```

Also, since public and the return type of object are Dynace's defaults the first example may also be written as follows. Explicit use of the public declaration is provided in order to be consistent with the private declaration and not especially recommended.

```
imeth gMyGeneric()
{
          return self;
}
```

It is often convenient to associate one method with several generics. This can be done as follows.

```
imeth gMyGeneric, gGeneric2, gGeneric3 ()
{
    return self;
}
```

Explicit method naming is sometimes needed if it is to be directly evoked within the same source file. This can be done as follows.

```
imeth gMyGeneric : SomeMethod ()
{
    return self;
}
```

Explicit method naming can also be used with multiple generic association as follows.

```
imeth gMyGeneric, gAnotherGeneric : SomeMethod ()
{
     return self;
}
```

The following example is a duplicate of the previous example, except that it returns an char *.

```
imeth char * gMyGeneric, gAnotherGeneric : SomeMethod ()
{
    return "String";
}
```

The following example illustrates the syntax used to associate a single method with generics which have argument checking turned on (imeth's) and generics which have them

turned off (ivmeth's). This syntax is only recognized by the dpp program when its -X option is enabled, otherwise this special syntax is just ignored.

```
imeth gMyGeneric, <vAnotherGeneric> ()
{
         return "String";
}
```

To use this feature the method must be declared as an imeth or cmeth. You then surround the generic name which is to be treated as an ivmeth or cvmeth in angled brackets as shown. All the previously described syntactical elements may be used without restriction when this option is used. And again, generic names in angled brackets will be ignored by the system unless the -X dpp option is used.

3.3.1.3 Private Method Definition

Private methods are methods who are not associated with any generic and are therefore only available for use within the file they are declared it - similar to static functions. However, like public methods, private methods always take object self as their first argument.

Private methods are mainly used as a way of creating method like functionality in cases where they are only used internally and no dynamic binding is needed. They are more efficient.

The following declares a typical private method. Unlike public methods, private method declarations name the method and have no generics associated with them. Once declared, private methods may be used like regular functions.

```
private imeth object MyMethod(object self)
{
    return self;
}
```

Like public methods, private methods default their return type and argument list. Therefore, the above declaration may also be written as follows.

```
private imeth MyMethod()
{
     return self;
}
```

3.3.1.4 Super Messages

Super messages are a way of evoking methods associated with a superclass of an object, as opposed to the method which is directly associated with the class. Typically, this is used to allow a method to wrap functionality around functionality already provided by a superclass. It is often used in the creation of new instances.

Typically, if you wanted to evoke the functionality associated with an instance, you would use the following syntax.

```
gSomeGeneric(someInstance, someArg);
```

However, if you wanted to instead evoke the method associated with the superclass if your instance, you would use the following syntax.

```
gSomeGeneric(super someInstance, someArg);
```

As a more complete example, lets say you have a class containing an instance variable which you wish to be initialized to some value whenever a new instance is created. The following illustrates the point.

In this example the instance variable is being initialized to a null string object for every new instance created. Remember that since this is a class method, self will be a class object. Since only one of the kernel classes knows how to actually create a new (blank) object, the gNew method must evoke the one above it in order to finally get to the one which can actually create the bare new object. Once the new object is obtained, it may be initialized and returned.

Note that you couldn't have just called gNew(self) because that would call the same method you're in to be called recursively and indefinitely.

In addition, since sending the super message to self is the most common use of super the self is actually optional. Therefore, line 1 above could be written as follows:

```
object obj = gNew(super); // line 1
```

3.3.1.5 Comments

In addition to normal C comments the // is used to signal comments to the end of the line.

3.3.2 Example Code

The following example illustrates a complete program which defines a new Dynace class. Each line is explained in the following sub-sections.

```
defclass MyNewClass {
                *iName;
        char
        int
                iAge;
        iSomeOtherObject;
 class:
                cTotalInstances;
        long
        int
                cAverageAge;
};
private imeth init(char *name, int age)
{
        iName = (char *) malloc(strlen(name)+1);
        strcpy(iName, name);
        iAge = age;
        return self;
}
cmeth gNewInstance(char *name, int age)
{
        return init(gNew(super), name, age);
}
imeth
        object
                  gDispose()
{
        free(iName);
        return gDispose(super);
}
imeth
        object
                 gDeepDispose()
{
        free(iName);
        if (iSomeOtherObject)
                gDeepDispose(iSomeOtherObject);
        return gDispose(super);
}
        gSetObject(obj)
imeth
{
        iSomeOtherObject = obj;
        return self;
}
        gPrint(FILE *fp)
imeth
        fprintf(fp, "%s is %d years old\n", iName, iAge);
        return self;
}
```

3.3.3 Class Definition

The first step in defining a new class would be to create a .d file with a defclass specification. This is discussed in detail in the section which describes the defclasss syntax.

Note the naming convention used. Class names begin with an upper case letter and are followed with upper and lower case letters. Instance variables start with an "i" and are followed with an upper case letter. Likewise, class variables start with a "c" and are followed with an upper case letter.

This naming convention is just that – a convention. Dynace does not enforce or necessarily encourage this convention. However, since Dynace allows direct access to instance and class variables from within methods, some naming convention is desirable, otherwise it would be difficult to distinguish instance variables from locally declared variables.

3.3.4 Defining Methods

Once the defclass specification is given, the methods may be declared. The syntax for this, as well as several examples are discussed in the section which described method syntax.

It is important to understand that **self** will always refer to the instance object which called the generic, if it is an instance method. And **self** will always refer to the class object if this is a class method.

The naming convention used is that generics with fixed number and type of arguments in which compile time argument checking is enabled start with "g" and are followed be an upper case letter.

Generics without compile time argument checking enabled may be passed arbitrary arguments. These generics start with "v" and are followed be an upper case letter.

This naming convention is not enforced or necessarily encourage by Dynace. However, it is intended to help a programmer distinguish normal C functions from various points where Dynamic binding is occurring.

3.3.4.1 Accessing Instance And Class Variables

An object's instance and class variables may only be accessed from within a routine located in the source file which defines the class. There are several ways available to access these variables. This subsection will discuss all the ways from the most frequently used methods to the least.

The most frequent use of instance variables is from within public or private instance (not class) methods. These methods may directly access the variables as they would access any local variable, by just using them by name.

Class variables are also directly accessible by name in *all* methods or regular C functions within the module.

There are four places where instance variable access gets a little tricky. Dynace, however, provides mechanisms to conveniently access instance variables in all circumstances.

The first difficulty is when attempting to access a newly created instance's instance variables from within a class method which had just created the new object. This is a

common problem within New generics. There are two solutions to this problem. One solution is clean but a little less efficient than a more dirty solution. Understanding of the dirty solution, however, is helpful when debugging code (regardless of which solution is used).

The clean solution is depicted in the following example.

```
private imeth init(char *name, int age)
{
     iName = (char *) malloc(strlen(name)+1);
     strcpy(iName, name);
     iAge = age;
     return self;
}
cmeth gNewInstance(char *name, int age)
{
     return init(gNew(super), name, age);
}
```

In the above example gNewInstance first calls gNew to create a new instance. It then passes the new instance along with the initialization arguments to an instance method (imeth) because instance methods can access the new instance's instance variables. Since the init method returns the object passed, gNewInstance can simply return it.

One interesting point about the above example is that private methods, unlike public ones, must either be defined or declared prior to use.

With the dirty solution it is important to understand that Dynace provides all instance variable access through a structure pointed to by a locally declared pointer named iv (which stands for "instance variables"). In the case of instance methods, this procedure is automatically handled by the Dynace preprocessor. However, it must be done explicitly, when needed, in class methods.

Dynace also declares a typedef which is a structure mirroring the instance variable definition contained with the defclass statement. Finally, Dynace provides macros for obtaining a pointer to the instance variables associated with a given object.

The following example depicts the solution to the above mentioned problem.

```
gNewInstance(char *name, int age)
cmeth
{
        object obj;
                                            line 1 */
                                            line 2 */
        ivType *iv;
        obj = gNew(super);
                                            line 3
        iv = ivPtr(obj);
                                            line 4 */
        iName = (char *) malloc(strlen(name)+1);
        strcpy(iName, name);
        iAge = age;
       return obj;
}
```

This example demonstrates all the above procedures. Line 1 declares a variable which will hold the new instance object to be created. Line 2 declares the iv variable which Dynace needs in order to access the object's instance variables.

Line 3 calls the super gNew in order to create a new and uninitialized instance object and assign it to obj. Line 4 gives Dynace access to the instance variables associated with the obj variable.

After line 4, the code may directly access the instance variables as would be done in an instance method.

The second problem associated with accessing instance variables has to do with normal C functions contained within the same module. Since C functions don't necessarily take the self argument, it is impossible for Dynace to know how to access the instance variables. However, a simple method of achieving this is provided.

As stated above, Dynace uses the iv variable in order to access instance variables, therefore, all that has to be done is to pass the iv pointer to the C function. For example:

```
static void MyFunc(ivType *iv, int age)  /* Line 1 */
{
    iAge = age;  /* Line 2 */
}
imeth gChange(int age, char *name)
{
    MyFunc(iv, age);  /* Line 3 */
    iName = name;
    return self;
}
```

In the above example, a normal C function is given access to the instance variables by passing it the noted iv pointer. Since Dynace automatically gives instance methods access to an iv pointer, it may be simply passed to the function (as shown in line 3).

Line 1 shows how the iv variable would be declared. It doesn't necessarily have to be the first argument. Line 2 shows how the instance variables are now directly accessible within the function.

The third problem associated with accessing instance variables has to do with accessing the instance variables of more than one object within the same module at the same time. The problem can be resolved (in a relatively inefficient, but clean manner) with instance variable accessing methods. However, Dynace provide a very efficient way to accommodate this situation.

Since Dynace gives a method of accessing the instance variable structure pointer associated with an object (ivPtr macro), these pointers may then be used as normal C structures. For example:

```
gCopy()
imeth
{
       object obj2;
                                      /* Line 1 */
       ivType iv2;
                                      /* Line 2 */
       obj2 = gNew(super MyClass);
                                     /* Line 3
       iv2 = ivPtr(obj2);
                                     /* Line 4
       iv2->iAge = iAge;
                                     /* Line 5 */
                                      /* Line 6
       return obj2;
}
```

The above example defines an instance method which produces a new instance of the class and initializes it to have the same age as the instance object passed. Line 1 declares the variable which will hold the new object being created.

Line 2 declares a pointer which will point to the instance variables contained within obj2. Note that you couldn't use the name iv because that would conflict with Dynace's use of that variable relative to the implied self argument.

Line 3 creates a new blank instance of the class. Line 4 gives access to the instance variables contained within the new object.

Line 5 is the neat part. The left side of the assignment references an instance variable associated with obj2 and the right side references an instance variable associates with the object passed (self). This line could have also been written as follows:

```
iv2->iAge = iv->iAge;
```

since Dynace automatically creates the iv structure pointer and associates it with self. The key point here is that all direct instance variable usage is always relative to the iv variable.

The final difficulty is associated with instance variable access has to do with the C preprocessor. The following example will cause problems.

```
#define ASSIGN iAge = age
imeth gChangeAge(int age)
{
         ASSIGN;
         return self;
}
```

The above example will cause problems because Dynace will scan the method and determine that since it can't find any instance variable names referenced in the method, there is no need to gain access to them. Therefore, Dynace will not generate the iv variable for this method and you will receive a compile error.

This problem may be corrected by explicitly requesting Dynace to give access to the instance variables by use of the accessIVs macro. The following example corrects the previous example as discussed.

```
#define ASSIGN iAge = age
imeth gChangeAge(int age)
{
         accessIVs;
         ASSIGN;
         return self;
}
```

This macro must be placed in the variable declaration portion of the instance method's definition. The accessIVs macro actually declares and initializes a variable called iv from the self argument to the method. This iv variable will point to a normal C language structure which will look like the structure you defined when defining the instance variables.

3.3.4.2 Determining the Class of an Object

There is a macro in Dynace which will return the class of any object. This macro is called ClassOf. The following example illustrates its usage:

```
object o1, o2;
o1 = ClassOf(o2);
```

Now o1 will contain the class of o2.

3.3.4.3 Sending Super Messages

The process of evoking a method which is located in a superclass is sometimes necessary when executing a method within a particular class. Normally, when a generic function is evoked, the search for an applicable method starts at the class of the object which is the first argument to the generic. If no method is found, the superclasses are then searched. When sending a super message, the superclasses of the object are searched first. If no method is found then the superclasses of the superclasses are searched, and so on. The class of the object is bypassed.

An example will clarify this concept. Lets say you have a class defined as follows:

```
defclass MyClass {
        int iA;
};

imeth gPrint()
{
        printf("iA = %d\n", iA);
        return self;
}
```

This is a simple class which just holds the integer iA, and has a method to print it. Now let's define a second class which inherits from the above class. The second class will look as follows:

```
defclass AnotherClass : MyClass {
        int iB;
};

imeth gPrint()
{
        gPrint(super self);
        printf("iB = %d\n", iB);
        return self;
}
```

Not that both class's print methods share the same generic function, gPrint.

Since the second class inherits from the first class, instances of the second class will actually contain both the integer iB, and also the integer iA, defined in the first class. Since the second class's print method has no direct access to the iA instance variable, because of strict encapsulation, there is no way for it to print the iA instance variable's value. When the self argument to the gPrint generic function is of the second class's type, the second class's print method would always be evoked. There needs to be a way to evoke the print method associated with the first class from the print method in the second class.

In the second class's print method, the super syntax shown would accomplish the desired effect. This syntax works like evoking the gPrint method on an instance of the current class, except that it starts its search with the superclasses.

The end result of all this is that when a gPrint generic function is called with an instance of the second class, the second class's print method will be evoked. Then the second class's print method will evoke the first class's print method, printing the instance variable iA. When the first class's print method is through, it returns to the second class's print method, which called it. After that, the second class's print method prints the iB instance variable, and returns.

This super message concept is very important to understand. It is one of the key features which allows you to take a pre-existing class and modify its behavior to suit your needs without having to re-write the pre-existing code.

3.3.5 Class Initialization

During startup, when your application executes InitDynace, Dynace initializes the Dynace kernel, the generic objects and the Dynace kernel classes. The remaining classes get initialized when they are used. If you use a class which is a subclass of other classes, Dynace automatically initializes the parent classes first.

Explicit class initialization may be accomplished by simply referencing the class. The following example, which should exist inside a function, explicitly initializes the MyClass class.

MyClass;

3.3.5.1 Class Initialization Function

Sometimes it is desirable to perform some additional procedures at the time the class is initialized. For this case it is possible to have Dynace evoke class specific initialization functions declared by the programmer. Most often this feature is used to initialize class variables.

A class specific initialization should be a static function which take no arguments and returns no results. This function will get automatically evoked by Dynace immediately after the creation of the class it's associated with. Therefore, it will have full access to all the class variables.

In order to inform Dynace of the existence of a class initialization function, it should be declared in the defclass statement as described in the defclass specification described in a previous section.

3.3.5.2 An Example

The following code fragment depicts a class initialization function being used.

```
class_init(void);
static void
defclass
         MyClass
        int
                iVar;
 class:
        object cVar;
init:
        class_init;
};
static void
                class_init()
{
        cVar = gNew(Set);
}
```

3.3.6 What Gets Linked

Regardless of what classes exist in a particular library or what classes are mentioned in the generics.h or generics.c files Dynace is designed in such a fashion so that at link time only the classes which your application actually uses will get linked in.

3.3.7 The gNew Class Method

Most classes will have an instance creation method. This is the method which is responsible for creating and initializing instances of the new class, also called the *constructor*. If no local instance variable initializing is necessary, then no constructor method need be defined. One of the superclasses, or the Dynace kernel will automatically create and initialize the instance. In the absence of any explicitly initialized instance variables in a new instance, the Dynace kernel will zero out all instance variables of a new object.

The gNew class method works like any other class method. It receives, as its first argument, the object representing the class. If the constructor needs to take additional arguments you can either use the vNew generic (which has no compile time argument checking so the method can have any signature) or you can use a different generic name (such as gNewInstance) which will have the desired argument signature.

The first thing the gNew method normally does is create an instance of the class. This can be done by sending a super message to gNew. It must then pass the new object to an instance method so that the instance variables can be accessed and initialized.

```
defclass MyClass {
        char
                *iName;
        int
                iAge;
};
private imeth init(char *name, int age)
{
        iName = (char *) malloc(strlen(name)+1);
        strcpy(iName, name);
        iAge = age;
        return self;
}
cmeth
       gNewInstance(char *name, int age)
{
        return init(gNew(super), name, age);
}
```

Notice how the above example was also able to allocate additional storage for iName.

3.3.8 The Dispose Instance Method

Any class whose instances must do something more when being disposed of than just freeing themselves, must define an instance disposal method. This method, called the *destructor*, is usually associated with the gDispose and gDeepDispose generic functions.

In the example in the previous section one of the instance variables (iName) contained a pointer to allocated storage. If the instance was freed without regard for this allocated storage, the system would soon run out of heap space. Even the garbage collector couldn't help. So what we do is define a destructor which will free the instance appropriately. The following code will illustrate this procedure:

```
imeth object gDispose()
{
    free(iName);
    return gDispose(super);
}
```

There are several things which may be noted from this example.

First, the method returns what is returned from the gDispose super call. By convention the disposal generics return NULL. This is often used to null out a variable which references an object which is being disposed and hence no longer valid.

Second, the call to free, frees the storage allocated and assigned to the iName instance variable. It does not free the entire instance.

Third, the call to the super method is used to request any superclasses to perform their freeing. Eventually, the super call will terminate at the Dynace Object class which will do the actual freeing of the entire instance.

As discussed before, there are two ways to dispose of an object. The first, is by explicitly evoking the gDispose generic function on an object. The second, and preferred, way is to allow the garbage collector to dispose of the object when necessary.

If no special processes need to be performed to free an object, no destructor need be defined. Dynace has a default disposal procedure which simply disposes of the individual object.

3.3.9 Creating Generic Files

The generics.h and generics.c files are created by the dpp program. dpp reads in the pre-defined classes and generics from a pre-existing generics.h files as well as user added classes and generic information from class definition (.d files) files. dpp is able to parse the necessary files and merge the information in order to obtain sufficient information to generate the correct generic files for the application. See the section describing dpp for a complete description of it.

3.4 Dynace Pre-Processor (DPP)

The dpp program is the heart of the compile time functionality of Dynace. Dpp is capable of reading in pre-existing generics declaration files (normally generics.h) and class definition files (*.d files) and using this information to perform five specific tasks.

First, dpp is able to assimilate all the information read in and produce a merged generics declaration file (normally generics.h) which can be included by the application. This file includes all necessary declarations for the entire application, including class and generic declarations and system includes.

Second, dpp is also able to use the information read in to produce an application specific generics.c file. This is the file which contains all the actual generics as well as the generic and class initialization procedures.

Third, dpp is able to read in a class definition file (*.d file) and produce a normal C file (*.c) for compilation by your compiler.

Fourth, dpp will validate the argument and return type declarations between methods and pre-existing generics to make sure there are no inconsistencies. This will only be done for methods which have argument checking turned on. If an inconsistency is encountered, dpp issues an error message, but does not stop its processing. It will, however, optionally return an error code.

Fifth, it provides facilities so that the application specific generics.c file only need be generated and compiled when absolutely necessary. It does this by comparing any pre-existing generics.h file with one it's about to create. If they are the same (i.e. no new generics or classes have actually been added), then instead of generating the file, the generics.h, generics.c and generics.obj files are just touched.

3.4.1 Controlling DPP

Dpp operates by first reading in all input files (regardless of their order on the command line) and then using this information to check the input consistency and produce any requested output files.

Dpp is non-interactive, all operational requests and parameters are given at the command line. However, these command line arguments may also be located in files which dpp can read as an extension of the command line. These files, called command files, may contain any number of parameters in the same format as the normal command line. Parameters may be spread across any number of lines because dpp ignores new lines, tabs and multiple spaces located in one of these command files.

Command files are identified by a "@" followed by a file name with no intervening spaces. Command files and normal command line parameters may be freely intermixed. For example the following is quite legal.

Unlike the DOS standard, dpp only supports a hyphen or dash as an option switch. All options are case sensitive.

A complete list of options may obtained by evoking dpp without any arguments. It will display a complete list of all options and exit.

3.4.2 DPP Status Messages

During dpp operation, it will display the name of each file it is reading or writing, in addition to any warning or error messages. At the end of its run, dpp will display a status message similar to the following.

```
Classes = 48, 3, 51
Generics = 193, 15, 208
```

The first line indicates that dpp read in 48 class definitions via generic header files (i.e. generics.h). It then encountered 3 new class definitions while processing source files (i.e. *.c, *.d). This totaled 51 classes.

The second line indicates the same thing for generics.

3.4.3 Input Options (-g & -G)

Input options are those which cause dpp to read a file.

3.4.3.1 Generic Declaration Input

It is important that dpp have complete access to all related class and generic declarations when processing any files. This is the only way dpp can have sufficient information to adequately verify system consistency and produce complete generic files.

Typically, the single generics.h file associated with the application is all that is needed. The main exception to this rule is when initially building the application specific generics.h file or when wanting to build a new, clean one. In that case you should read in all the generics.h files associated with all the subsystems you intend to use.

As shipped, Dynace only includes two such files in the include directory. One called <code>generics.h</code> includes all the classes and generics defined by the Dynace kernel and class library. A second, called <code>wingens.h</code>, includes all that's in <code>generics.h</code> file plus all the classes and generics associated with the Dynace Window Development System. You would use one or the other, not both.

The command line argument used for this purpose is -g. Immediately following this option may be a list of zero or more, space separated, generic file names to be read in. There is always a space after the -g. If no file names follow the option, the single generics.h file is assumed.

There is also a similar -G option which works the same except that it won't return an error code if one of the files can't be found.

3.4.3.2 Source File Input (-s & -p)

Dpp includes two options for reading in source files. One command is for reading only and the other is for reading and pre-processing.

The -s option is for reading only. It reads in the specified files and uses this information for consistency checks and producing complete generic files. It is capable of reading in the new class definition files (*.d) as well as the old Dynace 2.x class definition files (*.c).

The -p option is for reading and pre-processing class definition files (*.d), thus producing associated C source files (*.c) with the same file name prefix. The information read in is also used as in the -s option, therefore, it would never be necessary to include the same file for processing under the -s and -p options.

In addition to recognizing *.d files as class definition files, dpp will likewise recognize *.dd, *.n, *.nn, *.i and *.ii in upper or lower case. Input file names ending in .dd, .nn or .ii will produce corresponding .cc or .cpp files depending on whether you are on Unix or DOS respectively.

3.4.4 Output Options

Output options are those options which cause dpp to create a file.

3.4.4.1 Generic Declaration File Creation (-h)

Once all the pre-existing generic declaration files (typically generics.h) and class definition files have been read in, dpp is then able to produce a merged class and generic declaration file for inclusion by application code.

The -h option is used for this purpose. The -h option may, optionally, be followed by a space and file name. If the file name is given, dpp will use that file for the generic class definition file. Otherwise, the default of generics.h will be used.

3.4.4.2 Generic Source File Creation (-c)

Use of the -c option causes dpp to generate the application specific C source file which contains all the generics used by the application as well as generic and class initialization code. Typically, the application specific generics declaration file (generics.h) contains all the information needed for creation of this file.

The -c option may, optionally, be followed by a space and file name. If the file name is given, dpp will use that file for the generic file. Otherwise, the default of generics.c will be used.

If the generics.c file gets too large for your compiler environment see the Splitting the Generics File (-M) dpp option.

3.4.4.3 Processing Class Definition Files (-p)

Dpp is capable, after reading in the appropriate generics declaration file, of reading a class definition file, verifying its consistency with the system and generating a corresponding C source file for compilation.

The -p option is for reading and pre-processing class definition files (*.d), thus producing associated C source files (*.c) with the same file name prefix. The information read in is also used as in the -s option, therefore, it would never be necessary to include the same file for processing under the -s and -p options.

Input files ending in .dd will produce corresponding .cpp or .cc files depending on whether you are on Unix or DOS.

3.4.4.4 Java Interface Files (-j)

Dynace has the ability to call Java code and have Java code call Dynace generics. The -j option to dpp causes dpp to generate files used to interface with Java. This option also takes an optional package name argument. The files generated are named object.java, DynaceClassRef.java, and LoadDynClasses.c. These Java interface files, in concert with the Dynace / Java interface DLL named JavaDynace.dll makes the interface possible.

3.4.4.5 Scheme Interface Files (-L1 & -L2)

Dpp has the ability to generate interface code to allow Dynace generic functions to be accessible from within a Scheme language environment. Once the <code>generics.h</code> file is read in (via the -g option) these options cause <code>dpp</code> to generate the necessary interface files for two supported Scheme environments, LibScheme and MzScheme. This interface file may be named after the option and will default to <code>scminter.c</code>. This file must be compiled and linked with your application.

MzScheme is available at http://www.plt-scheme.org

3.4.5 Misc. Options

Dpp supports a variety of other options documented in this section. Some options, however, are not documented. This is because some features are either experimental and not ready for use or only used to support old versions of Dynace which are no longer supported in any other fashion.

3.4.5.1 Preventing Unnecessary Compiles (-t)

Generic files (both .c and .h) files change whenever classes or generics are added or deleted, or arguments to existing generics change. Whenever a class definition file is changed it must be pre-processed to produce a compilable C file. Also, when class definition files change, it may or may not be the case that new classes or generics have been added or existing generics have changed argument types. In fact, except for a new development project, adding classes and generics is relatively rare when compared to other code changes.

Given this fact, dpp is able to determine whether a significant change has occurred or not. It does this by comparing the pre-existing application specific generics declaration file (generics.h) with one it's about to create. If they are the same, dpp does not create the new generic file and instead remembers the fact that it was not necessary.

If it wasn't necessary to generate the generic declaration file and the -t option is given, dpp will touch the specified files in order to prevent the make utility from unnecessarily building and compiling the corresponding generics.c file. This can lead to a significant savings in time.

The -t option may, optionally, be followed by a space and space delimited list of file names to touch. If the file list is given, dpp will touch the given files in the order given. Otherwise, the default of generics.h generics.c generics.obj will be used. On unix

systems generics.o is used instead. If any of the files don't already exist, dpp will just skip it.

3.4.5.2 Removing Classes or Generics (-r)

It is sometimes necessary to cause dpp to remove classes or generics from an existing generics.h file. This is necessary when an old class or generic is no longer used, or when the return type or arguments to a generic has been changed. If the return type or arguments to a generic has been changed and you don't want to rebuild the generics.h file from scratch, it's often easier to remove the old generic from the generics.h file and then just re-scan the source file with the new generic definition to re-add the changed generic. Once the generics.h file has been corrected a new generics.c file can be generated from the correct generics.h file (with the -g -c options).

To use this option when generating generics files simply follow the -r option with a list of classes and/or generics to remove (each separated by a space).

3.4.5.3 Splitting the Generics File (-M)

As a system becomes increasingly complex the number of generic functions increases. Dpp typically generates a single generics.c file which contains all the generic functions defined within the system. The problem with this is that in some limited environments (DOS or 16 bit Windows) there is a limit to the size a single source (.c) file can be so generics.c gets too big to be compiled. The solution is to split generics.c into multiple smaller files. Note that there isn't any problem associated with the size of the generics.h file in these environments.

The -M option causes dpp to split the generics.c file at the time it is created (using the -c option). As part of the -M option you must include the number of generic functions to split at. This option is not separated with a space. For example, using -M900 will cause the first 900 generic functions to be defined in generics.c and the remaining generic functions will be placed in a file names gens1.c. Gens1.c will have to be compiled and linked into the application just as generics.c.

3.4.5.4 Including Additional Header Files (-Isc, -Iac, -Ish & -Iah)

It is sometimes necessary to cause additional header files to be included in the dpp generated generics.c or generics.h files. This occurs when generic return or argument types are defined in other include files. Therefore, these files must be included prior to declaring these generics. Dpp has the -I series of options in order to support this feature.

Any particular -I type option should be followed by a space and space delimited list of file names to include. Dpp will cause the specified files to be included by the generated generics file in the specified order.

Use -Isc for system include files to be added to the generics.c file. Use -Iac for application include files to be added to the generics.c file. Use -Ish for system include files to be added to the generics.h file. And use -Iah for application include files to be added to the generics.h file.

3.4.5.5 Ignoring Errors (-i)

Normally, while processing the input files, if dpp encounters some kind of an error, it displays the error message and continues processing the input files. However, if an error occurs, dpp does not normally produce any output files. The -i option causes dpp to produce the output files requested anyway.

3.4.5.6 Quiet Operation (-q)

Normally, dpp displays continuous status messages indicating what files it is reading and writing in order to give some idea of where it is in its process. The -q option may be used to cause all unnecessary messages not to be displayed. This option, however, will not inhibit error messages.

3.4.5.7 Return Code (-z)

Under normal operation dpp returns 0 if no error occurs and non-zero otherwise. This is typically used to signal the make facility that an error occurred. The -z option is used to cause dpp to return 0 regardless of whether or not an error occurs.

3.4.5.8 Compile Time Argument Checking (-N)

The -N option is used to cause dpp to treat all generics as if they were defined with compile time argument checking turned off and generate code accordingly. In this case all generics will take arbitrary arguments and depend entirely on runtime argument validation.

This was the way Dynace versions 1 and 2 worked. The capability is kept for two reasons. First for backward compatibility. And second, to support environment which require complete flexibility with respect to generic arguments.

3.4.5.9 Disabling #line directives (-nld)

Normally dpp generates line directives when preprocessing a class definition file into a C source file. This is done in order to allow debugging on the original class definition file instead of the generated C file.

If this feature is not wanted use the -nld option.

3.4.5.10 Extra #line directives (-eld)

Normally dpp generates line directives only when necessary (when the files get out of line sync). This option causes dpp to (in addition to it's normal #line directive output) output a #line directive prior to each method.

3.4.5.11 Preprocessing Strategies (-S)

Dpp is capable of supporting four different code generation strategies. The various strategies refer to different linkage conventions between generics and methods. The various alternatives offer choices which determine the generated code's portability, efficiency, and use of C++ specific features.

Class definition files will work the same regardless of which strategy is selected. However, it is absolutely critical that the entire system be compiled for one and the same strategy. This includes generic files, class definition files and the Dynace system and class libraries as well.

To use this option you would use -Sn where n is a number between 1 and 4. There is no space between the -S and the number. The various strategies are as follows:

Strategy 1 incorporates a small, system and compiler specific, piece of assembler code. This strategy is the most efficient and the most recommended. This assembler piece is supplied for many of the popular platforms. Writing the assembler piece for a new platform is very easy for an assembler expert and documented in the next section of this manual. The only down side of this strategy is lack of portability (if the assembler piece is unavailable).

Strategy 2 uses a total C based approach. This strategy maximizes portability and for that reason it is the default strategy and the one used to generate the Dynace system as shipped. The down side to this strategy is that it is less efficient in terms of execution speed and stack space use than strategy 1.

Strategy 3 attempts to reduce the runtime overhead associated with strategy 2 by the use of C++'s inline function facility. The resulting code will run faster but will incur a heavy penalty in code size due to the inline expansions. This strategy is not typically recommended.

Strategy 4 produces code similar to strategy 3 except that generics which have variable arguments are treated like strategy 2 instead. This was done in order to accommodate compilers such as GCC which cannot inline variable argument functions.

Remember, Dynace is shipped using strategy 2. If you wish to use a different strategy you must rebuild the entire system with the selected strategy.

3.4.5.12 Generic Overloading (-X)

Dynace allows many methods to share the same generic function. This option has no effect on that facility of Dynace.

Dynace also has the ability to simultaneously associate a single method with a fixed argument generic which has compile time argument checking and a variable argument generic which has no compile time argument checking using the '<>' method declaration syntax. Under normal operation dpp ignores the '<>' syntax and does not perform this association. The -X option is used to enable dpp's support for this feature.

This facility is used to enable Dynace to support users who like maximum compile time argument checking and those who prefer maximum flexibility with regard to generic overloading with the same code base.

3.4.5.13 Force Generics.h File Generation (-f)

Under normal operation, when generating a generics.h file dpp will first read in any existing generics.h file and not generate a new file if the existing one is correct. The -f option is used to force a new generics.h file regardless of its status.

This feature is useful when changing strategies. If none of the generics or classes have changed Dynace would not normally generate a new generics file. This option will force a new one, with the correct strategy, to be created.

3.4.5.14 Generating External Structures (-iv & -cv)

These options cause Dynace to generate external declarations for a class's instance and class variables respectively when preprocessing a class definition file. The file names used will be the same as the source file except that the file will end in .iv or .cv respectively.

3.4.5.15 Class Initialization (-ni)

Under normal operation dpp generates the necessary class initialization file when preprocessing a class definition file. This option is used to cause dpp not to generate this function. The programmer will then be responsible for this function.

3.4.5.16 Auto Include Generation (-nai)

Under normal operation dpp automatically adds code to include the <code>generics.h</code> file in generated <code>generics.c</code> and C source files. This option causes dpp not to perform this auto inclusion.

This option along with the <code>-mg</code> option are used to support users who prefer a single header per class.

3.4.5.17 Macro Guard Typedefs (-mg)

This option causes dpp to macro guard all typedefs and inline generics in the generics.h file. This is used in conjunction with the -nai option to support one header per class. This is an unrecommended configuration.

3.5 Dynace Customization & Special Techniques

The Dynace kernel includes a class called Dynace. This class is used to query and set various parameters which effect the global operation of Dynace. The following subsections detail the various parameters which may be effected in Dynace as well as other special issues.

3.5.1 Makefile / Generics.h File Dependencies

All source files are technically dependent upon the application specific generics.h file. However, it is important that the make utility not be made aware of this fact. This is important because one of the main goals and advantages of Dynace is the fact that rarely do changes to a class require other modules to have to be recompiled - even when the changes cause changes to the generics.h file. If the makefile were made aware of this dependency, there would be many, many totally unnecessary compiles performed.

Most changes to a class definition file, including changes in the instances or class variables associated with the class, changes in the class hierarchy or algorithmic changes, have no effect on the generics.h file. The only things which could potentially cause a change to the generics.h file are the addition or removal of an entire class, the addition or removal of a generic, or the changing of the argument list or return type associated with a generic.

With a little programmer cooperation and the disassociation (for make utility purposes) of the <code>generics.h</code> file from other source modules the need for re-compiles can be very drastically reduced. The make utility DMAKE and the example programs (the ones which create classes) were designed with these concepts in mind. Emulation of these approaches is highly advised.

The following subsections detail all the things which could change a generics.h file and what effect it has on other modules. Advice on how to handle each situation will be discussed.

3.5.1.1 Adding New Classes

The addition of a new class never requires automatic recompilation of any other modules. Since the class was just added, the only modules which could even use the new class must have also been edited in order to reference the new class object. In that case, those modules will already be automatically recompiled anyway. Other modules don't directly reference the new class object and don't require recompilation.

Remember that because of Dynace's design, any previously compiled code which doesn't explicitly access a class by name, may still process and use arbitrary objects without having knowledge of those objects prior to being compiled.

3.5.1.2 Removal Of Classes

Again, the removal of a class should never cause the automatic recompilation of all modules. For starters, any module which references that class object will have to be edited, causing it to be recompiled. You can't possible forget to edit a file because the system won't link until all references to the removed class are eliminated.

The best approach is to use grep or some other file search utility to find all references to the removed class and make the appropriate changes.

In addition to the above, it should be noted that dpp never removes a class declaration from a generics.h file. Of course it really doesn't matter if an unused declaration exists, however, periodic rebuilding of the generics.h file from scratch will remove the accumulated junk.

3.5.1.3 Adding New Generics

Adding new generics never causes the need for mass recompilation for the exact same reasons as the addition of new classes. The only modules which could possible use it have to be edited to put the new generic in and that will cause only the appropriate modules to be recompiled. No other module is effected in any way.

3.5.1.4 Generic Removal

The removal of generics is a little more complex. First of all, if you remove a generic from a class definition file, Dynace doesn't automatically remove it from the <code>generics.h</code> file. In fact, the removal of a generic from a class definition file has no effect at all on the <code>generics.h</code> file. This is because without scanning all the class definition files and building the <code>generics.h</code> file from scratch, Dynace has no way of knowing whether or not any other module makes use of that generic. Therefore, Dynace leaves it in.

Because of the above, there is no advantage to associating the <code>generics.h</code> file to other code. The bottom line is that if a generic is removed, you'll have to search the code for use of that generic and make appropriate changes. This will cause the appropriate modules to be recompiled.

Another interesting thing about these facts is that rebuilding generics.h from scratch on a periodic basis is a good idea in order to get rid of any unnecessary generics.

3.5.1.5 Generic Argument Or Return Type Changes

Of all the possible changes to a generics.h file this is the most troublesome. It's also the change which is performed the least. Once an application or class library reaches any level of maturity, the existing protocols tend to change little. New features are implemented with new generics.

It's also difficult to change generic arguments because of the fact that the person making the change must take into account the effect it will have on any other classes which use the same generic. Generics with argument checking turned on must agree with all methods which they are associated with. Generics with argument checking turned off are not effected with this issue.

Having said that, however, there are only two ways of dealing with this situation. First of all, if working on a team project, it should be agreed that no generics will be changed without mutual agreement. It's more common to just create a new generic.

The best way to deal with the problem is to search through all the code for references to the generic and make the appropriate changes. This will cause only the effected files to be recompiled.

Another, and poor, answer is to recompile everything and fix the modules which get a compiler error.

This issue is not bad if you think about it. What would you normally have to do if you change the arguments to a regular C function? Answer - the same thing.

3.5.2 Compile Time Argument Checking

Dynace supports the simultaneous use of generics which have compile time argument checking enabled and those that have the option turned off. By convention only, generics which have compile time argument checking turned on begin with "g" and those that have compile time argument checking turned off begin with "v".

The programmer determines which generics have compile time argument checking turned on or off at the time the generics are defined. Those introduced with imeth or cmeth have argument checking turned on and those introduced with ivmeth or cvmeth have argument checking turned off.

For those generics which have compile time argument checking enabled, the Dynace preprocessor (dpp) will validate the argument lists between generics and their associated methods during preprocessing time. All discrepancies between generics and their associated methods will be reported at this time. Code which uses generics which have compile time argument checking enabled will be validated by your normal C compiler by use of the dpp generated declarations which exist in the generics.h file.

For generics with compile time argument checking turned off none of these checks will be performed at compile time. The runtime system will be used to perform the necessary checks.

3.5.2.1 Compile Time vs. Runtime Argument Checking

Before jumping to the conclusion that it's always best to have compile time argument checking turned on a few things should be mentioned. First of all Dynace has ample facilities to perform argument validation at runtime. Second, runtime-only argument checking is much more accurate and safe than compile-only time argument checking. Third, enabling compile time argument checking on a generic causes inconvenient restrictions placed on that generic as follows.

All methods associated with a generic which has compile time argument checking turned on must have the exact same argument signature. On the other hand, a generic with compile time argument checking turned off may be associated with methods with arbitrary argument signatures. This adds a great deal of flexibility and convenience to the system at no loss of safety except that you'll not discover a problem until runtime instead of compile time.

The problem with compile time argument checking shows itself most with the gNew generic. Instead of being able to use gNew for creation of instances of all classes, we have to use things like gNewWithInt and gNewWithStr to differentiate the various argument signatures. Not only is this ugly but it also causes the programmer to constantly ask "now, which gNew do I use for this class?".

The next sub-section details an alternative approach.

3.5.2.2 Sharing Methods

In order to accommodate programmers with different demands Dynace has the ability to simultaneous support programmers who prefer compile time argument checking turned on all the time and those who prefer more flexibility and better esthetics at the cost of not detecting argument errors until runtime. Dynace has the ability to associate a single method with both compile time argument checking generics and those without compile time argument checking within a single code base. The programmer may enable this feature when building the system via the -X dpp option (see the appropriate section).

As shipped, Dynace includes several generics which are used to provide non-compile time argument checking versions of conveniently overloaded generic functions including vNew, vFind, vRemove, vFormat and vAdd. The entire system must be compiled with the dpp -X option in order to enable them however.

3.5.3 Runtime Argument Validation

Whenever a generic function is evoked in Dynace, the system checks the validity of the first argument. It makes sure that the first argument is in fact a valid Dynace object. If it is not, Dynace will report that fact and abort the program. Otherwise, the continuation of the program could reek havoc with the entire system.

This object checking comes at a runtime cost, however. This cost is incurred at every evocation of any generic function. While the cost is relatively minimal, programs which are well debugged may turn the checking off to maximize performance. The following code fragment illustrates your control over object checking:

```
gObjectChecking(Dynace, 0); /* This line turns off object checking */
gObjectChecking(Dynace, 1); /* This line turns on object checking */
```

The default is for object checking to be turned on.

3.5.3.1 Additional Argument Validation

If runtime argument checking is turned on (the default) Dynace automatically checks the validity and type of the first argument to all generics. It then dispatches to the appropriate method. Since different methods associated with a particular generic may contain a different number and types of arguments, it is the responsibility of the individual methods to validate their remaining arguments.

Dynace provides several mechanisms to accomplish and simplify this task. The most convenient mechanism is the use of several macros called ChkArg, ChkArgTyp, ChkArgNul and ChkArgTypNul. These macros provide a very simple way of validating an argument as being a valid Dynace object and, optionally, of being of a particular type. If the argument is invalid an appropriate and meaningful error message will appear. These macros are also used internally by Dynace where appropriate and may be controlled by the object checking mode described in the previous section.

Other mechanisms which may be used are the IsObj function, the gIsKindOf generic, the ClassOf macro, the gInvalidObject generic, the gInvalidType generic and the gAbort generic, as well as others.

The following code fragment illustrates the use of the ChkArgTyp macro:

```
/* Validate that arg3 (the 3rd argument) is an instance of String
  (or one of its sub-types) */
ChkArgTyp(arg3, 3, String);
/* Validate that arg4 (the 4th argument) is any Dynace object */
ChkArg(arg4, 4);
```

Note that the ChkArg set of macros may only be used as the first executable statements in a method.

3.5.4 Methods With A Variable Number Of Arguments

Due to the way Dynace deals with the various method / generic interface strategies (described under dpp subsection "Preprocessing Strategies") it was necessary to construct a standard way of dealing with methods which implement variable arguments. Use of these conventions or standards assures the portability of method definitions across all support strategies without loss of functionality or convenience.

The conventions used to deal with variable argument lists are fully described in the section on the MAKE_REST and GetArg Dynace macros.

3.5.5 Tracing Facility

Dynace includes a powerful and flexible tracing facility to assist in the debugging of applications. The facility traces generic calls of arbitrary combinations of classes, generics and methods. Each traced generic prints out the generic name, the type of the first argument to the generic, the name of the method found and the class of the method found.

The tracing facility has three global modes controlled by Trace::Dynace. It can be turned off (the default) to disable all generic tracing. It can be turned on in order to trace generic calls associated with classes, generics or methods which have their tracing options activated (via Trace::Behavior, Trace::GenericFunction and Trace::Method) and none deactivated. The third mode is to turn tracing on all. This traces all generic calls which do not have their tracing specifically deactivated or are not associated with classes or methods which are specifically turned off.

Note that when referring to classes in the context of the tracing facility, it refers to both the class of the first argument to the generic and the class associated to the method found.

The tracing facility can be turned on and modified at any number of arbitrary points of the application.

Trace output is sent to the stream traceStream which defaults to stdout.

See Trace::Dynace, Trace::Behavior, Trace::GenericFunction, Trace::Method, TracePrint::Dynace and traceStream for more information.

3.5.6 Memory Management and Object Disposal

As stated earlier, all objects in Dynace are allocated from the heap. In fact the object declaration actually declares a variable to be a pointer to this allocated memory. Therefore, when an object is no longer needed, it must be returned to the heap. If this is not done

you would eventually run out of heap space. Dynace has two methods of accomplishing this task, disposal generics and the garbage collector.

Any class whose instances must do something more when being disposed of than just freeing themselves must define an instance disposal method. The types of additional things this disposal method would normally do is free any additionally allocated storage which is local to the object being freed or perform any processing which needs to be performed at object disposal time.

The disposal methods are associated with the gDispose and gDeepDispose generic functions.

The gDispose generic is typically used to dispose of a single object and any associated allocated space it may reference. The system default gDispose will handle getting rid of the single object so the only time a specific method is needed is when the object allocates its own memory from the heap or other processing needs to occur at the disposal time. A programmer defined gDispose method would typically free any allocated space associated with the object and then call its super gDispose method.

The gDeepDispose generic, in addition to performing the same functions as the gDispose generic, is typically used to dispose of whole group of related objects at the same time. This method will typically recursively call the gDeepDispose generic on all objects being referenced within the object being disposed. The system default gDeepDispose method performs the same function as the system default gDispose method.

3.5.7 Speeding Up IsObj

IsObj is a function which validates a Dynace object pointer at runtime. This function is a small and fast function but gets called quite a lot and often accounts for much of the overhead associated with Dynace. This overhead is significantly exasperated in the Windows environment where the heap is non-contiguous.

Dynace's allocation scheme is designed to be memory efficient. However, this scheme is at odds, under Windows, with the speed of the system. Dynace has facilities to eliminate this overhead under Windows. If you build and run a Dynace based application, you can call <code>gMaxMemUsed(Dynace)</code> after running through a representative run of the application and before exiting to determine the amount of Dynace memory the application used. You can then use the <code>Dynace_GetInitialPageSize()</code> function to cause <code>Dynace</code> to allocate that amount as a single chunk of memory thus significantly speeding up the application. <code>Dynace_GetPageSize()</code> can also be used to set reasonable values. See the relevant documentation for those functions in this manual.

Note that this issue and its corresponding solution are only relevant in a Windows environment. Unix / Linux don't suffer from these problems.

3.5.8 Garbage Collection

The way the garbage collector works is that it keeps track of your maximum real memory requirements, after a garbage collection. Whenever your current memory usage exceeds a user defined number of bytes over the maximum real memory requirements, a garbage collection is evoked. Thus, the automatic aspects of the garbage collection process may

be controlled by specifying this user defined buffer area. If the buffer area is negative, no garbage collection process will take place. You will just have to explicitly dispose of any unneeded objects. The buffer area may be defined as follows:

gSetMemoryBufferArea(Dynace, 40000L);

Notice that the argument must be a long type. If passed a negative long value, garbage collection will be turned off. The default setting is -1L.

The smaller the buffer area is, the more often the garbage collector will have to run, and the slower the system will operate. However, the memory requirements of the system will be as small as possible. The larger the buffer area the less frequently the garbage collector will have to run, and therefore, the faster the system will run. However, if the buffer area is too large, the system will experience delays when the very infrequently called garbage collector has to collect a large volume of garbage. The best setting should be determined experimentally. Just remember that the memory requirements of the system will be equal to the real memory requirements of the system plus the buffer area. A starting value of about 40000L is recommended.

The garbage collector may be manually evoked with the following line:

gGC(Dynace);

Any class whose instances allocate memory from the heap must define an instance method which is associated with the gGCDispose generic. The garbage collector automatically calls this method when it frees an object. It must free the allocated space and call the gGCDispose super method just like a gDispose method. The only difference between the gDispose and gGCDispose methods is that the gGCDispose method should free allocated memory but must *never* dispose of any other Dynace object. Although it may perform any other necessary disposal type processing. Typically the gDispose method is adequate as a gGCDispose method and is used as such.

The garbage collector in Dynace uses an algorithm which does not require a lot of stack space even while collecting highly recursive data structures. The stack requirements are constant regardless of the objects being collected.

Dynace offers an alternative garbage collection scheme which has important tradeoffs. See the sub-section on the Boehm Garbage Collector.

3.5.9 Global or Static Variables

The Dynace garbage collector only marks objects which are accessible, either directly or indirectly, via automatic variables (those on the stack). Therefore, if you create an object and assign it to a global or static variable (a variable not on the stack) only, the garbage collector will not mark those objects. If those objects are not marked they will be freed. This is probably not what you want.

Note that under Win32, Dynace has special code and can automatically detect and mark unregistered globals or statics. Therefore manual registration of these memory locations is not needed under Win32.

Dynace has the ability to register a memory range with the garbage collector so that any valid objects referenced in this range will be marked. This will prevent the freeing of these needed objects. The following example illustrates the registration of a single global variable, GV:

```
RegisterVariable(GV);
```

This will cause the garbage collector to mark all objects which GV refers to, either directly or indirectly. It is OK for GV to not refer to a valid object.

Dynace also includes a method of marking a range of addresses. The following example illustrates its usage:

```
gRegisterMemory(Dynace, begRange, size);
```

The RegisterVariable macro actually calls gRegisterMemory.

3.5.10 Boehm Garbage Collector

In addition to the garbage collector (GC) which is part of Dynace, Dynace supports another GC which is freely available and widely used throughout the industry. This GC is not owned or supported by Algorithms Corporation or Blake McBride. It is called the Boehm GC and is copyrighted by Hans-J. Boehm, Alan J. Demers and Xerox Corporation.

The Dynace GC is only capable of collecting Dynace objects and requires a bit of programmer effort when dealing with non-Dynace objects such as application malloc'ed memory (which the Dynace GC will not collect) or global variables. The Boehm collector has been integrated with Dynace such that it will collect Dynace objects as well as application malloc'ed memory. In addition, the Boehm GC requires somewhat less programmer effort in order to work correctly. The main advantage of the Dynace GC is that it is more portable and comes with vanilla Dynace. The Boehm GC will not work in 16 bit environments such as DOS or 16 bit Windows.

In order to use the Boehm GC you must re-compile the entire Dynace system with the macro BOEHM_GC defined. In addition, the application must also be compiled with that macro defined and linked with the Boehm GC library. Both collectors cannot be used at the same time, one or the other. When using the Boehm GC there is no need to enable it, set the buffer area, or register memory regions. It's on all the time and functions automatically. See the Boehm GC documentation.

If your Dynace package didn't come with the Boehm GC source code you may obtain it via one of the following internet or e-mail sources:

```
http://www.hpl.hp.com/personal/Hans_Boehm/gc/http://reality.sgi.com/employees/boehm_mtiftp://parcftp.xerox.com/pub/gcHans_Boehm@hp.comboehm@acm.org
```

3.5.11 Native Thread Support

Dynace has been designed to support a truly multi-threading environment. This is not the simulated threads supplied with Dynace but the true threads provided by the underlying

system. Dynace utilizes critical sections or semaphores to ensure safe operation in a true multi-threading environment.

To enable this facility Dynace must be built from scratch with NATIVE_THREADS=1 set on the makefile line. The same is true for all applications which intend to use native threads. Dpp generates class files with the structures defined and used by Dynace already protected.

Additionally, the interface to the underlying system's critical section or semaphore facility will have to be provided. With knowledge of this area it is simple to provide. Dynace comes shipped with native thread support for Win32 only at this time. See include/dynl.h and the *.c files generated by dpp.

3.5.12 Method Cache

As stated earlier, the Dynace system caches method dispatching. This caching speeds up the system tremendously. The larger the cache the better. The default cache size is rather small, and may be user controlled. The following line may be used to set the cache size:

gResizeMethodCache(Dynace, 51, 101);

This example sets the cache size to 51 classes and 101 generics. These numbers do not have to reflect the actual number of classes and generics you have. They are just used to setup the cache. Regardless of the numbers used, the system can handle any number of classes and generic functions.

If this function is used, it should be used soon after initialization of the Dynace system.

3.5.13 Memory Compaction

Dynace includes a memory allocator which is capable of performing memory compaction. This is used by the String class (as well as possibly other classes) to reduce or eliminate memory fragmentation. Since the compactor (MA_compact()) may relocate memory, it is never called automatically by Dynace. After a call to MA_compact all pointers previously returned by Dynace generics such as gStringValue may be invalid. All object pointers, however, will always be valid.

The compactor would typically be called, manually, after a number of operations which would typically fragment memory.

3.5.14 Avoiding Runtime Method Lookup Costs

There is a small runtime overhead associated with the runtime binding mechanism of Dynace (or any system which has runtime binding). This overhead is kept to a minimum by the Dynace method cache and other techniques employed by the Dynace system. It is possible, however, to locally cache a method so as to reduce the future runtime overhead to zero. This technique is normally only used in tight loops where there is no chance of using the wrong method. Overuse of this technique is strongly discouraged.

See the macros cmcPointer, cmiPointer, imcPointer and imiPointer for further details and examples. There is also an example program which demonstrates the technique.

3.5.15 Generic Functions As First Class C Objects

In C, variables are treated as first class objects. That is they may be defined, initialized, assigned to (value change) and localized in any arbitrary block. C functions, on the other hand, are sort of second class (or static) objects. They may be defined but they can't be changed (at runtime) or localized in an arbitrary block.

In Dynace generic functions are implemented in such a way that they are first class objects, just like variables. That is they may be assigned to, passed and localized just like variables.

See the relevant example for more details.

3.5.16 Static Binding

It is possible to perform static binding with the Dynace system. Doing so, however, is highly discouraged because it eliminates much of the flexibility and encapsulation properties of Dynace. The only reason someone might want static binding is for efficiency reasons. These needs, however, may be met by local method caching described above. (See the sub-section on Avoiding Runtime Method Lookup Costs.)

In order to perform static binding you declare your method as a normal C function instead of using the method declaration syntax. You must also declare its first argument to be object self, and explicitly use the accessIVs macro.

From that point on it will act as other methods and may then be called directly, without going through the generic.

When calling a method directly it is the programmers responsibility to validate the validity and type of the first argument.

3.5.17 Allocating Objects From The Stack

All objects in Dynace are normally allocated from the heap. This allows for the maximum flexibility in terms of their life time and scope. However, Dynace does have a limited capability to allocate objects from the stack.

The two advantages of allocating objects from the stack are that the allocation process, and hence the creation of the object, is very fast. The second advantage is that no explicit object disposal is necessary. Stack based objects simply disappear when the code goes out of scope in a fashion similar to automatic variables. Thus, there is zero overhead associated with the object's disposal.

The two disadvantages associated with stack based objects are that stack based objects are limited to the stack size and there is no provision for auto execution of an object destructor. In addition, object creation is a bit clumsy.

Dynace provides two ways to dispose of a heap based object. First it can be explicitly disposed via the gDispose or similar generic. Second, it can be automatically disposed via the garbage collector. Both mechanisms allow the programmer to specify additional processing which must be performed when the object is disposed (such as freeing memory or closing files). Unfortunately, stack based objects do not have this ability unless they

are explicitly disposed and explicitly disposing of objects mostly negates the whole value of having stack based objects in the first place.

Explicit disposal of stack based objects does not free up any stack space until the scope is exited. Therefore, if five objects are created and freed in sequence in the same stack frame the stack space required will be that of all five objects.

Due to the above facts stack based objects are generally discouraged. However, in cases where they are needed and no special disposal is required they can fit the bill.

See documentation on the StackAlloc for further details.

3.6 Notes On Compilers, Rebuilding And Porting Dynace

Dynace has been designed and tested to be as portable as possible. At the time of the writing of this manual Dynace has been compiled and tested under MS–DOS, Windows 3.1, Windows 95, Windows NT, Interactive UNIX, UHC UNIX, Linux and Sun SPARC and the Alpha processor. Compilers used were Microsoft Visual C++ 1.0 and above (16 and 32 bit), Borland C++ 3.1 and above (16 and 32 bit), WATCOM C/C++^32 9.0 and above, Symantec C++ version 7.21 (32 bit), GNU C 2.4 and above. In addition several prior versions of each of the above compilers were also tested.

When dpp strategy 1 is selected there is one small piece of assembler (the jumpTo code) used by the Dynace system. This code is specific to each compiler/model/OS combination. All jumpTo assembler routines which have been developed have been included with the system. There is no assembler required for the default strategy of 2.

The Dynace threader uses the C library functions setjmp/longjmp. When using these functions it is important not to over-optimize a program (as most compiler documentation attest). The included makefiles where designed to maximize the reliability of the Dynace threader. If the threader is not going to be used more aggressive optimization may be used.

The generics file must always be compiled with the optimization options (usually maximum) defined in the makefiles.

3.6.1 DMAKE

The makefile utility used for all builds, except unix, is DMAKE. DMAKE is a very powerful, portable and enhanced make utility developed by Dennis Vadura. It is freely distributable and not owned by Algorithms Corporation or Blake McBride. Complete documentation for this utility is contained in \DYNACE\DOCS\DMAKE.MAN

3.6.2 MS-DOS

All 16 bit MS–DOS libraries were built using the large memory model. There is no reason why Dynace could not be run in other models other than the size restrictions they present.

Compilation for other memory model may require different jumpTo assembler code which is not needed when using the default dpp strategy of 2.

3.6.2.1 Microsoft Visual C++

The makefiles used for this compiler are all called M16.DM or M32.DM depending on whether it's for the 16 or 32 bit compiler.

Since the Dynace threader makes use of setjmp/longjmp and the Microsoft Visual C++ documentation recommends not to use most of the optimization features when setjmp is used, it is recommended to use only the optimization options used in the included make files. It has been demonstrated that the -Oe option causes problems with the threader. If the threader is not going to be used much heavier optimization may be used.

Maximum optimization with no stack checking must always be used when compiling the generics file.

Jumto assembler for both the 16 and 32 bit compilers are provided for this compiler so any dpp strategy may be used.

3.6.2.2 WATCOM Compilers

The makefiles used for this compiler are all called W32.DM.

All testing was done with WATCOM $C/C++^32$ version 10.0. Versions 9.0 and 9.5 were used in the past.

The flat memory model is used with argument passing on the stack. The target system is DOS4G.

When switching between version 9.0 and 9.5 of the compiler two different jumpTo routines must be used. jumpto.w is for version 9.5 and 10.0, jumpto.w90 is for version 9.0.

Maximum optimization with no stack checking must always be used when compiling the generics file.

3.6.2.3 Borland C++

The makefiles used for this compiler are all called B16.DM or B32.DM depending on whether the 16 or 32 bit compiler is used.

Since the Dynace threader makes use of setjmp/longjmp and the Borland C++ documentation recommends not to use most of the optimization features when setjmp is used, it is recommended to use only the optimization options used in the included make files. If the threader is not going to be used much heavier optimization may be used.

The Dynace threader will not run under the huge model with the Borland compiler due to what is believed to be a problem with the Borland huge model setjmp/longjmp functions.

Maximum optimization must always be used when compiling the generics file.

Jumto assembler for both the 16 and 32 bit compilers are provided for this compiler so any dpp strategy may be used.

3.6.2.4 Symantec C++

The makefiles used for this compiler are all called S32.DM for their 32 bit compiler.

Symantec compilers version 7.2 and prior are known not to work due to compiler bugs. Version 7.2 plus a patch from Symantec as well as 7.21 did work.

There is no jump to assembler code for this compiler so dpp strategies 2 or above must be used. The 16 bit version of their compiler was never tested.

3.6.3 UNIX

The makefiles associated with the UNIX build are all named makefile.unx.

Only the GNU C compiler has been used.

Because of the linear memory associated with UNIX (or other 32 bit environments) Dynace runs quite well under it.

Since DOS puts CR/LF pairs at the end of each line and UNIX expects just a LF there is a problem with several source files. Since Dynace uses multi-line macros UNIX expects lines which are continued to end in backslash/LF combinations. In DOS they end in backslash/CR/LF combinations. The extra CR causes a problem under UNIX. In order

to fix the source files (get rid of the extra CR) Dynace includes a utility (in source form) to correct the files. The utility is called delcr.c and is located under the bin directory. It may be compiled and applied to all *.c, *.h, *.s, makefile.unx, readme files. The files which causes the most trouble are dynl.h under the include directory, thread.c under the threads directory, array2.h under the class directory and all the makefile.unx files. delcr may be used by simply naming the files to be converted on the command line. Wild characters are ok.

In addition note that the top level makefile is set up to correct all the files in the system automatically.

The -0 option cannot be used with any GNU C compiler prior to version 2.5. This is because functions declared volatile (returning type object) were assumed not to ever return (by design). This feature has been eliminated in GNU C 2.5.

Although we can not support it, Dynace has been ported to the Sun/SPARC and Alpha chip environments by some of our users. The jumpTo code is contained in the file name jumpto.s2. All necessary files are included with the system. See the makefiles for additional information.

3.6.4 Using A Debugger

Because of the way Dynace dispatches methods it is often difficult to trace through a generic call at the C source level. It has been found that if a break point is placed at the beginning of the actual method the debugger will stop there when going through the generic. So, for example, if you want to trace into a call to the gNew generic and you know you are dealing with the ShortInteger class, you may put a break point on the ShortInteger_im_gNew method in the shortint.c file and continue. The system will stop at the ShortInteger_im_gNew method and you should be able to continue as normal. If you are not sure what class the object is just but a break point on all the possible methods the generic will dispatch to.

There is not a problem when debugging a program at the machine instruction level. Therefore, it is possible to step at the C level up to a generic call, switch to the machine instruction level, step through the generic call until the method is reached, and then switch back to the C source level.

See the section on the Dynace tracing facility for help debugging a program.

3.6.5 Porting To Other Compilers, Memory Models or OSs

There are several issues associated with porting Dynace to a new environment. These issues are covered in the following subsections.

Dynace includes a few short programs to assist in the porting process. They are located under \DYNACE\KERNEL\PORT.

3.6.5.1 JumpTo Assembler Code

The Dynace preprocessor (dpp) is capable of supporting various method / generic interface strategies which are described on the section documenting dpp. While the default strategy (2) does not require any assembler code, the more efficient strategy (1) does. Although

Dynace comes with the necessary assembler code for many platforms, this section outlines the steps necessary to create the assembler code for a new environment.

Basically, the assembler must take a pointer to a function as an argument, pop two stack frames and jump (not jsr) to the function passed.

The best way to create this code is to compile jumpto.c (provided with Dynace) into assembler, modify it and then assemble it. Compiling generics.c into assembler for reference is also helpful. Running the code through a machine instruction debugger is a must.

Basically what you need to do is write down the state of the stack pointer and registers upon entry of the generic function. Next, allow the generic function to calculate the method to execute and call the jumpTo code. Finally, (and this is the part that needs to be modified) the jumpTo code should call the method such that upon entry of the method the stack pointer and registers look as though they did when the generic function was entered.

For someone that knows assembler this process should take about an hour.

3.6.5.2 GC & CPU Registers

If objects can exist in CPU registers, then the Dynace Garbage collector must have access to them in order to mark them so as not to incorrectly collect them. Dynace has two ways of dealing with this.

The first way is to declare objects to be volatile. This causes the compiler not to keep any objects in registers. While this is a safe and portable solution it also slows the system down a bit. It is, however, required by 16 bit compilers because they tend to split far pointers and store them on the stack in non-contiguous locations.

The second possibility is to explicitly mark objects which are referenced via registers. This is the best solution but requires a small bit of inline assembler. This code would be located in kernel.c under the GC function.

3.6.5.3 Memory Alignment

Memory alignment determines where in memory objects can be stored. By selecting efficient memory alignments you can maximize the code and garbage collector efficiency. Typically, alignment is on 4 byte boundaries for 32 bit systems and 2 byte on 16 bit systems.

Dynace includes support for 2 and 4 byte alignments via the ALIGN2 and ALIGN4 macros located in kernel.c.

3.6.5.4 Linear vs. Segmented Memory

As might be expected, Dynace runs much more efficiently in 32 bit, linear memory mode. Under linear mode Dynace can more quickly determine object validity, a function which is often performed.

Dynace supports both modes via the SEGMENTED_MEMORY macro contained within kernel.c.

3.6.5.5 Thread Timer

The Dynace multi-threader requires some mechanism whereby the OS is able to execute an application defined function on a regular basis. The frequency would normally be between 50 and 100 times or more a second.

3.6.5.6 Setjmp/longjmp Functionality

Since the multi-threader makes heave use of the setjmp/longjmp system functions, it is important that those functions save and restore the registers in addition to the stack frame. This will enable maximum reliability of local variables associated with threads.

4 Kernel Reference

The Dynace kernel consists of the bare minimum of classes, methods, and generic functions needed to implement the object oriented concepts discussed herein. This chapter will discuss the structure and various facilities available in the Dynace kernel.

Note that the first argument to all class methods is always the associated class object and the first argument to all instance methods is always an instance of the associated class. Therefore, documentation for the first argument of generics is not always given – it's redundant.

A convention used throughout the Dynace system is for method names to start with a capital letter and for the associated generic to have the same name with a lower case "g" placed at the beginning. Therefore, even though this manual documents the methods, the programmer would access the methods through their associated generics (add the "g").

4.1 Kernel Class Hierarchy

This Dynace kernel contains the following class hierarchy:

Object
Behavior
Class
MetaClass
Method
GenericFunction
Dynace

4.2 Object Class

The Object Class is the root of all objects in Dynace. It is the last place searched when looking for a given method. As such, the Object Class defines the default behavior for all objects in Dynace.

4.2.1 Object Class Methods

There are no class methods defined for the Object class.

4.2.2 Object Instance Methods

Object's instance methods define the default behavior for all objects in Dynace.

```
BasicSize::Object
sz = gBasicSize(obj);
object obj;
```

sz;

This method is used to obtain the entire size of an object including all header information and instance variables. The number returned does not include space allocated and pointed to by the object.

Example:

int

```
object x;
int sz;
x = gNewWithInt(ShortInteger, 77);
sz = gBasicSize(x); /* sz = 6 */
```

See also: Size::Object, InstanceSize::Behavior

Compare::Object

[Compare]

[BasicSize]

```
r = gCompare(i, obj);
object i;
object obj;
int r;
```

This is the default method used by the generic container classes to determine the equality of the values represented by i and obj. r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

This method only compares the pointer values of the two objects and is, therefore, usually overridden in other classes.

```
See also: Hash::Object
```

Copy::Object [Copy]

```
new = gCopy(obj);
object obj;
object new;
```

This method is used to make a copy of an object. A new instance of the same class as obj is created. Then the information contained in obj is copied to the new object created (new). The new object is returned.

Any classes whose instance's allocate memory may need to override this method.

This default method is the same as the DeepCopy::Object method and would need to be overridden if they need to be different.

Example:

This method is used to make a copy of an object. A new instance of the same class as obj is created. Then the information contained in obj is copied to the new object created (new). The new object is returned.

Any classes whose instance's allocate memory may need to override this method.

This default method is the same as the Copy::Object method and would need to be overridden if they need to be different.

Example:

```
object x, y;
x = gNewWithInt(ShortInteger, 77);
y = gDeepCopy(x);
```

This method is used to free the storage allocated when a new object is created. Any class whose instances don't contain pointers to other allocated space or references to other objects may normally just default to this DeepDispose.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object x;

x = gNewWithInt(ShortInteger, 77);
x = gDeepDispose(x);

See also: Dispose::Object, GCDispose::Object

Dispose::Object

r = gDispose(obj);

object obj;
object r; /* NULL */
```

This method is used to free the storage allocated when a new object is created. Any class whose instances don't contain pointers to allocated space may normally just default to this Dispose for their disposal when no longer needed. Note that when the garbage collector disposes of objects it calls the GCDispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Example:

```
object x;
x = gNewWithInt(ShortInteger, 77);
x = gDispose(x);
```

See also: DeepDispose::Object, GCDispose::Object

Equal::Object [Equal]

```
r = gEqual(obj1, obj2);
object obj1, obj2;
int r;
```

This method is the default method used to check two objects for equality by comparing their contents. 1 is returned if they are of the same class and contain the same contents and 0 otherwise.

This method should be overridden if the comparison should take into account storage other than the local instance storage. The String class is a good example of this.

Example:

```
object a, c, c, d, e;
int
       r;
a = gNewWithInt(ShortInteger, 77);
b = gNewWithInt(ShortInteger, 77);
c = gNewWithInt(ShortInteger, 8);
d = gNewWithInt(Dictionary, 99);
e = gCopy(b);
r = gEqual(a, a);
                   /* r == 1 */
r = gEqual(a, b); /* r == 1 */
r = gEqual(a, c);
                 /* r == 0 */
r = gEqual(a, d); /* r == 0 */
                 /* r == 1 */
r = gEqual(a, e);
```

See also: EQ

Error::Object [Error]

```
gError(obj, msg)
object obj;
char *msg; /* Error message */
```

This method is used to display an error message (msg using Puts::Stream and stderrStream) and abort the program. msg may also be an instance of String.

Example:

```
gError(Dynace, "Out of memory.\n");
```

See also: Puts::Stream, stderrStream

GCDispose::Object [GCDispose]

```
r = gGCDispose(obj);
object obj;
object r; /* NULL */
```

This method is used to free the storage allocated when a new object is created. This is a special type of dispose method which should only be called by the garbage collector in Dynace. The GCDispose method must be defined for any class whose instances contain allocated space. It should unregister any registered memory associated with the object, free the allocated space and then call the super GCDispose. It must not free any objects which are referenced, either directly or indirectly, by the object being disposed of.

This default method simply disposes of the individual object.

See also: Dispose::Object, DeepDispose::Object

Hash::Object [Hash]

```
val = gHash(i);
object i;
int val;
```

This is the default method used by the generic container classes to obtain hash values for the object. val is a hash value between 0 and a large integer value.

This default method only hashes on the pointer value of the object, therefore, it is normally overridden in other classes.

See also: Compare::Object

Init::Object

```
r = gInit(obj);
object obj;
object r;
```

This method is used as the default object initialization method for new objects when used in conjunction with Alloc::Behavior. The default behavior is to do nothing, therefore, this method does nothing but return its argument. Normally, classes would redefine this method to perform some class specific useful initialization.

```
Example:
```

This method is used to determine if class cls is the class of or a superclass of obj. If so a 1 is returned and 0 otherwise.

Example:

```
object a, b;
int c;

a = gNewWithInt(ShortInteger, 7);
b = gNewWithInt(Dictionary, 101);
c = gIsKindOf(a, ShortInteger); /* c == 1 */
c = gIsKindOf(a, LongInteger); /* c == 0 */
c = gIsKindOf(b, Dictionary); /* c == 1 */
c = gIsKindOf(b, Set); /* c == 1 */
c = gIsKindOf(b, LinkList); /* c == 0 */
```

See also: IsKindOf::Behavior, IsInstanceOf, ClassOf

```
Print::Object [Print]
```

```
ret = gPrint(obj, stm);
object obj;
object stm;
object ret;
```

This method is used to print out a representation of an object and its value to stream stm. It evokes StringRep on obj in order to obtain a printable representation of the object.

The returned value is just obj.

Example:

See also: PrintValue::Object, StringRepValue::Object, stdoutStream

PrintValue::Object

[PrintValue]

```
ret = gPrintValue(obj, stm);
object obj;
object stm;
object ret;
```

This method is used to print out a representation of an object's value to stream stm. It evokes StringRepValue on obj in order to obtain a printable representation of the object.

The returned value is just obj.

Example:

```
object x;
x = gNewWithInt(ShortInteger, 77);
gPrintValue(x, stdoutStream);
/* this would print something like: 77 */
```

See also: Print::Object, StringRepValue::Object, stdoutStream

ShouldNotImplement::Object

[ShouldNotImplement]

```
gShouldNotImplement(obj, meth)

object obj;
char *meth;
```

This method is used to display an error message indicating that the class of obj (or any of its subclasses) should not implement method meth. meth is the name of the method.

This method may be useful to help catch class misuse by users of a class. It issues a helpful message when attempting to use a class inappropriately.

The message is output via Error::Object which also aborts the program.

See also: Error::Object

Size::Object [Size]

```
sz = gSize(obj);
object obj;
int sz;
```

This is the default method used to obtain the size of an object. It returns the total number of bytes use by the objects instance variables. This method is often overridden.

Example:

```
object x;
int sz;
x = gNewWithInt(ShortInteger, 77);
sz = gSize(x); /* sz = 2 */
```

See also: BasicSize::Object

StringRep::Object [StringRep]

```
s = gStringRep(i);
object i;
object s;
```

This method is used to provide a default format for the display of instance objects. It creates an instance of the String class which represents the class of the object, its address and value. The value is obtained by calling the object's StringRepValue method. This is often used to print or display a representation of an object. It is also used by by Print::Object (a method useful during the debugging phase of a project) in order to directly print an object to a stream.

See also: Print::Object, PrintValue::Object, StringRepValue::Object

StringRepValue::Object

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to provide a default mechanism for creating an instance of the String class for the display of instance object's values. It displays the class of the object, and its address. This method is called by the StringRep method to obtain the value of the object and is normally overridden by particular classes.

It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

SubclassResponsibility::Object

[SubclassResponsibility]

```
gSubclassResponsibility(obj, meth)
object obj;
char *meth;
```

This method is used to display an error message indicating that method meth should be implemented by a subclass of the class of obj. meth is the name of the method.

This method may be useful when grouping common interfaces in an abstract class to insure that its subclasses implement the correct methods.

The message is output via Error::Object which also aborts the program.

See also: Error::Object

4.3 Behavior Class

The Behavior Class is used to define the default behavior common to Class and MetaClass type objects.

4.3.1 Behavior Class Methods

There are no class methods defined for the Behavior class.

4.3.2 Behavior Instance Methods

Behavior's instance methods define the default behavior common to all Class and MetaClass type objects.

Alloc::Behavior [Alloc]

```
obj = gAlloc(cls);
object cls;
object obj;
```

This method creates instances of class type objects. The returned value is an instance of class cls. All instance variables in the obj object are initialized to NULL or 0.

This method works exactly like New::Behavior except that it is not normally redefined by subclasses. Alloc is strictly used to allocate new instances without also initializing them. Init::Object would be defined and called to initialize the object. Conceptually, New::Behavior should be equivalent to calling Alloc and Init.

Example:

```
object x;
x = gInit(gAlloc(MyClass));
See also: Init::Object, New::Behavior, StackAlloc macro

DoesNotImplement::Behavior [DoesNotImplement]

gDoesNotImplement(cls, gen);

object cls;
object gen;
```

This method is used to issue an error message when there is an attempt to execute a generic function (gen) for class cls. The message prints to standard error (stderr) and exits the program.

Example:

```
gDoesNotImplement(MyClass, Generic(MyGeneric));
```

See also: RespondesTo, InvalidObject::Method

DontCollect::Behavior [DontCollect]

```
obj = gDontCollect(cls);
object cls;
object obj;
```

This method is used to turn garbage collection off for a single class of objects. It doesn't effect any of its superclasses or subclasses and has no effect of garbage collection is not being used. It returns cls.

Example:

```
gDontCollect(ShortInteger);
```

FindMethod::Behavior [FindMethod]

This method may be used to find the correct method associated with a particular generic-class combination. gen is the generic function object (not a pointer to the generic function). cls is the class where the search should start and lev tells whether this is a regular or superclass type search. 1 is regular and 2 indicates a superclass search.

A pointer to the C function which implements the method is returned. If no method is found NULL is returned.

There also exists a function named _FindMethod which works similar to gFindMethod except it issues an error message if no method is found. _FindMethod is the one which does all the work to find the correct method associated with a particular generic—class combination when executing generics.

FindMethod should not be called by an application. The relevant macros should be used instead.

There is a similar method called FindMethodObject::Behavior which returns the method object instead of the C function pointer which implements the method.

```
See also: imcPointer, cmcPointer, imiPointer, cmiPointer, iSuper,
RespondsTo, cSuper,
DoesNotImplement::Behavior, FindMethodObject::Behavior
```

FindMethodObject::Behavior

[FindMethodObject]

This method may be used to find the correct method associated with a particular generic—class combination. gen is the generic function object (not a pointer to the generic function). cls is the class where the search should start and lev tells whether this is a regular or superclass type search. 1 is regular and 2 indicates a superclass search.

This method return the method object found. If no method is found NULL is returned.

There is a similar method called FindMethod::Behavior which returns the C function which implements the method instead of the method object.

See also: FindMethod::Object, Generic

InstanceSize::Behavior

[InstanceSize]

This method is used to obtain the total size a direct instances of class cls would be. This includes space used by the instance variables defined in class cls as well as all the superclasses of cls.

See also: BasicSize::Object, StackAlloc::Behavior

IsKindOf::Behavior

[IsKindOf]

```
r = gIsKindOf(cls1, cls2);
object cls1, cls2;
int r;
```

This method is used to determine if class cls2 is a superclass of cls1. If so a 1 is returned and 0 otherwise. A 1 will also be returned if cls1 is the same class as cls2.

Example:

```
int c;
c = gIsKindOf(ShortInteger, Object);    /* c == 1 */
c = gIsKindOf(ShortInteger, LongInteger); /* c == 0 */
c = gIsKindOf(Dictionary, Set);    /* c == 1 */
c = gIsKindOf(Dictionary, LinkList);    /* c == 0 */
```

See also: IsKindOf::Object, IsInstanceOf, ClassOf

MarkingMethod::Behavior

[MarkingMethod]

```
obj = gMarkingMethod(cls, fun);
object cls;
object (*fun)(cls);
object obj;
```

This method is used to specify an additional marking method to be used by the garbage collector. It should only be needed in extremely special cases. After the garbage collector marks all used objects it checks for any classes which have a special marking method. The special marking method would normally mark additional objects which are accessed in a very unusual way.

```
See also: MarkRange::Dynace, MarkObject::Dynace, RegisterMemory::Dynace
```

Name::Behavior [Name]

```
name = gName(cls);
object cls;
char *name;
```

This method is used to obtain the name of a given class type object.

Example:

```
char *name;
name = gName(ShortInteger);
/* name now points to: "ShortInteger" */
```

New::Behavior [New]

```
obj = gNew(cls);
      or
obj = vNew(cls);
object cls;
object obj;
```

This is the method which creates instances of class type objects. The returned value is an instance of class cls. All New methods call this method. All instance variables in the obj object are initialized to NULL or 0. This method is often redefined in particular classes so that instance variables may be set to appropriate initial values.

Both gNew and vNew are associated with this method.

Example:

```
object x;
x = gNew(LinkList);
```

See also: Alloc::Behavior, Init::Object, StackAlloc macro

StackAlloc::Behavior [StackAlloc]

```
obj = gStackAlloc(cls, ptr);
object cls;
void *ptr;
object obj;
```

This method is used to turn arbitrary storage pointed to by ptr into an instance of cls. The storage is assumed to be large enough (the value returned by

InstanceSize::Behavior). The object returned will function as a normal object except that when it is disposed (via gDispose, etc.) no actual freeing of the object will occur. However, user defined disposal code will be utilized.

This facility is currently only used to allocate objects from the stack. The cover macro, StackAlloc, should be used instead of this method.

See also: StackAlloc macro, InstanceSize::Behavior

StringRep::Behavior

[StringRep]

```
s = gStringRep(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the object i and its value. The String contains the name of the class, and its address. It then calls the StringRepValue method to obtain its contents. This is often used to print or display a representation of a class object. It is also used by Print::Object (a method useful during the debugging phase of a project) in order to directly print an object to a stream.

See also: Print::Object, PrintValue::Object, StringRepValue::Link

StringRepValue::Behavior

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

SubClasses::Behavior

[SubClasses]

```
lst = gSubClasses(cls);
object cls;
object lst;
```

This method is used to obtain a list of all the direct subclasses of class cls. The list returned is an instance of LinkObject.

Use gDispose1() on the list when no longer needed.

Example:

```
object lst;
lst = gSubClasses(ShortInteger);
```

```
See also: SuperClasses::Behavior
```

SuperClasses::Behavior

[SuperClasses]

```
lst = gSuperClasses(cls);
object cls;
object lst;
```

This method is used to obtain a list of all the direct superclasses of class cls. The list returned is an instance of LinkObject.

Use gDispose1() on the list when no longer needed.

Example:

```
object lst;
lst = gSuperClasses(ShortInteger);
```

See also: SubClasses::Behavior

Trace::Behavior [Trace]

This method is used to set the trace mode associated with a particular class (cls). This mode only has an effect when the Dynace tracing facility is activated (via Trace::Dynace). The possible settings (defined in dynl.h) are as follows:

```
DYNACE_TRACE_DONT_CARE OK to trace this class if a related method or generic has tracing turned on (default)

DYNACE_TRACE_OFF Turn all tracing related to this class off
```

The value returned is the previous trace mode in effect. See the section on tracing (under Dynace Customization & Special Techniques) for more information.

Activate tracing for this class

Example:

DYNACE_TRACE_ON

```
gTrace(Set, DYNACE_TRACE_ON); /* turn tracing on for Set */
```

See also: Trace::Dynace, TracePrint::Dynace, Trace::GenericFunction, Trace::Method

4.4 Class Class

The Class Class is mainly used for the creation of new class objects.

4.4.1 Class Class Methods

The only class methods in the class Class are used to create new class objects and find class objects.

FindClass::Class [FindClass]

```
cls = gFindClass(Class, cname)
char *cname; /* the name of the class */
object cls; /* The class found */
```

This method is used to find a class object from its name. The requested class is returned or NULL if it doesn't exist.

Example:

```
object cls;
cls = gFindClass(Class, "Set");
```

GetAll::Class [GetAll]

```
cl = gGetAll(Class);
object cl; /* LinkObject of all class objects */
```

This method is used to get a linked list (of type LinkObject) of all the class objects (classes). It is useful for enumerating through all the class objects. Once a class object is obtained, it can be used to obtain information about the class.

Once cl is no longer needed it is important that it is disposed with gDispose and not gDeepDispose. Use of gDeepDispose on cl will dispose of all the class objects in the system and crash it.

See also: GetAll::Class

NewClass::Class [NewClass]

```
cls = gNewClass(Class, cname, ivsize, cvsize, superClasses...)
char
        *cname; /* the name of the new class
                                                 */
int
        ivsize; /*
                   the size of the instance variables in
                    the new class */
int
        cvsize; /* the size of the class variables
object
        superClasses; /* an END terminated list of
                           superclasses */
object
       cls;
                   The new class being created */
```

This method is used to create new classes. It automatically creates the class object, the metaclass object associated with the new class object and sets up all the necessary internal pointers and data structures.

The name parameter is the name associated with the new class. The metaclass created will have the same name with "meta" prepended to the name.

The ivsize parameter defines the size of the locally declared instance variables associated with the new class. If there are no local instance variables 0 should be used.

The cvsize parameter is used to declare the size of the locally defined class variables associated with the new class. If there are no locally defined class variables 0 should be used, otherwise, the size of the class variable structure should be used.

The remainder of this method's arguments define the superclasses the new class will have. The last argument must be END. If no superclasses are defined the single class Object will be the default superclass. The order of the superclasses will determine the method lookup order.

Example:

```
object NewClass;
NewClass = gNewClass(Class, ShortInteger, END);
```

See also: NewStdClass::Class

NewStdClass::Class [NewStdClass]

```
cls = gNewStdClass(Class, cname, ivsize, mclass, nipib,
                   sCls...)
        *cname; /*
                    the name of the new class
char
int
        ivsize: /*
                    the size of the instance variables in
                    the new class */
                    the metaclass of the new class */
obiect
       mclass; /*
       nipib;
                    number of instances per instance block */
object
        sCls;
                    an END terminated list of
                           superclasses */
                    The new class being created */
object cls;
```

This method is used to create new classes. Unlike NewClass::Class, which automatically creates a corresponding metaclass (like Smalltalk – more convenient), NewStdClass::Class creates single independent classes with the ability to set the metaclass (like CLOS – more powerful but more cumbersome to use).

The name parameter is the name associated with the new class.

The ivsize parameter defines the size of the locally declared instance variables associated with the new class. If there are no local instance variables 0 should be used.

The mclass parameter is used to set the class of the newly created class. This is the class which defines the behavior and characteristics of the newly created class. Note that any number of classes may share the same metaclass. This adds a great deal of power to the meta-language aspects of the system.

For efficiency reasons Dynace does not allocate memory for objects one at a time. They are allocated in blocks which are measured by the number of instances per block of memory. This factor may be specified by the use of the nipib parameter. When creating a class which will have many small instances used it is best to have nipib high (~50). However, if the instances are large and there will only be a few of them 1 would be a good choice. The use of 0 will cause the system to estimate an appropriate value based on the instance size.

The remainder of this method's arguments define the superclasses the new class will have. The last argument must be END. If no superclasses are defined the single class <code>Object</code> will be the default superclass. The order of the superclasses will determine the method lookup order.

See also: NewClass::Class

4.4.2 Class Instance Methods

The class Class has no instance methods.

4.5 MetaClass Class

All metaclasses in the system are instances of the class MetaClass. Since all metaclasses are instances of the MetaClass class, and all class objects are instances of their associated metaclasses, the MetaClass class is the heart of the Dynace class system. The MetaClass class has no class or instance methods.

4.6 Method Class

The Method class gives Dynace the ability to represent methods (static C language functions) as true objects. The principal use of this class is to create new methods.

4.6.1 Method Class Methods

There is only one class method associated with the Method class and it is used for the creation of new methods.

NewMethod::Method [NewMethod]

```
method = gNewMethod(Method, name, cls, gen, cf, ff)
char
        *name; /* the name of the new method
object
       cls;
                   the class associated with the method */
       gen;
               /* the generic associated with the method */
object
object
       (*cf)();/* the C function which implements
                             the method */
object
      (*ff)();/* the C function which implements
                             the method - fixed args */
object method; /* the new method object */
```

This method is used to create a new method object. The new method object associates a class object, a generic object, and a C function. The macros iMethodFor, ivMethodFor, cMethodFor provide the normal access to this method. See those macros for a full description.

See also: iMethodFor, ivMethodFor, cvMethodFor, cMethodFor

4.6.2 Method Instance Methods

The instances methods associated with this class are used to obtain information about a method object.

ChangeFunction::Method [ChangeFunction]

```
ofun = gChangeFunction(m, nfun);
object m;
object (*nfun)();
object (*ofun)();
```

This method is used to change the C function associated with a method object to **nfun**. The old C function pointer is returned.

See also: FindMethodObject::Behavior, Function::Method

Function::Method [Function]

```
fun = gFunction(m);
object m;
object (*fun)();
```

This method is used to obtain the C function associated with a method object.

See also: FindMethodObject::Behavior, ChangeFunction::Method

Name::Method [Name]

```
name = gName(m);
object m;
char *name;
```

DYNACE_TRACE_ON

This method is used to obtain the name of a given method type object.

See also: FindMethodObject::Behavior

Trace::Method [Trace]

```
pm = gTrace(mth, mode)

object mth;  /* method object */
int mode;  /* trace mode */
int pm;  /* previous trace mode */
```

This method is used to set the trace mode associated with a particular method (mth). This mode only has an effect when the Dynace tracing facility is activated (via Trace::Dynace). The possible settings (defined in dynl.h) are as follows:

```
DYNACE_TRACE_DONT_CARE OK to trace this method if a related generic or class has tracing turned on (default)

DYNACE_TRACE_OFF Turn all tracing related to this method off
```

The value returned is the previous trace mode in effect. See the section on tracing (under Dynace Customization & Special Techniques) for more information.

Activate tracing for this method

```
Example:
```

```
object mth;

mth = gFindMethodObject(Set, Generic(gRemove), 1);
   /* turn tracing on for Remove::Set */
   gTrace(mth, DYNACE_TRACE_ON);

See also: Trace::Dynace, TracePrint::Dynace,
        FindMethodObject::Behavior, Generic,
        Trace::Behavior, Trace::GenericFunction
```

4.7 GenericFunction Class

The GenericFunction class gives Dynace the ability to represent generic functions (C language functions) as true objects. The principal use of this class is to create new generic function objects.

4.7.1 GenericFunction Class Methods

The class methods in this class are used to create new generic objects and obtain a list of all generics.

FindGeneric::GenericFunction [FindGeneric]

```
gf = gFindGeneric(GenericFunction, name);
char *name; /* name of generic function to find */
object gf; /* GenericFunction object associated with name */
```

This method is used to obtain the generic function object named name. The generic function object is returned unless it is not found, in that case a NULL is returned.

See also: GetAll::GenericFunction

GetAll::GenericFunction [GetAll]

```
gf = gGetAll(GenericFunction);
object gf; /* LinkObject of all generic function objects */
```

This method is used to get a linked list (of type LinkObject) of all the generic objects. It is useful for enumerating through all the generic objects. Once a generic object is obtained, it can be used to obtain information about the generic.

Once gf is no longer needed it is important that it is disposed with gDispose and not gDeepDispose. Use of gDeepDispose on gf will dispose of all the generic objects in the system and crash it.

See also: GetAll::Class, FindGeneric::GenericFunction

NewGeneric::GenericFunction [NewGeneric]

```
gf = gNewGeneric(GenericFunction, name, fp);
char *name; /* the name of the new generic function */
object gf; /* the new generic function object */
void *fp; /* pointer to generic function */
```

This method is used to create a new generic function object. The generic function object is used to store the relationship between classes, generics and methods. Normally, all generics are created in a single file called "generics.c". All external declarations for the generics are kept in a file called "generics.h". These files are created automatically by the dpp program from the class documentation.

The macros InitGeneric, defGeneric, externGeneric provide the normal access to this method and the generic function object in general.

```
See also: dpp, defGeneric, externGeneric, InitGeneric, GetGenericPtr::GenericFunction
```

4.7.2 GenericFunction Instance Methods

GenericFunction instance methods define the behavior of all generic functions.

This method is used to get a pointer to the generic function associated with a generic object. gfp must be correctly typecast prior to use.

```
See also: Generic, GetAll::GenericFunction
```

```
InvalidObject::GenericFunction [InvalidObject]
```

```
gInvalidObject(gf, argn, arg1);
object gf;  /* the generic function object */
int argn; /* argument number */
object arg1; /* the first argument to generic */
```

This method is used to report the case when a generic is passed an argument which is not a valid object. After generation of the error message it calls Error::Object to report the error and abort the program. It is normally called automatically by a generic or by the use of one of the ChkArg macros.

```
See also: ChkArg, InvalidType::GenericFunction, Error::Object
```

InvalidType::GenericFunction [InvalidType]

```
gInvalidType(gf, argn, arg1, cls, arg);

object gf;  /* the generic function object */
int argn; /* argument number */
object arg1; /* the first argument to generic */
object cls; /* type of object expected */
object arg; /* the argument which is bad */
```

This method is used to report the case when a generic is passed an argument which is not the expected type. It passes the error message to Error::Object which prints the message and aborts the program. It is normally called via one of the ChkArg type macros.

See also: ChkArg, InvalidObject::GenericFunction, Error::Object

Name::GenericFunction [Name]

```
name = gName(g);
object g;
char *name;
```

This method is used to obtain the name of a given generic function type object.

Example:

```
char *name;
name = gName(Generic(vNew));
/* name now points to: "vNew" */
```

See also: Generic

Trace::GenericFunction [Trace]

```
pm = gTrace(gf, mode)

object gf;  /* generic function object */
int mode; /* trace mode */
int pm; /* previous trace mode */
```

This method is used to set the trace mode associated with a particular generic function (gf). This mode only has an effect when the Dynace tracing facility is activated (via Trace::Dynace). The possible settings (defined in dynl.h) are as follows:

DYNACE_TRACE_DONT_CARE OK to trace this generic if a

related method or class has tracing

turned on (default)

DYNACE_TRACE_OFF Turn all tracing related to this

generic off

DYNACE_TRACE_ON Activate tracing for this generic

The value returned is the previous trace mode in effect. See the section on tracing (under Dynace Customization & Special Techniques) for more information.

Example:

```
/* turn tracing on for vNew */
gTrace(Generic(vNew), DYNACE_TRACE_ON);
```

See also: Generic, Trace::Dynace, TracePrint::Dynace,

Trace::Behavior, Trace::Method

4.8 Dynace Class

The Dynace Class is used to affect various parameters which control the internal operation of the Dynace kernel. The user may control whether the garbage collector is activated or not and what parameters it is running under. You may also control such things as the size of the method cache. All operations performed through this class are performed by sending messages directly to the Dynace class. There are no instance methods.

4.8.1 Dynace Class Methods

All functionality of the Dynace class is accessed through it's class methods.

ChangeRegisteredMemory::Dynace [Ch

[ChangeRegisteredMemory]

```
rmp = gChangeRegisteredMemory(Dynace, rmp, beg, size)
void *rmp; /* registered memory pointer */
void *beg; /* pointer to beginning of region */
long size; /* size of region */
```

This method is used to change the memory region associated with a memory region pointer. rmp must have been a pointer returned by gRegisterMemory.

Example:

```
static object a, b;
void *rmp;

rmp = gRegisterMemory(Dynace, &a, (long) sizeof(a));
    .
    .
    .
gChangeRegisteredMemory(Dynace, rmp, &b, (long) sizeof(b));
```

See also: RegisterMemory::Dynace, GC::Dynace

CurMemUsed::Dynace [CurMemUsed]

```
cmu = gCurMemUsed(Dynace)
long cmu; /* current memory used */
```

This method is used to obtain the current amount of storage being used by Dynace objects. This number increases every time a new object is created, and decreases every time an object is disposed.

```
Example:
```

```
long cmu;
cmu = gCurMemUsed(Dynace);
```

See also: MaxMemUsed::Dynace, GC::Dynace, DumpObjects::Dynace

DumpObjects::Dynace [DumpObjects]

```
c = gDumpObjects(Dynace, file, mc)

object c;  /* the Dynace class */
char *file; /* file to dump object list on */
int mc; /* O=no metaclasses, 1=metaclasses too */
```

This method is used to dump a list of all Dynace objects in a human readable format into the file named by file. The mc flag is used to determine whether or not metaclasses are included in the dump.

This method is mainly used to find leaks in an application. Typically, a body of code would be run, then an object dump performed, then run again, and finally a second object dump to another file is performed. The two dump files would then be sorted and diff'ed. A list of object leaks would result.

Example:

```
gDumpObjects(Dynace, "objects.lst", 0);
```

See also: DumpObjectsString::Dynace, MaxMemUsed::Dynace, GC::Dynace

```
DumpObjectsDiff::Dynace [DumpObjectsDiff]
```

```
sd = gDumpObjectsDiff(Dynace, d1, d2)
object d1, d2; /* values from gDumpObjectsString */
object sd; /* StringDictionary instance */
```

This method is used to create a string dictionary representing the difference between two calls to gDumpObjectsString. The string is the name of the class and the value is an instance of LongInteger which represents the number of instances different.

This method is mainly used to find leaks in an application. Typically, a body of code would be run, then an object dump performed, then run again, and finally a second object dump is performed. The two dump string dictionaries would then be compared using gDumpObjectsDiff. A list of object leaks would result.

Example:

See also: DumpObjectsString::Dynace, DumpObjects::Dynace

DumpObjectsString::Dynace

[DumpObjectsString]

This method is used to create a string dictionary representing all Dynace objects in the system. The string is the name of the class and the value is an instance of LongInteger which represents the number of instances. The mc flag is used to determine whether or not metaclasses are included in the list.

This method is mainly used to find leaks in an application. Typically, a body of code would be run, then an object dump performed, then run again, and finally a second object dump is performed. The two dump string dictionaries would then be compared using <code>gDumpObjectsDiff</code>. A list of object leaks would result.

See also: DumpObjectsDiff::Dynace, DumpObjects::Dynace

```
GC::Dynace [GC]
```

```
c = gGC(Dynace)
object c; /* the Dynace class */
```

This method is used to force the Dynace system to perform a garbage collection. All inaccessible objects will be collected and made available for reuse. This method is not normally used because the Dynace system will automatically start the garbage collector when necessary (if turned on via the SetMemoryBufferArea method).

Example:

```
gGC(Dynace);
```

```
See also: SetMemoryBufferArea::Dynace, RegisterMemory::Dynace, DumpObjects::Dynace, NumbGC::Dynace
```

MaxAfterGC::Dynace [MaxAfterGC]

```
mem = gMaxAfterGC(Dynace)
long mem; /* maximum memory used */
```

This method is used to obtain the maximum memory that was in use immediately after the last garbage collection. If no garbage collection has taken place the returned value will represent the current memory usage. The value of this number is that the amount of storage between the current memory usage and this number is considered potential garbage and used (internally) by Dynace to help determine when an automatic garbage collection should occur.

Example:

```
long mem;
mem = gMaxAfterGC(Dynace);
```

See also: MaxMemUsed::Dynace, CurMemUsed::Dynace, GC::Dynace

MaxMemUsed::Dynace [MaxMemUsed]

```
mem = gMaxMemUsed(Dynace)
long mem; /* maximum memory used */
```

This method is used to obtain the maximum memory that was used by the system during the entire run of the application.

Example:

```
long mem;
mem = gMaxMemUsed(Dynace);
```

See also: MaxAfterGC::Dynace, CurMemUsed::Dynace, GC::Dynace, DumpObjects::Dynace

 ${\tt NumbGC::Dynace} \qquad \qquad [{\tt NumbGC}]$

```
ngc = gNumbGC(Dynace)
long    ngc;    /* maximum memory used */
```

This method is used to obtain the total number of times the garbage collector ran during the entire run of the application.

Example:

```
long ngc;
ngc = gNumbGC(Dynace);
```

See also: MaxAfterGC::Dynace, CurMemUsed::Dynace, GC::Dynace

ObjectChecking::Dynace [ObjectChecking]

```
c = gObjectChecking(Dynace, flag)
int flag; /* 1=on, 0=off */
object c; /* the Dynace class */
```

Since the first argument to all generics is the Dynace object which is being sent the message, the first argument to all generics must always be a valid Dynace object. Whenever a generic is called Dynace verifies that the first argument is in fact a valid Dynace object. If it is not Dynace will issue an error message and abort the program. This is a fatal error.

There is a runtime overhead associated with this check. It's very similar to the stack checking which some C compilers perform at runtime. Once a program is sufficiently debugged it is possible to turn this runtime checking off in order to achieve maximum performance. Turning the checking off is, however, not recommended. If an untested portion of code which contains a bug is executed and the checking is off very unpredictable results will occur. It's very similar to dereferencing an uninitialized pointer in C.

There are techniques to totally eliminate the runtime overhead associated with object validation and method lookup within Dynace. See the text.

By default Dynace has object checking turned on. The ObjectChecking method may be called at arbitrary points in a program to turn the checking on or off. A flag value of 1 turns checking on and a value of 0 turns it off.

Example:

```
gObjectChecking(Dynace, 0);
```

See also: ChkArg

RegisterMemory::Dynace [RegisterMemory]

```
rmp = gRegisterMemory(Dynace, beg, size)

void *beg; /* beginning of registered memory */
long size; /* size of region */
void *rmp; /* registered memory pointer */
```

The Dynace garbage collector uses the C stack in order to determine which objects are still accessible, either directly or indirectly, by the program and need to be saved. All remaining objects will be collected and returned to the free store. This scheme allows Dynace to automatically handle objects which are being referenced, directly or indirectly, by automatic variables and function parameters.

Dynace has no way of knowing about objects which are referenced by global and static variables or objects which are being referenced by memory allocated from the heap. If an objects is only being referenced by one of these methods Dynace will dispose of it the next time the garbage collector is called. If the program later tries to use the object an error will occur. The solution to this problem is to register these memory regions with Dynace.

The beg parameter specifies the address of the beginning of the region which needs to be protected. The size parameter specifies the size in bytes of the region. RegisterMemory returns a pointer which may be used to un-register the region at a later time.

The RegisterVariable macro provides a convenient interface to protect global and static variables.

If the Dynace garbage collector is not being used there is no need to register any memory regions.

Example:

 ${\tt RemoveRegisteredMemory::Dynace} \qquad \qquad [{\tt RemoveRegisteredMemory}]$

```
gRemoveRegisteredMemory(Dynace, rmp)
void *rmp; /* registered memory pointer */
```

This method is used to remove a memory region from those registered with the Dynace system. The rmp parameter must be a pointer which was obtained from a call to gRegisterMemory. Once this method is called the specified region of memory will no longer be protected from the garbage collector.

Example:

ResizeMethodCache::Dynace [ResizeMethodCache]

```
c = gResizeMethodCache(Dynace, nClasses, nGenerics)
int    nClasses;    /* size of class cache table */
int    nGenerics;    /* size of generic cache table */
object c;    /* the Dynace class */
```

The first time a particular method is evoked it must be searched for as described elsewhere in this manual. This is a time consuming process. It is, however, necessary for this process to occur at runtime in order to obtain the true benefit of Object Oriented Programming. C++, Objective–C, and Smalltalk all perform this search when using their dynamic binding capabilities.

Once the appropriate method is found it is placed in a fast cache automatically maintained by Dynace. This cache is designed such that it never overflows. It just grows on an as-needed basis. Therefore, once a correct method is found it will never be searched for again. All future messages to that particular method will be found in the cache.

When Dynace is initialized a default cache is established. Under normal circumstances you may never need to be concerned with the cache at all. However, under conditions where there are a very large number of classes or generics it may be beneficial to enlarge the cache table sizes.

If the cache size is to be changed the best place to do it is immediately after the initialization of Dynace. You could, however, change the cache size at any point at the one time cost of some additional CPU time.

The nClasses parameter should be set to some number larger than the total number of classes in your program. The nGenerics parameter should also be set to some number larger than the number of generics in the program. These numbers may be set lower than the number of classes and/or generics in order to save memory at the relatively low cost of runtime speed. Since the cache is implemented as a hash table choosing numbers that are prime is best. Choosing odd numbers is good too.

There are techniques to totally eliminate the runtime overhead associated with object validation and method lookup within Dynace. See the text.

Example:

```
gResizeMethodCache(Dynace, 101, 203);
```

SetMemoryBufferArea::Dynace

[SetMemoryBufferArea]

```
c = gSetMemoryBufferArea(Dynace, size)
long size; /* size of buffer area */
object c; /* the Dynace class */
```

This method is used to activate and control the automatic operation of the Dynace garbage collector. When Dynace is first started the default memory buffer area is set to -1. This value indicates that Dynace should not automatically start the garbage collector.

If the value of **size** is positive then Dynace will automatically start the garbage collector every time the program creates enough *new* objects to exceed the storage specified by the **size** parameter (in bytes). Dynace will automatically adjust its heap storage requirements based on the **size** parameter and the storage history of the application program.

The actual value of size must be determined experimentally. A typical starting place would be about 40000. The higher the value of size the less frequently the garbage collector will be started but the longer it will take to run. The lower the value of size the more often the garbage collector will run but also the faster. The garbage collector is very fast and you will probably not notice much of a difference for a wide range of size.

The typical storage Dynace requires to support this facility is roughly equal to the maximum storage of all the active objects in the application at any given time plus the value of the size parameter. Therefore, making size unnecessarily large would be wasteful.

Note that the size parameter must be of type long.

Example:

```
gSetMemoryBufferArea(Dynace, 40000L);
```

See also: GC::Dynace, RegisterMemory::Dynace

Trace::Dynace [Trace]

```
pm = gTrace(Dynace, mode)
int    mode;  /* trace mode     */
int    pm;  /* previous trace mode */
```

This class method is used to set the global trace mode of the Dynace system. The possible settings (defined in dynl.h) are as follows:

```
DYNACE_TRACE_OFF Turn all tracing off (default setting)

DYNACE_TRACE_ON Trace objects which are activated for tracing

DYNACE_TRACE_ALL Trace all except those explicitly deactivated
```

The value returned is the previous trace mode in effect. See the section on tracing (under Dynace Customization & Special Techniques) for more information.

Example:

TracePrint::Dynace [TracePrint]

```
c = gTracePrint(Dynace, msg)
char *msg; /* trace output message */
object c; /* the Dynace class */
```

This class method is used to output trace messages and is called by the Dynace internal tracing functions. This method simply outputs msg to traceStream. It is documented here in case there is a need to override it.

See the section on tracing (under Dynace Customization & Special Techniques) for more information.

See also: traceStream::Stream, Trace::Dynace, Trace::Behavior, Trace::GenericFunction, Trace::Method

4.8.2 Dynace Instance Methods

There are no instance methods associated with the Dynace class.

4.9 Kernel Macros

Dynace has a number of macros to simplify the creation and usage of objects. These macros are all defined in the file dynl.h. The following text describe each macro.

accessIVs [accessIVs]

```
accessIVs;
```

This macro is used to access the instance variables from within an instance method. It may be used anywhere within the variable declaration section of a normal C function. accessIVs actually declares a local variable named iv and initializes it to a pointer to the instance variable structure. Once accessIVs is called the local variable iv may be used to access all the locally defined instance variables in the class being defined in the current file.

accessIVs uses the variable named self to determine which object to obtain instance variables for. See ivPtr to access instance variables for other variables.

If an instance method makes only a single access to its instance variables the use of the ivsPtr macro would be better suited.

Note that it is rarely ever necessary to explicitly use the accessIVs macro due to the fact the Dynace preprocessor (dpp) automatically adds this code when preprocessing the class definition file.

Example:

```
defclass {
      char name[30];
      int age;
};

imeth void PrintInstances(object self, FILE *fp)
{
      accessIVs;

      fprintf(fp, "%s is %d years old\n", iv->name, iv->age);
}
```

See also: ivsPtr, ivPtr, ivType, GetIVs

ChkArg [ChkArg]

```
ChkArg(arg, argn);
object arg; /* the argument to be checked */
int argn; /* the argument number */
```

This macro provides a convenient way of validating method arguments. If arg is not a valid Dynace object a meaningful error message will be displayed and the program will be aborted. argn is used in the error message to tell which argument caused the problem.

The argument checking properties of this macro may be enabled / disabled via the gObjectChecking generic. It defaults to ON.

Since Dynace automatically checks the first argument to all generics (if argument checking is on) there is never a need to manually check the first argument. ChkArg would only be needed for arguments beyond the first.

ChkArg may only be used as the first executable statements in a method (prior to any other generic calls).

Example:

```
imeth object MyMethod(object self, object arg2, object arg3)
{
    accessIVs;
    ChkArg(arg2, 2);
    ChkArg(arg3, 3);
    .
    .
    .
    .
```

See also: ObjectChecking::Dynace, IsObj, IsKindOf::Object, ChkArgTyp, ChkArgNul, ChkArgTypNul

ChkArgNul [ChkArgNul]

```
ChkArgNul(arg, argn);
object arg; /* the argument to be checked */
int argn; /* the argument number */
```

This macro provides a convenient way of validating method arguments. Unlike ChkArg this will also permit an argument of NULL. If arg is not a valid Dynace object (or NULL) a meaningful error message will be displayed and the program will be aborted. argn is used in the error message to tell which argument caused the problem.

The argument checking properties of this macro may be enabled / disabled via the gObjectChecking generic. It defaults to ON.

Since Dynace automatically checks the first argument to all generics (if argument checking is on) there is never a need to manually check the first argument. ChkArgNul would only be needed for arguments beyond the first.

ChkArgNul may only be used as the first executable statements in a method (prior to any other generic calls).

Example:

```
imeth object MyMethod(object self, object arg2, object arg3)
{
    accessIVs;
    ChkArgNul(arg2, 2);
    ChkArgNul(arg3, 3);
    .
    .
    .
    .
    .
```

See also: ObjectChecking::Dynace, IsObj, IsKindOf::Object, ChkArgTyp, ChkArg, ChkArgTypNul

 ${\tt ChkArgTyp} \qquad \qquad [{\tt ChkArgTyp}]$

```
ChkArgTyp(arg, argn, type);
object arg;  /* the argument to be checked */
int argn;  /* the argument number */
object type;  /* the expected class of arg */
```

This macro provides a convenient way of validating method arguments. If arg is not a valid Dynace object a meaningful error message will be displayed and the program will be aborted. argn is used in the error message to tell which argument caused the problem.

type is used to specify the expected type of the argument. If arg is not an instance of class type (or one of its subclasses) an error message will be displayed and the program will be aborted. If no argument type checking is required type should be passed a NULL and no type checking will be performed.

The argument checking properties of this macro may be enabled / disabled via the gObjectChecking generic. It defaults to ON.

Since Dynace automatically checks the first argument to all generics (if argument checking is on) there is never a need to manually check the first argument. ChkArgTyp would only be needed for arguments beyond the first.

ChkArgTyp may only be used as the first executable statements in a method (prior to any other generic calls).

Example:

```
imeth object MyMethod(object self, object arg2, object arg3)
{
     accessIVs;
     ChkArgTyp(arg2, 2, String);
     ChkArgTyp(arg3, 3, Set);
     .
     .
     .
```

See also: ObjectChecking::Dynace, IsObj, IsKindOf::Object, ChkArg, ChkArgNul, ChkArgTypNul

ChkArgTypNul [ChkArgTypNul]

```
ChkArgTypNul(arg, argn, type);
object arg;  /* the argument to be checked */
int argn;  /* the argument number */
object type;  /* the expected class of arg */
```

This macro provides a convenient way of validating method arguments. Unlike ChkArgTyp this will also permit an argument of NULL. If arg is not a valid Dynace object (or NULL) a meaningful error message will be displayed and the program will be aborted. argn is used in the error message to tell which argument caused the problem.

type is used to specify the expected type of the argument. If arg is not an instance of class type (or one of its subclasses) an error message will be displayed and the program will be aborted. If no argument type checking is required type should be passed a NULL and no type checking will be performed.

The argument checking properties of this macro may be enabled / disabled via the gObjectChecking generic. It defaults to ON.

Since Dynace automatically checks the first argument to all generics (if argument checking is on) there is never a need to manually check the first argument. ChkArgTypNul would only be needed for arguments beyond the first.

ChkArgTypNul may only be used as the first executable statements in a method (prior to any other generic calls).

Example:

```
imeth object MyMethod(object self, object arg2, object arg3)
{
     accessIVs;
     ChkArgTypNul(arg2, 2, String);
     ChkArgTypNul(arg3, 3, Set);
     .
     .
     .
     .
```

See also: ObjectChecking::Dynace, IsObj, IsKindOf::Object, ChkArg, ChkArgNul, ChkArgTyp

ClassOf [ClassOf]

```
c = ClassOf(obj);
object obj; /* an object */
object c; /* the class of the object */
```

This macro provides a very fast way of obtaining the class of any object. Since all objects in Dynace (including classes) are also regular objects and since all objects are instances of some class the ClassOf macro may be called repeatedly and indefinitely for any Dynace object and you would always receive a valid object. This macro may also be used to map any class hierarchy.

Example:

```
object a, b;
a = gNewWithInt(ShortInteger, 7);
b = ClassOf(a); /* b now contains ShortInteger */
```

See also: IsKindOf::Object, IsInstanceOf

cmcPointer [cmcPointer]

```
meth = cmcPointer(cls, gen);

object cls;    /* the class */
object (*gen)();    /* generic function */
RTYPE (*meth)();    /* method */
```

This macro returns the class method associated with class cls and generic function gen. The normal runtime search is used to obtain the method. The process performed by this macro accounts for all the additional runtime overhead associated with the runtime binding of Dynace generic function usage. The method pointer returned may be used as a normal C function pointer, thus nullifying all future runtime overhead associated with dynamic binding. This macro may therefore be used to locally cache a method and eliminate any runtime costs while retaining the full dynamic capabilities of Dynace.

This macro correctly typecasts its returned pointer to agree with the associated generic's return type and argument list.

The use of this macro should be used sparingly. It is a little cumbersome to use and, if not used with care, may defeat the dynamic nature and benefits of dynamic binding. However, if used appropriately (in tight loops where efficiency is important), this macro may be a valuable tool.

This macro returns a pointer to the C function which implements the method. NULL is returned if no method is found.

Example:

```
vNew_t meth;
object vec[100];
int i;

meth = cmcPointer(ShortInteger, vNew);
for (i=0; i != 100;)
     vec[i++] = meth(ShortInteger, 4);
/* or: vec[i++] = (*meth)(ShortInteger, 4); */
     /* on old C compilers */
/* same as vec[i++] = gNewWithInt(ShortInteger, 4); */
/* except 0 runtime overhead in loop */
```

See also: cmiPointer, imiPointer, imcPointer, FindMethod::Behavior

cmeth [cmeth]

cmeth

This macro is used to label and introduce a C function which is to serve as a class method. All it really does is declare the C function to be static, and therefore not directly accessible externally to other source modules. It is important that all methods be declared static to enforce the encapsulation and enable name space overloading.

Example:

```
cmeth object New(self)
object self;
{
    ...
}
```

See also: imeth, method

cMethodFor [cMethodFor]

```
meth = cMethodFor(cls, gen, cf);

object cls;    /* class    */
object (*gen)();    /* generic function    */
object (*cf)();    /* C function    */
object meth;    /* method object    */
```

This macro is used to associate a C function, which implements a class method, with a generic function for class cls. It is normally only used within the class initialization function associated with each class file.

This macro returns a Dynace object (an instance of the Method class) which represents the C function which implements the method. Each Class and Generic object contains a list of Method objects which it relates to so there is not normally a need to save the returned value.

Example:

```
cMethodFor(MyClass, gNew, my_new);
```

See also: cvMethodFor, iMethodFor

cmiPointer [cmiPointer]

This macro returns the class method associated with the class of instance i and generic function gen. The normal runtime search is used to obtain the method. The process performed by this macro accounts for all the additional runtime overhead associated with the runtime binding of Dynace generic function usage. The method pointer returned may be used as a normal C function pointer, thus nullifying all

future runtime overhead associated with dynamic binding. This macro may therefore be used to locally cache a method and eliminate any runtime costs while retaining the full dynamic capabilities of Dynace.

This macro correctly typecasts its returned pointer to agree with the associated generic's return type and argument list.

The use of this macro should be used sparingly. It is a little cumbersome to use and, if not used with care, may defeat the dynamic nature and benefits of dynamic binding. However, if used appropriately (in tight loops where efficiency is important), this macro may be a valuable tool.

This macro returns a pointer to the C function which implements the method. NULL is returned if no method is found.

Example:

See also: cmcPointer, imiPointer, imcPointer, FindMethod::Behavior

cSuper [cSuper]

```
meth = cSuper(cls, gen);

object cls;    /* class */
RTYPE (*gen)();    /* generic function */
RTYPE (*meth)();    /* method */
```

This macro returns the superclass class method associated with the generic function gen for class cls. If the method is not found the normal method search procedure will be used.

RTYPE is the return type associated with the generic and macro in question. The method pointer returned will be correctly typecast.

This macro has been superseded by oSuper.

Example:

See also: oSuper, iSuper

cvMethodFor [cvMethodFor]

```
meth = cvMethodFor(cls, gen, cf, ff);
                       /* class
object cls;
                                               */
object (*gen)();
                       /* generic function
                                               */
                       /* C function
object (*cf)();
                                               */
                       /* fixed C function
object (*ff)();
                                               */
                       /* method object
object meth;
                                               */
```

This macro is used to associate a C function, which implements a class method, with a generic function for class cls. It is normally only used within the class initialization function associated with each class file.

This macro returns a Dynace object (an instance of the Method class) which represents the C function which implements the method. Each Class and Generic object contains a list of Method objects which it relates to so there is not normally a need to save the returned value.

The difference between this macro and cMethodFor is the extra ff parameter. When using dpp strategies other then 1 (see the dpp section) under certain circumstance dpp will alter the argument signature of the defined method in order to accommodate the non-assembler generic / method interface. It will then create a new function which has the correct signature in case the programmer requests a pointer to the method. This way the returned function pointer will match the argument signature defined in the class definition file. ff is a pointer to this cover function.

Example:

```
cvMethodFor(MyClass, gNew, my_new, f_my_new);
```

See also: iMethodFor, cMethodFor, ivMethodFor

defGeneric [defGeneric]

```
defGeneric(typ, gen)

type typ; /* any valid type */
object (*gen)(); /* generic name */
```

The defGeneric macro is used to create a new generic function. All generic functions are normally created in a single source file called generics.c which is automatically created by the dpp program. typ defines the normal return type of the generic and gen is the name of the new generic function.

There would not normally be a reason to use this macro.

Example:

```
defGeneric(object, vNew)
```

See also: dpp, externGeneric, InitGeneric, NewGeneric::GenericFunction

END]

END

The END macro is simply syntactic sugar and is defined as (object) 0. It is used when creating a new class to indicate the end of the list of superclasses.

Example:

```
CLASS = gNewClass(Class, Dictionary, END);
```

See also: NewClass::Class

EQ [EQ]

```
r = EQ(obj1, obj2);
object obj1, obj2;
int r;
```

This macro is used to determine if obj1 and obj2 refer to the same exact object (not just the same value within the object). If so a 1 is returned and 0 otherwise.

Example:

```
object a, b, e;
int c;

a = gNewWithInt(ShortInteger, 7);
b = gNewWithInt(ShortInteger, 7);
e = a;
c = EQ(a, b);  /* c == 0 */
c = EQ(b, e);  /* c == 0 */
c = EQ(a, e);  /* c == 1 */
```

See also: Equal::Object, NEQ

externGeneric [externGeneric]

```
externGeneric(typ, gen)

type typ; /* any valid type */
object (*gen)(); /* generic name */
```

The externGeneric macro is used to declare a generic function to external modules. All generic functions are normally declared in a single source file called generics.h which is automatically created by the dpp program. typ defines the normal return type of the generic and gen is the name of the generic function.

There would not normally be a reason to call this macro.

Example:

```
externGeneric(object, vNew)
```

See also: dpp, defGeneric, InitGeneric

Generic [Generic]

```
gen = Generic(name)

object (*name)();
object gen;
```

The Generic macro is used to obtain the generic object from its associated C function which implements the generic.

Example:

```
object obj;
obj = Generic(vNew)
```

See also: FindMethodObject::Behavior

 $\operatorname{\mathsf{GetArg}}
olimits$

```
GetArg(type)
```

This macro is used in conjunction with the MAKE_REST macro in order to create a consistent mechanism for methods which take a variable number of arguments to obtain its optional arguments. This mechanism, as opposed to the normal va_* mechanism, is necessary in order to allow the same source code to work across the various dpp code strategies (see the dpp subsection "Preprocessing Strategies").

GetArg may be used anytime subsequent to the MAKE_REST macro call. Its single argument is the type of the argument being taken off the variable argument list. Each successive call gets successive arguments after the last named argument.

See MAKE_REST for a complete example.

See also: MAKE_REST, RESET_REST

 $[\operatorname{GetCVs}]$

```
p = GetCVs(cls);
object     cls;
CLASS_cv_t *p;
```

This macro is used to obtain a pointer to the class variable structure locally defined in class cls. See the section "Internal Naming Conventions" for a description of CLASS_cv_t.

Example:

```
MyClass_cv_t *cv = GetCVs(MyClass);
```

See also: GetIVs

GetIVs [GetIVs]

```
p = GetIVs(cls, obj);
object cls;
object obj;
CLASS_iv_t *p;
```

This macro is used to obtain a pointer to the instance variable structure locally defined in class cls and associated with object obj. obj must, at some level, be an instance of cls or one of its subclasses. See the section "Internal Naming Conventions" for a description of CLASS_iv_t.

Example:

```
MyClass_iv_t *iv = GetIVs(MyClass, myObj);
```

See also: GetCVs, accessIVs, ivPtr

imcPointer [imcPointer]

```
meth = imcPointer(cls, gen);

object cls;     /* the class */
object (*gen)();     /* generic function */
RTYPE (*meth)();    /* method */
```

This macro returns the instance method associated with an instance of class cls and generic function gen. The normal runtime search is used to obtain the method. The process performed by this macro accounts for all the additional runtime overhead associated with the runtime binding of Dynace generic function usage. The method pointer returned may be used as a normal C function pointer, thus nullifying all future runtime overhead associated with dynamic binding. This macro may therefore be used to locally cache a method and eliminate any runtime costs while retaining the full dynamic capabilities of Dynace.

This macro correctly typecasts its returned pointer to agree with the associated generic's return type and argument list.

The use of this macro should be used sparingly. It is a little cumbersome to use and, if not used with care, may defeat the dynamic nature and benefits of dynamic binding. However, if used appropriately (in tight loops where efficiency is important), this macro may be a valuable tool.

This macro returns a pointer to the C function which implements the method. NULL is returned if no method is found.

Example:

See also: imiPointer, cmiPointer, cmcPointer, FindMethod::Behavior

imeth [imeth]

imeth

This macro is used to label and introduce a C function which is to serve as an instance method. All it really does is declare the C function to be static, and therefore not directly accessible externally to other source modules. It is important that all methods be declared static to enforce the encapsulation and enable name space overloading.

Example:

```
imeth object ChangeValue(self)
object self;
{
    ...
}
```

See also: cmeth, method

iMethodFor [iMethodFor]

```
meth = iMethodFor(cls, gen, cf);

object cls;    /* class */
object (*gen)();    /* generic function */
object (*cf)();    /* C function */
object meth;    /* method object */
```

This macro is used to associate a C function, which implements an instance method, with a generic function for class cls. It is normally only used within the class initialization function associated with each class file.

This macro returns a Dynace object (an instance of the Method class) which represents the C function which implements the method. Each Class and Generic object contains a list of Method objects which it relates to so there is not normally a need to save the returned value.

Example:

```
iMethodFor(MyClass, gChangeValue, my_change);
```

See also: ivMethodFor, cMethodFor

imiPointer [imiPointer]

This macro returns the instance method associated with an instance i and generic function gen. The normal runtime search is used to obtain the method. The process performed by this macro accounts for all the additional runtime overhead associated with the runtime binding of Dynace generic function usage. The method pointer returned may be used as a normal C function pointer, thus nullifying all future runtime overhead associated with dynamic binding. This macro may therefore be used to locally cache a method and eliminate any runtime costs while retaining the full dynamic capabilities of Dynace.

This macro correctly typecasts its returned pointer to agree with the associated generic's return type and argument list.

The use of this macro should be used sparingly. It is a little cumbersome to use and, if not used with care, may defeat the dynamic nature and benefits of dynamic binding. However, if used appropriately (in tight loops where efficiency is important), this macro may be a valuable tool.

This macro returns a pointer to the C function which implements the method. NULL is returned if no method is found.

Example:

InitGeneric [InitGeneric]

```
InitGeneric(gen);
object (*gen)();
```

The InitGeneric macro is used to create Dynace generic function objects which know the address of the C function which implements it.

All generic functions are normally initialized from a single source file called generics.c which is automatically created by the dpp program. gen is the name of the generic function.

There would not normally be a reason to call this macro.

Example:

```
InitGeneric(vNew);
```

```
See also: dpp, NewGeneric::GenericFunction, defGeneric, externGeneric
```

[IsaClass]

```
r = IsaClass(obj);
object obj;
int r;
```

This macro is used to determine if obj refers to a class type object. It returns a 1 for class and metaclass type objects and 0 for instance type objects.

Example:

```
object a;
int c;
a = gNewWithInt(ShortInteger, 7);
c = IsaClass(a);    /* c == 0 */
c = IsaClass(ShortInteger) /* c == 1 */
c = IsaClass(ClassOf(a)); /* c == 1 */
c = IsaClass(ClassOf(ShortInteger)) /* c == 1 */
```

See also: IsaMetaClass, ClassOf, EQ

IsaMetaClass [IsaMetaClass]

```
r = IsaMetaClass(obj);
object obj;
int r;
```

This macro is used to determine if obj refers to a metaclass type object. It returns a 1 for metaclass type objects and 0 for instance and class type objects.

Example:

```
object a;
int c;
a = gNewWithInt(ShortInteger, 7);
c = IsaMetaClass(a);    /* c == 0 */
c = IsaMetaClass(ShortInteger) /* c == 0 */
c = IsaMetaClass(ClassOf(a));  /* c == 0 */
c = IsaMetaClass(ClassOf(ShortInteger)) /* c == 1 */
```

See also: IsaClass, ClassOf, EQ

IsInstanceOf [IsInstanceOf]

```
r = IsInstanceOf(i, cls);
object i;
object cls;
int r;
```

This macro is used to determine if i is a direct instance of cls. If so a 1 is returned and 0 otherwise.

Example:

```
object a, b;
int c;

a = gNewWithInt(ShortInteger, 7);
b = gNewWithInt(Dictionary, 101);
c = IsInstanceOf(a, ShortInteger); /* c == 1 */
c = IsInstanceOf(a, LongInteger); /* c == 0 */
c = IsInstanceOf(b, Dictionary); /* c == 1 */
c = IsInstanceOf(b, Set); /* c == 0 */
c = IsInstanceOf(b, LinkList); /* c == 0 */
```

See also: IsKindOf::Object, ClassOf

iSuper [iSuper]

```
meth = iSuper(cls, gen);

object cls;    /* class */
RTYPE (*gen)();    /* generic function */
RTYPE (*meth)();    /* method */
```

This macro returns the superclass instance method associated with the generic function gen for class cls. If the method is not found the normal method search procedure will be used.

RTYPE is the return type associated with the generic and macro in question. The method pointer returned will be correctly typecast.

This macro has been superseded by oSuper.

Example:

```
/* execute the superclass instance
  method associated with gDispose
  and pass it the single argument self */
iSuper(MyClass, gDispose)(self);
```

See also: oSuper, cSuper

ivMethodFor [ivMethodFor]

```
meth = ivMethodFor(cls, gen, cf, ff);
                       /* class
object cls;
                                               */
object (*gen)();
                       /* generic function
                                               */
                       /* C function
object (*cf)();
                                               */
                       /* fixed C function
object (*ff)();
                                               */
                       /* method object
object
       meth;
                                               */
```

This macro is used to associate a C function, which implements an instance method, with a generic function for class cls. It is normally only used within the class initialization function associated with each class file.

This macro returns a Dynace object (an instance of the Method class) which represents the C function which implements the method. Each Class and Generic object contains a list of Method objects which it relates to so there is not normally a need to save the returned value.

The difference between this macro and iMethodFor is the extra ff parameter. When using dpp strategies other then 1 (see the dpp section) under certain circumstance dpp will alter the argument signature of the defined method in order to accommodate the non-assembler generic / method interface. It will then create a new function which has the correct signature in case the programmer requests a pointer to the method. This way the returned function pointer will match the argument signature defined in the class definition file. ff is a pointer to this cover function.

Example:

```
ivMethodFor(MyClass, gChangeValue, my_change, f_my_change);
```

See also: iMethodFor, cMethodFor

ivPtr [ivPtr]

```
iv = ivPtr(i);
object i;
ivType *iv;
```

The ivPtr macro returns a pointer to the locally defined instance variable structure associated with instance i. It is used to gain access to the instance variables associated with the instance object pointed to by the i variable. It may only be used in a file which defines a class and i must be an instance of the class being defined or one of its subclasses.

If the method is going to make more than one access to its instances variables the pointer returned by ivPtr should normally be saved and reused.

If the variable containing the instance variables you wish to access is named self than the ivsPtr or accessIVs macro should be used.

Although the example below makes its illustration with the self variable (because it's always the name of the first argument to a method) ivPtr is most often used to access the instance variables of a second argument (which wouldn't have the name self) which is an instance of the same (or sub) class.

Example:

```
defclass {
    char
            name[30];
    int
            age;
};
imeth object PrintAge(object self)
{
    printf("Age = %d\n", ivPtr(self)->age);
    return self;
}
imeth object PrintInstance(object self)
    ivType *iv = ivPtr(self);
                                    /* save the pointer */
/* the above line is the same as accessIVs */
    printf("Name = %s\n", iv->name); /* use saved pointer
    printf("Age = %d\n", iv->age);
    return self;
}
```

See also: accessIVs, ivsPtr, ivType, GetIVs

ivsPtr [ivsPtr]

```
iv = ivsPtr;
ivType *iv;
```

The ivsPtr macro returns a pointer to the locally defined instance variable structure for the variable named self. It is used to gain access to the instance variables associated with the instance object pointed to by the self variable. It may only be used in instance methods, in a file which defines a class.

This macro is typically used when an instance method makes a single access to its instance variables. If the method is going to make more than one access to its instances variables the macro accessIVs would normally be used or the pointer returned by ivsPtr would normally be saved and reused.

If the variable containing the instance variables you wish to access is not named self than the ivPtr macro should be used.

Example:

```
defclass {
    char
           name[30];
    int
            age;
};
imeth object PrintAge(object self)
    printf("Age = %d\n", ivsPtr->age); /* single use
                                                            */
    return self;
}
imeth object PrintInstance(object self)
    ivType *iv = ivsPtr; /* save the pointer */
/* the above line is the same as accessIVs */
    printf("Name = %s\n", iv->name); /* use saved pointer
    printf("Age = %d\n", iv->age);
    return self;
}
```

See also: accessIVs, ivPtr, ivType, GetIVs

ivType [ivType]

ivType

This macro is used to declare a variable to be of a structure which is defined by the local instance variable declaration. It can only be used in a source file which is used to define a class and only of the structure of the locally defined instance variable structure. It's main use is while passing a pointer to a local variable structure to other, usually statically defined, C functions within a class definition file.

Example:

```
ivType *ivp;
ivp = ivsPtr;
```

See also: accessIVs, ivPtr, ivsPtr

MAKE_REST [MAKE_REST]

```
MAKE_REST(lst);
```

This macro is used in conjunction with the GetArg macro in order to create a consistent mechanism for methods which take a variable number of arguments to obtain its optional arguments. This mechanism, as opposed to the normal va_* mechanism, is necessary in order to allow the same source code to work across the various dpp code strategies (see the dpp subsection "Preprocessing Strategies").

Methods which take a variable number of arguments and wish to access those arguments must use the MAKE_REST macro. This macro must exist immediately following the declaration section of the method and prior to the normal executable code.

MAKE_REST takes a single argument which must be the last named argument in the method's argument list. The result of calling MAKE_REST is the creation of a variable named <code>_rest_</code> which acts as a pointer to the variable argument list, a <code>va_list</code>.

Example:

```
imeth gChangeValue(int a, char *b, ...)
{
         double var1;
         int dd;
         MAKE_REST(b);

        var1 = GetArg(double);
        dd = GetArg(int);
        ...
}
```

See also: GetArg, RESET_REST

NEQ [NEQ]

```
r = NEQ(obj1, obj2);
object obj1, obj2;
int r;
```

This macro is used to determine if obj1 and obj2 refer to the same exact object (not just the same value within the object). If so a 0 is returned and 1 otherwise.

Example:

```
object a, b, e;
int c;

a = gNewWithInt(ShortInteger, 7);
b = gNewWithInt(ShortInteger, 7);
e = a;
c = NEQ(a, b);  /* c == 1 */
c = NEQ(b, e);  /* c == 1 */
c = NEQ(a, e);  /* c == 0 */
```

See also: Equal::Object, EQ

oSuper [oSuper]

```
meth = oSuper(cls, gen, obj);

object cls;
RTYPE (*gen)();
object obj;
RTYPE (*meth)();
```

This macro returns the superclass instance or class method associated with the generic function gen for class cls. obj is used to tell whether the object being acted upon is a class or instance object. It should be the argument which will be the first argument to the methods being returned. If the method is not found the normal method search procedure will be used.

RTYPE is the return type associated with the generic and macro in question. The method pointer returned will be correctly typecast.

This macro effectively eliminates the need for the iSuper or cSuper macros.

Example:

```
/* execute the superclass
  method associated with gDispose
  and pass it the single argument self */
oSuper(MyClass, gDispose, self)(self);
```

See also: iSuper, cSuper

RegisterVariable

[RegisterVariable]

```
p = RegisterVariable(v);
object v;
void *p;
```

The RegisterVariable macro is used as a short hand way of registering global object variables to protect them from the automatic garbage collector. v is the global variable to be protected and p is a registered memory pointer which may be used to change or delete the registration at some later point.

See the text for a detailed description of the garbage collector.

```
See also: RegisterMemory::Dynace, RemoveRegisteredMemory::Dynace, ChangeRegisteredMemory::Dynace
```

RESET_REST [RESET_REST]

```
RESET_REST;
```

This macro is used in conjunction with the GetArg and MAKE_REST macros in order to create a consistent mechanism for methods which take a variable number of arguments to obtain its optional arguments. This macro allows the GetArg to go back over the argument list from the beginning, thus allowing multiple passes over the entire argument list. RESET_REST may be called anytime, and any number of times, after MAKE_REST has been called. Each time RESET_REST is called, GetArg will start back at the beginning of the argument list.

Example:

```
imeth gChangeValue(int a, char *b, ...)
{
    double var1;
    int dd;
    MAKE_REST(b);

    var1 = GetArg(double);
    dd = GetArg(int);
    /* get the same arguments again */
    RESET_REST;
    var1 = GetArg(double);
    dd = GetArg(int);
    ...
}
```

See also: GetArg, MAKE_REST

RespondsTo [RespondsTo]

```
r = RespondsTo(i, gen);
object i;
object (*gen)();
int r;
```

This macro is used to determine if the class of i implements a method which is associated with generic gen. If so a 1 is returned and 0 otherwise.

Example:

```
object a;
int c;
a = gNewWithInt(ShortInteger, 7);
c = RespondsTo(a, gShortValue); /* c == 1 */
c = RespondsTo(a, gNext); /* c == 0 */
```

See also: FindMethod::Behavior

StackAlloc [StackAlloc]

```
i = StackAlloc(cls);
object cls;
object i;
```

This macro is used to allocate a new instance of class cls from the local stack space. i will be an instance of class cls with all its instance variables initialized to NULL.

Disposal of the returned object will occur automatically when the local stack is exited, however, no automatic execution of additional disposal code will occur. Manual disposal may also be used (via gDispose, etc.) but the object will still take up stack space until the stack frame is exited.

Since the returned object is allocated from the current stack frame it cannot be returned from the function which allocated it.

This facility depends on a robust implementation of the alloca system call.

Example:

```
object a;
a = StackAlloc(ShortInteger);
```

See also: StackAlloc::Behavior

4.10 Kernel Functions

The number of regular C language functions available externally has been kept to an absolute minimum. The reason for this is the static nature of C functions and an effort to minimize the number of routines the programmer needs to use the system. The following text describes each function.

Dynace_GetInitialPageSize

[Dynace_GetInitialPageSize]

```
sz = Dynace_GetInitialPageSize();
long sz;
```

This is an application defined function optionally supplied to determine the amount of memory Dynace should allocate upon startup. If used, it must be defined and supplied as part of the application's code. The value returned, given in number of bytes, is what Dynace uses to allocate its initial block of memory for various objects to be allocated from. This is used to speed up Dynace under Windows. See [Speeding-Up-IsObj], page 76.

Example:

```
The following function would be defined by the application:
```

```
long Dynace_GetInitialPageSize()
{
         return 1000000;
}
```

See also: Dynace_GetPageSize

Dynace_GetPageSize

[Dynace_GetPageSize]

```
sz = Dynace_GetPageSize();
long sz;
```

This is an application defined function optionally supplied to determine the amount of memory Dynace should allocate after its startup allocation. If used, it must be defined and supplied as part of the application's code. The value returned, given in number of bytes, is what Dynace uses to allocate its blocks of memory, when needed, after its initial memory block is used up. This is used to speed up Dynace under Windows. See [Speeding-Up-IsObj], page 76.

Example:

```
The following function would be defined by the application:
```

```
long Dynace_GetPageSize()
{
     return 100000;
}
```

See also: Dynace_GetInitialPageSize

GetIVptr [GetIVptr]

```
iv = GetIVptr(obj, cls);
object obj;
object cls;
void *iv;
```

This function is the one which does all the work to obtain a pointer to the instances variables from an object. obj is the object whose instance variables are needed. cls is the class which describes the structure of the instance variables needed. obj must be an instance of class cls at some point in its hierarchy. The pointer returned will only allow access to the instance variables defined by class cls regardless of any other instance variables obj may contain.

This function should not be called by an application. The relevant macros should be used instead.

See also: ivPtr, ivsPtr, accessIVs

InitDynace [InitDynace]

```
InitDynace(sb);
void *sb; /* stack beginning */
```

This function is used to initialize the Dynace kernel and all classes and generics. It must be called prior to the use of any other Dynace facility. It is typically called in main().

This function calls InitKernel internally to initialize the kernel first. The sb parameter tells Dynace where the beginning of the stack resides. The garbage collector needs this information to automatically scan automatic variables. sb is typically passed the address of the argc argument to main().

Example:

See also: InitKernel, GC::Dynace

InitKernel [InitKernel]

```
InitKernel(sb);
void *sb; /* stack beginning */
```

This function is used to initialize the Dynace kernel. It must be called prior to the use of any other Dynace facility. Typically, however, InitKernel is called indirectly through another function (such as InitDynace which also initializes the class library and user added classes). The sb parameter tells Dynace where the beginning of the stack resides. The garbage collector needs this information to automatically scan automatic variables. sb is typically passed the address of the argc argument to main().

Example:

See also: InitDynace, GC::Dynace

[IsObj]

```
r = IsObj(obj);
object obj;
int r;
```

This function is used to determine the validity of an object. If obj is a valid Dynace object IsObj returns a 1 otherwise it returns a 0.

```
Example:
```

See [Speeding-Up-IsObj], page 76.

4.11 Kernel Data Types

There is really only one new data type associated with Dynace, the object type. However, Dynace also has some type definitions which are simply used to ease programming in the Dynace environment.

object [object]

object

This is the principal type of object in Dynace. All Dynace objects are of type object. object is actually a pointer to memory which is allocated (by Dynace) from the heap. Objects never reside on the stack or static memory, although pointers to them may.

The object declaration may be used any place the int declaration may be used.

Example:

```
object a, b, c;
```

ofun [ofun]

ofun

This declaration is just a short hand way of declaring a variable to be a pointer to a function which returns an object.

The ofun declaration may be used any place the int declaration may be used.

Example:

```
ofun a;
object (*b)();

/* a and b are of the same type */
```

5 Class Library Reference

The Dynace class library is built on top of the Dynace kernel. It provides a library of facilities which make the Dynace system useful to an application programmer. It provides various data representational type classes which represent the normal C language data types such as short, long, double, pointer, etc. It also provides new data type classes such as date.

The class library also provides generic container type classes such as dictionaries and linked lists. It also provides classes which implement the ability for Dynace to run multiple threads and for those threads to communicate and control each other.

This chapter will discuss the structure and various facilities available in the Dynace class library.

Note that most of the Dynace kernel will run independently of the Dynace class library. The value of this is that should a programmer desire to create his own class library (to replace the included class library) he may build on top of the Dynace kernel just as the included library does.

Note that the first argument to all class methods is always the associated class object and the first argument to all instance methods is always an instance of the associated class. Therefore, documentation for the first argument of generics is not always given – it's redundant.

There is a naming convention used with Dynace generics. All generics start with either a lower case "g" or "v", and are always followed by an upper case letter. The ones which start with "g" are normal generics and may be treated like normal C functions. The ones which begin with "v" use the variable argument facilities of C and you should, therefore, take a bit extra care when using them since there is no compile time argument checking being done with these functions.

Since all generics start with either "g" or "v" and in order to avoid the difficulty associated with grouping all the generics under two letters, the first letter is dropped for indexing or heading purposes. Therefore if you are looking up a generic, it will always appear in the index or header with its first letter missing. The syntax description and example code, however, will show the entire name.

5.1 Class Library Hierarchy

This Dynace class library contains the following class hierarchy (which of course includes the hierarchy described in the Kernel Reference):

Dynace Class Hierarchy

Object			
Behavior Class MetaClass	Set Dictionary StringDictionary IntegerDictionary		
Method	Stream		
GenericFunction	String File		
Dynace	LowFile Pipe Socket		
Number Character			
ShortInteger	PropertyList		
$\begin{array}{c} {\rm UnsignedShortInteger} \\ {\rm LongInteger} \end{array}$	Thread		
Date DateTime *	Semaphore		
DoubleFloat	Constant		
Time DateTime *	Array NumberArray		
Pointer	CharacterArray ShortArray UnsignedShortArray IntegerArray		
Link LinkList			
LinkObject LinkValue	LongArray FloatArray DoubleFloatArray		
Sequence LinkSequence	BitArray ObjectArray		
LinkObjectSequence SetSequence	PointerArray		
•	FindFile		
Association	DIT		

BTree

BTreeNode

StringAssociation IntegerAssociation

LookupKey ObjectAssociation

 $[\]ensuremath{^*}$ Date Time inherits from Date and Time

5.2 Array Class

The Array class is used to represent heterogeneous and non-heterogeneous indexable collections of arbitrary dimensions. These arrays are designed to be flexible – they have the ability to be dynamically re-dimensioned or reshaped – and space and speed efficient. Although most of the actual functionality contained in subclasses of the Array class are implemented in the Array class, most users will find the subclasses more useful. The documentation associated with this class serves to document the functionality which is common to all its subclasses.

5.2.1 Array Class Methods

The majority of class methods associated with this class are mainly used by and documented in subclasses of the Array class.

This method is used to set the index origin associated with all array indexing. The default is 0. This means that a 4 element, 1 dimension array would be indexed by 0, 1, 2, 3. If the index origin is set to one that same array would be indexed by 1, 2, 3, 4.

The index origin may be changed any number of times and has no actual effect on any arrays (either created previously or subsequently). It only effects how indexing works.

5.2.2 Array Instance Methods

Instance methods associated with this class provide functionality which is common to all subclasses of the Array class.

```
ArrayPointer::Array [ArrayPointer]

p = gArrayPointer(s)

object s;
void *p;
```

This method returns a pointer to the first element of an array represented be s. The return type will be a pointer to the type of array it is. For example a ShorArray will return a pointer to a short and a DoubleFloatArray will return a pointer to a double. Consecutive elements may be accessed by incrementing the pointer (although this is not the preferred way of going through an array).

```
Copy::Array [Copy]
```

```
r = gCopy(i);
object i;
object r;
```

This method is used to create a new array object which is an exact copy, including type, rank, shape and values, of i. The value returned is the new array object.

See also: DeepCopy::Array

```
DeepCopy::Array [DeepCopy]
```

```
r = gDeepCopy(i);
object i;
object r;
```

This method is used to create a new array object which is an exact copy, including type, rank, shape and values, of i. The value returned is the new array object.

The difference between this method and Copy::Array is that if the array being copied is an ObjectArray, DeepCopy will also make copies of the elements. Copy will not.

See also: Copy::Array

```
DeepDispose::Array [DeepDispose]
```

```
r = gDeepDispose(s)
object s;
object r; /* NULL */
```

This method disposes and frees all memory associated with an Array object. If it is an instance of the ObjectArray class each non-NULL element will also be DeepDispose'd.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

```
Dispose::Array [Dispose]
```

```
r = gDispose(s)
object s;
object r; /* NULL */
```

This method disposes and frees all memory associated with an Array object.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Equal::Array [Equal]

```
r = gEqual(i, a)
object i, a;
int r;
```

This method is used to determine the equality of two arrays. If they (i and a) are instances of the same class, same rank, same shape and same values than Equal returns a 1. Equal returns 0 otherwise.

See also: EQ

Index::Array [Index]

```
p = gIndex(i, idx)
object    i;
va_list idx;
```

This method is used to obtain a pointer to a single element of an array. It is only intended to be used internally by the subclasses of Array. i is the array to be indexed and idx is a va_list where each element indicates successive indices into the array. The number of elements in idx must equal the rank of the array. The pointer returned may be typecast to the appropriate type.

See also: ChangeValue::NumberArray, ShortValue::NumberArray

Rank::Array [Rank]

```
r = gRank(i)
object i;
unsigned r;
```

This method is used to obtain the number of dimensions a particular array (i) has.

See also: Shape::Array, Size::Array, Reshape::Array

Reshape::Array [Reshape]

```
i = vReshape(i, r, ...)
object i;
unsigned r;
```

This method is used to change the rank and shape of an array (i). r is the new rank (number of dimensions) of the array and the remaining arguments (type unsigned) indicate the size of each consecutive dimension. Not that the number of arguments after r must be equal to the number r.

If the new shape has fewer elements than the original, the remaining elements are discarded. If, however, the new shape has more elements, the elements in the original array will be reused (from the beginning) over and over until the new array is filled.

The value returned is the modified array passed.

See also: Shape::Array, Rank::Array

Shape::Array [Shape]

```
s = gShape(i)
object i;
object s;
```

This method is used to obtain the shape (or dimensions) of a particular array (i). The value returned (s) is an instance of the ShortArray class, each element of which contains a consecutive dimension.

See also: Reshape::Array, Rank::Array, Size::Array

Size::Array [Size]

```
s = gSize(i)
object i;
int s;
```

This method is used to obtain the total number of elements in array i.

See also: Rank::Array, Shape::Array

object i;
object s;

```
StringRep::Array [StringRep]
s = gStringRep(i);
```

This method is used to generate an instance of the String class which represents the type, rank, shape and values associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

This method is used to generate an instance of the String class which represents the values associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object, StringRep::Array

5.3 Association Class

The Association class is an abstract class which serves the sole purpose of grouping several subclasses which have common functionality. There is no specific class or instance methods directly implemented by this class, however, some methods are documented here because of their common interface with all subclasses of the Association class.

The subclasses of this class (LookupKey, ObjectAssociation, StringAssociation and IntegerAssociation) are used to associate a key with a value and provide a means for manipulating these associations. Instances of these classes are principally used by the Set and Dictionary classes but may also be useful wherever a key/value pair may be useful.

5.3.1 Association Class Methods

There are no class methods implemented by this class.

5.3.2 Association Instance Methods

There are no class methods implemented by this class, however, some methods are documented here because of their common interface with all subclasses of the Association class. These methods are actually implemented by all subclasses of this class.

Compare::Association [Compare]

```
r = gCompare(i, obj);
object i;
object obj;
int r;
```

This method is used by the generic container classes to determine the equality of the keys represented by i and obj. r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

See also: Hash::Association

Hash::Association [Hash]

```
val = gHash(i);
object i;
int val;
```

This method is used by the generic container classes to obtain hash values for the key. val is a hash value between 0 and a large integer value.

See also: Compare::Association

5.4 BitArray Class

This class, which is a subclass of Array, is used to represent arbitrary shaped arrays of on/off-yes/no information in an efficient manner. Much of the functionality of this class is implemented and documented in the Array class. Differences are documented in this section.

5.4.1 BitArray Class Methods

The only class method implemented by this class is one used to create new BitArray instances.

New::BitArray [New]

```
ary = vNew(BitArray, rnk, ...)
unsigned rnk, ...
object ary;
```

This class method is used to create a new bit array.

rnk is the number of dimensions the new array should have. The remaining arguments (each of type unsigned) indicates the size of each consecutive dimension. Note that the number of arguments following rnk must be the same as the value in rnk.

ary is the new array object created and will be initialized to all zeros.

Example:

```
object ary;
ary = vNew(BitArray, 2, 5, 4);
/* ary is a 5x4 matrix */
```

5.4.2 BitArray Instance Methods

The BitArray instance methods are implemented in the Array class for efficiency reasons but those methods which are particular to the BitArray are documented here.

BitValue::BitArray [BitValue]

```
v = vBitValue(ary, ...);
object ary;
unsigned ...
int v;
```

This method is used to obtain the bit (1 or 0) value associated with a particular element of an instance of the BitArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Note that this is one of the few generics which doesn't return a Dynace object. It returns an int.

Example:

```
object ary;
int v;
ary = vNew(BitArray, 2, 5, 4);
v = vBitValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeBitValue::BitArray

ChangeBitValue::BitArray

[ChangeBitValue]

```
ary = vChangeBitValue(ary, val, ...);
object ary;
int val;
unsigned ...
```

This method is used to change the value of one element of BitArray ary.

val is the value which the element of the array should be changed to (a 1 or 0).

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

The value returned is the modified array passed.

Example:

```
object ary;
ary = vNew(BitArray, 2, 5, 4);
vChangeBitValue(ary, 1, 1, 2);
/* ary[1][2] <- 1 */</pre>
```

See also: BitValue::BitArray

5.5 BTree Class

The BTree class provides a means to hold a group of key / value pairs in a collection. Objects in a BTree collection can then be rapidly accessed arbitrarily (as in hash tables) as well as retrieved in a specific sequence (as in an ordered linked lists). Keys and values may be arbitrary Dynace objects.

It is important that the key objects correctly respond to gCopy and gDeepCopy because copies of the keys are used within the key structure.

5.5.1 BTree Class Methods

The only class method used in this class is one to create instances of itself.

```
New::BTree
[New]
bt = gNew(BTree);
object bt;
```

This class method creates instances of the BTree class.

5.5.2 BTree Instance Methods

The instance methods associated with this class are used to add, remove, and retrieve key / value pairs.

AddValue::BTree [AddValue]

```
old = gAddValue(bt, key, val);
object bt;
object key;
object val;
object old;
```

This method is used to add an arbitrary key / value pair to BTree bt. Both key and val may be arbitrary Dynace objects.

By default the built in generic gCompare is used for all key comparisons. This may be over written via gSetFunction::BTree.

Each key added to a particular BTree must be unique (i.e. duplicate keys are not allowed).

AddValue normally returns NULL. However, if NULL is not returned then it means that the key / value pair just added replaced a similar key / value pair. In that case the old value associated with the key will be returned and the old key object will still be used. This will normally mean you will have to dispose of the old value returned and your new key (since the old one was used).

Example:

```
object key = gNewWithStr(String, "My Key");
object val = gNewWithStr(String, "My Value");
object old = gAddValue(bt, key, val);
if (old) {
        gDispose(key);
        gDispose(old);
}
```

DeepDispose::BTree

[DeepDispose]

```
r = gDeepDispose(bt);
object bt;
object r; /* NULL */
```

This method is used to DeepDispose all key / value pairs associated with the BTree and then dispose of bt itself.

See also: Dispose::BTree, DeepDisposeAllNodes::BTree

DeepDisposeAllNodes::BTree

[DeepDisposeAllNodes]

```
r = gDeepDisposeAllNodes(bt);
object bt;
object r;
```

This method is used to DeepDispose all key / value pairs associated with the BTree without disposing of bt itself. The BTree object passed is returned.

See also: Dispose::BTree, DeepDispose::BTree

DeepDisposeObj::BTree

[DeepDisposeObj]

```
r = gDeepDisposeObj(bt, key);
object bt;
object key;
object r;
```

This method is used to DeepDispose a specific key / value pair associated with the BTree. The key / value pair is determined by key. If the key / value pair was found and removed, gDeepDisposeObj will return non-NULL. If the key was not found then NULL is returned.

See also: DisposeObj::BTree, DeepDisposeAllNodes::BTree

Dispose::BTree [Dispose]

```
r = gDispose(bt);
object bt;
object r; /* NULL */
```

This method is used to Dispose of the BTree object without disposing of all of the key / value pairs.

See also: DeepDispose::BTree, DisposeAllNodes::BTree

DisposeAllNodes::BTree

[DisposeAllNodes]

```
r = gDisposeAllNodes(bt);
object bt;
object r;
```

This method is used to disassociate all key / value pairs from the given BTree. Neither the keys, values, nor bt are disposed. The BTree object passed is returned.

See also: DeepDispose::BTree, DisposeAllNodes::BTree

DisposeObj::BTree

[DisposeObj]

```
r = gDisposeObj(bt, key);
object bt;
object key;
object r;
```

This method is used to disassociate (not dispose) a specific key / value pair from the BTree. The key / value pair is determined by key. If the key / value pair was found and removed, gDisposeObj will return non-NULL. If the key was not found then NULL is returned.

See also: DeepDisposeObj::BTree, DisposeAllNodes::BTree

FindEQ::BTree [FindEQ]

```
val = gFindEQ(bt, key, fkey);
object bt;
object key;
object *fkey;
object val;
```

This method is used to retrieve the value associated with a given key. The object associated with a key which compares equally with key is returned. If none is found NULL is returned.

fkey points to a location which will receive the actual key object found. fkey may be NULL in which case that argument will not be used.

Example:

```
object fkey;
object key = ...;
object val = gFindEQ(bt, key, &fkey);
```

See also: AddValue::BTree, FindNext::BTree

FindFirst::BTree [FindFirst]

```
val = gFindFirst(bt, fkey);
object bt;
object *fkey;
object val;
```

This method is used to retrieve the first key / value pair. If no key value pairs exist NULL is returned.

fkey will be updated to point to the key associated to the value returned. It may be used on subsequent calls to gFindNext.

See also: AddValue::BTree, FindNext::BTree

FindGE::BTree [FindGE]

```
val = gFindGE(bt, key, fkey);
object bt;
object key;
object *fkey;
object val;
```

This method is used to retrieve the value associated with a given key. The object associated with a key which compares greater than or equal to key is returned. If none is found NULL is returned.

fkey points to a location which will receive the actual key object found. fkey may be NULL in which case that argument will not be used.

Example:

```
object fkey;
object key = ...;
object val = gFindGE(bt, key, &fkey);
```

See also: AddValue::BTree, FindNext::BTree

FindGT::BTree [FindGT]

```
val = gFindGT(bt, key, fkey);
object bt;
object key;
object *fkey;
object val;
```

This method is used to retrieve the value associated with a given key. The object associated with a key which compares strictly greater than **key** is returned. If none is found NULL is returned.

fkey points to a location which will receive the actual key object found. fkey may be NULL in which case that argument will not be used.

Example:

```
object fkey;
object key = ...;
object val = gFindGT(bt, key, &fkey);
```

See also: AddValue::BTree, FindNext::BTree

FindLast::BTree [FindLast]

```
val = gFindLast(bt, fkey);
object bt;
object *fkey;
object val;
```

This method is used to retrieve the last key / value pair. If no key value pairs exist NULL is returned.

fkey will be updated to point to the key associated to the value returned. It may be used on subsequent calls to gFindPrev.

See also: AddValue::BTree, FindPrev::BTree

FindLE::BTree [FindLE]

```
val = gFindLE(bt, key, fkey);
object bt;
object key;
object *fkey;
object val;
```

This method is used to retrieve the value associated with a given key. The object associated with a key which compares less than or equal to key is returned. If none is found NULL is returned.

fkey points to a location which will receive the actual key object found. fkey may be NULL in which case that argument will not be used.

Example:

```
object fkey;
object key = ...;
object val = gFindLE(bt, key, &fkey);
```

See also: AddValue::BTree, FindPrev::BTree

FindLT::BTree [FindLT]

```
val = gFindLT(bt, key, fkey);
object bt;
object key;
object *fkey;
object val;
```

This method is used to retrieve the value associated with a given key. The object associated with a key which compares strictly less than key is returned. If none is found NULL is returned.

fkey points to a location which will receive the actual key object found. fkey may be NULL in which case that argument will not be used.

Example:

```
object fkey;
object key = ...;
object val = gFindLT(bt, key, &fkey);
```

See also: AddValue::BTree, FindPrev::BTree

FindNext::BTree [FindNext]

```
val = gFindNext(bt, fkey);
object bt;
object *fkey;
object val;
```

This method is used to retrieve a key / value pair which comes immediately after the key pointed to by fkey. If fkey points to NULL than the first key / value pair is retrieved. If none is found NULL is returned.

fkey will be updated to point to the key associated to the value returned. It may be used on subsequent calls to gFindNext.

Example:

See also: AddValue::BTree, FindPrev::BTree

FindPrev::BTree [FindPrev]

```
val = gFindPrev(bt, fkey);
object bt;
object *fkey;
object val;
```

This method is used to retrieve a key / value pair which comes immediately before the key pointed to by fkey. If fkey points to NULL than the last key / value pair is retrieved. If none is found NULL is returned.

fkey will be updated to point to the key associated to the value returned. It may be used on subsequent calls to gFindPrev.

Example:

See also: AddValue::BTree, FindNext::BTree

SetFunction::BTree [SetFunction]

```
f = gSetFunction(bt, fun);
object bt;
int (*fun)(object, object);
object (*f)();
```

Normally, the BTree class uses the generic function gCompare for all its key comparisons. With gSetFunction you may override this behavior and specify an alternative generic (or regular C) function to call. See Compare::String for details on the semantics of that function.

gSetFunction returns the previous compare function set.

See also: AddValue::BTree, Compare::String

Size::BTree [Size]

```
n = gSize(bt);
object bt;
int n;
```

This method is used to obtain the number of key / value pairs associated with bt.

5.6 BTreeNode Class

This class is used by the ${\tt BTree}$ class to store objects in memory. There are no user methods associated with this class.

5.7 Character Class

The Character class is used to represent the C language char data type as a Dynace object. It is a subclass of the Number class. Even though the Character class implements most of its own functionality, it is documented as part of the Number class because most of the interface is the same for all subclasses of the Number class. Differences are documented in this section.

5.7.1 Character Class Methods

The Character class has only one class method and it is used to create new instances of itself.

NewWithChar::Character [NewWithChar]

```
i = gNewWithChar(Character, c);
int     c;
object i;
```

This class method creates instances of the Character class. c is the initial value of the character being represented. Note that c is of type int. That is because if you pass a character to a generic function (which uses a variable argument declaration) the C language will automatically promote it to an int.

The value returned is a Dynace instance object which represents the character passed.

Note that the default disposal methods are used by this class since there are no special storage allocation requirements.

Example:

5.7.2 Character Instance Methods

The instance methods associated with the Character class provide a means of changing and obtaining the value associated with an instance of the Character class. Most of the Character class instance methods are documented in the Number class because of their common interface with all other subclasses of the Number class. The remainder are documented in this section.

FormatChar::Character [FormatChar]

```
s = gFormatChar(i);
object i;
object s;
```

This method creates an instance of the String class which contains the character represented by i.

Example:

```
object x, y;

x = gNewWithChar(Character, 'a');
y = gFormatChar(x);
/* y is a String object which represents "a" */
```

See also: FormatNumber::Number

5.8 CharacterArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language char data type in an efficient manner. Although this class implements much of its own functionality it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.9 Constant Class

This class is used to represent constants. Constants are objects which can never be destroyed or copied. They always retain their value and when compared, they only equal themselves. An example of a constant would be an object which represents a true or false condition such as T and NIL in lisp.

5.9.1 Constant Class Methods

There are no specific class methods associated with this class. The default instance creation method (New) is used.

5.9.2 Constant Instance Methods

The instance methods associated with this class are used to override certain default methods in order to insure the "constant" status of instances of this class.

```
Copy::Constant
[Copy]
s = gCopy(s)
object s;
```

This method performs no function and returns the value passed. Its only use is to insure that there is only one copy of any particular instances of the Constant class.

This method performs no function and returns the value passed. Its only use is to insure that there is only one copy of any particular instances of the Constant class.

This method performs no function and returns the value passed. Its only use is to insure the undelete-ability of instances of the Constant class.

Dispose::Constant [Dispose]

```
r = gDispose(s)
object s;
object r;
```

This method performs no function and returns the value passed. Its only use is to insure the undelete-ability of instances of the Constant class.

Equal::Constant [Equal]

```
r = gEqual(s, t)
object s;
object t;
int r;
```

This method checks for the equality of two objects (s and t). If they are the same constant a 1 is returned and 0 otherwise.

5.10 Date Class

The Date class is a subclass of the LongInteger class and used to represent dates. The equivalent C language representation would be a long integer in the form YYYYMMDD so July 23, 1993 would be represented as 19930723L.

5.10.1 Date Class Methods

The Date class has only one class method. The New method is inherited from the LongInteger class.

```
CalToJul::Date
    i = gCalToJul(Date, dt);
    long i;
    long dt;
```

This class method returns a julian date calculated from the input calendar date.

Example:

```
long x;
x = gCalToJul(Date, 20000605L); /* x = julian date 730276L */
See also: JulToCal::Date, Julian::Date
```

FixInvalidDate::Date

[FixInvalidDate]

```
i = gFixInvalidDate(Date, mode);
int i;
int mode;
```

This class method sets the method of handling invalid dates. The previous mode is returned.

The list of valid modes is as follows:

- O Does nothing. Leaves the date invalid.
- 1 Changes the date to be the last day of the month.
- 2 Changes the date to be the corresponding day of the next month.

Example:

```
int x;
x = gFixInvalidDate(Date, 1); /* x = the previous mode */
```

```
JulToCal::Date
    i = gJulToCal(Date, jdt);
    long i;
    long jdt;
```

This class method returns a calendar date calculated from the input julian date.

Example:

```
long x;
x = gCalToJul(Date, 730276L);
    /* x = calendar date 20000605L */
```

See also: CalToJul::Date, Julian::Date

Today::Date [Today]

```
i = gToday(Date);
object i;
```

This class method creates instances of the Date class which represents the current date contained within the system.

Example:

```
object x;
x = gToday(Date); /* x = the current date */
```

See also: FormatDate::Date, Dispose::Object

5.10.2 Date Instance Methods

A portion of the Date class's functionality is obtained through its inheritance of the LongInteger class. The remaining functionality is defined by the following specific methods.

AddDays::Date [AddDays] i = gAddDays(i, days);

```
object i; long days;
```

This method is used to add an arbitrary number of days (days) to date i. Leap years and the correct number of days in each month are accounted for. The value returned is the object passed.

Example:

```
object dt;
dt = gNewWithLong(Date, 19940130L);
gAddDays(dt, 2L); /* dt contains 19940201 */
```

See also: AddMonths::Date, AddYears::Date

AddMonths::Date [AddMonths]

```
i = gAddMonths(i, m);
object i;
int m;
```

This method is used to add an arbitrary number of months (m) to date i. The correct number of months in each year is accounted for. The value returned is the object passed.

Example:

```
object dt;
dt = gNewWithLong(Date, 19940104L);
gAddMonths(dt, 2); /* dt contains 19940304 */
```

See also: AddDays::Date, AddYears::Date

AddYears::Date [AddYears]

```
i = gAddYears(i, y);
object i;
int y;
```

This method is used to add an arbitrary number of years (y) to date i. The value returned is the object passed.

Example:

```
object dt;
dt = gNewWithLong(Date, 19940104L);
gAddYears(dt, 2); /* dt contains 19960104 */
See also: AddDays::Date, AddMonths::Date
ChangeDateValue::Date [ChangeDateValue]
    i = gChangeDateValue(i, dt);
    object i;
    long dt;
```

This method is used to change the date associated with an instance of the Date class. Notice that this method returns the instance being passed. dt is the new date.

Example:

```
object x;
x = gNewWithLong(Date, 20000101L);
gChangeLongValue(x, 20000605L);
```

See also: ChangeLongValue::Number

DateValue::Date [DateValue]

```
dt = gDateValue(i);
object i;
long dt;
```

This method is used to obtain the long value that represents the date associated with an instance the Date class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a long.

Example:

```
object x;
long dt;
x = gNewWithLong(LongInteger, 20000605L);
dt = gDateValue(x); /* dt = 20000605L */
```

See also: LongValue::Number

```
DayName::Date [DayName]
```

```
s = gDayName(i);
object i;
object s;
```

This method returns an instance of the String class which represents the day of the week associated with instance i.

Example:

```
object s, dt;
dt = gToday(Date);
s = gDayName(dt); /* s contains "Monday" (or whatever) */
```

See also: FormatDate::Date, MonthName::Date

Difference::Date [Difference]

```
r = gDifference(i, dt);
object i;
object dt;
long r;
```

This method is used to obtain the difference, in days, between two date objects. Leap years and the correct number of days per month is accounted for.

Example:

```
object dt1, dt2;
long r;
dt1 = gNewWithLong(Date, 19940104L);
dt2 = gNewWithLong(Date, 19940204L);
r = gDifference(dt2, dt1); /* r = 31L */
```

%

object jdt;

FormatDate::Date [FormatDate]

```
s = gFormatDate(i, fmt);
object i;
char *fmt;
object s;
```

the % character

This method returns an instance of the String class which is a formatted representation of the date associated with instance i. fmt is the format specification used to determine the resulting String object. Each character in fmt is sequentially processed and except for the character '%', they are simply copied to the resulting String object. Whenever this method encounters the '%' character, the character following is used to determine what aspect and format of the date represented by i should be added to the resultant String object. It works much like the standard C printf. The following table indicates the available formatting option characters:

```
the day of the week (Friday)
          W
          Μ
                  the month name (June)
                   short month name (Feb)
          m
          d
                  day (8)
                   day to two places (08)
          D
                   short year to two places (04)
          У
                  full year (1994)
          Y
          s
                  day suffix (th)
                  month number (6)
          n
          N
                  month number to two places (06)
          t
                   current system time (10:05 AM)
     Example:
          object s, dt;
          dt = gToday(Date);
          s = gFormatDate(dt, "%w the %d%s of %M");
          /* s contains "Monday the 1st of March" (or whatever) */
     See also: MonthName::Date, DayName::Date
Julian::Date
                                                                        [Julian]
          jdt = gJulian(i);
          object i;
```

This method returns a Julian date representation of the date associated with instance i.

Example:

```
object jdt, dt;
dt = gToday(Date);
jdt = gMonthName(dt); /* s contains a Julian Date */
See also: CalToJul::Date, JulToCal::Date
```

MonthName::Date [MonthName]

```
s = gMonthName(i);
object i;
object s;
```

This method returns an instance of the String class which represents the month of the year associated with instance i.

Example:

```
object s, dt;
dt = gToday(Date);
s = gMonthName(dt); /* s contains "June" (or whatever) */
```

StringRepValue::Date [StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

See also: FormatDate::Date, DayName::Date

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
object x;
object s;

x = gNewWithLong(Date, 20000605L);
s = gStringRepValue(x);  /* s represents "6/05/00" */

See also: PrintValue::Object, Print::Object, FormatDate::Date

ValidDate::Date  [ValidDate]

r = gValidDate(i);
object i;
int r;
```

This method is used to determine the validity of a date. If i is a valid date 1 is returned and 0 otherwise. Leap years and the number of days in each month are all accounted for.

Example:

```
object dt;
int r;
dt = gNewWithLong(Date, 19940104L);
r = gValidDate(dt); /* r = 1 */
dt = gNewWithLong(Date, 19941404L);
r = gValidDate(dt); /* r = 0 */
dt = gNewWithLong(Date, 19940230L);
r = gValidDate(dt); /* r = 0 */
```

5.11 DateTime Class

The DateTime class uses multiple inheritance to inherit from both the Date and the Time classes and is used to represent precise moments in time.

5.11.1 DateTime Class Methods

The DateTime class has two class methods to create instances.

NewDateTime::DateTime [NewDateTime]

```
i = gNewDateTime(Time, dt, tm);
long dt, tm;
object i;
```

This class method creates instances of the DateTime class. dt represents the initial date value represented and tm represents the initial time value.

Example:

```
object x;
x = gNewWithLong(DateTime, 19990402L, 132345678L);
/* x = 4/02/1999 1:23:45.678 pm */
```

See also: Now::DateTime, Dispose::Object

Now::DateTime [Now]

```
i = gNow(DateTime);
object i;
```

This class method creates instances of the DateTime class which represents the current time contained within the system.

Example:

```
object x;
x = gNow(DateTime); /* x = the current date and time */
```

See also: NewDateTime::DateTime, Dispose::Object

[AddMilliseconds]

5.11.2 DateTime Instance Methods

A portion of the DateTime class's functionality is obtained through its inheritance of the Date class and of the Time. The remaining functionality is defined by the following specific methods.

AddHours::DateTime [AddHours]

i = gAddHours(i, hours);

object i;
long hours;

This method is used to add an arbitrary number of hours (hours) to date and time i. Adding an hour that goes past midnight will cause the time to cycle around to morning and add a day. Leap years and the correct number of days in each month are accounted for. The value returned is the object passed.

Example:

AddSeconds::DateTime

```
i = gAddMilliseconds(i, m);
object i;
```

AddMilliseconds::DateTime

long

This method is used to add an arbitrary number of milliseconds (m) to date and time i. Adding a millisecond that goes past midnight will cause the time to cycle around to morning and add a day. Leap years and the correct number of days in each month are accounted for. The value returned is the object passed.

```
Example:
```

AddMinutes::DateTime [AddMinutes]

```
i = gAddMinutes(i, m);
object i;
long m;
```

This method is used to add an arbitrary number of minutes (m) to date and time i. Adding a minute that goes past midnight will cause the time to cycle around to morning and add a day. Leap years and the correct number of days in each month are accounted for. The value returned is the object passed.

Example:

This method is used to add an arbitrary number of seconds (s) to date and time i. Adding a second that goes past midnight will cause the time to cycle around to

morning and add a day. Leap years and the correct number of days in each month are accounted for. The value returned is the object passed.

Example:

This method is used to change the date and time values associated with an instance of the DateTime class. Notice that this method returns the instance being passed. dt is the new date value and tm is the new time value and.

Example:

```
object d;
d = gNewDateTime(DateTime, 19990402L, 234500000L);
gChangeDateTimeValues(d, 19981231L, 44500000L);
/* d contains 12/31/1998 4:45:00.000 am */
```

See also: ChangeLongValue::DateTime, NewDateTime::DateTime

```
ChangeLongValue::DateTime
```

[ChangeLongValue]

```
i = gChangeLongValue(i, val);
object i;
long val;
```

This method is used to change the date value associated with an instance of the DateTime class. Notice that this method returns the instance being passed. val is the new date value. The time value associated with the instance of the DateTime class is reset to 0L (midnight).

Example:

```
object d;
d = gNewDateTime(DateTime, 19990402L, 234500000L);
gChangeLongValue(tm, 19991231L);
/* d contains 12/31/1999 12:00:00.000 am */
```

See also: ChangeDateTimeValues::DateTime, NewDateTime::DateTime

Compare::DateTime

[Compare]

```
r = gCompare(i, obj);
object i;
object obj;
int r;
```

This method is used by the generic container classes to determine the relationship of the values represented by i and obj. r is -1 if the date / time represented by i is less than the date / time represented by obj, 1 if the date / time value of i is greater than obj, and 0 if they are equal.

See also: Hash::DateTime

DateTimeDifference::DateTime

[DateTimeDifference]

```
i = gDateTimeDifference(i, d, dd, td);
object i, d;
long *dd, *td;
```

This method is used to obtain the difference, in days and milliseconds, between two time objects. dd is loaded with the difference in days and td is loaded with the difference in milliseconds. Notice that this method returns the instance being passed.

Example:

```
object d1, d2;
long dd, td;
d1 = gNewDateTime(DateTime, 19990402L, 234500000L);
d2 = gNewDateTime(DateTime, 19990403L, 234500111L);
gDateTimeDifference(d2, d1, &dd, &td);
/* dd = 1L, td = 111L */
```

DateTimeValues::DateTime

[DateTimeValues]

```
i = gDateTimeValues(i, dt, tm);
object i;
long *dt, *tm;
```

This method is used to obtain the long values that represent the date and time associated with an instance the DateTime class. Notice that this method returns the instance being passed.

Example:

```
object x;
long dt, tm;
x = gNewDateTime(DateTime, 19990402L, 234500000L);
gDateTimeValues(x, &dt, &tm);
/* dt = 19990402L and tm = 234500000L */
```

See also: NewDateTime::DateTime, ChangeDateTimeValues::Time

FormatDateTime::DateTime

[FormatDateTime]

```
s = gFormatDateTime(i, dtFmt, tmFmt);
object i;
char *dtFmt;
char *tmFmt;
object s;
```

This method returns an instance of the String class which is a formatted representation of the date and time associated with instance i. dtFmt is the format specification (see FormatDate::Date) used to determine the date portion of the resulting String object. tmFmt is the format specification (see FormatTime::Time) used to determine the time portion of the resulting String object.

Example:

```
object s, dt;
dt = gNow(DateTime);
s = gFormatDateTime(dt, "%w the %d%s of %M at ", "%h:%M %p");
/* s = "Monday the 1st of March at 9:45 am" (or whatever) */
```

See also: FormatDate::Date, FormatTime::Time

```
Hash::DateTime [Hash]
```

```
val = gHash(i);
object i;
int val;
```

This method is used by the generic container classes to obtain hash values for the date / time object. val is a hash value between 0 and a large integer value.

See also: Compare::DateTime

StringRepValue::DateTime

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the time associated with i. This is often used to print or display the date and time. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
object x;
object s;

x = gNewDateTime(DateTime, 19991231L, 234500000L);
s = gStringRepValue(x);
/* s represents "1999-12-31 11:45:00.000 pm" */
```

See also: PrintValue::Object, Print::Object

ValidDateTime::DateTime

[ValidDateTime]

```
r = gValidDateTime(i);
object i;
int r;
```

This method is used to determine the validity of a date / time. If i is a valid date / time 1 is returned and 0 otherwise.

Example:

```
object d;
int r;

d = gNewDateTime(DateTime, 19991231L, 234500000L);
r = gValidDateTime(tm);  /* r = 1 */
d = gNewDateTime(DateTime, 19941404L, 234500000L);
r = gValidDateTime(tm);  /* r = 0 */
d = gNewDateTime(DateTime, 19991231L, 254500899L);
r = gValidDateTime(tm);  /* r = 0 */
```

5.12 Dictionary Class

The Dictionary class combines the functionality of the Set and ObjectAssociation classes in order to store a collection of arbitrary key/value pairs. The key may be any unique Dynace object. The gHash and gCompare generics are used in order to access and compare the objects.

This class is a subclass of the Set class and therefore inherits all of its functionality.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.12.1 Dictionary Class Methods

There are no class methods for this class. It inherits the ability to create instances of itself through its superclass, Set.

5.12.2 Dictionary Instance Methods

The instance methods associated with this class are used to add, retrieve and remove key/value pairs from the Dictionary. Note that additional functionality may be obtained through its superclass, Set.

```
AddValue::Dictionary [AddValue]
```

```
r = gAddValue(i, key, value);
object i;
object key
object value; /* or NULL */
object r;
```

This method is used to add a new key/value pair to the Dictionary instance (i). If an object with the same key already exists in the Dictionary it will be left as is and AddValue will return NULL. If the key/value objects are added AddValue will return the ObjectAssociation instance created to represent the key/value pair passed.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

```
See also: Find::Dictionary, FindValue::Dictionary, RemoveObj::Dictionary
```

ChangeValueWithObj::Dictionary

[ChangeValueWithObj]

```
r = gChangeValueWithObj(i, key, value);
object i;
object key;
object value; /* or NULL */
object r;
```

This method is used to change the value associated with an existing key/value pair to the Dictionary instance (i). key represents the identity of the pre-existing key/value pair and value represents the new value to be associated with the key.

Normally, this method changes the value part of the association and returns the previous value which is not disposed. If key doesn't identify a pre-existing association, this method simply returns NULL.

```
See also: Find::Dictionary, FindValue::Dictionary, RemoveObj::Dictionary
```

DeepDisposeObj::Dictionary

[DeepDisposeObj]

```
r = gDeepDisposeObj(i, key);
object i;
object key;
object r;
```

This method is used to remove and dispose of a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The key, value and ObjectAssociation used to bind the two are all deep disposed.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

This method is the same as DisposeObj::Dictionary.

See also: RemoveObj::Dictionary

Dispose::Dictionary

[Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of an entire Dictionary. It does not dispose of any of the keys or values but does dispose of all the associations used to represent the pair.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

```
See also: RemoveObj::Dictionary, DeepDispose::Set, DisposeAllNodes::Dictionary
```

DisposeAllNodes::Dictionary

[DisposeAllNodes]

```
i = gDisposeAllNodes(i);
object i;
```

This method is used to remove all objects in a Dictionary instance without disposing of the instance itself. The objects in the Dictionary are simply disassociated from the Dictionary instance and are not disposed.

The value returned is always the instance passed.

```
See also: DeepDisposeAllNodes::Set, Dispose::Dictionary
```

```
DisposeObj::Dictionary
```

[DisposeObj]

```
r = gDisposeObj(i, key);
object i;
object key;
object r;
```

This method is used to remove and dispose of a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The key, value and ObjectAssociation used to bind the two are all deep disposed.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

This method is the same as DeepDisposeObj::Dictionary.

```
See also: RemoveObj::Dictionary
```

Find::Dictionary [Find]

```
r = gFind(i, key);
object i;
object key;
object r;
```

This method is used to find the instance of the ObjectAssociation class which is used to represent the key/value pair stored under key in Dictionary i. If key is not found NULL is returned.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

See also: FindValue::Dictionary

FindAddValue::Dictionary

[FindAddValue]

```
r = gFindAddValue(i, key, value);
object i;
object key;
object value; /* or NULL */
object r;
```

This method is used to find and return the instance of the ObjectAssociation class used to represent the key/value pair stored under the key key. If it is not found a new ObjectAssociation will be added and returned which represent the key/value pair representing key and value.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

See also: Find::Dictionary, FindValue::Dictionary

FindValue::Dictionary

[FindValue]

```
r = gFindValue(i, key);
object i;
object key;
object r;
```

This method is used to find the value stored under key in Dictionary i. If key is not found NULL is returned.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

See also: Find::Dictionary

```
RemoveObj::Dictionary
```

[RemoveObj]

```
r = gRemoveObj(i, key);
object i;
object key;
object r;
```

This method is used to remove a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The key and value are not disposed, however, the ObjectAssociation used to bind the two is.

key may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Dictionary.

See also: DeepDisposeObj::Dictionary

5.13 DoubleFloat Class

The DoubleFloat class is used to represent the C language double data type as a Dynace object. It is a subclass of the Number class. Even though the DoubleFloat class implements most of its own functionality, it is documented as part of the Number class because most of the interface is the same for all subclasses of the Number class. Differences are documented in this section.

5.13.1 DoubleFloat Class Methods

The DoubleFloat class has only one class method and it is used to create new instances of itself.

NewWithDouble::DoubleFloat [NewWithDouble]

```
i = gNewWithDouble(DoubleFloat, val);
double val;
object i;
```

This class method creates instances of the DoubleFloat class. val is the initial value of the number being represented.

The value returned is a Dynace instance object which represents the number passed.

Note that the default disposal methods are used by this class since there are no special storage allocation requirements.

Example:

```
object pi;
pi = gNewWithDouble(DoubleFloat, 3.14159265358979);
```

See also: DoubleValue::Number, Dispose::Object

5.13.2 DoubleFloat Instance Methods

The instance methods associated with the DoubleFloat class provide a means of changing and obtaining the value associated with an instance of the DoubleFloat class. Most of the DoubleFloat class instance methods are documented in the Number class because of their common interface with all other subclasses of the Number class. The remainder are documented in this section.

Round::DoubleFloat [Round]

```
i = gRound(i, pl);
object i;
int pl;
```

This method is used to round the value represented by i to pl decimal places. The object returned is the rounded object passed.

Example:

```
object pi;
pi = gNewWithDouble(DoubleFloat, 3.14159265358979);
gRound(pi, 4);  /* pi = 3.1416 */
```

See also: DoubleValue::Number, Truncate::DoubleFloat

Truncate::DoubleFloat

[Truncate]

```
i = gTruncate(i, pl);
object i;
int pl;
```

This method is used to truncate the value represented by i to pl decimal places. The object returned is the truncated object passed.

Example:

```
object pi;
pi = gNewWithDouble(DoubleFloat, 3.14159265358979);
gTruncate(pi, 4);  /* pi = 3.1415 */
```

See also: DoubleValue::Number, Round::DoubleFloat

5.14 DoubleFloatArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language double data type in an efficient manner. Although this class implements much of its own functionality it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.15 File Class

This class is used to encapsulate the standard C stream IO facility. It is a subclass of Stream and enables access to these routines through an interface which is common to all subclasses of Stream.

Although this class implements most of its own functionality, it is documented as part of the Stream class because most of the interface is the same for all subclasses of Stream. Differences are documented in this section.

5.15.1 File Class Methods

The class methods associated with this class are methods used to open or create files.

```
Flush::File [Flush]
```

```
i = gFlush(File);
int i;
```

This class method is used to flush all files opened with the stream IO system to disk. It returns the number of opened streams.

Example:

```
gFlush(File);
```

See also: instance Flush::File

```
OpenFile::File [OpenFile]
```

```
i = gOpenFile(File, name, mode);
char *name; /* file name */
char *mode; /* file mode */
object i;
```

This class method is used to open or create a normal file using the C stream IO facility. The name and mode parameters correspond to the local C library function fopen. The local library manuals can more completely describe those arguments. The value returned is an object which refers to the opened file. If the file cannot be opened a NULL will be returned.

Example:

```
object f;
f = gOpenFile(File, "myfile", "r");
```

See also: OpenTempFile::File, Dispose::File, Read::Stream

```
OpenTempFile::File
```

[OpenTempFile]

```
i = gOpenTempFile(File);
object i;
```

This class method is used to create a tempoary file using the C stream IO facility. The location of the file will be dictated by the TMP or TEMP environment variables (in that order). If those variables are not defined then the current directory is used. The file is created with the "w+" binary mode.

The value returned is an object which refers to the opened file. Since this is a temporary file, disposing of this object will also cause the file to be removed. If the file cannot be opened a NULL will be returned.

Example:

This class method is used to specify a path for the system to use to create temporary files (using gOpenTempFile. The given directory is appended to the normal system temp path. For example, if the system path is '/tmp' and dir is passed "App" then the path used will be '/tmp/App'.

The value returned is File.

Example:

```
gSetTempSubDir(File, "Application");
```

See also: OpenTempFile::File

5.15.2 File Instance Methods

The instance methods associated with this class are used to read and write data to the file represented by the instance.

Although this class implements most of its own functionality, it is documented as part of the Stream class because most of the interface is the same for all subclasses of Stream. Differences are documented in this section.

```
DeepDispose::File [DeepDispose]
```

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to close the file associated with the instance and dispose of the instance. It performs the same function as Dispose::File.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::File, OpenFile::File

```
Dispose::File [Dispose]
```

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to close the file associated with the instance and dispose of the instance. It performs the same function as DeepDispose::File.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::File, OpenFile::File

```
Flush::File [Flush]
```

```
i = gFlush(file);
object file;
int i;
```

This method is used to flush the stream associated with file to disk. It returns zero on success.

```
Example:
```

```
gFlush(file);
```

See also: class Flush::File

Name::File [Name]

```
n = gName(i);
object i;
char *n; /* the file name */
```

This method is used to obtain the name of the file represented by i.

PointerValue::File

[PointerValue]

```
fp = gPointerValue(i);
object i;
FILE *fp;
```

This method is used to obtain the file pointer associated with \mathtt{i} .

5.16 FindFile Class

The FindFile class is designed to provide a portable means of enumerating over the file names contained within a particular file system directory. Currently, this class has only been ported to the DOS and all Windows environments. There is no current support for Unix or Macintosh environments.

5.16.1 FindFile Class Methods

The only class method used in this class is one to create instances of itself.

NewFindFile [NewFindFile]

```
i = gNewFindFile(FindFile, name, attr);
char *name;
int attr;
object i;
```

This class method creates instances of the FindFile class. Each such instance is initialized to enable the instance to enumerate through all the file names which meet a particular set of parameters.

The name parameter is used to specify the pattern of the file name to be searched for. This pattern may or may not contain a relative or absolute directory path but *must* contain some wildcard characters (such as "?" and "*").

The attr parameter is used to narrow the search to file names which contain certain attributes. The list of available attribute type (which should be or'ed together) is as follows:

FF_FILE FF_DIRECTORY	include regular files include directories
FF_READWRITE	include files or directories in which you have read/write permission
FF_READONLY	include files or directories in which you only have read permission
FF_ARCHIVE_ONLY	don't include files/directories which don't have their archive bit set
FF_HIDDEN	include hidden files
FF_SYSTEM	include system files

The new instance is returned.

```
Example:
    object ff;
    char *file;

ff = gNewFindFile(FindFile, "*.c", FF_FILE | FF_READWRITE);
    while (file = gNextFile(ff)) {
         do something with file
    }
    gDispose(ff);
```

5.16.2 FindFile Instance Methods

See also: NextFile::FindFile

The instance methods associated with this class provide a means for sequentially enumerating through the selected file names and obtaining some degree of information associated with each particular file.

Attributes::FindFile [Attributes]

```
attr = gAttributes(ff);
object     ff;
unsigned     attr;
```

WriteTime::FindFile

This method is used to obtain attribute information relating to the last selected file returned from NextFile. The attribute flags are those defined under NewFindFile. If no valid file has been returned from NextFile this function simply returns 0.

Example:

```
object
               ff;
     char
              *file;
     unsigned attr;
     ff = gNewFindFile(FindFile, "*.*",
                       FF_FILE | FF_DIRECTORY | FF_READWRITE);
     while (file = gNextFile(ff)) {
             attr = gAttributes(ff);
             if (attr & FF_DIRECTORY)
                     handle a directory
             else if (attr & FF_FILE)
                     handle a file
     }
     gDispose(ff);
See also: NewFindFile::FindFile, NextFile::FindFile,
```

```
Length::FindFile [Length]
```

```
len = gLength(ff);
object ff;
long len;
```

This method is used to obtain the length or size (in bytes) of the file relating to the last selected file returned from NextFile. If no valid file has been returned from NextFile this function simply returns -1.

Example:

```
object ff;
char *file;
long len;

ff = gNewFindFile(FindFile, "*.c", FF_FILE | FF_READWRITE);
while (file = gNextFile(ff)) {
        len = gLength(ff);
}
gDispose(ff);
```

See also: Attributes::FindFile, NextFile::FindFile

Name::FindFile [Name]

```
nam = gName(ff);
object ff;
char *nam;
```

This method is used to obtain the name of the last file found via NextFile. It will be the same name as returned from NextFile. If no valid file has been returned from NextFile this function simply returns NULL.

Example:

```
object ff;
char *file;

ff = gNewFindFile(FindFile, "*.c", FF_FILE | FF_READWRITE);
while (gNextFile(ff)) {
     file = gName(ff);
}
gDispose(ff);
```

See also: NextFile::FindFile

NextFile::FindFile [NextFile]

```
nam = gNextFile(ff);
object ff;
char *nam;
```

This method is used to obtain the next file name in the sequential list specified when using NewFindFile. It also changes the context associated with the object ff such that all other methods operated on ff will refer to the file returned in the last call to this method. In spite of the name of this method, it is also used to obtain the first file name in the list, therefore, this method must be called prior to any other method on ff in order to obtain the first file context.

This method returns the name of the file associated with the file context this method establishes. If there is no first file or additional files this method returns NULL.

See also: NewFindFirst::FindFile

WriteTime::FindFile [WriteTime]

```
tim = gWriteTime(ff);
object ff;
long tim;
```

This method is used to obtain the date and time the file associated with the ff context was last written to. The value returned can be typecast to the common time_t type and represents the number of seconds past some date like 1970. If no valid file context was setup via NextFile, this method returns -1.

See also: Attributes::FindFile, NextFile::FindFile

5.17 FloatArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language float data type in an efficient manner. Although this class implements much of its own functionality it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.18 IntegerArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language int data type in an efficient manner. Although this class implements much of its own functionality it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.19 IntegerAssociation Class

This class is a subclass of Association and is used to represent an association between a C language int and an arbitrary Dynace object. It performs all the functions as the LookupKey and ObjectAssociation classes and is used in conjunction with the Set and Dictionary classes. The purpose of this class is to provide an efficient mechanism to form a common association.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.19.1 IntegerAssociation Class Methods

The only class method associated with this class is one needed to create new instances of itself.

NewWithIntObj::IntegerAssociation [NewWithIntObj]

```
i = gNewWithIntObj(IntegerAssociation, key, val);
int     key;
object val; /* or NULL */
object i;
```

This class method creates instances of the IntegerAssociation class. key is used to initialize the key associated with the instance created and val is used to initialize its associated value.

The new instance is returned.

5.19.2 IntegerAssociation Instance Methods

The instance methods associated with this class are used to obtain, change and print the key and value associated with the instance. Additional functionality, although implemented by this class, is documented in IntegerAssociation's superclass, Association. This is done because of the common interface these methods share with all subclasses of Association.

ChangeIntKey::IntegerAssociation

[ChangeIntKey]

```
i = gChangeIntKey(i, key);
object i;
int key;
```

This method is used to change the key associated with instance i. key is the new key. The old key is simply replaced. This method returns i.

See also: IntKey::IntegerAssociation, ChangeValue::IntegerAssociation ChangeValue::IntegerAssociation

[ChangeValue]

```
old = gChangeValue(i, val);
object i;
object val; /* or NULL */
object old;
```

This method is used to change the value associated with i to a value, val. The old value is simply no longer associated with the instance. It is not disposed. This method returns the old value being replaced.

See also: Value::IntegerAssociation, ChangeIntKey::IntegerAssociation

DeepCopy::IntegerAssociation

[DeepCopy]

```
c = gDeepCopy(i);
object i, c;
```

This method is used to create a new instance of the IntegerAssociation class which contains a *copy* of the value from the original IntegerAssociation. DeepCopy is used to create the copy of the value. The new IntegerAssociation instance is returned.

See also: Copy::Object

DeepDispose::IntegerAssociation

[DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of a IntegerAssociation instance. It also disposes of the value associated with the instance by the use of its DeepDispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::Object

```
IntKey::IntegerAssociation
```

[IntKey]

```
key = gIntKey(i);
object i;
int key;
```

This method is used to obtain the integer key associated with instance i.

See also: ChangeIntKey::IntegerAssociation

StringRepValue::IntegerAssociation

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

Value::IntegerAssociation

[Value]

```
val = gValue(i);
object i;
object val;
```

This method is used to obtain the value associated with i.

See also: ChangeValue::IntegerAssociation, IntKey::IntegerAssociation

5.20 IntegerDictionary Class

This class combines the functionality of the Set and IntegerAssociation classes in order to store a collection of arbitrary key/value pairs.

The difference between this class and the Dictionary class is that this class only accepts C language int values as keys. This class provides an efficient and simple to use means of representing a commonly needed collection.

This class is a subclass of the Set class and therefore inherits all of its functionality.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.20.1 IntegerDictionary Class Methods

There are no class methods for this class. It inherits the ability to create instances of itself through its superclass, Set.

5.20.2 IntegerDictionary Instance Methods

The instance methods associated with this class are used to add, retrieve and remove key/value pairs from the Dictionary. Note that additional functionality may be obtained through its superclass, Set.

```
AddInt::IntegerDictionary [AddInt]
r = gAddInt(i, key, value);
```

```
object i;
int key
object value;
object r;
```

This method is used to add a new key/value pair to the Dictionary instance (i). If an object with the same key already exists in the Dictionary it will be left as is and AddInt will return NULL. If the key/value objects are added AddInt will return the IntegerAssociation instance created to represent the key/value pair passed.

```
ChangeValueWithInt::IntegerDictionary
```

[ChangeValueWithInt]

```
r = gChangeValueWithInt(i, key, value);
object i;
int key
object value;
object r;
```

This method is used to change the value associated with an existing key/value pair to the IntegerDictionary instance (i). key represents the identity of the pre-existing key/value pair and value represents the new value to be associated with the key.

Normally, this method changes the value part of the association and returns the previous value which is not disposed. If key doesn't identify a pre-existing association, this method simply returns NULL.

DeepDisposeInt::IntegerDictionary

[DeepDisposeInt]

```
r = gDeepDisposeInt(i, key);
object i;
int key;
object r;
```

This method is used to remove and dispose of a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The value and IntegerAssociation used to bind the two are all deep disposed.

This method is the same as DisposeInt::IntegerDictionary.

See also: RemoveInt::IntegerDictionary

```
Dispose::IntegerDictionary
```

[Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of an entire Dictionary. It does not dispose of any of the values but does dispose of all the associations used to represent the pair.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

```
See also: RemoveInt::IntegerDictionary, DeepDispose::Set, DisposeAllNodes::IntegerDictionary
```

DisposeAllNodes::IntegerDictionary

[DisposeAllNodes]

```
i = gDisposeAllNodes(i);
object i;
```

This method is used to remove all objects in an IntegerDictionary instance without disposing of the instance itself. The objects in the IntegerDictionary are simply disassociated from the IntegerDictionary instance and are not disposed.

The value returned is always the instance passed.

```
See also: DeepDisposeAllNodes::Set, Dispose::IntegerDictionary
```

```
DisposeInt::IntegerDictionary
```

[DisposeInt]

```
r = gDisposeInt(i, key);
object i;
int key;
object r;
```

This method is used to remove and dispose of a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The value and IntegerAssociation used to bind the two are all deep disposed.

This method is the same as DeepDisposeInt::IntegerDictionary.

See also: RemoveInt::IntegerDictionary

```
FindInt::IntegerDictionary
```

[FindInt]

```
r = gFindInt(i, key);
object i;
int key;
object r;
```

This method is used to find the instance of the IntegerAssociation class which is used to represent the key/value pair stored under key in Dictionary i. If key is not found NULL is returned.

See also: FindValueInt::IntegerDictionary

```
FindAddInt::IntegerDictionary
```

[FindAddInt]

```
r = gFindAddInt(i, key, value);
object i;
int key;
object value;
object r;
```

This method is used to find and return the instance of the IntegerAssociation class used to represent the key/value pair stored under the key key. If it is not found a new IntegerAssociation will be added and returned which represent the key/value pair representing key and value.

```
See also: FindInt::IntegerDictionary, FindValueInt::IntegerDictionary
```

```
FindValueInt::IntegerDictionary
```

[FindValueInt]

```
r = gFindValueInt(i, key);
object i;
int key;
object r;
```

This method is used to find the value stored under key in Dictionary i. If key is not found NULL is returned.

```
See also: FindInt::IntegerDictionary
```

```
RemoveInt::IntegerDictionary
```

[RemoveInt]

```
r = gRemoveInt(i, key);
object i;
int key;
object r;
```

This method is used to remove a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The value is not disposed, however, the IntegerAssociation used to bind the two is.

 $See \ also: \ {\tt DeepDisposeInt::IntegerDictionary}$

5.21 Link Class

The Link class is used to represent a single link in a doubly linked list. It is normally used in conjunction with the LinkList class in order to manage arbitrary objects on a doubly linked list data structure.

Since instances of the Link class only contain enough information to describe the link, the Link class can be thought of as an abstract class. It is never used by itself (instances of it are never created). Instead a new class would be created which would have the Link class as a superclass. This new class would describe the data items which would be stored at each link. The Link class would keep track of its place in the linked list.

The Link class also has a subclass called LinkValue which allows a single arbitrary object to be stored at each link.

See the examples included with the Dynace system for an illustration of the use of the doubly linked list related classes.

5.21.1 Link Class Methods

The Link class has only a single class method. That method is used to create and initialize new instances of itself.

New::Link

```
i = gNew(Link);
object i;
```

This class method creates instances of the Link class. It is usually only used by subclasses of the Link class. The new link will not point to anything. It will just be an empty link.

This method is actually just inherited from Object in order to create a null link.

The value returned is the instance object created (the new link).

See also: Dispose::Link

5.21.2 Link Instance Methods

The instances methods associated with the Link class are used to link, unlink, move and dispose of particular instances of the Link class or (more often) one of its subclasses.

AddAfter::Link [AddAfter]

```
i = gAddAfter(i, lnk);
object i;
object lnk;
```

This method is used to insert a new link (lnk) after another link (i) on the linked list which link i is on. In order to accomplish this it modifies pointers in link i, link lnk and the link (if any) which is after link i in the associated linked list structure.

Link lnk must not already be a member of another list.

This method returns its first argument.

See also: AddBefore::Link

AddBefore::Link [AddBefore]

```
i = gAddBefore(i, lnk);
object i;
object lnk;
```

This method is used to insert a new link (lnk) before another link (i) on the linked list which link i is on. In order to accomplish this it modifies pointers in link i, link lnk and the link (if any) which is prior to link i in the associated linked list structure.

Link lnk must not already be a member of another list.

This method returns its first argument.

```
See also: AddAfter::Link, ChangeNext::Link, ChangePrevious::Link
```

ChangeNext::Link [ChangeNext]

```
i = gChangeNext(i, nxt);
object i;
object nxt;
```

This method is used to change the next pointer of a particular link represented by instance i. nxt is the link to be pointed to or NULL. This method does not effect the instance pointed to by nxt.

This method returns the link passed in its first argument.

```
See also: ChangePrevious::Link, Next::Link
```

```
ChangePrevious::Link
```

[ChangePrevious]

```
i = gChangePrevious(i, prev);
object i;
object prev;
```

This method is used to change the previous link pointer of a particular link represented by instance i. prev is the link to be pointed to or NULL. This method does not effect the instance pointed to by prev.

This method returns the link passed in its first argument.

See also: ChangeNext::Link, Previous::Link

Copy::Link [Copy]

```
c = gCopy(i);
object i, c;
```

This method is used to create a new object which is of the same type as its argument. However, the new link will not point to the same links. It will be uninitialized.

The new object is returned.

See also: DeepCopy::Link, Copy::Object

DeepCopy::Link [DeepCopy]

This method performs the same function as Copy::Link.

DeepDispose::Link [DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to unlink and dispose of a link object. It performs the same function as the Dispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::Link, Remove::Link

Dispose::Link [Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to unlink and dispose of a link object. It performs the same function as the DeepDispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::Link, Remove::Link

InitLink::Link [InitLink]

```
lnk = gInitLink(lnk, lst, prev, nxt);
object lnk;
object lst;
object prev;
object nxt;
```

This method is used to initialize a link. 1st is the list it will be associated with and prev and nxt are used to initialize the link pointers. Each argument must either be a link or NULL.

The link passed is returned.

See also: Previous::Link, Next::Link

List::Link [List]

```
lst = gList(i);
object i;
object lst;
```

This method is used to obtain the list object which link i is on. NULL will be returned if the link is not on a list.

See also: Previous::Link, Next::Link, InitLink::Link

MoveAfter::Link [MoveAfter]

```
i = gMoveAfter(i, lnk);
object i;
object lnk;
```

This method is used to unlink an arbitrary (located anywhere on the list) link (i) from any list and relink it immediately after link lnk which may be on the same or a different list. If link i wasn't originally on a list, it will simply be added after link lnk.

Link i is returned.

See also: MoveBefore::Link, MoveBeginning::Link

MoveBefore::Link [MoveBefore]

```
i = gMoveBefore(i, lnk);
object i;
object lnk;
```

This method is used to unlink an arbitrary (located anywhere on the list) link (i) from any list and relink it immediately before link lnk which may be on the same or a different list. If link i wasn't originally on a list, it will simply be added before link lnk.

Link i is returned.

See also: MoveAfter::Link, MoveEnd::Link

MoveBeginning::Link

[MoveBeginning]

```
i = gMoveBeginning(i);
object i;
```

This method is used to unlink an arbitrary (located anywhere on the list) link and relink it at the beginning of the linked list it's associated with.

The object passed is returned unless the link was not on a list. In that case NULL will be returned.

See also: MoveEnd::Link, MoveAfter::Link

MoveEnd::Link [MoveEnd]

```
i = gMoveEnd(i);
object i;
```

This method is used to unlink an arbitrary (located anywhere on the list) link and relink it at the end of the linked list it's associated with.

The object passed is returned unless the link was not on a list. In that case NULL will be returned.

See also: MoveBeginning::Link, MoveBefore::Link

Next::Link [Next]

```
nxt = gNext(i);
object i;
object nxt;
```

This method is used to obtain the link following the link represented by i. If no next link exists, NULL will be returned.

See also: Previous::Link, Nth::Link, List::Link

Nth::Link [Nth]

```
nxt = gNth(lnk, idx);
object lnk;
int idx;
object nxt;
```

This method is used to provide a mechanism to index into a linked list in a manner similar to an array. If idx is positive this method returns the link which is idx links after lnk. If idx is negative this method returns the link which is idx links prior to lnk. If idx is zero lnk is returned, and if idx represents a position beyond the end of the list NULL is returned.

See also: Previous::Link, Next::Link, List::Link

```
Previous::Link [Previous]
```

```
prev = gPrevious(i);
object i;
object prev;
```

This method is used to obtain the link prior to the link represented by i. If no such link exists, NULL will be returned.

```
See also: Next::Link, Nth::Link, List::Link
```

Remove::Link [Remove]

```
i = gRemove(i);
object i;
```

This method is used to remove a link (i) from a linked list. In addition to effecting link i, it also effects the pointers associated with the links which link i points to in its next and previous pointers (which may be NULL) to make the removal complete.

This method should have no effect on a link which is not on a list.

This method returns the link passed.

```
See also: ChangeNext::Link, ChangePrevious::Link
```

StringRep::Link [StringRep]

```
s = gStringRep(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the object i and its value. This is often used to print or display a representation of an object. It is also used by Print::Object (a method useful during the debugging phase of a project) in order to directly print an object to a stream.

```
See also: Print::Object, PrintValue::Object, StringRepValue::Link
```

StringRepValue::Link

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
object x;
object s;
x = gNew(Link);
s = gStringRepValue(x);
```

See also: PrintValue::Object, Print::Object

5.22 LinkList Class

Instances of this class are used to coordinate and handle doubly linked lists as a whole. It is used with instances of the Link class (or one of its subclasses) which represent the individual links of the list.

The Link class is a superclass of this class. See that class for functionality which is inherited by this class.

See the examples included with the Dynace system for an illustration of the use of the doubly linked list related classes.

5.22.1 LinkList Class Methods

There is only one class method associated with this class and it is used to create new instances of the class.

New::LinkList [New]

```
i = gNew(LinkList);
object i;
```

This class method creates a new and empty linked list object.

The value returned is the instance object created (the new LinkList).

See also: Dispose::LinkList

5.22.2 LinkList Instance Methods

The instance methods associated with this class perform functions to add, change, inquire, enumerate and dispose of links associated with the linked list. They also provide information such as how many links are on the list.

AddFirst::LinkList [AddFirst]

```
i = gAddFirst(i, lnk);
object i;
object lnk;
```

This method is used to add a new link to the beginning of the linked list. i is the linked list, lnk is the new link (an instance of the Link class or one of its subclasses).

The value returned is the linked list passed (i).

See also: AddLast::LinkList, DisposeFirst::LinkList

AddLast::LinkList [AddLast]

```
i = gAddLast(i, lnk);
object i;
object lnk;
```

This method is used to add a new link to the end of the linked list. i is the linked list, lnk is the new link (an instance of the Link class or one of its subclasses).

The value returned is the linked list passed (i).

See also: AddFirst::LinkList, DisposeLast::LinkList

Copy::LinkList [Copy]

```
c = gCopy(i);
object i, c;
```

This method is used to create a new instance of the LinkList class with copies of all the links which were on i. These copies are made via Copy so any values associated with the link are the same objects as those on i.

The new LinkList instance is returned.

See also: DeepCopy::LinkList, Copy::Object

DeepCopy::LinkList [DeepCopy]

```
c = gDeepCopy(i);
object i, c;
```

This method is used to create a new instance of the LinkList class with copies of all the links and their associated values which were on i. These copies are made via DeepCopy so the values associated with the links are also copied.

The new LinkList instance is returned.

See also: Copy::LinkList, Copy::Object

DeepDispose::LinkList [DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of the linked list and all its associated links. The DeepDispose method is used to dispose of each link on the linked list.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::LinkList, Dispose::Object

DeepDisposeAllNodes::LinkList

[DeepDisposeAllNodes]

```
i = gDeepDisposeAllNodes(i);
object i;
```

This method is used to dispose of all the links on a linked list without disposing of the linked list object itself. The DeepDispose method is used to dispose of the links so all the objects contained on the links will be deep disposed as well.

This method returns the object passed.

See also: DeepDispose::LinkList, DisposeAllNodes::LinkList

DeepDisposeFirst::LinkList

[DeepDisposeFirst]

```
i = gDeepDisposeFirst(i);
object i;
```

This method is used to unlink and dispose of the first link in the linked list i. If there is no first link this method simply returns.

The first link is disposed of by executing the DeepDispose method on it.

This method returns the linked list passed.

See also: DeepDisposeLast::LinkList, DisposeFirst::LinkList

DeepDisposeLast::LinkList

[DeepDisposeLast]

```
i = gDeepDisposeLast(i);
object i;
```

This method is used to unlink and dispose of the last link in the linked list i. If there are no links this method simply returns.

The last link is disposed of by executing the DeepDispose method on it.

This method returns the linked list passed.

See also: DeepDisposeFirst::LinkList, DisposeLast::LinkList

Dispose::LinkList

[Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of the linked list and all its associated links. The Dispose method is used to dispose of the links without disposing of the objects contained on the links.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::LinkList, DisposeAllNodes::LinkList

DisposeAllNodes::LinkList

[DisposeAllNodes]

```
i = gDisposeAllNodes(i);
object i;
```

This method is used to dispose of all the links on a linked list without disposing of the linked list object itself. The Dispose method is used to dispose of the links without disposing of the objects contained on the links.

This method returns the object passed.

See also: Dispose::LinkList, DeepDisposeAllNodes::LinkList

```
DisposeFirst::LinkList [DisposeFirst]
```

```
i = gDisposeFirst(i);
object i;
```

This method is used to unlink and dispose of the first link in the linked list i. If there is no first link this method simply returns.

The first link is disposed of by executing the Dispose method on it.

This method returns the linked list passed.

```
See also: DisposeLast::LinkList, DeepDispose::LinkList, RemoveFirst::LinkList
```

```
DisposeLast::LinkList [DisposeLast]
```

```
i = gDisposeLast(i);
object i;
```

This method is used to unlink and dispose of the last link in the linked list i. If there are no links this method simply returns.

The last link is disposed of by executing the Dispose method on it.

This method returns the linked list passed.

```
See also: DisposeFirst::LinkList, DeepDispose::LinkList, RemoveLast::LinkList
```

First::LinkList [First]

```
lnk = gFirst(i);
object i;
object lnk;
```

This method is used to obtain the first link on linked list i. If there are no links, this method returns NULL.

This method does not modify the linked list or the link returned.

```
See also: Last::LinkList, RemoveFirst::LinkList
```

IncNelm::LinkList [IncNelm]

```
i = gIncNelm(i, inc);
object i;
int lnc;
```

Each linked list automatically keeps track of the number of links on it. This method is used to change that value by inc. It is mainly used internally to keep the number accurate and would not normally be used externally.

Last::LinkList [Last]

```
lnk = gLast(i);
object i;
object lnk;
```

This method is used to obtain the last link on linked list i. If there are no links, this method returns NULL.

This method does not modify the linked list or the link returned.

See also: First::LinkList, RemoveLast::LinkList

Remove::LinkList [Remove]

This method has been superseded by Remove::Link.

See also: Dispose::Link, RemoveFirst::LinkList

RemoveFirst::LinkList [RemoveFirst]

```
lnk = gRemoveFirst(i);
object i;
object lnk;
```

This method is used to unlink the first link from the linked list i and return it. The link will no longer be linked on the list. However, the link is not disposed. If there are no links this method simply returns NULL.

This method returns the link removed.

See also: RemoveLast::LinkList, DisposeFirst::LinkList

```
RemoveLast::LinkList
```

```
lnk = gRemoveLast(i);
object i;
object lnk;
```

This method is used to unlink the last link from the linked list i and return it. The link will no longer be linked on the list. However, the link is not disposed. If there are no links this method simply returns NULL.

[RemoveLast]

This method returns the link removed.

See also: RemoveFirst::LinkList, DisposeLast::LinkList

Sequence::LinkList [Sequence]

```
s = gSequence(i);
object i;
object s;
```

This method takes an instance of the LinkList class (i) and returns an instance of the LinkSequence class (s). The link list represented by i is not effected by this operation. The link sequence item, s, is used to enumerate through all the links in link list i. See the LinkSequence class for documentation of other methods needed to use s.

Example:

See also: Next::LinkSequence

Size::LinkList [Size]

```
sz = gSize(i);
object i;
int sz;
```

This method is used to obtain the number of links on the linked list.

```
StringRep::LinkList [StringRep]
```

```
s = gStringRep(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the object i and its value. This is often used to print or display a representation of an object. It is also used by Print::Object (a method useful during the debugging phase of a project) in order to directly print an object to a stream.

This method obtains the values of each link by calling StringRepValue on each link.

See also: Print::Object, PrintValue::Object

5.23 LinkObject Class

The LinkObject class is a subclass of the LinkList class. Since this class inherits much of its functionality from the LinkList and Link classes, see those classes for additional functionality. It is used in conjunction with the LinkValue class in order to manage arbitrary objects on a doubly linked list data structure.

The difference between this class and the LinkList class is that the LinkList class deals with instances of the Link class (or one of its subclasses) which may contain arbitrary objects and the LinkObject class deals with arbitrary objects directly. There is no need to deal with link objects at all. While this simplifies the usage of a linked lists quite a bit it comes at the expense of flexibility. However, since the LinkList class is a superclass of the LinkObject class you can often use the inherited functionality of the LinkList class in conjunction with the LinkObject object. It is, therefore, recommended that the LinkObject class be used whenever possible to simplify linked list operations

This class (LinkObject) inherits much of its functionality from its superclass (LinkList), therefore, in addition to the specific documentation on this class please also refer to the documentation of its superclass.

See the examples included with the Dynace system for an illustration of the use of the doubly linked list related classes.

5.23.1 LinkObject Class Methods

The LinkObject class has no specific class methods. It inherits all of its abilities from its superclass, LinkList.

5.23.2 LinkObject Instance Methods

The instance methods associated with this class perform functions to add, inquire and enumerate objects associated with the linked list. Since this class is a subclass of the LinkList class, additional functionality is inherited from it. The LinkList class documentation should, therefore, be consulted.

```
AddFirst::LinkObject
    i = gAddFirst(i, obj);
    object i;
    object obj;
```

This method is used to add a new link to the beginning of the list, i, containing the arbitrary object obj. The list object, i, is returned.

Example:

```
object ll, obj;
ll = gNew(LinkObject);
obj = gNewWithInt(ShortInteger, 44);
gAddFirst(ll, obj);
```

See also: AddLast::LinkObject, First::LinkObject

AddLast::LinkObject

[AddLast]

```
i = gAddLast(i, obj);
object i;
object obj;
```

This method is used to add a new link to the end of the list, i, containing the arbitrary object obj. The list object, i, is returned.

Example:

```
object ll, obj;
ll = gNew(LinkObject);
obj = gNewWithInt(ShortInteger, 44);
gAddLast(ll, obj);
```

See also: AddFirst::LinkObject, Last::LinkObject

First::LinkObject

[First]

```
obj = gFirst(i);
object i;
object obj;
```

This method is used to obtain the object stored in the first link of the list i. If there are no links on the list this method will return NULL. The list, i, is not effected by this operation.

Example:

```
object 11, obj, obj2;

11 = gNew(LinkObject);
obj = gNewWithInt(ShortInteger, 44);
gAddFirst(11, obj);
obj2 = gFirst(11);
/* obj and obj2 are the same object */

See also: AddFirst::LinkObject, Last::LinkObject

GetValues::LinkObject
[GetValues]
```

```
11 = vGetValues(11, ...);
object 11;
```

This method is used to extract numerous values from a LinkObject instance. It does this without modifing the list. Each argument must be a pointer to a variable which is to hold one of the values. The first variable gets the first object on the list and the second gets the second, etc. The argument list must end in NULL to signify the end.

If there are more variables than links on the list the remaining variables will be set to NULL. If there are more elements on the list than variables the remiaining list elements are ignored.

The LinkObject instance passed is returned unaltered.

Example:

```
object 11, obj1, obj2;
object obj3, obj4;

obj1 = gNewWithInt(ShortInteger, 44);
obj2 = gNewWithInt(ShortInteger, 66);
11 = vMakeList(LinkObject, obj1, obj2, NULL);
vGetValues(11, &obj3, &obj4, NULL);
```

See also: MakeList::LinkObject, Nth::LinkObject

```
Last::LinkObject [Last]
```

```
obj = gLast(i);
object i;
object obj;
```

This method is used to obtain the object stored in the last link of the list i. If there are no links on the list this method will return NULL. The list, i, is not effected by this operation.

Example:

```
object 11, obj, obj2;

11 = gNew(LinkObject);
obj = gNewWithInt(ShortInteger, 44);
gAddLast(11, obj);
obj2 = gLast(11);
/* obj and obj2 are the same object */
```

See also: AddLast::LinkObject, First::LinkObject

MakeList::LinkObject

[MakeList]

```
obj = vMakeList(LinkObject, ...);
object obj;
```

This method is used to create a new LinkObject containing all the objects listed in the method call. For example, if there are five objects listed, the returned LinkObject will be a list containing five links, each with an object associated with it.

Since this is a variable argument method you must tell the system when there are no more arguments by using a last argument of NULL. GetValues can be used to take the list back apart. All the other LinkObject methods may be used as well. The value returned is the new LinkObject instance.

Example:

```
object ll, obj1, obj2;
obj1 = gNewWithInt(ShortInteger, 44);
obj2 = gNewWithInt(ShortInteger, 66);
ll = vMakeList(LinkObject, obj1, obj2, NULL);
```

See also: GetValues::LinkObject

Nth::LinkObject

[Nth]

```
See [Nth::Link], page 231,
```

```
Pop::LinkObject [Pop]
```

```
obj = gPop(lst);
object lst;
object obj;
```

This method is used to obtain the first element of a list while removing it from the list at the same time. It works in conjunction with gPush to utilize a list as a stack. obj is either the first object on the list or NULL if the list was empty.

Example:

```
object 11, obj, obj2;

11 = gNew(LinkObject);
obj = gNewWithInt(ShortInteger, 44);
gPush(11, obj);
obj2 = gPop(11);
```

See also: Push::LinkObject

Push::LinkObject [Push]

```
lst = gPush(lst, obj);
object lst;
object obj;
```

This method is used to utilize a linklist as a stack. Pushing is the same as adding a new link to the beginning of the list. Object obj is added (pushed) on list 1st. The list object, 1st, is returned. This method is the same as gAddFirst.

Example:

```
object ll, obj;
ll = gNew(LinkObject);
obj = gNewWithInt(ShortInteger, 44);
gPush(ll, obj);
```

See also: Pop::LinkObject

Sequence::LinkObject [Sequence]

```
s = gSequence(i);
object i;
object s;
```

This method takes an instance of the LinkObject class (i) and returns an instance of the LinkObjectSequence class (s). The link list represented by i is not effected by this operation. The link sequence item, s, is used to enumerate through all the objects in link list i. See the LinkObjectSequence class for documentation of other methods needed to use s.

The difference between the Sequence and SequenceLinks methods in this class is that the Sequence method provides a means to enumerate over the objects in the linked list and the SequenceLinks provides a means to enumerate over the links which hold the objects in the list.

Example:

See also: Next::LinkObjectSequence, SequenceLinks::LinkObject

SequenceLinks::LinkObject

[SequenceLinks]

```
s = gSequenceLinks(i);
object i;
object s;
```

This method takes an instance of the LinkObject class (i) and returns an instance of the LinkSequence class (s). The link list represented by i is not effected by this operation. The link sequence item, s, is used to enumerate through all the links in link list i. See the LinkSequence class for documentation of other methods needed to use s.

The difference between the Sequence and SequenceLinks methods in this class is that the Sequence method provides a means to enumerate over the objects in the linked

list and the SequenceLinks provides a means to enumerate over the links which hold the objects in the list.

Example:

See also: Next::LinkSequence, Sequence::LinkObject

5.24 LinkObjectSequence Class

This class is a subclass of Sequence and is used to provide a mechanism to enumerate through all the objects on the links in a linked list structure without effecting the structure.

The linked list structure is usually represented by instances of the LinkObject class. Typically, the Sequence instance method of this class is used to create the instances of the LinkObjectSequence class.

5.24.1 LinkObjectSequence Class Methods

There is only one class method associated with this class. It is used to create new instances of itself and is normally only called by sequence methods associated with the LinkObject class.

This class method creates instances of the LinkObjectSequence class. It is normally only called by the sequence method associated with the LinkObject class. lnk is the first link in the list, and i is the sequence instance.

See also: Next::LinkObjectSequence, Sequence::LinkObject

5.24.2 LinkObjectSequence Instance Methods

This class only has a single instance method which is used to enumerate through object on a list.

This method is used to enumerate through the objects contained within the links on a linked list. Each time Next is called the following object on the linked list is returned. It does this in a non-destructive way so the associated linked list is not effected.

When Next is called after the last object has been returned (or if there are no links on the list) it will return NULL and automatically dispose of the sequence object i. Therefore, the only time Dispose would be needed (if the garbage collector weren't being used) would be if the entire list was not enumerated.

Example:

See also: Sequence::LinkObject

5.25 LinkSequence Class

This class is a subclass of Sequence and is used to provide a mechanism to enumerate through all the links in a linked list structure without effecting the structure.

The linked list structure is usually represented by instances of the LinkList or LinkObject classes. Typically, instance methods of these classes are used to create the instances of the LinkSequence class. These methods have names which begin with Sequence.

5.25.1 LinkSequence Class Methods

There is only one class method associated with this class. It is used to create new instances of itself and is normally only called by sequence methods associated with the LinkList or LinkObject classes.

```
NewWithObj::LinkSequence [NewWithObj]

i = gNewWithObj(LinkSequence, lnk);
```

```
object lnk;
object i;
```

This class method creates instances of the LinkSequence class. It is normally only called by sequence methods associated with the LinkList or LinkObject classes. lnk is the first link in the list, and i is the sequence instance.

See also: Next::LinkSequence, Sequence::LinkList

5.25.2 LinkSequence Instance Methods

This class only has a single instance method which is used to enumerate through links on a list.

Next::LinkSequence [Next]

```
lnk = gNext(i);
object i;
object lnk;
```

This method is used to enumerate through the links on a linked list. Each time Next is called the following link on the linked list is returned. It does this in a non-destructive way so the associated linked list is not effected.

When Next is called after the last link has been returned (or if there are no links on the list) it will return NULL and automatically dispose of the sequence object i. Therefore, the only time Dispose would be needed (if the garbage collector weren't being used) would be if the entire list was not enumerated.

Example:

See also: Sequence::LinkList, SequenceLinks::LinkObject

5.26 LinkValue Class

The LinkValue class is a subclass of the Link class. It is used in conjunction with the LinkList class in order to manage arbitrary objects on a doubly linked list data structure.

Like the Link class, it is used to represent a single link on a doubly linked list. However, the LinkValue class has the additional capability to store a single arbitrary object at each link. Therefore, the LinkValue class may be used without creating a subclass of it.

This class (LinkValue) inherits much of its functionality from its superclass (Link), therefore, in addition to the specific documentation on this class please also refer to the documentation of its superclass.

See the examples included with the Dynace system for an illustration of the use of the doubly linked list related classes.

5.26.1 LinkValue Class Methods

The LinkValue class has only a single class method. That method is used to create and initialize new instances of itself.

```
NewWithObj::LinkValue [NewWithObj]
```

```
i = gNewWithObj(LinkValue, item);
object item;
object i;
```

This class method creates instances of the LinkValue class. item is the object to be associated with the new link.

The value returned is the instance object created (the new link).

See also: Dispose::Link, DeepDispose::LinkValue

5.26.2 LinkValue Instance Methods

The instances methods associated with the LinkValue class are used to link, unlink, move and dispose of particular instances of the LinkValue class. The majority of its linking type functionality is inherited from its superclass, Link.

```
ChangeValue::LinkValue [ChangeValue]
```

```
i = gChangeValue(i, obj);
object i;
object obj;
```

This method is used to change the object associated with a link. i is the instance of the LinkValue class, and obj is the new object to be associated with it. Any previous association is simply disassociated (not disposed).

This method returns i.

See also: Value::LinkValue, NewWithObj::LinkValue

DeepCopy::LinkValue [DeepCopy]

```
c = gDeepCopy(i);
object i, c;
```

This method is used to create a new instance of the LinkValue class which contains a *copy* of the value associated with the link. DeepCopy is used to create the copied value. The new LinkValue instance is returned.

Note that the new link returned will not be associated with any list. It will just be an unlinked link.

See also: Copy::Object

DeepDispose::LinkValue [DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This instance method is used to perform a deep disposal of an instance of the LinkValue class. It does this by calling gDeepDispose on the item associated with the link and then calling the link's superclass to dispose of the LinkValue instance.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::Link

StringRep::LinkValue [StringRep]

```
s = gStringRep(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the object i and its value. This is often used to print or display a representation of an object. It is also used by Print::Object (a method useful during the debugging phase of a project) in order to directly print an object to a stream.

```
See also: Print::Object, PrintValue::Object, StringRepValue::LinkValue
```

StringRepValue::LinkValue

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

Value::LinkValue [Value]

```
obj = gValue(i);
object i;
object obj;
```

This method is used to obtain the object associated with a link. i is the instance of the LinkValue class, and obj is the object associated with it.

See also: ChangeValue::LinkValue, NewWithObj::LinkValue

5.27 LongArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language long data type in an efficient manner. Although this class implements much of its own functionality it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.28 LongInteger Class

The LongInteger class is used to represent the C language long data type as a Dynace object. It is a subclass of the Number class. Even though the LongInteger class implements most of its own functionality, it is documented as part of the Number class because most of the interface is the same for all subclasses of the Number class. Differences are documented in this section.

5.28.1 LongInteger Class Methods

The LongInteger class has only one class method and it is used to create new instances of itself.

NewWithLong::LongInteger [NewWithLong]

```
i = gNewWithLong(LongInteger, val);
long val;
object i;
```

This class method creates instances of the LongInteger class. val is the initial value of the integer being represented.

The value returned is a Dynace instance object which represents the integer passed.

Note that the default disposal methods are used by this class since there are no special storage allocation requirements.

Example:

```
object x;
x = gNewWithLong(LongInteger, 55L);
```

See also: LongValue::Number, Dispose::Object

5.28.2 LongInteger Instance Methods

The instance methods associated with the LongInteger class provide a means of changing and obtaining the value associated with an instance of the LongInteger class. All of the LongInteger class instance methods are documented in the Number class because of their common interface with all other subclasses of the Number class.

5.29 LookupKey Class

The LookupKey class, which is a subclass of Association, is used to represent an object which contains a key. It is normally used in conjunction with the ObjectAssociation, Set and Dictionary classes in order to manage a group of arbitrary objects.

Since instances of the LookupKey class only contain enough information to describe the key, the LookupKey class can be thought of as an abstract class. It is never used by itself (instances of it are never created). Instead a new class would be created which would have the LookupKey class as a superclass. This new class would describe the data items which would be stored at each link. The LookupKey class would keep track of the key to the object. Alternatively, a new class with the same methods as this class could be created and used with the Set and Dictionary classes.

The LookupKey class also has a subclass called ObjectAssociation which associates a single arbitrary object with the key.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.29.1 LookupKey Class Methods

This class has only a single class method which is used to create and initialize instances of itself. Although this class can handle NULL key values, their use is discouraged.

This class method creates instances of the LookupKey class. key is used to initialize the key associated with the instance created. The new instance is returned.

5.29.2 LookupKey Instance Methods

object old;

The instance methods associated with this class are used access, change, dispose and print the key associated with the instances of this class. Additional functionality, although implemented by this class, is documented in LookupKey's superclass, Association. This is done because of the common interface these methods share with all subclasses of Association.

This method is used to change the key associated with instance i. key is the new key. The old key is simply replaced, it is not disposed. This method returns the old key object.

See also: Key::LookupKey

object i, c;

This method is used to create a new instance of the LookupKey class which contains a *copy* of the key value from the original LookupKey. DeepCopy is used to create the copy of the value. The new LookupKey instance is returned.

See also: Copy::Object

DeepDispose::LookupKey [DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of instance i as well as the key associated with it. It disposes of the key by calling the DeepDispose method on it.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::Object

Key::LookupKey [Key]

```
key = gKey(i);
object i;
object key;
```

This method is used to obtain the key associated with instance i.

See also: ChangeKey::LookupKey

```
StringRepValue::LookupKey
```

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

5.30 LowFile Class

This class is used to encapsulate the standard C low level IO facility. It is a subclass of Stream and enables access to these routines through an interface which is common to all subclasses of Stream.

Although this class implements most of its own functionality, it is documented as part of the Stream class because most of the interface is the same for all subclasses of Stream. Differences are documented in this section.

5.30.1 LowFile Class Methods

The one class method associated with this class is the method used to open or create a file.

```
OpenLowFile::LowFile [OpenLowFile]
```

```
i = gOpenLowFile(LowFile, name, oflag, pmode);
char *name; /* file name */
int oflag;
int pmode;
object i;
```

This class method us used to open or create a normal file using the C low level IO facility. name is the file name to be opened and may also be an instance of the String class. The name, oflag and pmode parameters correspond to the local C library function open. The local library manuals can more completely describe those arguments. The value returned is an object which refers to the opened file. If the file cannot be opened a NULL will be returned.

Example:

See also: Dispose::LowFile, Read::Stream

5.30.2 LowFile Instance Methods

The instance methods associated with this class are used to read and write data to the file represented by the instance.

Although this class implements most of its own functionality, it is documented as part of the Stream class because most of the interface is the same for all subclasses of Stream. Differences are documented in this section.

```
DeepDispose::LowFile [DeepDispose]
```

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to close the file associated with the instance and dispose of the instance. It performs the same function as Dispose::LowFile.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::LowFile, OpenLowFile::LowFile

Dispose::LowFile

[Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to close the file associated with the instance and dispose of the instance. It performs the same function as DeepDispose::LowFile.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::LowFile, OpenLowFile::LowFile

FileHandle::LowFile

[FileHandle]

```
h = gFileHandle(i);
object i;
int h;
```

This method is used to obtain the file handle associated with i.

Name::LowFile [Name]

```
n = gName(i);
object i;
char *n; /* the file name */
```

This method is used to obtain the name of the file represented by i.

5.31 Number Class

The Number class is an abstract class used to combine common functionality of the primitive C numeric data types. Although most of the functionality is actually implemented in the subclasses of the Number class, they are documented here because of their common interface.

5.31.1 Number Class Methods

The Number class has no specific class methods.

5.31.2 Number Instance Methods

Although most of the instance methods are actually implemented in the subclasses of the Number class, they are documented here because of their common interface. Regardless of the numeric type being represented there has been every effort made to make a standard set of interfaces to these data elements. Therefore, you are able to change the value associated with an instance of the ShortInteger class to a double value of 3.141, however, when you retrieve the double value you will only get back 3.0. (Of course you wouldn't loose the fractional part if you were dealing with an instance of the DoubleFloat class.)

ChangeCharValue::Number

[ChangeCharValue]

```
i = gChangeCharValue(i, c);
object i;
int c;
```

This method is used to change the value associated with an instance of a subclass of the Number class. Notice that this method returns the instance being passed. c is the new value. If it is not the same type as i it will be converted.

Note that c is of type int. That is because if you pass a character to a generic function (which uses a variable argument declaration) the C language will automatically promote it to an int.

Example:

double val;

```
object x;

x = gNewWithChar(Character, 'a');
gChangeCharValue(x, 'b');

See also: CharValue::Number

ChangeDoubleValue::Number [ChangeDoubleValue]

i = gChangeDoubleValue(i, val);

object i;
```

This method is used to change the value associated with an instance of a subclass of the Number class. Notice that this method returns the instance being passed. val is the new value. If it is not the same type as i it will be converted.

Example:

```
object x;

x = gNewWithDouble(DoubleFloat, 3.14);
gChangeDoubleValue(x, 7.56);

See also: NewWithDouble::DoubleFloat, DoubleValue::Number

ChangeLongValue::Number [ChangeLongValue]

i = gChangeLongValue(i, val);

object i;
long val;
```

This method is used to change the value associated with an instance of a subclass of the Number class. Notice that this method returns the instance being passed. val is the new value. If it is not the same type as i it will be converted.

Example:

object

int

i;

```
object x;

x = gNewWithLong(LongInteger, 55L);
gChangeLongValue(x, 66L);

See also: NewWithLong::LongInteger, LongValue::Number

ChangeShortValue::Number [ChangeShortValue]

i = gChangeShortValue(i, s);
```

This method is used to change the value associated with an instance of a subclass of the Number class. Notice that this method returns the instance being passed. s is the new value. If it is not the same type as i it will be converted.

Note that s is of type int. That is because if you pass a short to a generic function (which uses a variable argument declaration) the C language will automatically promote it to an int.

Example:

```
object x;
x = gNewWithInt(ShortInteger, 55);
gChangeShortValue(x, 66);
```

See also: NewWithInt::ShortInteger, ShortValue::Number

ChangeUShortValue::Number

[ChangeUShortValue]

```
i = gChangeUShortValue(i, s);
object i;
unsigned s;
```

This method is used to change the value associated with an instance of a subclass of the Number class. Notice that this method returns the instance being passed. s is the new value. If it is not the same type as i it will be converted.

Note that s is of type unsigned. That is because if you pass a short to a generic function (which uses a variable argument declaration) the C language will automatically promote it to an unsigned.

Example:

```
object x;
x = gNewWithUnsigned(UnsignedShortInteger, 55);
gChangeUShortValue(x, 66);
```

See also: NewWithUnsigned::UnsignedShortInteger

ChangeValue::Number

[ChangeValue]

```
i = gChangeValue(i, v);
object i;
object v;
```

This method is used to change the value associated with an instance of a subclass of the Number class. Notice that this method returns the instance being passed. v is an object which represents the new value. If it is not the same type as i it will be converted. Note that this conversion does not effect the object v, just the value changed in i.

Example:

```
object x, y;

x = gNewWithInt(ShortInteger, 88);
y = gNewWithDouble(DoubleFloat, 3.141);
gChangeValue(x, y);  /* x is changed to 3 */
```

See also: ChangeCharValue::Number, ChangeShortValue::Number, etc.

CharValue::Number

[CharValue]

```
c = gCharValue(i);
object i;
char c;
```

This method is used to obtain the char value associated with an instance of a subclass of the Number class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a char. If the instance does not represent an instance of the Character class, the returned value of whatever is represented will be converted to a char.

Example:

```
object x;
char c;

x = gNewWithChar(Character, 'a');
c = gCharValue(x);
```

See also: NewWithChar::Character, ChangeValue::Number

Compare::Number

[Compare]

```
r = gCompare(i, obj);
object i;
object obj;
int r;
```

This method is used by the generic container classes to determine the relationship of the values represented by i and obj. r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal. obj may be any type of object.

See also: Hash::Number

DoubleValue::Number [DoubleValue]

```
val = gDoubleValue(i);
object i;
double val;
```

This method is used to obtain the double value associated with an instance of a subclass of the Number class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a double. If the instance does not represent an instance of the DoubleFloat class, the returned value of whatever is represented will be converted to a double.

Example:

```
object x;
double val;
x = gNewWithDouble(DoubleFloat, 7.62);
val = gDoubleValue(x);
```

See also: NewWithDouble::DoubleFloat, ChangeValue::Number

FormatNumber::Number [FormatNumber]

```
val = gFormatNumber(i, msk, wth, dp);
object i;
                /* object to be formatted
                                                */
                /* format mask
char
        *msk;
                                                */
int
                /* field width
        wth;
                                                */
                /* number of decimal places
int
        dp;
                                                */
                /* String value
                                                */
object val;
```

This method is used to convert a number into a nicely formatted string. i is the numeric object to be formatted.

msk is a character string which tells the formatter specific which formatting options to use. Each character in the string represents a different option. The order is not significant. The following table lists the available options:

```
В
   blank if zero
    add commas every 3 digits to the left of the decimal point
C
L
    left justify
Ρ
    put parentheses around negative numbers
Z
    zero fill
D
    floating dollar sign
    upper-case letters in conversion (used in bases greater
    than 10)
R
    add a percent sign to the end of the number
```

wth indicates the width of the field and hence the length of the resultant String object. If wth <= 0 FormatNumber will calculate and use the minimum width which will represent i.

dp indicates the number of decimal places that should appear in the string. If dp is less than the number of decimal places in i rounding will occur. However if dp < 0 Nfmt will calculate and use the minimum number of decimal places required to fully represent i.

The value returned by this method is an instance of the String class.

Example:

```
object x, y;
x = gNewWithDouble(DoubleFloat, 1234567.127);
y = gFormatNumber(x, "C", 0, 2);  /* y = "1,234,567.13" */
```

See also: StringRepValue::Number

Hash::Number [Hash]

```
val = gHash(i);
object i;
int val;
```

This method is used by the generic container classes to obtain hash values for the object. val is a hash value between 0 and a large integer value.

See also: Compare::Number

LongValue::Number [LongValue]

```
val = gLongValue(i);
object i;
long val;
```

This method is used to obtain the long value associated with an instance of a subclass of the Number class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a long. If the instance does not represent an instance of the LongInteger class, the returned value of whatever is represented will be converted to a long.

Example:

```
object x;
long val;
x = gNewWithLong(LongInteger, 55L);
val = gLongValue(x);
```

See also: NewWithLong::LongInteger, ChangeLongValue::Number

ShortValue::Number [ShortValue]

```
s = gShortValue(i);
object i;
short s:
```

This method is used to obtain the **short** value associated with an instance of a subclass of the **Number** class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a **short**. If the instance does not represent an instance of the **ShortInteger** class, the returned value of whatever is represented will be converted to a **short**.

Example:

```
object x;
short s;
x = gNewWithInt(ShortInteger, 55);
s = gShortValue(x);
```

See also: NewWithInt::ShortInteger, ChangeShortValue::Number

StringRepValue::Number [StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
object x;
object s;

x = gNewWithInt(ShortInteger, 55);
s = gStringRepValue(x);  /* s represents "55" */

See also: PrintValue::Object, Print::Object, FormatNumber::Number

UnsignedShortValue::Number  [UnsignedShortValue]

s = gUnsignedShortValue(i);
object i;
unsigned short s;
```

This method is used to obtain the unsigned short value associated with an instance of a subclass of the Number class. Note that this is one of the few generics which doesn't return a Dynace object. It returns an unsigned short. If the instance does not represent an instance of the UnsignedShortInteger class, the returned value of whatever is represented will be converted to an unsigned short.

Example:

```
object x;
unsigned short s;
x = gNewWithUnsigned(UnsignedShortInteger, 55);
s = gUnsignedShortValue(x);
```

See also: NewWithUnsigned::UnsignedShortInteger, ChangeUShortValue::Number

5.32 NumberArray Class

The NumberArray class, which is a subclass of Array, is an abstract class used to combine common functionality of numeric arrays. Although most of the functionality is actually implemented in the subclasses of the NumberArray class, they are documented here because of their common interface.

5.32.1 NumberArray Class Methods

The only class method associated with this class is the New method which is used to create new instances of numeric arrays. This method is actually implemented by subclasses of NumberArray.

New::NumberArray [New]

```
ary = vNew(cls, rnk, ...)
object cls, ary;
unsigned rnk, ...
```

This class method is used to create a new numeric array. This method is actually implemented by and should only be used with subclasses of the NumberArray class. It is documented here because it is the same for all subclasses of the NumberArray class.

cls would be one of the subclasses of the NumberArray class (such as CharacterArray ShortArray UnsignedShortArray LongArray FloatArray or DoubleFloatArray). This will indicate the type of array to be created.

rnk is the number of dimensions the new array should have. The remaining arguments (each of type unsigned) indicates the size of each consecutive dimension. Note that the number of arguments following rnk must be the same as the value in rnk.

ary is the new array object created and will be initialized to all zeros.

Example:

```
object ary;
ary = vNew(DoubleFloatArray, 2, 5, 4);
/* ary is a 5x4 double matrix */
```

5.32.2 NumberArray Instance Methods

The instance methods associated with this class are actually implemented by subclasses of NumberArray. They are documented here because of their common interface with all subclasses of NumberArray.

Regardless of the array type, each subclass of NumberArray implements a full complement of methods necessary to deal with all C language data types. In all cases, if the value being stored into an array is not the same as the array, the value being stored will be converted to the correct type prior to the assignment. Also, if the desired return type is not the same

as the array type, the returned value will be converted. The type of the array will remain unchanged. This naturally means that if you store the number 3.141 into an element of a ShortArray you will only get 3.0 when attempting to get back a double value.

```
ChangeCharValue::NumberArray
```

[ChangeCharValue]

```
ary = vChangeCharValue(ary, val, ...);
object ary;
int val;
unsigned ...
```

This method is used to change the value of one element of array ary which should be an instance of a subclass of NumberArray.

val is the value which the element of the array should be changed to. The reason it is of type int is because C promotes char to int when variable arguments are used.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

If ary and val do not represent the same types, normal data type conversion will take place during the assignment without changing the type of ary.

The value returned is the modified array passed.

Example:

```
object ary;
ary = vNew(CharacterArray, 2, 5, 4);
vChangeCharValue(ary, 'C', 1, 2);
/* ary[1][2] <- 'C' */</pre>
```

See also: ChangeValue::NumberArray, ChangeDoubleValue::NumberArray, ChangeCharValue::NumberArray ...

ChangeDoubleValue::NumberArray

[ChangeDoubleValue]

```
ary = vChangeDoubleValue(ary, val, ...);
object ary;
double val;
unsigned ...
```

This method is used to change the value of one element of array ary which should be an instance of a subclass of NumberArray. This method should also be used for arrays of type FloatArray.

val is the value which the element of the array should be changed to.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

If ary and val do not represent the same types, normal data type conversion will take place during the assignment without changing the type of ary.

The value returned is the modified array passed.

Example:

```
object ary;
ary = vNew(DoubleFloatArray, 2, 5, 4);
vChangeDoubleValue(ary, 3.141, 1, 2);
/* ary[1][2] <- 3.141 */</pre>
```

See also: ChangeValue::NumberArray, ChangeCharValue::NumberArray, ChangeShortValue::NumberArray ...

```
ChangeLongValue::NumberArray
```

[ChangeLongValue]

```
ary = vChangeLongValue(ary, val, ...);
object ary;
long val;
unsigned ...
```

This method is used to change the value of one element of array ary which should be an instance of a subclass of NumberArray.

val is the value which the element of the array should be changed to.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

If ary and val do not represent the same types, normal data type conversion will take place during the assignment without changing the type of ary.

The value returned is the modified array passed.

Example:

```
object ary;
ary = vNew(LongArray, 2, 5, 4);
vChangeLongValue(ary, 27L, 1, 2);
/* ary[1][2] <- 27L */</pre>
```

See also: ChangeValue::NumberArray, ChangeDoubleValue::NumberArray, ChangeShortValue::NumberArray ...

ChangeShortValue::NumberArray

[ChangeShortValue]

```
ary = vChangeShortValue(ary, val, ...);
object ary;
int val;
unsigned ...
```

This method is used to change the value of one element of array ary which should be an instance of a subclass of NumberArray.

val is the value which the element of the array should be changed to. The reason it is of type int is because C promotes short to int when variable arguments are used.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

If ary and val do not represent the same types, normal data type conversion will take place during the assignment without changing the type of ary.

The value returned is the modified array passed.

Example:

```
object ary;
ary = vNew(ShortArray, 2, 5, 4);
vChangeShortValue(ary, 27, 1, 2);
/* ary[1][2] <- 27 */</pre>
```

See also: ChangeValue::NumberArray, ChangeDoubleValue::NumberArray, ChangeShortValue::NumberArray ...

ChangeUShortValue::NumberArray

[ChangeUShortValue]

```
ary = vChangeUShortValue(ary, val, ...);
object ary;
unsigned val;
unsigned ...
```

This method is used to change the value of one element of array ary which should be an instance of a subclass of NumberArray.

val is the value which the element of the array should be changed to. The reason it is of type unsigned is because C promotes unsigned short to unsigned when variable arguments are used.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

If ary and val do not represent the same types, normal data type conversion will take place during the assignment without changing the type of ary.

The value returned is the modified array passed.

Example:

```
object ary;
ary = vNew(UnsignedShortArray, 2, 5, 4);
vChangeUShortValue(ary, 27U, 1, 2);
/* ary[1][2] <- 27U */</pre>
```

See also: ChangeValue::NumberArray, ChangeDoubleValue::NumberArray, ChangeShortValue::NumberArray ...

ChangeValue::NumberArray

[ChangeValue]

```
ary = vChangeValue(ary, val, ...);
object ary;
object val;
unsigned ...
```

This method is used to change the value of one element of array ary which should be an instance of a subclass of NumberArray.

val should be an instance of the Number class and is the value which the element of the array should be changed to.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

If ary and val do not represent the same types, normal data type conversion will take place during the assignment without changing the types of ary or val.

The value returned is the modified array passed.

Example:

CharValue::NumberArray [CharValue]

```
v = vCharValue(ary, ...);
object ary;
unsigned ...
char v;
```

This method is used to obtain the **char** value associated with a particular element of an instance of a subclass of the NumberArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Note that this is one of the few generics which doesn't return a Dynace object. It returns a char. If the instance does not represent an instance of the CharacterArray class, the returned value of whatever is represented will be converted to a char.

Example:

```
object ary;
char v;

ary = vNew(CharacterArray, 2, 5, 4);
v = vCharValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeCharValue::NumberArray

DoubleValue::NumberArray [DoubleValue]

```
v = vDoubleValue(ary, ...);
object ary;
unsigned ...
double v;
```

This method is used to obtain the double value associated with a particular element of an instance of a subclass of the NumberArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Note that this is one of the few generics which doesn't return a Dynace object. It returns a double. If the instance does not represent an instance of the DoubleFloatArray class, the returned value of whatever is represented will be converted to a double.

Example:

```
object ary;
double v;
ary = vNew(DoubleFloatArray, 2, 5, 4);
v = vDoubleValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeDoubleValue::NumberArray

LongValue::NumberArray [LongValue]

```
v = vLongValue(ary, ...);
object ary;
unsigned ...
long v;
```

This method is used to obtain the long value associated with a particular element of an instance of a subclass of the NumberArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Note that this is one of the few generics which doesn't return a Dynace object. It returns a long. If the instance does not represent an instance of the LongArray class, the returned value of whatever is represented will be converted to a long.

Example:

```
object ary;
long v;
ary = vNew(LongArray, 2, 5, 4);
v = vLongValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeLongValue::NumberArray

ShortValue::NumberArray [ShortValue]

```
v = vShortValue(ary, ...);
object ary;
unsigned ...
short v;
```

This method is used to obtain the **short** value associated with a particular element of an instance of a subclass of the NumberArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Note that this is one of the few generics which doesn't return a Dynace object. It returns a short. If the instance does not represent an instance of the ShortArray class, the returned value of whatever is represented will be converted to a short.

Example:

```
object ary;
short v;

ary = vNew(ShortArray, 2, 5, 4);
v = vShortValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeShortValue::NumberArray

UnsignedShortValue::NumberArray

[UnsignedShortValue]

```
v = vUnsignedShortValue(ary, ...);
object ary;
unsigned ...
unsigned short v;
```

This method is used to obtain the unsigned short value associated with a particular element of an instance of a subclass of the NumberArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Note that this is one of the few generics which doesn't return a Dynace object. It returns an unsigned short. If the instance does not represent an instance of the UnsignedShortArray class, the returned value of whatever is represented will be converted to a unsigned short.

Example:

```
object ary;
unsigned short v;
ary = vNew(UnsignedShortArray, 2, 5, 4);
v = vUnsignedShortValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeUShortValue::NumberArray

5.33 ObjectArray Class

This class, which is a subclass of Array, is used to represent arbitrary shaped arrays of Dynace objects in an efficient manner. By using ObjectArrays it is possible to have arrays where each element contains an arbitrary object including another arrays. Therefore it is possible to create nested or general arrays which are nested to arbitrary levels.

Much of the functionality of this class is implemented and documented in the Array class. Differences are documented in this section.

5.33.1 ObjectArray Class Methods

The only class method implemented by this class is one used to create new ObjectArray instances.

New::ObjectArray [New]

```
ary = vNew(ObjectArray, rnk, ...)
unsigned rnk, ...
object ary;
```

This class method is used to create a new instance of ObjectArray.

rnk is the number of dimensions the new array should have. The remaining arguments (each of type unsigned) indicates the size of each consecutive dimension. Note that the number of arguments following rnk *must* be the same as the value in rnk.

ary is the new array object created and will be initialized to all NULL's.

Example:

```
object ary;
ary = vNew(ObjectArray, 2, 5, 4);
/* ary is a 5x4 matrix */
```

5.33.2 ObjectArray Instance Methods

Most instance functionality is obtained and documented in the Array class, however, functionality which is particular to this class is documented in this section.

Value::ObjectArray [Value]

```
v = vValue(ary, ...);
object ary;
unsigned ...
object v;
```

This method is used to obtain the object (or NULL) value associated with a particular element of an instance of the ObjectArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Example:

```
object ary;
object v;

ary = vNew(ObjectArray, 2, 5, 4);
v = vValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeValue::ObjectArray

ChangeValue::ObjectArray

[ChangeValue]

```
ary = vChangeValue(ary, val, ...);
object ary;
object val;
unsigned ...
```

This method is used to change the value of one element of ObjectArray ary.

val is the value which the element of the array should be changed to (or NULL).

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

The value returned is the modified array passed.

Example:

```
object ary, v;
ary = vNew(ObjectArray, 2, 5, 4);
v = gNewWithInt(ShortInteger, 6);
vChangeValue(ary, v, 1, 2);
/* ary[1][2] <- v */</pre>
```

See also: Value::ObjectArray

5.34 ObjectAssociation Class

This class is a subclass of the LookupKey class. It is used to associate a value (an arbitrary object) with a key. The documentation on the LookupKey should be consulted since much of this class's functionality is inherited from it.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.34.1 ObjectAssociation Class Methods

The only class method associated with this class is the one used to create instances of the <code>ObjectAssociation</code> class.

```
NewWithObjObj::ObjectAssociation [NewWithObjObj]

i = gNewWithObjObj(ObjectAssociation, key, val);

object key; /* or NULL */
object val; /* or NULL */
object i;
```

This class method creates instances of the ObjectAssociation class. key is used to initialize the key associated with the instance created and val is used to initialize its associated value. The new instance is returned.

5.34.2 ObjectAssociation Instance Methods

The instance methods associated with this class are used to obtain, change and print the value associated with its instances. Much additional functionality is achieved through its superclass, LookupKey.

This method is used to change the value associated with ObjectAssociation i to a value, val. The old value is simply no longer associated with the instance. It is not disposed. This method returns the old value being replaced.

See also: Value::ObjectAssociation, ChangeKey::LookupKey

DeepCopy::ObjectAssociation

[DeepCopy]

```
c = gDeepCopy(i);
object i, c;
```

This method is used to create a new instance of the ObjectAssociation class which contains a *copy* of the key and value from i. DeepCopy is used to create the copy of the key and value. The new ObjectAssociation instance is returned.

See also: Copy::Object

DeepDispose::ObjectAssociation

[DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of the instance passed as well as associated key and value. The key and value are disposed of by using the DeepDispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::LookupKey

 ${\tt StringRepValue::ObjectAssociation}$

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

Value::ObjectAssociation [Value]

```
val = gValue(i);
object i;
object val;
```

This method is used to obtain the value associated with \mathtt{i} .

 $See \ also: \verb|ChangeValue::ObjectAssociation|, \verb|Key::LookupKey||$

5.35 ObjectPool Class

The ObjectPool class provides a means to group arbitrary objects in a pool. This pool may later be disposed causing all the objects contained in the pool to be disposed as well. This is useful when running a particular functional module. All the new objects can be added to a pool and then disposed en-mass when the functional unit is complete. This makes object disposal a little easier to organize.

This class can maintain numerous pools as well as global pools.

5.35.1 ObjectPool Class Methods

Class methods for this class are used to create new pools as well as manage global pools.

New::ObjectPool [New]

```
i = gNew(ObjectPool);
object i;
```

This class method creates instances of the ObjectPool class. It is usually only used by subclasses of the ObjectPool class. The new link will not point to anything. It will just be an empty link.

This method is actually just inherited from Object in order to create a null link.

The value returned is the instance object created (the new link).

See also: Dispose::ObjectPool

5.36 Pipe Class

The Pipe class is used to provide a mechanism for threads to transfer information via a uni-directional byte stream. If bi-directional communications is needed two pipes may be used.

The Pipe class is a subclass of Stream and as such shares much of its functionality with other subclasses of the Stream class. Although this class implements most of its own functionality, it is documented as part of the Stream class because most of the interface is the same for all subclasses of Stream. Differences are documented in this section.

See the relevant text for a detailed description of pipes.

5.36.1 Pipe Class Methods

There are only two class methods associated with the Pipe class. They are used to create new pipes and find existing ones.

```
FindStr::Pipe [FindStr]
```

```
p = gFindStr(Pipe, name)
char *name;
object p;
```

This method is used to obtain a pipe object from its name. p is the pipe object found or NULL if not found.

See also: New::Pipe

New::Pipe [New]

```
p = gNew(Pipe)
object p;
```

This class method is used to create and initialize a new unnamed pipe with a default buffer size.

The value returned (p) is the pipe object created.

```
See also: NewWithStrInt::Pipe, FindStr::Pipe, Dispose::Pipe
```

NewWithStrInt::Pipe [NewWithStrInt]

```
p = gNewWithStrInt(Pipe, name, bufsiz)
char *name;
int bufsiz;
object p;
```

This class method is used to create and initialize a new pipe.

name is the name of the new pipe and may be NULL if no name is to be associated with the pipe.

bufsiz is the size of the buffer associated with the pipe. The size of the buffer determines how many bytes of information may be buffered before a thread has to held. If set too small the system will become inefficient because of the constant switching between threads. Typical values are 128 or 512. It depends on the quantity and size of the data being transferred.

The value returned (p) is the pipe object created. Other threads may obtain the thread object by the use of the FindStr::Pipe method.

```
See also: New::Pipe, FindStr::Pipe, Dispose::Pipe
```

5.36.2 Pipe Instance Methods

The instance methods associated with this class are used to put bytes on the pipe, take bytes off, dispose of, and obtain information about particular pipes.

Although this class implements most of its own functionality, it is documented as part of the Stream class because most of the interface is the same for all subclasses of Stream. Differences are documented in this section.

```
DeepDispose::Pipe [DeepDispose]
```

```
r = gDeepDispose(p)
object p;
object r; /* NULL */
```

This method is used to dispose of a pipe instance.

It is the same as Dispose::Pipe.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Dispose::Pipe [Dispose]

```
r = gDispose(p)
object p;
object r; /* NULL */
```

This method is used to dispose of a pipe instance.

It is the same as DeepDispose::Pipe.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

Length::Pipe [Length]

```
n = gLength(p)
object p;
long n;
```

This method is used to determine the number of bytes currently on the pipe's buffer. Note that this method returns a long. This is to retain consistency with Length::Stream.

See also: Room::Pipe, Size::Pipe

Mode::Pipe [Mode]

```
p = gMode(p, rblock, wblock)

object p;
int rblock; /* read block */
int wblock: /* write block */
```

This method is used to set the blocking attributes of a particular Pipe. A 1 turns on the blocking and a 0 turns it off.

If blocking is turned on when a particular request for reading or writing occurs and there is insufficient bytes or room available the thread requesting the read or write will go into a hold state until another thread can either supply the requested bytes or make the necessary room available. If blocking is not turned on then the particular read or write request will only perform the operation with as many bytes is available at the time. There will be no waiting.

The rblock flag effects read requests and the wblock effects write requests.

This method returns the Pipe instance passed.

```
See also: Room::Pipe, Length::Pipe
```

Room::Pipe [Room]

```
n = gRoom(p)
object p;
int n;
```

This method is used to determine the number of bytes currently available on the pipe's buffer.

See also: Length::Pipe

Size::Pipe [Size]

```
n = gSize(p)
object p;
int n;
```

This method is used to determine the size of the buffer associated with a Pipe.

See also: Length::Pipe

5.37 Pointer Class

The Pointer class is used to represent the C language void * data type as a Dynace object.

5.37.1 Pointer Class Methods

The Pointer class has only one class method and it is used to create new instances of itself.

NewWithPtr::Pointer [NewWithPtr]

```
i = gNewWithPtr(Pointer, val);
void *val;
object i;
```

This class method creates instances of the Pointer class. val is the initial value of the pointer being represented.

The value returned is a Dynace instance object which represents the pointer passed.

Note that the default disposal methods are used by this class since there are no special storage allocation requirements.

Example:

```
object x;
int v = 3;
x = gNewWithPtr(Pointer, &v);
```

See also: PointerValue::Pointer, Dispose::Object

5.37.2 Pointer Instance Methods

The instance methods associated with the Pointer class provide a means of changing and obtaining the value associated with an instance of the Pointer class. Methods are also included to help the generic container classes to quickly access members of this class.

ChangeValue::Pointer [ChangeValue]

```
i = gChangeValue(i, val);
object i;
void *val;
```

This method is used to change the value associated with an instance of the Pointer class. Notice that this method returns the instance being passed. val is the new value.

Example:

```
object x;
int v1 = 4, v2 = 5;
x = gNewWithPtr(Pointer, &v1);
gChangeValue(x, &v2);
```

See also: NewWithPtr::Pointer, PointerValue::Pointer

Compare::Pointer

[Compare]

```
r = gCompare(i, obj);
object i;
object obj;
int r;
```

This method is used by the generic container classes to determine the equality of the values represented by i and obj. r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

See also: Hash::Pointer

Hash::Pointer [Hash]

```
val = gHash(i);
object i;
int val;
```

This method is used by the generic container classes to obtain hash values for the object. val is a hash value between 0 and a large integer value.

See also: Compare::Pointer

PointerValue::Pointer

[PointerValue]

```
val = gPointerValue(i);
object i;
void *val;
```

This method is used to obtain the void * value associated with an instance of the Pointer class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a void * pointer.

Example:

```
object x;
int a = 4, *b;
void *val;
x = gNewWithPtr(Pointer, &a);
b = (int *) gPointerValue(x);
/* b now points to a */
```

See also: NewWithPtr::Pointer, ChangeValue::Pointer

StringRepValue::Pointer

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
object x;
object s;
x = gNewWithPtr(Pointer, NULL);
s = gStringRepValue(x);
```

See also: PrintValue::Object, Print::Object

5.38 PointerArray Class

This class, which is a subclass of Array, is used to represent arbitrary shaped arrays of arbitrary C language pointers in an efficient manner.

Much of the functionality of this class is implemented and documented in the Array class. Differences are documented in this section.

5.38.1 PointerArray Class Methods

The only class method implemented by this class is one used to create new PointerArray instances.

```
New::PointerArray [New]
```

```
ary = vNew(PointerArray, rnk, ...)
unsigned rnk, ...
object ary;
```

This class method is used to create a new instance of PointerArray.

rnk is the number of dimensions the new array should have. The remaining arguments (each of type unsigned) indicates the size of each consecutive dimension. Note that the number of arguments following rnk must be the same as the value in rnk.

ary is the new array object created and will be initialized to all NULL's.

Example:

```
object ary;
ary = vNew(PointerArray, 2, 5, 4);
/* ary is a 5x4 matrix */
```

5.38.2 PointerArray Instance Methods

Most instance functionality is obtained and documented in the Array class, however, functionality which is particular to this class is documented in this section.

```
PointerValue::PointerArray
```

[PointerValue]

```
v = vPointerValue(ary, ...);
object ary;
unsigned ...
void *v;
```

This method is used to obtain the pointer value associated with a particular element of an instance of the PointerArray class.

The arguments after the ary argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the ary argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

Example:

```
object ary;
void *v;
ary = vNew(PointerArray, 2, 5, 4);
v = vPointerValue(ary, 1, 2);
/* v has ary[1][2] */
```

See also: ChangeValue::PointerArray

ChangeValue::PointerArray

[ChangeValue]

```
ary = vChangeValue(ary, val, ...);
object ary;
void *val;
unsigned ...
```

This method is used to change the value of one element of PointerArray ary.

val is the value which the element of the array should be changed to.

The arguments after the val argument (each an unsigned) are used to specify the exact index into each consecutive dimension of the array. The number of arguments after the val argument *must* be equal to the number of dimensions (or rank) of array ary. See IndexOrigin::Array for more information.

The value returned is the modified array passed.

Example:

```
object ary;
int v = 5;
ary = vNew(PointerArray, 2, 5, 4);
vChangeValue(ary, &v, 1, 2);
/* ary[1][2] <- &v */</pre>
```

See also: PointerValue::PointerArray

5.39 PropertyList Class

Property lists allow arbitrary string name / Dynace object pairs to be associated with any Dynace object. The Dynace objects being associated are associated and retrieved via a unique string name. Any number of these associations may be applied to an instance of a class with this capability.

This class is used as a mixin class. A mixin class is one which is sub-classed with another class (multiple inheritance) in order to give additional functionality to the first class. This class gives any class which inherits from it the ability to set and retrieve arbitrary Dynace objects which are accessed by string names (properties).

For example, if you had a class called MyClass and wanted to give it the ability to have property lists you would create a new class called MyClassWithProperties (for example) which would inherit from MyClass and PropertyList. The new class (MyClassWithProperties) would contain all the functionality of MyClass plus it would be able to handle property lists.

5.39.1 PropertyList Class Methods

There are no class methods implemented by this class.

5.39.2 PropertyList Instance Methods

```
DisposePropertyList::PropertyList
                                                        [DisposePropertyList]
         r = gDisposePropertyList(ins);
          object ins;
                        /* the instance */
                        /* ins */
          object r;
```

This method is used to remove all properties previously associated with an object. The properties will either be deep disposed or simply disassociated depending on how they were added (see PropertyPut). The instance passed is returned.

```
Example:
         gDisposePropertyList(ins);
     See also: PropertyRemove::PropertyList
PropertyGet::PropertyList
                                                              [PropertyGet]
         r = gPropertyGet(ins, pr);
                        /* the instance */
         object ins;
         char
                        /* the property name */
         object r; /* value */
```

This method is used to retrieve a property previously associated with an object. The property is returned otherwise, if no property with that name was added, then NULL is returned.

Example:

```
object val;
val = gPropertyGet(ins, "Color");
```

See also: PropertyPut::PropertyList, PropertyRemove::PropertyList

PropertyPut::PropertyList

[PropertyPut]

```
r = gPropertyPut(ins, pr, ad, val);
object ins; /* the instance */
char *pr; /* the property name */
int ad; /* auto dispose flag */
object val; /* value to be associated */
object r; /* val */
```

This method is used to associate an object (val) to instance ins under the property name given by pr. If the given property has already been used it will be overwritten by val.

ad is a flag used to determine what happens to val once ins is disposed or if the property is overwritten. If ad is 1 the object will be deep disposed otherwise (if it's zero) it will be simply disassociated with the object and not disposed.

Example:

```
object ins = gNew(MyClass);
gPropertyPut(ins, "Color", 1, gNewWithStr(String, "Red"));
```

See also: PropertyGet::PropertyList, PropertyRemove::PropertyList

PropertyRemove::PropertyList

[PropertyRemove]

```
r = gPropertyRemove(ins, pr);
object ins; /* the instance */
char *pr; /* the property name */
object r; /* ins */
```

This method is used to remove a property previously associated with an object. The property will either be deep disposed or simply disassociated depending on how it was added (see PropertyPut). The instance passed is returned.

Example:

```
gPropertyRemove(ins, "Color");
```

 $See \ also: \ {\tt DisposePropertyList::PropertyList}, \ {\tt PropertyRemove::PropertyList}$

5.40 Semaphore Class

This class provides a mechanism to coordinate the activity of multiple threads. It provides counting, named and unnamed semaphores. See the manual for a detailed description of semaphores.

See the examples included with the Dynace system for an illustration of the use of the thread / pipe / semaphore related classes.

5.40.1 Semaphore Class Methods

The only two class methods associated with this class provide a means to create new semaphore instances and to find existing semaphores by name.

```
FindStr::Semaphore
```

[FindStr]

```
s = gFindStr(Semaphore, name)
char *name;
object s;
```

This method is used to obtain a semaphore object from its associated name. If found it is returned, otherwise NULL is returned.

See also: New::Semaphore

New::Semaphore [New]

```
s = gNew(Semaphore)
object s;
```

This class method is used to create and initialize a new unnamed semaphore with an initial and maximum count of 1.

The value returned (s) is the semaphore object created.

```
See also: NewSemaphore::Semaphore, FindStr::Semaphore, Dispose::Semaphore
```

NewSemaphore::Semaphore

[NewSemaphore]

```
s = gNewSemaphore(Semaphore, name, cnt, max)
char *name;
int cnt, max;
object s;
```

This class method is used to create and initialize a new semaphore.

name is the name of the new semaphore and may be NULL if no name is to be associated with the semaphore.

cnt is the initial count associated with the counting semaphore and is used to indicate the maximum number of threads which may hold this semaphore at one time. A typical value would be 1 and indicates that only a single thread may hold it at a time.

max is the maximum value the count of the semaphore is allowed to achieve. If set higher (with Release) it will be reset to max. This is typically set to the same value as cnt.

The value returned (s) is the semaphore object created. If not kept it may be obtained later by the use of the FindStr::Semaphore method.

```
See also: NewSemaphore::Semaphore, FindStr::Semaphore, Dispose::Semaphore
```

5.40.2 Semaphore Instance Methods

The instance methods associated with this class provide a means for locking, releasing, disposing and getting information about semaphore instances.

```
Count::Semaphore [Count]
```

```
cnt = gCount(s)
object s;
int cnt;
```

This method is used to obtain the current lock count associated with semaphore s.

See also: New::Semaphore, Name::Semaphore

```
DeepDispose::Semaphore [DeepDispose]
```

```
r = gDeepDispose(s)
object s;
object r; /* NULL */
```

This method is used to dispose of a semaphore. All locks will be released and the semaphore is disposed. This method is the same as Dispose::Semaphore.

See also: Release::Semaphore

Dispose::Semaphore [Dispose]

```
r = gDispose(s)
object s;
object r; /* NULL */
```

This method is used to dispose of a semaphore. All locks will be released and the semaphore is disposed. This method is the same as DeepDispose::Semaphore.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Release::Semaphore

Name::Semaphore [Name]

```
nam = gName(s)
object s;
char *nam;
```

This method is used to obtain the name of semaphore s.

See also: New::Semaphore, Count::Semaphore

Release::Semaphore [Release]

```
s = gRelease(s, cnt)

object s;
int cnt;
```

This method is used to release a lock on a semaphore. The semaphore lock count will be incremented by cnt, which is normally 1. As soon as a semaphore's lock count goes above 0 any threads which are waiting for the semaphore will be taken off hold and receive the lock (limited to the number of locks available). This method returns the semaphore instance passed.

See also: WaitFor::Semaphore

WaitFor::Semaphore [WaitFor]

```
r = gWaitFor(s)
object s;
int r;
```

This method is used to obtain a lock on semaphore s. If the semaphore has already exceeded its lock count the current thread will be placed on hold until the semaphore is available. Each call to WaitFor uses up a single count associated with semaphore s. This method always returns 0.

See also: Release::Semaphore

5.41 Sequence Class

The Sequence class is an abstract class which serves the sole purpose of grouping several subclasses which have common functionality. There is no specific class or instance methods directly associated with this class.

The subclasses of this class (LinkSequence, LinkObjectSequence and SetSequence) are used to provide a convenient mechanism to enumerate (or sequence) through all the elements of a collection.

5.42 Set Class

The Set class is used to store a collection of objects which contain some means of unique identification for quick access. The objects stored may be any Dynace object. gHash and gCompare will be used on the object to be added in order to store and compare it amongst other objects in the Set.

Since Dynace contains default methods for Hash and Compare, any group of Dynace objects may be stored in any Set instance.

If values are to be associated with the keys one of the Dictionary classes would be preferred. The Set class, however, provides most of the functionality needed by the Dictionary classes.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.42.1 Set Class Methods

The only class method used in this class is one to create instances of itself.

New::Set [New]

```
i = gNew(Set);
object i;
```

This class method creates instances of the Set class. The set created is designed to accommodate rather small sets of about 30 elements. If a Set becomes too full it automatically re-sizes itself. See NewWithInt::Set for a method of creating a set while specifying its initial size.

The new instance is returned.

See also: NewWithInt::Set, Resize::Set

NewWithInt::Set [NewWithInt]

This class method creates instances of the Set class. size is used to give the instance some idea of the initial maximum number of objects to be stored in the Set. The actual number of objects may exceed this number, however, some loss of efficiency will occur.

Since a Set is implemented as a hash table it is best if size is actually larger than the number of objects to be held. It should be an odd number or better yet a prime

number. Keep in mind, however, that there is storage requirements associated with this number and the use of a very large number will consume large memory resources. In reality most reasonable numbers will work fine.

Regardless of the size specified the set object will never overflow. It will just be less efficient if many more elements then size are added.

The new instance is returned.

See also: New::Set, Resize::Set

5.42.2 Set Instance Methods

The instance methods associated with this class provide all the means to add, inquire, remove and print instances of the Set class.

```
Add::Set [Add]
```

```
r = gAdd(i, luk);
object i;
object luk;
object r;
```

This method is used to add a new object (luk) to the Set instance (i). If an object with the same key already exists in the Set it will be left as is and Add will return NULL. If luk is added it will also be returned.

luk may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Set.

```
See also: Find::Set, FindAdd::Set, RemoveObj::Set
```

Copy::Set [Copy]

```
so = gCopy(i);
object i, so;
```

This method is used to create a new instance of the Set class with the *same* elements as Set i. Or put more simply, it makes a copy. The new Set instance is returned.

Note that this method is designed to also work correctly for the Dictionary subclasses of Set.

Example:

```
object x, y;
x = gNewWithInt(Set, 101);
y = gCopy(x);
```

See also: NewWithInt::Set, DeepCopy::Set

DeepCopy::Set [DeepCopy]

```
so = gDeepCopy(i);
object i, so;
```

This method is used to create a new instance of the Set class which contains *copies* of all the elements from the original Set. DeepCopy is used on each element to create the copies. The new Set instance is returned.

Note that this method is designed to also work correctly for the Dictionary subclasses of Set.

Example:

```
object x, y;
x = gNewWithInt(Set, 100);
y = gDeepCopy(x);
```

See also: NewWithInt::Set, Copy::Set

DeepDispose::Set

[DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of an entire Set instance. It also disposes of all the objects or associations in the Set by use of the DeepDispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::Set, Dispose1::Set, DisposeAllNodes::Set

```
DeepDisposeAllNodes::Set
```

[DeepDisposeAllNodes]

```
i = gDeepDisposeAllNodes(i);
object i;
```

This method is used to remove all objects in a **Set** instance without disposing of the set itself. Each object or association is disposed of via **DeepDispose**.

The value returned is always the instance passed.

```
See also: DisposeAllNodes::Set, Dispose::Set, DisposeAllNodes1::Set
```

DeepDisposeGroup::Set

[DeepDisposeGroup]

```
i = gDeepDisposeGroup(i, fun);
object i;
int (*fun)(object);
```

This method is used to remove and dispose of a group of objects from the Set i. The function, fun, is executed for each object in the Set. With each call fun is passed the object at that point in the Set. If fun returns a 1 that particular object will be removed, or else if fun returns a 0 the object will not be removed. fun is used to decide which objects will be removed.

The objects removed are disposed of by use of the DeepDispose method.

```
See also: GroupRemove::Set, DisposeGroup::Set, DisposeAllNodes::Set
```

```
DeepDisposeObj::Set
```

[DeepDisposeObj]

```
r = gDeepDisposeObj(i, luk);
object i;
object luk;
object r;
```

This method is used to remove and dispose of an object (luk) from the Set instance (i). If it is not found NULL is returned, otherwise i is returned. luk is disposed of by use of the DeepDispose method.

luk may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Set.

```
See also: RemoveObj::Set, DisposeObj::Set
```

Dispose::Set [Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of an entire Set instance. It does not dispose of any of the objects or associations in the Set.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::Set, Dispose1::Set, DisposeAllNodes::Set

Dispose1::Set [Dispose1]

```
gDispose1(i);
object i;
```

This method is used to dispose of an entire Set instance. It also disposes of all of the objects or associations in the Set by the use of the Dispose method applied to each object. There is no value returned.

See also: DeepDispose::Set, Dispose::Set, DisposeAllNodes1::Set

DisposeAllNodes::Set [DisposeAllNodes]

```
i = gDisposeAllNodes(i);
object i;
```

This method is used to remove all objects in a **Set** instance without disposing of the set itself. It does not dispose of any of the objects or associations in the **Set**, they are simply disassociated with the **Set**.

The value returned is always the instance passed.

See also: DeepDisposeAllNodes::Set, DisposeAllNodes1::Set, Dispose::Set

```
DisposeAllNodes1::Set
```

[DisposeAllNodes1]

```
i = gDisposeAllNodes1(i);
object i;
```

This method is used to remove all objects in a **Set** instance without disposing of the set itself. Each object or association in the set are disposed of via **Dispose**.

The value returned is always the instance passed.

```
object i;
int (*fun)(object);
```

This method is used to remove and dispose of a group of objects from the Set i. The function, fun, is executed for each object in the Set. With each call fun is passed the object at that point in the Set. If fun returns a 1 that particular object will be removed, or else if fun returns a 0 the object will not be removed. fun is used to decide which objects will be removed.

The objects removed are disposed of by use of the Dispose method.

```
See also: GroupRemove::Set, DeepDisposeGroup::Set
```

```
DisposeObj::Set
```

[DisposeObj]

```
r = gDisposeObj(i, luk);
object i;
object luk;
object r;
```

This method is used to remove and dispose of an object (luk) from the Set instance (i). If it is not found NULL is returned, otherwise i is returned. luk is disposed of by use of the Dispose method.

luk may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Set.

```
See also: RemoveObj::Set, DeepDisposeObj::Set
```

Find::Set [Find]

```
r = gFind(i, luk);
object i;
object luk;
object r;
```

This method is used to find an existing object (luk) in the Set instance (i). If the object is found in the Set it will be returned otherwise Find will return NULL.

luk may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Set.

See also: Add::Set, FindAdd::Set, RemoveObj::Set

FindAdd::Set [FindAdd]

```
r = gFindAdd(i, luk);
object i;
object luk;
object r;
```

This method is used to find an existing object (luk) in the Set instance (i) and return it. If the object is not found it will be added and returned.

luk may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Set.

See also: Add::Set, Find::Set, RemoveObj::Set

First::Set [First]

```
r = gFirst(i);
object i;
object r;
```

This method returns one of the objects in the set. The returned object will be an arbitrary one in the set. This method is useful in cases where you want to enumerate through each object in the set where you will perform some operation on the returned object and then remove or dispose it from the set. In that case the next call to <code>gFirst</code> will simply return a different object from the set.

If no objects are left in the set, gFirst returns NULL.

```
See also: RemoveObj::Set, Sequence::Set
```

ForAll::Set [ForAll]

```
r = gForAll(i, fun);
object i;
object (*fun)(object);
object r;
```

This method is used to execute function fun on each object in a Set.

Each time fun is called it is passed the next object in the Set as its first and only argument. If fun returns a non-NULL object, ForAll returns immediately with the value returned by fun. As long as fun returns NULL it will be passed successive objects in the Set until there are no more objects. At that time ForAll will just return NULL indicating that all objects have been enumerated.

See also: Sequence::Set

GroupRemove::Set [GroupRemove]

```
i = gGroupRemove(i, fun);
object i;
int (*fun)(object);
```

This method is used to remove a group of objects from the Set i. The function, fun, is executed for each object in the Set. With each call fun is passed the object at that point in the Set. If fun returns a 1 that particular object will be removed, or else if fun returns a 0 the object will not be removed. fun is used to decide which objects will be removed.

The objects removed are not disposed.

See also: DisposeGroup::Set, DeepDisposeGroup::Set

RemoveObj::Set [RemoveObj]

```
r = gRemoveObj(i, luk);
object i;
object luk;
object r;
```

This method is used to remove an object (luk) from the Set instance (i) and return it. If the object is not found NULL will be returned. luk is not disposed.

luk may be any Dynace object. The gHash and gCompare generics are used to find and compare the various objects in the Set.

See also: DisposeObj::Set, DeepDisposeObj::Set

Resize::Set [Resize]

```
r = gResize(i, size);
object i;
int size;
object r;
```

This method is used to change the size of the hash table used to implement the Set. It may be used if during runtime it is discovered that the number of objects stored or to be stored in the Set are very different than the number used when the Set was created.

Since a Set is implemented as a hash table it is best if size is actually larger than the number of objects to be held. It should be an odd number or better yet a prime number. Keep in mind, however, that there is storage requirements associated with this number and the use of a very large number will consume large memory resources. The Set will support more objects than defined by size at a lesser efficiency. In reality most reasonable numbers will work fine.

r is the re-sized Set.

This method is very time consuming and should only be used when absolutely necessary.

See also: NewWithInt::Set

Sequence::Set [Sequence]

```
s = gSequence(i);
object i;
object s;
```

This method takes an instance of the Set class (i) and returns an instance of the SetSequence class (s). The Set represented by i is not effected by this operation. The Set sequence item, s, is used to enumerate through all the objects in Set i. See the SetSequence class for documentation of other methods needed to use s.

Example:

See also: Next::SetSequence, First::Set

Size::Set [Size]

```
sz = gSize(i);
object i;
int sz;
```

This method is used to obtain the number of objects in the Set.

```
StringRep::Set [StringRep]
```

```
s = gStringRep(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the object i and its value. This is often used to print or display a representation of an object. It is also used by Print::Object (a method useful during the debugging phase of a project) in order to directly print an object to a stream.

This method obtains the values of each object by calling StringRepValue on each element.

See also: Print::Object, PrintValue::Object

5.43 SetSequence Class

This class is a subclass of Sequence and is used to provide a mechanism to enumerate through all the objects in a Set (or one of its subclasses) without effecting the structure.

Typically, the Sequence instance method of the Set class is used to create the instances of the SetSequence class.

5.43.1 SetSequence Class Methods

There is only one class method associated with this class. It is used to create new instances of itself and is only called by the Sequence method associated with the Set class.

5.43.2 SetSequence Instance Methods

This class only has a single instance method which is used to enumerate through objects in the Set.

```
Next::SetSequence [Next]
```

```
obj = gNext(i);
object i;
object obj;
```

This method is used to enumerate through all the objects in a Set. Each time Next is called the following object in the Set is returned. It does this in a non-destructive way so the associated Set is not effected.

When Next is called after the last object has been returned (or if there are no objects in the Set) it will return NULL and automatically dispose of the sequence object i. Therefore, the only time Dispose would be needed (if the garbage collector weren't being used) would be if the entire list was not enumerated.

Note that if this method is used with one of the Dictionary classes each call to Next returns the appropriate Association type. The gValue and gKey generics may be used to obtain the desired values from the Association returned.

Example:

See also: Sequence::Set

5.44 ShortArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language short data type in an efficient manner. Although this class implements much of its own functionality most of it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.44.1 ShortArray Class Methods

There is only one class method which is particular to this class.

This method is used to create a ShortArray which has 1 dimension of length n. The first element is initialized with the value set by IndexOrigin::Array and each successive element is given a value one greater than the previous element.

The value returned is the new array.

Example:

int

```
object ary;
ary = gIota(ShortArray, 5);
/* ary = (0, 1, 2, 3, 4) */
```

See also: IndexOrigin::Array

5.45 ShortInteger Class

The ShortInteger class is used to represent the C language short data type as a Dynace object. It is a subclass of the Number class. Even though the ShortInteger class implements most of its own functionality, it is documented as part of the Number class because most of the interface is the same for all subclasses of the Number class. Differences are documented in this section.

5.45.1 ShortInteger Class Methods

The ShortInteger class has only one class method and it is used to create new instances of itself.

NewWithInt::ShortInteger [NewWithInt]

```
i = gNewWithInt(ShortInteger, s);
int    s;
object i;
```

This class method creates instances of the ShortInteger class. s is the initial value of the integer being represented. Note that s is of type int. That is because if you pass a short type to a generic function (which uses a variable argument declaration) the C language will automatically promote it to an int.

The value returned is a Dynace instance object which represents the integer passed.

Note that the default disposal methods are used by this class since there are no special storage allocation requirements.

Example:

```
object x;
x = gNewWithInt(ShortInteger, 55);
```

See also: ShortValue::Number, Dispose::Object

5.45.2 ShortInteger Instance Methods

The instance methods associated with the ShortInteger class provide a means of changing and obtaining the value associated with an instance of the ShortInteger class. All of the ShortInteger class instance methods are documented in the Number class because of their common interface with all other subclasses of the Number class.

5.46 Socket Class

The Socket class is a subclass of Stream and provides facilities which make utilizing sockets easy and portable. Sockets provide a mechanism for network communication over TCP or the Internet.

At present only the client-side methods are implemented.

5.46.1 Socket Class Methods

The only class method is used to open a new socket which equates to forming a connection with a server.

SocketConnect::Socket [SocketConnect]

```
skt = gSocketConnect(Socket, addr, port);
char *addr;
int port;
object skt;
```

This method is used to form a connection between a client and server. The application calling this method would be the client side. In order to form a connection the IP address ("123.456.789.012") or domain name ("prep.ai.mit.edu") as well as the port number of the server application must be known. addr is a character string representing the IP address or domain name, and port is the port number for the server application. This information would always be known by the organization responsible for the server end.

gSocketConnect returns an object which represents the connection or NULL if the connection was not made.

Example:

```
object skt = gSocketConnect(Socket, "192.44.32.44", 4099);
```

See also: Dispose::Socket

5.46.2 Socket Instance Methods

Instance methods associated with the Socket class enable data to be sent to and from a client / server pair of applications.

```
Dispose::Socket [Dispose]
```

```
r = gDispose(skt);
object skt;
object r; /* NULL */
```

This method is used to close a socket connection and dispose of its associated object. There is also a gDeepDispose which performs the same function.

```
GetErrorCode::Socket [GetErrorCode]
```

```
r = gGetErrorCode(skt);
object skt;
int r;
```

This method is used to obtain an error code which describes the last error on more detail.

Read::Socket [Read]

```
r = gRead(skt, buf, n);

object skt;
char *buf;
unsigned n;
int r;
```

This method is used to read n bytes into buf from Socket skt. The value returned is the actual number of bytes read or -1 on error. An error can occur for two reasons: a severed connection, or a time out error. In the case of a severed connection one would not want to continue use of that socket since it is probably not valid anymore.

gRead normally waits up to 60 seconds for reception of the requested bytes. If part of the data is received gRead will again wait up to 60 seconds for the remaining data. gRead continues to wait for *all* the data unless a connection error occurs or no data is received for at least 60 seconds.

Example:

See also: gTimedRead::Socket

RecvFile::Socket [RecvFile]

```
r = gRecvFile(skt, tf);

object skt;
char *tf;
int r;
```

This method is used to receive a whole file over a socket connection. ff is the name (and path) of the local file to where the received file is to be saved.

This method returns 0 on success or non-zero upon failure. This method makes some degree of effort (via acknowledgments and check sums) to assure that the file was in fact correctly received.

This method is unique to Dynace which means that the server end would have to have the correct receive function in order for this facility to be used.

Example:

See also: SendFile::Socket

SendFile::Socket [SendFile]

```
r = gSendFile(skt, ff, tf);

object skt;
char *ff;
char *tf;
int r;
```

This method is used to transmit a whole file over a socket connection. ff is the name (and path) of the local file to be transmitted. tf is the name of the file that the receiving end will see (i.e. the name of the file the receiving end will think you are sending). If tf is NULL then ff is used.

This method returns 0 on success or non-zero upon failure. This method makes some degree of effort (via acknowledgments and check sums) to assure that the file was in fact correctly received by the other end.

This method is unique to Dynace which means that the server end would have to have the correct receive function in order for this facility to be used.

Example:

```
if (gSendFile(skt, "../myFile", NULL))
     handle error;
```

See also: RecvFile::Socket

TimedRead::Socket [TimedRead]

```
r = gTimedRead(skt, buf, n, w);

object skt;
char *buf;
unsigned n;
int w;
int r;
```

This method is used to read n bytes into buf from Socket skt. The value returned is the actual number of bytes read or -1 on error. An error can occur for two reasons: a severed connection, or a time out error. In the case of a severed connection one would not want to continue use of that socket since it is probably not valid anymore.

gTimedRead normally waits up to w seconds for reception of the requested bytes. If part of the data is received gTimedRead will again wait up to w seconds for the remaining data. gTimedRead continues to wait for *all* the data unless a connection error occurs or no data is received for at least w seconds.

Example:

See also: gRead::Socket

TimedWrite::Socket [TimedWrite]

```
r = gTimedWrite(skt, buf, n, w);

object skt;
char *buf;
unsigned n;
int w;
int r;
```

This method is used to send n bytes from buf to Socket skt. The value returned is the actual number of bytes sent or -1 on error. An error can occur for two reasons: a severed connection, or a time out error. In the case of a severed connection one would not want to continue use of that socket since it is probably not valid anymore.

gTimedWrite normally waits up to w seconds for the ability to send the requested bytes. If part of the data is sent gTimedWrite will again wait up to w seconds for the remaining data. gTimedWrite continues to wait until all the data is sent unless a connection error occurs or no data is able to send for at least w seconds.

Successfully sending data does not guarantee that the data was received on the other end. You must send back some kind of acknowledgement to assure that.

Example:

```
if (12 != gTimedWrite(skt, "Hello, World", 12, 60))
    error code;
```

See also: gWrite::Socket

Write::Socket [Write]

```
r = gWrite(skt, buf, n);
object skt;
char *buf;
unsigned n;
int r;
```

This method is used to send n bytes from buf to Socket skt. The value returned is the actual number of bytes sent or -1 on error. An error can occur for two reasons: a severed connection, or a time out error. In the case of a severed connection one would not want to continue use of that socket since it is probably not valid anymore.

gWrite normally waits up to 60 seconds for the ability to send the requested bytes. If part of the data is sent gWrite will again wait up to 60 seconds for the remaining data. gWrite continues to wait until all the data is sent unless a connection error occurs or no data is able to send for at least 60 seconds.

Successfully sending data does not guarantee that the data was received on the other end. You must send back some kind of acknowledgement to assure that.

Example:

```
if (12 != gWrite(skt, "Hello, World", 12))
    error code;
```

See also: gTimedWrite::Socket

5.47 Stream Class

The Stream class is an abstract class used to group other classes which poses the ability to read and write characters sequentially. Although much of the actual functionality is implemented by its subclasses, the methods are documented here because of their common interface.

5.47.1 Stream Class Methods

There are no class methods associated with this class.

5.47.2 Stream Instance Methods

Although most of the following methods are actually implemented in the subclasses of Stream, they are documented here because of their common interface. Note that some methods are not available for all subclasses of the Stream class. This would occur if the method is inappropriate for a particular Stream subclass (such as seeking backward on a String).

Advance::Stream [Advance]

```
r = gAdvance(i, n);
object i;
long n;
long r;
```

This method is used to advance the position of the next read of Stream i forward by n bytes. The value returned is the actual number of bytes advanced or 0 on error.

See also: Seek::Stream, Retreat::Stream

EndOfStream::Stream [EndOfStream]

```
r = gEndOfStream(i);
object i;
int r;
```

This method returns 1 if Stream i is at the end of available characters and 0 otherwise. by i.

See also: Length::Stream, Position::Stream

```
Gets::Stream [Gets]
```

```
r = gGets(i, buf, sz);

object i;
char *buf;
int sz;
char *r;
```

This method is used to read a new-line terminated string from Stream i into buf. It will read no more than sz-1 bytes, but room permitting, the new-line will be included. r will be the same as buf unless there is an error, in which case r will be NULL.

Example:

```
char buf[80];
gGets(stdinStream, buf, sizeof buf);
```

See also: Read::Stream, Puts::Stream

```
Length::Stream [Length]
```

```
r = gLength(i);
object i;
long r;
```

This method is used obtain the total length of the Stream represented by i.

See also: Seek::Stream, Position::Stream

Position::Stream [Position]

```
r = gPosition(i);
object i;
long r;
```

This method is used obtain the current position in the stream relative to its beginning.

See also: Seek::Stream, Length::Stream

Printf::Stream [Printf]

```
r = vPrintf(i, fmt, ...);

object i;
char *fmt;
int r;
```

This method is used to write a formatted string to stream i. fmt specifies the format of the output as well as the types and number of remaining arguments. Since this method is implemented by the use of the vsprintf function supplied by the host system you may find more detailed description of the arguments to this method in the manual supplied by your host compiler (under fprintf). The only difference would be the first argument which would now be a Stream instance.

The value returned is the number of bytes actually written to the stream.

Example:

```
vPrintf(stdoutStream, "I am %d years old.\n", 10);
```

See also: Puts::Stream

Putc::Stream [Putc]

```
r = gPutc(i, ch);
object i;
char ch;
int r;
```

This method is used to write a character (ch) to stream i. The value returned is the character written or EOF if error.

Example:

```
gPutc(stdoutStream, 'x');
```

See also: Puts::Stream

Puts::Stream [Puts]

```
r = gPuts(i, str);
object i;
char *str; /* or: object str; */
int r;
```

This method is used to write a string (str) to stream i. str may also be an instance of the String class in which case the associated string will be written. All the characters up to the first null byte will be written. The value returned is the number of bytes written to the stream.

Example:

```
gPuts(stdoutStream, "Hello\n");
See also: Putc::Stream, Printf::Stream
```

Read::Stream [Read]

```
r = gRead(i, buf, n);
object i;
char *buf;
unsigned n;
int r;
```

This method is used to read n bytes into buf from Stream i. The value returned is the actual number of bytes read or -1 on error.

Example:

```
char buf[80];
gRead(stdinStream, buf, 10);
```

See also: Gets::Stream

Retreat::Stream [Retreat]

```
r = gRetreat(i, n);
object i;
long n;
long r;
```

This method is used to retreat the position of the next read of Stream i by n bytes. The value returned is the actual number of bytes retreated or 0 on error.

See also: Seek::Stream, Advance::Stream

Seek::Stream [Seek]

```
r = gSeek(i, n);
object i;
long n;
long r;
```

This method is used to seek to position n of Stream i relative to the beginning of the stream. The value returned is the actual position seeked to or 0 on error.

See also: Retreat::Stream, Advance::Stream

Write::Stream [Write]

```
r = gWrite(i, buf, n);
object i;
char *buf;
unsigned n;
int r;
```

This method is used to write n bytes from buf into Stream i. The value returned is the actual number of bytes written or -1 on error.

Example:

```
gWrite(stdoutStream, "Hello", 5);
```

See also: Puts::Stream, Read::Stream

5.47.3 Stream Global Variables

There are several global variables associated with the Stream class. These variables represent standard streams used throughout Dynace. They are used for diagnostic output as well as any other input or output which may be necessary on a global basis. These variables may be assigned different streams in order to redirect the output. The remainder of this section documents all the global stream variables.

```
stderrStream::Stream [stderrStream]
```

```
object stderrStream;
```

The stderrStream global variable is used to direct error messages to the correct output medium. It is initialized to an instance of the File class using the C language stderr stream. It may be set to any instance of a subclass of Stream.

See also: stdoutStream::Stream

stdinStream::Stream [stdinStream]

object stdinStream;

The stdinStream global variable is used as a global mechanism for obtaining input. It is initialized to an instance of the File class using the C language stdin stream. It may be set to any instance of a subclass of Stream.

See also: stdoutStream::Stream

stdoutStream::Stream [stdoutStream]

object stdoutStream;

The stdoutStream global variable is used to direct normal output to the correct output medium. It is initialized to an instance of the File class using the C language stdout stream. It may be set to any instance of a subclass of Stream.

See also: stderrStream::Stream

traceStream::Stream [traceStream]

object traceStream;

The traceStream global variable is used to direct Dynace trace output to the correct output medium. It is initialized to an instance of the File class using the C language stdout stream. It may be set to any instance of a subclass of Stream.

See also: stderrStream::Stream

5.48 String Class

The String class is used to represent the C language char * data type as a Dynace object. It is a subclass of the Stream class and it provides an array of methods to operate on the string objects. Unlike C strings this class will dynamically expand a string buffer as needed so you should never have to worry about the buffer size. You can also use the MA_compact function to compact the string memory and reduce memory fragmentation.

Most of the String methods which take string arguments (except the first argument) will accept a C language string (char *) or an instance of the String class arbitrarily. The system can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

Instances of this class will also operate like other subclasses of **Stream**. That is you can write (append), read (copy and remove), advance (remove leading characters) and obtain its length. This comes in handy when you wish to keep a small (and fast) sequential file in memory.

5.48.1 String Class Methods

The String class has several class methods which create new String instances. They are provided to lend various levels of flexibility.

```
Build::String [Build]
```

```
i = vBuild(String, ...);
object i;
```

This class method creates a new instance of the String class. The initial value of the new instance will be the concatenation of all the String or char * arguments up to an END.

Each argument may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

Note that the variable argument list MUST end with an END. There is no other way in C to tell when the last argument has been reached. If you forget the END the system will probably hang! (If you have a problem with the system hanging you might want to check all the vBuild generic calls.)

The value returned is the new String instance.

Example:

```
object x, y;
x = gNewWithStr(String, "World");
y = vBuild(String, "Hello", x, "!", END);
/* y = "Hello World!" */
```

See also: StringValue::String, Dispose::String, There is also an instance method Build::String

MaskFunction::String

[MaskFunction]

```
fun = gMaskFunction(String, ch);
char ch;
int (*fun)();
```

This method is used to return the masking function associated with the mask character ch.

Currently there are only two masking characters used in the system, '#' (numbers) and '@' (letters). The '#' character's associated function is isdigit while the '@' character's associated function is isalpha.

The masking function associated with a masking character takes a character as its only parameter and returns non-zero if the character is the masking character associated with the function and returns zero if it is not.

Example:

See also: gSetMaskFiller::String, gApplyMask::String, gRemoveMask::String

New::String [New]

```
i = gNew(String);
object i;
```

This class method creates instances of the String class. The returned String object is initialized to "".

The value returned is a Dynace instance object which represents a null string.

Example:

This class method creates instances of the String class. val is the initial value of the string being represented.

val may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

The value returned is a Dynace instance object which represents the string passed.

Example:

This class method creates instances of the String class. val is the initial value of the string being represented.

val may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

The value returned is a Dynace instance object which represents the string passed.

Example:

This class method creates a new instances of the String class. Except for the first argument and return value, this method takes the same arguments and performs the same function as the normal **sprintf** contained in your C library. See that documentation.

Note that except for the first argument, this method does not take Dynace objects.

The value returned is a Dynace instance object which represents the result of the operation.

Example:

```
object x;
x = vSprintf(String, "%s is %d years old", "John", 66);
```

5.48.2 String Instance Methods

See also: StringValue::String, Dispose::String

The instance methods associated with the String class provide a means of changing and obtaining the value associated with an instance of the String class. Methods are also included to help the generic container classes to quickly access members of this class.

Append::String [Append]

```
i = gAppend(i, str);
object i;
char *str; /* or object */
```

This method is used to append the string represented by str to the end of the string represented by i.

str may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

The value returned is the String instance passed (i).

Example:

```
object x;
x = gNewWithStr(String, "Hello");
gAppend(x, " World!");
/* x = "Hello World!" */
```

See also: ChangeValue::String, Build::String

ApplyMask::String [ApplyMask]

```
i = gApplyMask(i, mask, text);
object i;
char *mask;
char *text;
```

This method is used to apply mask to text and set the resulting value to i. If NULL or an empty string ("") is passed in to mask then i has its string value changed to text. If NULL or an empty string ("") is passed in to text then mask is applied directly to the current string value in i.

Mask definitions contain any combination of mask characters and literal characters. The first character of a mask can optionally be either '>' or '<' indicating the direction which the mask is applied to the string. If the first character is '<' then the mask is applied from right to left. If the first character is '>' or is neither of the directional characters, then the mask is applied from left to right. The mask character '#' indicates that the character in this position must be a number while the mask character '@' indicates that the character in this position must be a letter. Any other character in the mask is a literal character and is left in the resulting string in its position unchanged.

The value returned is the String instance passed (i).

Example:

```
object x;

char mask = "<(###) ###-####";

x = gNewWithStr(String, "1234567890");

gApplyMask(x, mask, NULL); /* x = "(123) 456-7890" */

gApplyMask(x, mask, "9876543210"); /* x = "(987) 654-3210" */

gApplyMask(x, NULL, "1234567890"); /* x = "1234567890" */
```

See also: gMaskFunction::String, gSetMaskFiller::String, gRemoveMask::String

Build::String [Build]

```
i = vBuild(str, first, ...);
object str;
char *first; /* or object */
object i;
```

This method is used to modify the string associated with instance str by optionally overwriting and optionally appending a group of C strings or String objects.

first may be an instance of the String class, a C string char * or a NULL. If first is NULL the initial value of str will remain intact, otherwise, it will be replaced with the string represented by first.

After the first argument has been processed the remaining String or char * arguments, up to an END, will be concatenated to the end of str.

Each argument may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

Note that the variable argument list MUST end with an END. There is no other way in C to tell when the last argument has been reached. If you forget the END the system will probably hang! (If you have a problem with the system hanging you might want to check all the vBuild generic calls.)

The value returned is the String instance passed (str).

Example:

```
object x;

x = gNewWithStr(String, "Hello");
vBuild(x, NULL, " World", gNewWithStr(String, "!"), END);
/* x = "Hello World!" */

vBuild(x, "Goodbye", " World", "!", END);
/* x = "Goodbye World!" */
```

See also: ChangeValue::String, Append::String, There is also a class method Build::String

ChangeCharAt::String

[ChangeCharAt]

```
i = gChangeCharAt(i, n, c);
object i;
int n;
int c;
```

This method is used to change the character at position n within String instance i to character c. The index origin is zero.

If n is equal to the number of characters in instance i (that is one greater than the number of indexable characters), string i will be extended by one character (c). However, if any larger index is used Dynace will issue an error message and abort the program.

Example:

```
object x;
x = gNewWithStr(String, "Hello");
gChangeCharAt(x, 1, 'E');
/* x = "HEllo" */
```

See also: CharValueAt::String

ChangeStrValue::String

[ChangeStrValue]

```
i = gChangeStrValue(i, val);
object i;
char *val;
```

This method is used to change the value associated with an instance of the String class. The new value may be of any length.

The value returned is the instance i.

Example:

```
object x, y;
x = gNewWithStr(String, "Hello World");
gChangeStrValue(x, "Are you all using Dynace?");
```

See also: ChangeValue::String, Append::String, Build::String

ChangeValue::String [ChangeValue]

```
i = gChangeValue(i, val);
object i;
object val; /* or char * */
```

This method is used to change the value associated with an instance of the String class. The new value may be of any length.

val may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

The value returned is the instance i.

Example:

```
object x, y;

x = gNewWithStr(String, "Hello World");
y = gNewWithStr(String, "Are you all using Dynace?");
gChangeValue(x, y);
```

See also: ChangeStrValue::String, Append::String, Build::String

CharValueAt::String [CharValueAt]

```
c = gCharValueAt(i, n);
object i;
int n;
char c;
```

This method is used to obtain character n from String instance i. The index origin is zero. If an index greater than the available characters is used Dynace will issue an error message and abort the program.

Example:

```
object x;
char c;

x = gNewWithStr(String, "Hello");
c = gCharValueAt(x, 1);
/* c = 'e' */
```

See also: ChangeCharAt::String

Compare::String

[Compare]

```
r = gCompare(i, obj);
object i;
object obj; /* or char * */
int r;
```

This method is used to determine the equality of the values represented by i and obj.

obj may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

This method is also used by the generic container classes to determine object relationships.

See also: Equal::String, CompareI::String, CompareN::String

CompareI::String

[CompareI]

```
r = gCompareI(i, obj);
object i;
object obj; /* or char * */
int r;
```

This method is used to determine the equality of the values represented by i and obj without regard for the case of the letters. Therefore, strings such as "abc" and "ABC" will be considered equal.

obj may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

See also: Compare::String, CompareN::String

CompareN::String [CompareN]

```
r = gCompareN(i, obj, n);
object i;
object obj; /* or char * */
int n; /* max number of characters to compare */
int r;
```

This method is used to determine the equality of the values represented by i and obj. No more than n characters will be compared. If the two strings only differ past n characters they will be considered equal.

obj may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

See also: Compare::String, CompareNI::String

CompareNI::String [CompareNI]

```
r = gCompareNI(i, obj, n);
object i;
object obj; /* or char * */
int n; /* max number of characters to compare */
int r:
```

This method is used to determine the equality of the values represented by i and obj without regard for the case of the letters. Therefore, strings such as "abc" and "ABC" will be considered equal. No more than n characters will be compared. If the two strings only differ past n characters they will be considered equal.

obj may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

[DeepCopy]

r is -1 if the value represented by i is less than the value represented by obj, 1 if the value of i is greater than obj, and 0 if they are equal.

See also: CompareI::String, CompareN::String

Copy::String [Copy]

```
so = gCopy(i);
object i, so;
```

This method is used to create a new instance of the String class with the same string value as string i. Or put more simply, it makes a copy. The new String instance is returned.

This method performs the same function as DeepCopy::String.

Example:

```
object x, y;

x = gNewWithStr(String, "Hello");
y = gCopy(x);
/* x = "Hello" */
```

See also: New::String, DeepCopy::String

DeepCopy::String

```
so = gDeepCopy(i);
object i, so;
```

This method is used to create a new instance of the String class with the same string value as string i. Or put more simply, it makes a copy. The new String instance is returned.

This method performs the same function as Copy::String.

Example:

```
object x, y;

x = gNewWithStr(String, "Hello");
y = gDeepCopy(x);
/* x = "Hello" */
```

```
See also: New::String, Copy::String
DeepDispose::String
                                                                    [DeepDispose]
          r = gDeepDispose(i);
          object i;
                          /* NULL */
           object r;
     This method is used to dispose of an instance of the String class. It performs the
     same operation as Dispose.
     Example:
          object x;
           x = gNewWithStr(String, "Hello World");
           gDeepDispose(x);
                                                                        [Dispose]
Dispose::String
          r = gDispose(i);
           object i;
                         /* NULL */
           object r;
     This method is used to dispose of an instance of the String class. It performs the
     same operation as DeepDispose.
     Example:
          object x;
           x = gNewWithStr(String, "Hello World");
           gDispose(x);
Drop::String
                                                                           [Drop]
           i = gDrop(i, num);
```

This method is used to drop num characters from string i. If num is positive characters will be dropped from the beginning of the string, otherwise, characters will be dropped from the end of the string. An attempt to drop more characters than exist will lead to a zero length string.

The modified String instance passed is returned.

object i;

num;

int

Example:

```
object x, y;

x = gNewWithStr(String, "Hello World");
gDrop(x, 4);  /* x = "o World" */
x = gNewWithStr(String, "Hello World");
gDrop(x, -4);  /* x = "Hello W" */
x = gNewWithStr(String, "ABC");
gDrop(x, 5);  /* x = "" */
```

See also: Take::String, SubString::String

Equal::String [Equal]

```
r = gEqual(i, obj);
object i;
object obj; /* or char * */
int r;
```

This method is used to determine the equality of the values represented by i and obj. If they contain the same string values a 1 is returned and 0 otherwise.

obj may be a C language char * or an instance of the String class. Dynace can tell the difference between them at runtime. If it is a valid Dynace object the system will assure that it is a kind of String, otherwise it is assumed to be a C string.

Example:

See also: Compare::String

Hash::String [Hash]

```
val = gHash(i);
object i;
int val;
```

This method is used by the generic container classes to obtain hash values for the object. val is a hash value between 0 and a large integer value.

See also: Compare::String

object i;

This method is used to center justify the text within a string. The length of the string is not modified, only the position of the characters within the string. It is often used in conjunction with Take::String in order to format text.

The modified String instance passed is returned.

Example:

```
object x;

x = gNewWithStr(String, "ABD DEF DD ");
gJustifyCenter(x); /* x = " ABD DEF DD " */
x = gNewWithStr(String, "ABD DEF");
gJustifyCenter(gTake(x, 14)); /* x = " ABD DEF " */
```

See also: Take::String, JustifyRight::String, JustifyLeft::String

```
JustifyLeft::String
    i = gJustifyLeft(i);
    object i;
[JustifyLeft]
```

This method is used to left justify the text within a string. The length of the string is not modified, only the position of the characters within the string. It is often used in conjunction with Take::String in order to format text.

The modified String instance passed is returned.

Example:

```
object x;
          x = gNewWithStr(String, "
                                                 DD");
                                       ABD DEF
          gJustifyLeft(x);
                            /* x = "ABD DEF
          x = gNewWithStr(String, "ABD DEF");
          gJustifyLeft(gTake(x, 10));
                                        /* x = "ABD DEF
                                                                */
     See also: Take::String, JustifyCenter::String,
             JustifyRight::String
JustifyRight::String
                                                                [JustifyRight]
          i = gJustifyRight(i);
          object i;
```

This method is used to right justify the text within a string. The length of the string is not modified, only the position of the characters within the string. It is often used in conjunction with Take::String in order to format text.

The modified String instance passed is returned.

Example:

```
object x;
          x = gNewWithStr(String, "ABD DEF DD
                                                   ");
          gJustifyRight(x);
                             /* x = "
                                          ABD DEF DD"
          x = gNewWithStr(String, "ABD DEF");
          gJustifyRight(gTake(x, 10));
                                        /* x = "
                                                   ABD DEF"
     See also: Take::String, JustifyCenter::String,
             JustifyLeft::String
NumbPieces::String
                                                                [NumbPieces]
         n = gNumbPieces(i, d);
          object
                 i;
          char
                  d;
                     /* delimiter
          int
                    /* number of pieces */
```

This method is used to determine the number of sub-strings located in i. It is assumed that i is a string which contains the delimiter character d. That delimiter character is used to logically split string i into several sub-strings.

Example:

```
object x;
int n;
x = gNewWithStr(String, "ABD,DEF,DD");
n = gNumbPieces(x, ','); /* n = 3 */
```

See also: Piece::String

Piece::String [Piece]

```
r = gPiece(i, d, n);

object i;
char d; /* delimiter */
int n; /* piece wanted */
object r; /* sub-string */
```

This method is used to create a new string object which will contain a copy of a sub-string of i. It is assumed that i is a string which contains the delimiter character d. That delimiter character is used to logically split string i into several sub-strings. n is used to specify which sub-string is desired.

This method returns a new string object which will contain a copy of the desired sub-string. A NULL is returned if n is greater than the number of sub-strings in i.

Example:

```
object x, y;

x = gNewWithStr(String, "ABD,DEF,DD");
y = gPiece(x, ',', 0); /* y="ABD" */
y = gPiece(x, ',', 1); /* y="DEF" */
y = gPiece(x, ',', 2); /* y="DD" */
```

See also: NumbPieces::String

PrintLength::String

[PrintLength]

```
sz = gPrintLength(i, ts);
object i;
int ts;
int sz;
```

This method is used to obtain the length of the string associated with the instance of the String class passed when it is printed. This method takes into account tabs, backspaces and return characters in its calculations.

ts is the tab stop size that the method should use.

Note that this is one of the few generics which doesn't return a Dynace object. It returns an integer.

Example:

```
object x;
int sz;
x = gNewWithStr(String, "Hello\tWorld\bx");
sz = gPrintLength(x, 8);
/* sz = 13 */
```

See also: Size::String

Process::String [Process]

```
i = gProcess(i);
object i;
```

This method is used to process a string with embedded escape sequences. The escape sequences will be processed and converted into the appropriate control characters. For example "\r" will be converted in to a return control character. All the ANSI standard escape sequences are supported. In addition, "\e" gets converted into the escape character. "\^L" (where L may be any letter - upper or lower case) gets converted into the corresponding control character, for example "\^G" will get converted to the control-G character. "\dnnn" works like "\xnnn" except that nnn is treated as a decimal number.

Example:

```
object x;
x = gNewWithStr(String, "Hello\\tWorld\\bx");
gProcess(x);
/* x will now contain the real control characters */
```

See also: PrintLength::String

RemoveMask::String [RemoveMask]

```
i = gRemoveMask(i, mask, text);
object i;
char *mask;
char *text;
```

This method is used to remove mask from text and set the resulting value to i. If NULL or an empty string ("") is passed in to mask then i has its string value changed to text. If NULL or an empty string ("") is passed in to text then mask is removed from the current string value in i.

The value returned is the String instance passed (i).

Example:

```
object x;

char mask = "<(###) ###-####";

x = gNewWithStr(String, "(123) 456-7890");

gRemoveMask(x, mask, NULL); /*x="1234567890" */

gRemoveMask(x, mask, "(987)654-3210"); /*x="9876543210" */

gRemoveMask(x, NULL, "(123) 456-7890");/*x="(123) 456-7890"*/
```

See also: gMaskFunction::String, gSetMaskFiller::String, gApplyMask::String

```
SetMaskFiller::String [SetMaskFiller]
```

```
r = gSetMaskFiller(i, ch);
object i;
char ch;
char r;
```

This method is used to set the character to be used to fill the unused space in a masked string. This character defaults to be a space but is frequently set to be the underscore ('_') character. This method returns the previous mask filler character.

Example:

See also: gMaskFunction::String, gApplyMask::String, gRemoveMask::String

Size::String [Size]

```
sz = gSize(i);
object i;
int sz:
```

This method is used to obtain the length of the string associated with the instance of the String class passed.

Note that this is one of the few generics which doesn't return a Dynace object. It returns an integer.

Example:

```
object x;
int sz;
x = gNewWithStr(String, "Hello World");
sz = gSize(x);
/* sz = 11 */
```

See also: PrintLength::String

StringRepValue::String

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
object x;
object s;

x = gNewWithStr(String, "Hello");
s = gStringRepValue(x);
    /* s represents "Hello" (with quotes) */

See also: StringValue::String, PrintValue::Object, Print::Object

StringValue::String [StringValue]

val = gStringValue(i);
object i;
char *val;
```

This method is used to obtain the **char** * value associated with an instance of the String class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a char * string.

Example:

object i;

```
object x;
char *val;

x = gNewWithStr(String, "Hello World");
val = gStringValue(x);

See also: New::String, ChangeValue::String

StripCenter::String [StripCenter]

i = gStripCenter(i);
```

This method is used to strip off blank characters (space, tab, new line, carriage return) from both sides of a string. The return value is the modified String instance passed.

Example:

```
object x, y;
x = gNewWithStr(String, " ABD DEF DD ");
gStripCenter(x); /* x = "ABD DEF DD" */
```

See also: StripRight::String, StripLeft::String

StripLeft::String

[StripLeft]

```
i = gStripLeft(i);
object i;
```

This method is used to strip off blank characters (space, tab, new line, carriage return) from the left side of a string. The return value is the modified String instance passed.

Example:

```
object x, y;
x = gNewWithStr(String, " ABD DEF DD ");
gStripLeft(x); /* x = "ABD DEF DD " */
```

See also: StripRight::String, StripCenter::String

StripRight::String

[StripRight]

```
i = gStripRight(i);
object i;
```

This method is used to strip off blank characters (space, tab, new line, carriage return) from the right side of a string. The return value is the modified String instance passed.

Example:

```
object x, y;
x = gNewWithStr(String, " ABD DEF DD ");
gStripRight(x); /* x = " ABD DEF DD" */
```

See also: StripLeft::String, StripCenter::String

SubString::String [SubString]

```
so = gSubString(i, beg, num);
object i;
int beg, num;
object so;
```

This method is used to create a new instance of the String class which is initialized to a copy of a sub-string of instance i. beg indicates the beginning position number of the string to be copied, index origin zero. num is the number of characters to copy.

If beg is negative, beg will be converted to a beginning point relative to the end of the string. Therefore, a -1 would indicate a starting point of the last character in the string and -2 would indicate a starting point of the second to the last character in the string. Zero indicates to start at the beginning of the string.

If num is negative, -num characters before beg will be taken.

The new String instance is returned.

Example:

```
object x, y;

x = gNewWithStr(String, "Hello World");
y = gSubString(x, 1, 3); /* y = "ell" */
y = gSubString(x, -5, 5); /* y = "World" */
```

See also: Take::String, Drop::String

Take::String [Take]

```
i = gTake(i, num);
object i;
int num:
```

This method is used to change the length of the string associated with the String instance i. num is the new length of the string. If num is less than the previous length of the string, the string will be terminated to the shorter length. If num is greater than the previous length, the string will be padded with spaces until it is num characters long.

If num is negative, characters will be taken from the end of the string and padding will be performed at the beginning of the string.

The modified String instance passed is returned.

Example:

```
object x, y;

x = gNewWithStr(String, "Hello World");
gTake(x, 4);  /* x = "Hello" */
x = gNewWithStr(String, "Hello World");
gTake(x, -4);  /* x = "orld" */
x = gNewWithStr(String, "ABC");
gTake(x, 5);  /* x = "ABC" */
x = gNewWithStr(String, "ABC");
gTake(x, -5);  /* x = "ABC" */
```

See also: Drop::String, SubString::String

ToLower::String [ToLower]

```
i = gToLower(i);
object i;
```

This method is used to convert all the characters in String instance i to lower case. Non-alphabetic characters are left unchanged. The instance passed is returned.

Example:

```
object x;
x = gNewWithStr(String, "Hello World");
gToLower(x);
/* x = "hello world" */
```

See also: ToUpper::String

ToUpper::String [ToUpper]

```
i = gToUpper(i);
object i;
```

This method is used to convert all the characters in String instance i to upper case. Non-alphabetic characters are left unchanged. The instance passed is returned.

Example:

```
object x;
x = gNewWithStr(String, "Hello World");
gToUpper(x);
/* x = "HELLO WORLD" */
```

See also: ToLower::String

5.49 StringAssociation Class

This class is a subclass of Association and is used to represent an association between a C language string and an arbitrary Dynace object. It performs all the functions as the LookupKey and ObjectAssociation classes and is used in conjunction with the Set and Dictionary classes. The purpose of this class is to provide an efficient mechanism to form a common association.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.49.1 StringAssociation Class Methods

The only class method associated with this class is one needed to create new instances of itself.

```
NewWithStrObj::StringAssociation [NewWithStrObj]
```

```
i = gNewWithStrObj(StringAssociation, key, val);
char *key;
object val; /* or NULL */
object i;
```

This class method creates instances of the StringAssociation class. key is used to initialize the key associated with the instance created and val is used to initialize its associated value. Note that internally key is copied into an allocated buffer so that it is all right to reuse the buffer passed to this method.

The new instance is returned.

5.49.2 StringAssociation Instance Methods

The instance methods associated with this class are used to obtain, change and print the key and value associated with the instance. Additional functionality, although implemented by this class, is documented in StringAssociation's superclass, Association. This is done because of the common interface these methods share with all subclasses of Association.

```
{\tt ChangeStringKey::StringAssociation} \qquad \qquad [{\tt ChangeStringKey}]
```

```
i = gChangeStringKey(i, key);
object i;
char *key;
```

This method is used to change the key associated with instance i. key is the new key. The old key is simply replaced. This method returns i.

```
See also: StringKey::StringAssociation,
ChangeValue::StringAssociation
```

```
ChangeValue::StringAssociation
```

[ChangeValue]

```
old = gChangeValue(i, val);
object i;
object val; /* or NULL */
object old;
```

This method is used to change the value associated with an association, i, to a value, val. The old value is simply no longer associated with the instance. It is not disposed. This method returns the old value being replaced.

See also: Value::StringAssociation,

ChangeStringKey::StringAssociation

Copy::StringAssociation

[Copy]

```
so = gCopy(i);
object i, so;
```

This method is used to create a new instance of the StringAssociation class with the *same* value as StringAssociation i. Or put more simply, it makes a copy. The new StringAssociation instance is returned.

See also: DeepCopy::StringAssociation

DeepCopy::StringAssociation

[DeepCopy]

```
so = gDeepCopy(i);
object i, so;
```

This method is used to create a new instance of the StringAssociation class which contains a *copy* of the value from the original StringAssociation. DeepCopy is used to create the copy of the value. The new StringAssociation instance is returned.

See also: Copy::StringAssociation

DeepDispose::StringAssociation

[DeepDispose]

```
r = gDeepDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of a StringAssociation instance. It also disposes of the value associated with the instance by the use of its DeepDispose method.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Dispose::StringAssociation

```
Dispose::StringAssociation
```

[Dispose]

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of a StringAssociation instance. It does not dispose of its associated value.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: DeepDispose::StringAssociation

Key::StringAssociation

[Key]

```
key = gKey(i);
object i;
object key;
```

This method is used to obtain the key associated with instance i.

See also: StringKey::StringAssociation

StringKey::StringAssociation

[StringKey]

```
key = gStringKey(i);
object i;
char *key;
```

This method is used to obtain the key associated with instance i.

```
See also: Key::StringAssociation,
```

ChangeStringKey::StringAssociation, Value::StringAssociation

```
StringRepValue::StringAssociation
```

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the value associated with i. This is often used to print or display the value. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

See also: PrintValue::Object, Print::Object

Value::StringAssociation

[Value]

```
val = gValue(i);
object i;
object val;
```

This method is used to obtain the value associated with i.

See also: ChangeValue::StringAssociation, StringKey::StringAssociation

5.50 StringDictionary Class

This class combines the functionality of the Set and StringAssociation classes in order to store a collection of arbitrary key/value pairs.

The difference between this class and the Dictionary class is that this class only accepts C language strings as keys. This class provides an efficient and simple to use means of representing a commonly needed collection.

This class is a subclass of the Set class and therefore inherits all of its functionality.

See the examples included with the Dynace system for an illustration of the use of the Set/Dictionary related classes.

5.50.1 StringDictionary Class Methods

There are no class methods for this class. It inherits the ability to create instances of itself through its superclass, Set.

5.50.2 StringDictionary Instance Methods

object r;

The instance methods associated with this class are used to add, retrieve and remove key/value pairs from the Dictionary. Note that additional functionality may be obtained through its superclass, Set.

```
AddStr::StringDictionary [AddStr]

r = gAddStr(i, key, value);

object i;
char *key
object value;
```

This method is used to add a new key/value pair to the StringDictionary instance (i). If an object with the same key already exists in the Dictionary it will be left as is and AddStr will return NULL. If the key/value objects are added AddStr will return the StringAssociation instance created to represent the key/value pair passed.

```
See also: FindStr::StringDictionary, FindValueStr::StringDictionary, ChangeValueWithStr::StringDictionary, RemoveStr::StringDictionary
```

```
ChangeValueWithStr::StringDictionary [ChangeValueWithStr]
```

```
r = gChangeValueWithStr(i, key, value);
object i;
char *key
object value;
object r;
```

This method is used to change the value associated with an existing key/value pair to the StringDictionary instance (i). key represents the identity of the pre-existing key/value pair and value represents the new value to be associated with the key.

Normally, this method changes the value part of the association and returns the previous value which is not disposed. If key doesn't identify a pre-existing association, this method simply returns NULL.

```
See \ also: \ FindStr::StringDictionary, \ FindValueStr::StringDictionary, \\ RemoveStr::StringDictionary
```

```
DeepDisposeStr::StringDictionary [DeepDisposeStr]
```

```
r = gDeepDisposeStr(i, key);
object i;
char *key;
object r;
```

This method is used to remove and dispose of a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The value and StringAssociation used to bind the two are all deep disposed.

This method is the same as DisposeStr::StringDictionary.

```
See also: RemoveStr::StringDictionary
```

```
Dispose::StringDictionary [Dispose]
```

```
r = gDispose(i);
object i;
object r; /* NULL */
```

This method is used to dispose of an entire Dictionary. It does not dispose of any of the values but does dispose of all the associations used to represent the pair.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

```
See also: RemoveStr::StringDictionary, DeepDispose::Set, DisposeAllNodes::StringDictionary
```

DisposeAllNodes::StringDictionary

[DisposeAllNodes]

```
i = gDisposeAllNodes(i);
object i;
```

This method is used to remove all objects in a StringDictionary instance without disposing of the instance itself. The objects in the StringDictionary are simply disassociated from the StringDictionary instance and are not disposed.

The value returned is always the instance passed.

```
See also: DeepDisposeAllNodes::Set, Dispose::StringDictionary
```

```
DisposeStr::StringDictionary
```

[DisposeStr]

```
r = gDisposeStr(i, key);
object i;
char *key;
object r;
```

This method is used to remove and dispose of a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The value and StringAssociation used to bind the two are all deep disposed.

This method is the same as DeepDisposeStr::StringDictionary.

See also: RemoveStr::StringDictionary

```
FindStr::StringDictionary
```

[FindStr]

```
r = gFindStr(i, key);
object i;
char *key;
object r;
```

This method is used to find the instance of the StringAssociation class which is used to represent the key/value pair stored under key in Dictionary i. If key is not found NULL is returned.

See also: FindValueStr::StringDictionary

```
FindAddStr::StringDictionary
```

[FindAddStr]

```
r = gFindAddStr(i, key, value);
object i;
char *key;
object value;
object r;
```

This method is used to find and return the instance of the StringAssociation class used to represent the key/value pair stored under the key key. If it is not found a new StringAssociation will be added and returned which represent the key/value pair representing key and value.

See also: FindStr::StringDictionary, FindValueStr::StringDictionary

FindValueStr::StringDictionary

[FindValueStr]

```
r = gFindValueStr(i, key);
object i;
char *key;
object r;
```

This method is used to find the value stored under key in Dictionary i. If key is not found NULL is returned.

See also: FindStr::StringDictionary

RemoveStr::StringDictionary

[RemoveStr]

```
r = gRemoveStr(i, key);
object i;
char *key;
object r;
```

This method is used to remove a key/value pair from a Dictionary. If found and removed i is returned. If key is not found NULL is returned.

The value is not disposed, however, the StringAssociation used to bind the two is.

See also: DeepDisposeStr::StringDictionary

5.51 Thread Class

The Thread class gives Dynace the ability to create, manage and execute multiple threads of execution in a timesharing fashion. See the manual for a detailed description of threads.

See the examples included with the Dynace system for an illustration of the use of the thread / pipe / semaphore related classes.

5.51.1 Thread Class Methods

The class methods associated with the Thread class provide a means to create new instances of the Thread class. Each instance represents a unique thread of execution. The class methods also provide other functionality which is not related to any particular thread, such as the ability to initialize the threading system.

```
BlockingGetkey::Thread [BlockingGetkey]
```

```
c = gBlockingGetkey(Thread)
int    c;
```

This method is used to get a key from the keyboard. It does it in a way that allows other threads to continue if there is no key ready. This allows the system to continue to operate while waiting for a user entry.

The thread which calls this method will be placed on hold until a key has been hit. At that time the thread will be enabled and the method will return the key hit.

Only one thread may use this method at a time.

See also: StartThreader

```
FindStr::Thread [FindStr]
```

```
t = gFindStr(Thread, name)
char *name;
object t;
```

This method is used to obtain a thread object from its associated name. If found it is returned, otherwise NULL is returned. Note that the name of the thread which started the thread system is "main". If name is NULL Find returns the currently running thread object.

See also: NewThread::Thread

NewThread::Thread [NewThread]

This class method creates instances of the Thread class. Each thread represents a unique thread of execution.

name is the name of the thread. This name may be used to access the thread object via its name at a future point. name may be null if no particular name is desired.

fun is the C language function which will implement the process to be run by the new thread. When fun is first executed it is passed the pointer defined by arg as its only argument. fun may return an integer result which may be accessed by other threads.

priority sets the initial priority of the thread. This is a number between 1 and 30000. The higher the number the greater the priority. Threads of higher priority (which are ready to run) always run before any threads of lesser priority. Only ready threads of the same priority share CPU time. There is a macro named DEFAULT_PRIORITY which may be used to create threads which share resources equally. Creating higher or lower priority threads may be accomplished relative to the DEFAULT_PRIORITY macro. Note that all ready threads of a higher priority must complete before threads of a lower priority will receive any CPU time.

arg provides a simple mechanism to pass data to the thread when it starts. When fun is started it is passed a single argument arg.

run is a flag to tell the system how to initialize the thread. If run is 1 the new thread will be created in a ready-to-run state. It will be placed on the queue of ready threads and will automatically start when it gets CPU time. If the thread is started at a higher priority than the thread which created the new thread then the current thread will be timed-out and the new thread will immediately start. If run is set to 0 the new thread will be created in a hold state and must be released from this state in order to start running.

autoDispose is used to control what happens to the thread object once the thread completes. If set to 1 the thread will be automatically disposed when it completes. If set to 0 the thread will remain in the system until manually disposed. This may be useful if the return value of the thread is desired after it has completed. Note that the garbage collector never collects thread objects. They must be handled manually. Note also that the way the system was implemented completed threads and threads on hold take up 0 CPU resources.

The value returned (t) is the thread object created. If not kept it may be obtained later by the use of the FindStr::Thread method. This thread object may be used for many purposes to control a thread. You may hold, release, change priority, kill or otherwise query the state of the thread via this object.

Note that the threader must be started prior to the creation of any new threads. This may be accomplished by the use of the StartThreader method.

See also: StartThreader, FindStr::Thread

5.51.2 Thread Instance Methods

The instance methods associated with this class are used to manage and query various aspects related to particular threads. Each instance represents a single unique thread.

DeepDispose::Thread [DeepDispose]

```
r = gDeepDispose(t)

object t;
object r; /* NULL */
```

This method is used to permanently stop the execution of an arbitrary thread, t (if it is running) and dispose of it. t may be the current thread, in which case the next thread on the queue will start.

In order to give the thread a return value use Kill::Thread and then this method.

This method is the same as Dispose::Thread.

See also: Kill::Thread, Hold::Thread

Dispose::Thread [Dispose]

```
r = gDispose(t)
object t;
object r; /* NULL */
```

This method is used to permanently stop the execution of an arbitrary thread, t (if it is running) and dispose of it. t may be the current thread, in which case the next thread on the queue will start.

In order to give the thread a return value use Kill::Thread and then this method.

This method is the same as DeepDispose::Thread.

The value returned is always NULL and may be used to null out the variable which contained the object being disposed in order to avoid future accidental use.

See also: Kill::Thread, Hold::Thread

```
ChangePriority::Thread [ChangePriority]
```

```
t = gChangePriority(t, pri)
object t;
int pri;
```

This method is used to change the priority of thread t. Thread t may be the currently running thread. If thread t is changed to a higher priority than the currently running thread, the currently running will immediately release the CPU to thread t.

The priority is a number between 1 and 30000. The higher the number the greater the priority. Threads of higher priority (which are ready to run) always run before any threads of lesser priority. Only ready threads of the same priority share CPU time. There is a macro named DEFAULT_PRIORITY which may be used to create threads which share resources equally. Creating higher or lower priority threads may be accomplished relative to the DEFAULT_PRIORITY macro. Note that *all* ready threads of a higher priority must complete before threads of a lower priority will receive any CPU time.

See also: Priority::Thread, NewThread::Thread, State::Thread

```
Hold::Thread [Hold]
```

```
t = gHold(t)
object t;
```

This method is used to place a temporary hold on a thread (t). The thread stops execution and waits until released. Threads on hold take no CPU time. Any number of threads may place any number of holds on any threads, however, an equal number of releases are required to release a thread which has been held multiple times. A thread may put itself on hold. The value returned is the thread passed.

See also: Release::Thread, Kill::Thread

IntValue::Thread [IntValue]

```
r = gIntValue(t)
object t;
int r;
```

This method is used to obtain the return value of a thread (t) which has completed or been killed. If the thread is still running (or on hold) this method will just return 0.

See also: State::Thread, WaitFor::Thread, Kill::Thread

```
Kill::Thread [Kill]
```

```
t = gKill(t, rtn)
object t;
int rtn;
```

This method is used to permanently stop the execution of an arbitrary thread, t. Once this method is called on a thread it cannot be run again. t may be the current thread, in which case the next thread on the queue will start. Thread t is not disposed. Attempting to Kill a thread which has already been killed or completed has no ill effect, rtn is just ignored.

rtn represents the return value of the thread, which may be queried by other threads. Any holds associated with the thread will be expunged. Thread t is returned.

Note that killed threads take up no CPU time.

See also: Dispose::Thread, Hold::Thread

Name::Thread [Name]

```
nam = gName(t)
object t;
char *nam;
```

This method is used to obtain the name of thread t.

See also: NewThread::Thread, State::Thread, Priority::Thread

Priority::Thread [Priority]

```
pri = gPriority(t)

object t;
int pri;
```

This method is used to obtain the priority of thread t.

The priority is a number between 1 and 30000. The higher the number the greater the priority. Threads of higher priority (which are ready to run) always run before any threads of lesser priority. Only ready threads of the same priority share CPU time. There is a macro named DEFAULT_PRIORITY which may be used to create threads which share resources equally. Creating higher or lower priority threads may be accomplished relative to the DEFAULT_PRIORITY macro. Note that *all* ready threads of a higher priority must complete before threads of a lower priority will receive any CPU time.

See also: ChangePriority::Thread, NewThread::Thread, State::Thread

```
Release::Thread [Release]
```

```
t = gRelease(t, yld)
object t;
int yld;
```

This method is used to release a hold placed by the Hold method on a thread (t). The thread will not really be released until the number of calls to Release is equal to the number of times Hold was called on thread t.

yld is a flag. It indicates whether the current thread should yield to the thread being released (if the thread being released has a higher priority). If yld is 1 and the thread being released has a higher priority than the current thread the system will immediately transfer the CPU to the thread being released. If yld is set to 0 the current thread will be allowed to complete its time slice. The value returned is the thread passed.

See also: Hold::Thread

State::Thread [State]

```
s = gState(t)
object t;
int s;
```

This method is used to obtain the current state of a thread (t). The valid states are macros defined in dynl.h and are defined as follows:

NEW_THREAD New thread which hasn't started running

yet

RUNNING_THREAD Thread ready to run
HOLD_THREAD Thread placed on hold

DONE_THREAD Thread has completed or been killed WAITING_FOR_THREAD Thread waiting for another thread to

complete

WAITING_FOR_SEMAPHORE Thread waiting for semaphore

WaitFor::Thread [WaitFor]

r = gWaitFor(t)

object t;
int r;

This method is used to place the current thread on hold until thread t completes, gets killed or disposed. At that point the thread gets released and WaitFor returns the return value from thread t. Note that threads waiting for other threads take up no CPU time.

See also: Kill::Thread, Dispose::Thread, Hold::Thread

5.51.3 Thread Macros

The thread system includes a few macros which are used to provide some additional functionality without incurring much system overhead.

ENABLE_THREADER

[ENABLE_THREADER]

ENABLE_THREADER;

This macro is used to re-enable the threader after the INHIBIT_THREADER has been used. Since consecutive calls to INHIBIT_THREADER stack, an equal number of ENABLE_THREADER calls must be used.

The two macros, INHIBIT_THREADER and ENABLE_THREADER, are used to surround code which you want to be absolutely certain that a context switch doesn't occur during. Since these macros nest it is ok if between a pair a function is called which also uses these macros.

Note that when the threader is enabled a context switch can only occur during a generic function call or by the use of the YIELD macro.

Example:

See also: INHIBIT_THREADER, StartThreader

INHIBIT_THREADER

[INHIBIT_THREADER]

INHIBIT_THREADER;

This macro is used to temporarily disable the threader. Once disabled no context switches will occur until the threader is re-enabled by the use of the ENABLE_THREADER macro. Consecutive calls to INHIBIT_THREADER stack, therefore, an equal number of ENABLE_THREADER calls must be used to re-enable the threader.

The two macros, INHIBIT_THREADER and ENABLE_THREADER, are used to surround code which you want to be absolutely certain that a context switch doesn't occur during. Since these macros nest it is ok if between a pair a function is called which also uses these macros.

Note that when the threader is enabled a context switch can only occur during a generic function call or by the use of the YIELD macro.

Example:

See also: ENABLE_THREADER, StartThreader

StartThreader [StartThreader]

```
StartThreader(argc)
```

int argc;

This macro is used to initialize the threading system. It must be called before any other thread operations (except for initializing the thread class). It *must* be called from the C function called main, and should only be called once. It is typically called immediately following the Dynace system initialization.

Once this macro is called all execution is performed by threads. The program (main) which called StartThreader becomes the single running thread with the name "main". Any future threads created at the default priority will share CPU time equally with the main thread. There is nothing special about the main thread.

argc is simply the argument normally passed to C language main functions. The value doesn't matter. It is used to obtain the address of the stack.

See also: NewThread::Thread

YIELD [YIELD]

YIELD;

The YIELD macro is used to force a context switch (unless the threader has been disabled with the INHIBIT_THREADER macro).

Since Dynace only provides automatic context switching during a generic function call, if a thread is running a long compute cycle without any generic function calls it will hog the system until a generic is called unless the YIELD macro is used. This macro may be placed at regular intervals in the code to be sure that it shares the CPU time. The YIELD macro will only cause an actual context switch when the threads time is complete, otherwise YIELD will do nothing.

Example:

See also: StartThreader

5.52 Time Class

The Time class uses the same set of instance and class methods as the LongInteger class. The equivalent C language representation would be a long integer in the form HHMMSSLLL so 1:23:45.678 pm would be represented as 132345678L.

5.52.1 Time Class Methods

object i;

The Time class has two class methods to create instances.

This class method creates instances of the Time class. tm represents the initial time value represented.

Example:

```
object x;
x = gNewWithLong(Time, 132345678L); /* x = 1:23:45.678 pm */
```

See also: Now::Time, FormatTime::Time, Dispose::Object

Now::Time [Now]

```
i = gNow(Time);
object i;
```

This class method creates instances of the Time class which represents the current time contained within the system.

Example:

```
object x;
x = gNow(Time); /* x = the current time */
```

See also: NewWithLong::Time, FormatTime::Time, Dispose::Object

5.52.2 Time Instance Methods

A portion of the Time class's functionality is identical to the functionality of the LongInteger class. The remaining functionality is defined by the following specific methods.

This method is used to add an arbitrary number of hours (hours) to time i. Adding an hour that goes past midnight will cause the time to cycle around to morning. The value returned is the object passed.

Example:

```
object tm;
tm = gNewWithLong(Time, 234500000L);
gAddHours(tm, 2L); /* tm = 14500000L (1:45:00.000 am) */
```

See also: AddMilliseconds::Time, AddMinutes::Time, AddSeconds::Time

AddMilliseconds::Time

[AddMilliseconds]

```
i = gAddMilliseconds(i, m);
object i;
long m;
```

This method is used to add an arbitrary number of milliseconds (m) to time i. Adding a millisecond that goes past midnight will cause the time to cycle around to morning. The value returned is the object passed.

Example:

```
object tm;
tm = gNewWithLong(Time, 234500000L);
gAddMilliseconds(tm, 20L);
   /* tm = 500020L (11:45:00.020 pm) */
```

See also: AddHours::Time, AddMinutes::Time, AddSeconds::Time

AddMinutes::Time [AddMinutes]

```
i = gAddMinutes(i, m);
object i;
long m;
```

This method is used to add an arbitrary number of minutes (m) to time i. Adding a minute that goes past midnight will cause the time to cycle around to morning. The value returned is the object passed.

Example:

```
object tm;
tm = gNewWithLong(Time, 234500000L);
gAddMinutes(tm, 20L); /* tm = 500000L (1:05:00.000 am) */
```

See also: AddHours::Time, AddMilliseconds::Time, AddSeconds::Time

AddSeconds::Time [AddSeconds]

```
i = gAddSeconds(i, s);
object i;
long s;
```

This method is used to add an arbitrary number of seconds (s) to time i. Adding a second that goes past midnight will cause the time to cycle around to morning. The value returned is the object passed.

Example:

object i;

val;

long

```
object dt;

tm = gNewWithLong(Time, 234500000L);
   gAddSeconds(tm, 20L); /* tm = 520000L (11:45:20.000 pm) */

See also: AddHours::Time, AddMilliseconds::Time, AddMinutes::Time

ChangeLongValue::Time [ChangeLongValue]

i = gChangeLongValue(i, val);
```

This method is used to change the time value associated with an instance of the Time class. Notice that this method returns the instance being passed. val is the new time value.

Example:

This method is used to change the time value associated with an instance of the Time class. Notice that this method returns the instance being passed. val is the new time value.

Example:

```
object tm;

tm = gNewWithLong(Time, 234500000L);
gChangeTimeValue(tm, 44500000L);  /* tm = 4:45:00.000 am */
```

See also: ChangeLongValue::Time, NewWithLong::Time

```
{\tt ChangeValue::Time} \qquad \qquad [{\tt ChangeValue}]
```

```
i = gChangeValue(i, v);
object i;
object v;
```

This method is used to change the value associated with an instance of the Time class. Notice that this method returns the instance being passed. v is an object which represents the new time value.

Example:

```
object x, y;

x = gNewWithLong(Time, 234500000L);
y = gNewWithLong(Time, 44500000L);
gChangeValue(x, y);  /* x is changed to 4:45:00.000 am */
```

See also: ChangeLongValue::Time, ChangeTimeValue::Time

Compare::Time

[Compare]

```
r = gCompare(i, obj);
object i;
object obj;
int r;
```

This method is used by the generic container classes to determine the relationship of the values represented by i and obj. r is -1 if the time represented by i is less than the time represented by obj, 1 if the time value of i is greater than obj, and 0 if they are equal.

See also: Hash::Time

Difference::Time

[Difference]

```
r = gDifference(i, tm);
object i;
object tm;
long r;
```

This method is used to obtain the difference, in milliseconds, between two time objects.

Example:

```
object tm1, tm2;
long r;
tm1 = gNewWithLong(Time, 234515023L);
tm2 = gNewWithLong(Time, 234515000L);
r = gDifference(dt2, dt1); /* r = 23L */
```

See also: TimeDifference::Time

FormatTime::Time [FormatTime]

```
s = gFormatTime(i, fmt);
object i;
char *fmt;
object s;
```

This method returns an instance of the String class which is a formatted representation of the time associated with instance i. fmt is the format specification used to determine the resulting String object. Each character in fmt is sequentially processed and except for the character '%', they are simply copied to the resulting String object. Whenever this method encounters the '%' character, the character following is used to determine what aspect and format of the time represented by i should be added to the resultant String object. It works much like the standard C printf. The following table indicates the available formatting option characters:

```
%
             the % character
             hour in military (government) time.
     g
             Eleven o'clock is 23:00 (5)
     G
             the hour to two places in military (government)
             time (05)
             hour (5)
     h
     Η
             the hour to two places (05)
             minutes (5)
     m
     М
             the minutes to two places (05)
             seconds (5)
     s
     S
             the seconds to two places (05)
     1
             milliseconds (20)
     L
             the milliseconds to three places (020)
             the am / pm flag in lower case (pm)
     р
             the am / pm flag in upper case (PM)
     р
Example:
     object s, tm;
     tm = gNow(Time);
     s = gFormatTime(tm, "%h:%M:%S.%L %p");
     /* s contains "5:45:23.678 pm" (or whatever) */
```

See also: StringRepValue::Time

Hash::Time [Hash]

```
val = gHash(i);
object i;
int val;
```

This method is used by the generic container classes to obtain hash values for the time object. val is a hash value between 0 and a large integer value.

See also: Compare::Time

Hours::Time [Hours]

```
h = gHours(i);
object i;
int h;
```

This method returns the number of hours associated with an instance of the Time class.

Example:

```
object tm;
tm = gToday(Time);
h = gHours(tm); /* h contains 14 (or whatever) */
```

See also: Milliseconds::Time, Minutes::Time, Seconds::Time

LongValue::Time [LongValue]

```
val = gLongValue(i);
object i;
long val;
```

This method is used to obtain the long value that represents the time associated with an instance the Time class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a long.

```
Example:
          object x;
          long
                  val;
          x = gNewWithLong(LongInteger, 234500000L);
          val = gLongValue(x);  /* val = 234500000L */
     See also: NewWithLong::Time, ChangeLongValue::Time, TimeValue::Time
Milliseconds::Time
                                                                    [Milliseconds]
          m = gMilliseconds(i);
          object i;
          int
     This method returns the number of milliseconds associated with an instance of the
     Time class.
     Example:
          object tm;
          tm = gToday(Time);
          m = gMilliseconds(tm); /* m contains 154 (or whatever) */
     See also: Hours::Time, Minutes::Time, Seconds::Time
Minutes::Time
                                                                       [Minutes]
          m = gMinutes(i);
          object i;
          int
                  m;
     This method returns the number of minutes associated with an instance of the Time
     class.
     Example:
          object tm;
```

m = gMinutes(tm); /* h contains 55 (or whatever) */

tm = gToday(Time);

See also: Hours::Time, Milliseconds::Time, Seconds::Time

Seconds::Time [Seconds]

```
m = gSeconds(i);
object i;
int s;
```

This method returns the number of seconds associated with an instance of the Time class.

Example:

```
object tm;
tm = gToday(Time);
s = gSeconds(tm); /* s contains 30 (or whatever) */
```

See also: Hours::Time, Milliseconds::Time, Minutes::Time

StringRepValue::Time

[StringRepValue]

```
s = gStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the time associated with i. This is often used to print or display the time. It is also used by PrintValue::Object and indirectly by Print::Object (two methods useful during the debugging phase of a project) in order to directly print an object's value.

Example:

```
TimeDifference::Time
```

```
[{\bf Time Difference}]
```

```
r = gTmieDifference(i, tm);
object i;
object tm;
long r;
```

This method is used to obtain the difference, in milliseconds, between two time objects.

Example:

```
object tm1, tm2;
long r;
tm1 = gNewWithLong(Time, 234515023L);
tm2 = gNewWithLong(Time, 234515000L);
r = gTimeDifference(dt2, dt1); /* r = 23L */
```

See also: Difference::Time

TimeStringRepValue::Time

[TimeStringRepValue]

```
s = gTimeStringRepValue(i);
object i;
object s;
```

This method is used to generate an instance of the String class which represents the time associated with i. This is often used to print or display the time.

Example:

```
object x;
object s;

x = gNewWithLong(Time, 234500000L);
s = gTimeStringRepValue(x);
   /* s represents "11:45:00.000 pm" */
```

See also: PrintValue::Object, Print::Object, FormatTime::Time, StringRepValue::Time

TimeValue::Time [TimeValue]

```
val = gTimeValue(i);
object i;
long val;
```

This method is used to obtain the long value that represents the time associated with an instance the Time class. Note that this is one of the few generics which doesn't return a Dynace object. It returns a long.

Example:

```
object x;
long val;
x = gNewWithLong(LongInteger, 234500000L);
val = gTimeValue(x); /* val = 234500000L */
```

See also: NewWithLong::Time, ChangeLongValue::Time, LongValue::Time

ValidTime::Time [ValidTime]

```
r = gValidTime(i);
object i;
int r;
```

This method is used to determine the validity of a time. If i is a valid time 1 is returned and 0 otherwise.

Example:

```
object tm;
int r;
tm = gNewWithLong(Time, 234515899L);
r = gValidTime(tm); /* r = 1 */
tm = gNewWithLong(Time, 254500899L);
r = gValidTime(tm); /* r = 0 */
tm = gNewWithLong(Time, 114567000L);
r = gValidTime(tm); /* r = 0 */
```

5.53 UnsignedShortArray Class

This class, which is a subclass of NumberArray, is used to represent arbitrary shaped arrays of the C language unsigned short data type in an efficient manner. Although this class implements much of its own functionality it is documented within the NumberArray and Array classes because the interface is shared by all subclasses of the NumberArray class.

5.54 UnsignedShortInteger Class

The UnsignedShortInteger class is used to represent the C language unsigned short data type as a Dynace object. It is a subclass of the Number class. Even though the UnsignedShortInteger class implements most of its own functionality, it is documented as part of the Number class because most of the interface is the same for all subclasses of the Number class. Differences are documented in this section.

5.54.1 UnsignedShortInteger Class Methods

The UnsignedShortInteger class has only one class method and it is used to create new instances of itself.

NewWithUnsigned::UnsignedShortInteger [NewWithUnsigned]

```
i = gNewWithUnsigned(UnsignedShortInteger, s);
unsigned s;
object i;
```

This class method creates instances of the UnsignedShortInteger class. s is the initial value of the integer being represented. Note that s is of type unsigned. That is because if you pass an unsigned short type to a generic function (which uses a variable argument declaration) the C language will automatically promote it to an unsigned.

The value returned is a Dynace instance object which represents the integer passed.

Note that the default disposal methods are used by this class since there are no special storage allocation requirements.

Example:

```
object x;
x = gNewWithUnsigned(UnsignedShortInteger, 55);
```

See also: UnsignedShortValue::Number, Dispose::Object

5.54.2 UnsignedShortInteger Instance Methods

The instance methods associated with the UnsignedShortInteger class provide a means of changing and obtaining the value associated with an instance of the

UnsignedShortInteger class. All of the UnsignedShortInteger class instance methods are documented in the Number class because of their common interface with all other subclasses of the Number class.

Method, Macro, Function And Variable Index

\mathbf{A}	ChangeLongValue::NumberArray	273
accessIVs	ChangeLongValue::Time	
Add::Set	ChangeNext::Link	
AddAfter::Link	ChangePrevious::Link	
AddBefore::Link	ChangePriority::Thread	
AddDays::Date	ChangeRegisteredMemory::Dynace	
AddFirst::LinkList	ChangeShortValue::Number	
AddFirst::LinkObject	ChangeShortValue::NumberArray	
AddHours::DateTime	${\tt ChangeStringKey::StringAssociation}$	
AddHours::Time	ChangeStrValue::String	
AddInt::IntegerDictionary	ChangeTimeValue::Time	
AddLast::LinkList	ChangeUShortValue::Number	
AddLast::LinkObject	ChangeUShortValue::NumberArray	
AddMilliseconds::DateTime	ChangeValue::IntegerAssociation	
AddMilliseconds::Time	ChangeValue::LinkValue	
AddMinutes::DateTime	ChangeValue::Number	
AddMinutes::Time	ChangeValue::NumberArray	
AddMonths::Date	ChangeValue::ObjectArray	
AddSeconds::DateTime	ChangeValue::ObjectAssociation	
AddSeconds::Time	ChangeValue::Pointer	
AddStr::StringDictionary	ChangeValue::PointerArray	
AddValue::BTree	ChangeValue::String	
AddValue::Dictionary	ChangeValue::StringAssociation	
AddYears::Date	ChangeValue::Time	
Advance::Stream	ChangeValueWithInt::IntegerDictionary	
Alloc::Behavior	ChangeValueWithObj::Dictionary	
Append::String	ChangeValueWithStr::StringDictionary	
ApplyMask::String	CharValue::Number	
ArrayPointer::Array	CharValue::NumberArray	
Attributes::FindFile	CharValueAt::String	
	ChkArg	
D	ChlArgNul	
В	ChkArgTyp	
BasicSize::Object		
BitValue::BitArray	ClassOf	
BlockingGetkey::Thread	cmeth	
Build::String	cMethodFor	
	cmiPointer	
~	Compare::Association	
\mathbf{C}	Compare::DateTime	
CalToJul::Date	Compare::Number	
ChangeBitValue::BitArray	Compare::Object	
ChangeCharAt::String	Compare::Pointer	
ChangeCharValue::Number	Compare::String	
ChangeCharValue::NumberArray	Compare::Time	
ChangeDateTimeValues::DateTime	CompareI::String	
ChangeDateValue::Date	CompareN::String	
ChangeDoubleValue::Number	CompareNI::String	
ChangeDoubleValue::NumberArray	Copy::Array	
ChangeFunction::Method	Copy::Constant	
ChangeIntKey::IntegerAssociation	Copy::Link	
ChangeKey::LookupKey	Copy::LinkList	
ChangeLongValue::DateTime	Copy::Object	
ChangeLongValue::Number	Copy::Set	
		

Copy::String	Dispose::Constant
Copy::StringAssociation	Dispose::Dictionary
Count::Semaphore	Dispose::File
cSuper	Dispose::IntegerDictionary
CurMemUsed::Dynace	Dispose::Link
cvMethodFor	Dispose::LinkList
	Dispose::LowFile
D	Dispose::Object
ט	Dispose::Pipe
DateTimeDifference::DateTime	Dispose::Semaphore
DateTimeValues::DateTime	Dispose::Set
DateValue::Date	Dispose::Socket
DayName::Date	Dispose::String
DeepCopy::Array	Dispose::StringAssociation
DeepCopy::Constant	Dispose::StringDictionary356
DeepCopy::IntegerAssociation	Dispose::Thread
DeepCopy::Link	Dispose1::Set
DeepCopy::LinkList	DisposeAllNodes::BTree
DeepCopy::LinkValue	DisposeAllNodes::Dictionary
DeepCopy::LookupKey	DisposeAllNodes::IntegerDictionary 223
DeepCopy::Object	DisposeAllNodes::LinkList
DeepCopy::ObjectAssociation	DisposeAllNodes::Set
DeepCopy::Set	DisposeAllNodes::StringDictionary357
DeepCopy::String	DisposeAllNodes1::Set
DeepCopy::StringAssociation	DisposeFirst::LinkList
DeepDispose::Array	DisposeGroup::Set
DeepDispose::BTree	DisposeInt::IntegerDictionary
DeepDispose::Constant	
DeepDispose::File	DisposeLast::LinkList
DeepDispose::IntegerAssociation	DisposeObj::BTree
DeepDispose::Link	DisposeObj::Dictionary
DeepDispose::LinkList	DisposeObj::Set
DeepDispose::LinkValue	DisposePropertyList::PropertyList 295
DeepDispose::LookupKey	DisposeStr::StringDictionary
DeepDispose::LowFile	DoesNotImplement::Behavior
DeepDispose::Object91	DontCollect::Behavior
DeepDispose::ObjectAssociation	DoubleValue::Number
DeepDispose::Pipe	DoubleValue::NumberArray277
DeepDispose::Semaphore	Drop::String
DeepDispose::Set	DumpObjects::Dynace
DeepDispose::String	DumpObjectsDiff::Dynace
DeepDispose::StringAssociation	DumpObjectsString::Dynace
DeepDispose::Thread	Dynace_GetInitialPageSize
DeepDisposeAllNodes::BTree	Dynace_GetPageSize
DeepDisposeAllNodes::LinkList	
DeepDisposeAllNodes::Set	П
DeepDisposeFirst::LinkList	${f E}$
DeepDisposeGroup::Set	ENABLE_THREADER
DeepDisposeInt::IntegerDictionary 222	EndOfStream::Stream
DeepDisposeLast::LinkList	END
DeepDisposeObj::BTree	Equal::Array
DeepDisposeObj::Dictionary	Equal::Constant
DeepDisposeObj::Set 306	Equal::0bject
DeepDisposeStr::StringDictionary 356	Equal::String
defGeneric	EQ
Difference::Date	Error::Object
Difference::Time	externGeneric
Dispose::Array	511521145115115115115115115115115115115115115
Dispose: RTree 171	

F	H	
FileHandle::LowFile	Hash::Association	166
Find::Dictionary	Hash::DateTime	
Find::Set	Hash::Number	
FindAdd::Set	Hash::Object	
FindAddInt::IntegerDictionary	Hash::Pointer	
FindAddStr::StringDictionary	Hash::String	
FindAddValue::Dictionary	Hash::Time	
FindClass::Class	Hold::Thread	
FindEQ::BTree	Hours::Time	
FindFirst::BTree	Hours::IIme	310
FindGE::BTree		
FindGeneric::GenericFunction	т	
FindGT::BTree	I	
FindInt::IntegerDictionary	imcPointer	139
FindLast::BTree	imeth	
FindLE::BTree	iMethodFor	
FindLT::BTree 175	imiPointer	
FindMethod::Behavior	IncNelm::LinkList	
FindMethodObject::Behavior	Index::Array	
FindNext::BTree	IndexOrigin::Array	
FindPrev::BTree		
FindStr::Pipe	INHIBIT_THREADER	
FindStr::Semaphore	Init::Object	
FindStr::StringDictionary357	InitDynace	
FindStr::Thread	InitGeneric	
FindValue::Dictionary	InitKernel	
${\tt FindValueInt::IntegerDictionary$	InitLink::Link	
FindValueStr::StringDictionary	InstanceSize::Behavior	
First::LinkList	IntKey::IntegerAssociation	
First::LinkObject	IntValue::Thread	
First::Set	${\tt InvalidObject::GenericFunction$	
FixInvalidDate::Date	${\tt InvalidType::GenericFunction$	
Flush::File	Iota::ShortArray	
ForAll::Set	IsaClass	
FormatChar::Character	IsaMetaClass 1	
FormatDate::Date	IsInstanceOf 1	
FormatDateTime::DateTime	IsKindOf::Behavior	
FormatNumber::Number	<pre>IsKindOf::Object</pre>	
FormatTime::Time	${\tt IsObj$	155
Function::Method	iSuper	
	$\verb ivMethodFor$	
G	ivPtr	145
	ivsPtr 1	
GC::Dynace	$\verb"ivType" \dots \dots$	147
GCDispose::Object93		
Generic		
GetAll::Class	J	
GetAll::GenericFunction	J	
GetArg	Julian::Date	189
GetCVs	JulToCal::Date	
GetErrorCode::Socket	JustifyCenter::String	
GetGenericPtr::GenericFunction	JustifyLeft::String	340
GetIVptr	JustifyRight::String	341
GetIVs		
Gets::Stream		
GetValues::LinkObject		
GroupRemove::Set		

K	NewClass::Class
Key::LookupKey	NewDateTime::DateTime
Key::StringAssociation	NewFindFile::FindFile
Kill::Thread	NewGeneric::GenericFunction
	NewMethod::Method
т	NewSemaphore::Semaphore
\mathbf{L}	NewStdClass::Class
Last::LinkList	NewThread::Thread
Last::LinkObject	NewWithChar::Character
Length::FindFile	NewWithDouble::DoubleFloat
Length::Pipe	NewWithInt::Set
Length::Stream	NewWithInt::ShortInteger315
List::Link	NewWithIntObj::IntegerAssociation
LongValue::Number	NewWithLong::LongInteger
LongValue::NumberArray	NewWithLong::Time
LongValue::Time	NewWithObj::LinkObjectSequence
	NewWithObj::LinkSequence
NI	NewWithObj::LinkValue
M	NewWithObj::LookupKey
MAKE_REST	NewWithObj::String
MakeList::LinkObject	NewWithObjObj::ObjectAssociation
MarkingMethod::Behavior	NewWithDtjubjubjectAssociation
MaskFunction::String	NewWithStr::String
MaxAfterGC::Dynace	NewWithStrInt::Pipe
MaxMemUsed::Dynace	NewWithStrObj::StringAssociation 351
Milliseconds::Time	NewWithUnsigned::UnsignedShortInteger381
Minutes::Time	Next::Link
Mode::Pipe 288 MonthName::Date 190	Next::LinkObjectSequence
MoveAfter::Link	Next::LinkSequence
MoveBefore::Link	Next::SetSequence
MoveBeginning::Link	NextFile::FindFile
MoveEnd::Link	Now::DateTime
	Now::Time
N T	Nth::Link
N	Nth::LinkObject
Name::Behavior	NumbGC::Dynace
Name::File	NumbPieces::String
Name::FindFile	Numbi lecesbulling
Name::GenericFunction	
Name::LowFile	
Name::Method	0
Name::Semaphore	
Name::Thread	object
NEQ	ObjectChecking::Dynace
New::Behavior	ofun
New::BTree	OpenFile::File
New::Link	OpenLowFile::LowFile
New::LinkList	OpenTempFile::File
New::NumberArray	oSuper 149
New::ObjectArray	
New::ObjectPool	
New::Pipe	
New::PointerArray	
New::Semaphore	
New::Set	
New::String	

P	\mathbf{S}	
Piece::String	Seconds::Time 3	377
PointerValue::File	Seek::Stream 3	325
PointerValue::Pointer	SendFile::Socket	
PointerValue::PointerArray	Sequence::LinkList	
Pop::LinkObject	Sequence::LinkObject	
Position::Stream	Sequence::Set	
Previous::Link	SequenceLinks::LinkObject	
Print::Object	SetFunction::BTree	
Printf::Stream	SetMaskFiller::String	
PrintLength::String 342	SetMemoryBufferArea::Dynace	
PrintValue::Object	SetTempSubDir::File 2 Shape::Array 1	
Priority::Thread	ShortValue::Number	
Process::String	ShortValue::NumberArray	
PropertyGet::PropertyList	ShouldNotImplement::Object	
PropertyPut::PropertyList	Size::Array	
PropertyRemove::PropertyList	Size::BTree	
Push::LinkObject	Size::LinkList	
Putc::Stream	Size::Object	
Puts::Stream 323	Size::Pipe	
	Size::Set	312
	Size::String 3	345
R	SocketConnect::Socket 3	
16	Sprintf::String 3	
Rank::Array	StackAlloc	
Read::Socket 317	StackAlloc::Behavior	
Read::Stream 324	StartThreader 3	
RecvFile::Socket	State::Thread	
RegisterMemory::Dynace	stderrStream::Stream	
${\tt RegisterVariable$	stdinStream::Stream	
Release::Semaphore	stdoutStream::Stream	
Release::Thread	StringRep::Array	
Remove::Link	StringRep::Behavior	
Remove::LinkList	StringRep::Link	
RemoveFirst::LinkList	StringRep::LinkList	
${\tt RemoveInt::IntegerDictionary} \dots \dots 224$	StringRep::LinkValue	
RemoveLast::LinkList	StringRep::Object	
RemoveMask::String	StringRep::Set 3	
RemoveObj::Dictionary	StringRepValue::Array	
RemoveObj::Set	${\tt StringRepValue::Behavior$.03
RemoveRegisteredMemory::Dynace	${\tt StringRepValue::Date$	
RemoveStr::StringDictionary	${\tt StringRepValue::DateTime$	
RESET_REST	${\tt StringRepValue::IntegerAssociation$	
Reshape::Array	StringRepValue::Link	
Resize::Set	StringRepValue::LinkValue	
ResizeMethodCache::Dynace	StringRepValue::LookupKey	
RespondsTo	StringRepValue::Number	
Retreat::Stream	StringRepValue::Object	
Room::Pipe	StringRepValue::ObjectAssociation2	
Round::DoubleFloat	StringRepValue::Pointer	
	StringRepValue::StringAssociation	
	StringRepValue::Time	
	StringValue::String	
	StripCenter::String	
	StripLeft::String	

StripRight::String	\mathbf{V}
SubClasses::Behavior 103 SubclassResponsibility::Object 97	ValidDate::Date
SubString::String	ValidDateTime::DateTime
SuperClasses::Behavior	ValidTime::Time
	Value::IntegerAssociation
\mathbf{T}	Value::LinkValue
Take::String	Value::ObjectArray
TimeDifference::Time	Value::ObjectAssociation
TimedRead::Socket	Value::StringAssociation
TimedWrite::Socket	
TimeStringRepValue::Time	
TimeValue::Time	
Today::Date	TX 7
ToLower::String	\mathbf{W}
ToUpper::String	WaitFor::Semaphore
Trace::Behavior	WaitFor::Thread
Trace::Dynace 125 Trace::GenericFunction 115	Write::Socket
Trace::Method	Write::Stream
TracePrint::Dynace	Write::Stream
traceStream::Stream	wilterime indiffe
Truncate::DoubleFloat	
ŢJ	
· ·	Y
UnsignedShortValue::Number	
UnsignedShortValue::NumberArray279	YIELD