Chapter 8 Data Structures

8.1 Subroutines

subroutines = procedures = functions

Target: To enable the programmer to write the code more efficiently.

8.1.1 Call/Return Mechanism

Call instruction: JSR, JSRR

The JSR(R) instruction does **two** things:

- 1. Loads PC, overwriting the incremented PC that was loaded during FETCH phase of the JSR(R) instruction.
- 2. Store the incremented PC into R7.

JSR: PCoffset11, bitd[10:0]

JSRR: BaseR

Return instruction: JMP R7

8.1.2 Saving and Restoring Registers

Why we need saving & restoring?

• Every time an instruction loads a value into a register, the value that was previously in the register is **lost**

When we need saving & restoring?

• The value will be destroyed by some subsequent instruction **and** we need it after that subsequent instruction.

Caller & Callee

A calls B \rightarrow A: caller, B: callee

Caller save & Callee save

How to decide to use which save?

• The one who knows the register will be "polluted" or overwritten **should save the** values.

How to decide the given codes is caller save or callee save?

- In a relationship A calls B,:
 - if the save(LD) -> restore(ST) happens in A, which is usually before & after the JSR(R) , it is a caller save.

e.g.: save R7

• if the save(LD) -> restore(ST) happens in B, which is usually at the beginning of the subroutine & before the JMP R7, it is a callee save.

8.1.3 Library Routines

Chapter 8.1.4 in the textbook is recommend reading.

8.2 The Stack

8.2.1 ADT

An Abstract Data Type (ADT) is a data type that is organized in such a way that the specification on the **objects** and specification of the **operations** on the objects are separated from the **representation** of the objects and the **implementation** on the operations.

8.2.2 The defining notion of a stack

LIFO, that is the last thing you stored in the stack is the first thing you remove from it.

8.2.3 Two typical operations on stack

- PUSH: to store a value into the stack, it will be at the top of the stack
- **POP**: to get and remove the value of the top of the stack.

8.2.4 Implementation in Memmory

We use a **stack pointer(SP)** to keep track of the top of the stack. In LC-3, we use **R6** as a SP.

In LC-3, the stack **grows to zero**, which means that the stack will grows to lower location, for example, from x3FFF to x3FFFE, x3FFD and so on.

System Stack: x0000 - x2FFF, which can not be accessed by usual user.

So we can make our stack start and end from anywhere between $\mathbf{x3000}$ and \mathbf{xFCFF} . (xFD00 to xFFFF is used for I/O)

Usually, we choose xFCFF as the beginning of our user stack.

8.2.5 Push & Pop

To improve our efficiency, we **do not physically move** our data during pop operation.

So the basic push & pop operation is as follow:

PUSH

Suppose the value has been stored in $\it r0$ previously.

```
PUSH: ADD r6, r6, #-1; Move the SP
STR r0, r6, #0; Store the value
```

POP

Suppose the value is asked to store in r0.

```
POP: LDR r0, r6, #0 ; Get the value

ADD r6, r6, #1 ; Move the SP to remove the value
```

8.2.6 Overflow & Underflow

Overflow:

The stack has been **full** when trying inserting a new value. Only happens in PUSH.

Underflow:

The stack has been **empty** when trying removing a value. Only happens in POP.

RET instruction

It is the same as JMP r7;

Detect & Handle Overflow in PUSH

Suppose the Stack begins at x3FFF and its capacity is 5. And we handle Overflow by set r5 (make r5 be 1).

Key point: Judge if SP points to the lowest location.

```
PUSH: AND r5, r5, #0 ; Initialize r5

LD r1, MAX ; Initialize r1 with the opposite number of the lowest location

ADD r2, r6, r1

BRZ Failure ; Judge if SP points to the lowest location

ADD r6, r6, #-1; No overflow, just do PUSH

STR r0, r6, #0

RET ; Return to caller

Failure ADD r5, r5, #1 ; Set r5

RET ; Return to caller

MAX .FILL xC005 ; The opposite number of the lowest location
```

HINT:

The lowest location should be: x3FFB (x3FFF - #5), which is

```
0011 1111 1111 1011
```

Then we get its opposite number by calculating its 2's complement number:

```
1100 0000 0000 0101
```

which is xC005

Detect & Handle Underflow in POP

Suppose the Stack begins at x3FFF (its capacity has nothing to do with underflow). And we handle Overflow by set r5 (make r5 be 1).

Key point: Judge if SP points to the highest location.

```
POP: AND r5, r5, #0 ; Initialize r5

LD r1, EMPTY ; Initialize r1 with the opposite number of the highest location

ADD r2, r6, r1

BRZ Failure ; Judge if SP points to the lowest location

STR r0, r6, #0 ; No overflow, just do POP

ADD r6, r6, #1

RET ; Return to caller

Failure ADD r5, r5, #1 ; Set r5

RET ; Return to caller

EMPTY .FILL xC000 ; The opposite number of the lowest location
```

HINT:

The highest location should be: x4000 (x3FFF + #1), which is

```
0100 0000 0000 0000
```

Then we get its opposite number by calculating its 2's complement number:

```
1100 0000 0000 0000
```

which is xC000