# SSJ User's Guide

Package probdist

Probability Distributions

Version: March 31, 2009

This package provides tools to compute densities, mass functions, distribution functions and their inverses, and reliability functions, for various continuous and discrete probability distributions. It also offers facilities for estimating the parameters of some distributions from a data set.

March 31, 2009 CONTENTS i

# Contents

Overview	2
eneral Classes	4
Distribution	4
DiscreteDistribution	5
DiscreteDistributionInt	
Continuous Distribution	9
DistributionFactory	11
iscrete Distributions over Integers	13
BinomialDist	13
GeometricDist	16
HypergeometricDist	18
LogarithmicDist	20
NegativeBinomialDist	22
PascalDist	24
PoissonDist	25
UniformIntDist	27
iscrete Distributions over Real Numbers	29
EmpiricalDist	29
ontinuous Distributions	31
BetaDist	31
BetaSymmetricalDist	34
CauchyDist	36
ChiDist	38
ChiSquareDist	40
ChiSquareDistQuick	42
ChiSquareNoncentralDist	43
ErlangDist	45
ExponentialDist	47
ExponentialDistFromMean	49

March 31, 2009 CONTENTS 1

ExtremeValue	eDist			 	 	 		 			50
FatigueLifeDi	st			 	 	 		 			52
FisherFDist				 	 	 		 			54
FoldedNorma	$lDist \dots \dots$			 	 	 		 			56
GammaDist				 	 	 	 	 			58
GammaDistF	romMoments.			 	 	 	 	 			61
HalfNormalD	ist			 	 	 		 			62
HyperbolicSe	cantDist			 	 	 		 			64
InverseGaussi	anDist			 	 	 	 	 			66
JohnsonSBDi	st			 	 	 		 			68
JohnsonSUDi	st			 	 	 		 			70
LaplaceDist				 	 	 	 	 			72
LogisticDist				 	 	 		 			74
LoglogisticDis	st			 	 	 	 	 			76
LognormalDis	st			 	 	 		 			78
LognormalDis	$\operatorname{stFromMoments}$			 	 	 	 	 			80
NakagamiDis	t			 	 	 		 			81
NormalDist				 	 	 	 	 			83
NormalDistQ	uick			 	 	 		 			86
NormalInvers	eGaussianDist			 	 	 		 			87
ParetoDist .				 	 	 		 			89
Pearson5Dist				 	 	 	 	 			91
Pearson6Dist				 	 	 	 	 			93
PiecewiseLine	earEmpiricalDis	5		 	 	 		 			95
PowerDist .				 	 	 		 			97
RayleighDist				 	 	 		 			99
StudentDist				 	 	 		 			101
TriangularDis	st			 	 	 		 			103
UniformDist				 	 	 	 	 			105
WeibullDist				 	 	 		 			107
TruncatedDis	t			 	 	 		 			110
Empirical Dist			`	 ,							112
	lingDist										112
	lingDistQuick .										113
	isesDist										114
Ŭ	mirnovPlusDist										116
O .	mirnovDist										118
Ŭ	mirnovDistQuic										119
				 	 	 		 			120
WatsonUDist											122

March 31, 2009 CONTENTS 2

# Overview

This package contains a set of Java classes providing methods to compute mass, density, distribution, complementary distribution, and inverse distribution functions for some discrete and continuous probability distributions. It also provides methods to estimate the parameters of some distributions from empirical data. It does not generate random variates; for that, see the package randvar. It is possible to plot the density or the cumulative probabilities of a distribution function either on screen, or in a LATEX file, but for this, one has to use the package charts.

# **Distributions**

We recall that the distribution function of a continuous random variable X with density f over the real line is

$$F(x) = P[X \le x] = \int_{-\infty}^{x} f(s)ds \tag{1}$$

while that of a discrete random variable X with mass function p over a fixed set of real numbers  $x_0 < x_1 < x_2 < \cdots$  is

$$F(x) = P[X \le x] = \sum_{x_i \le x} p(x_i), \tag{2}$$

where  $p(x_i) = P[X = x_i]$ . For a discrete distribution over the set of integers, one has

$$F(x) = P[X \le x] = \sum_{s=-\infty}^{x} p(s), \tag{3}$$

where p(s) = P[X = s].

We define  $\bar{F}$ , the complementary distribution function of X, by

$$\bar{F}(x) = P[X \ge x]. \tag{4}$$

With this definition of  $\bar{F}$ , one has  $\bar{F}(x) = 1 - F(x)$  for continuous distributions and  $\bar{F}(x) = 1 - F(x-1)$  for discrete distributions over the integers. This definition is non-standard for the discrete case: we have  $\bar{F}(x) = P[X \ge x]$  instead of  $\bar{F}(x) = P[X > x] = 1 - F(x)$ . We find it more convenient especially for computing p-values in goodness-of-fit tests.

The inverse distribution function is defined as

$$F^{-1}(u) = \inf\{x \in \mathbb{R} : F(x) \ge u\},$$
 (5)

for  $0 \le u \le 1$ . This function  $F^{-1}$  is often used, among other things, to generate the random variable X by inversion, by passing a U(0,1) random variate as the value of u.

The package probdist offers two types of tools for computing  $p, f, F, \bar{F}$ , and  $F^{-1}$ : static methods, for which no object needs to be created, and methods associated with distribution

March 31, 2009 CONTENTS **3** 

objects. Standard distributions are implemented each in their own class. Constructing an object from one of these classes can be convenient if F,  $\bar{F}$ , etc., has to be evaluated several times for the same distribution. In certain cases (for the Poisson distribution, for example), creating the distribution object would precompute tables that would speed up significantly all subsequent method calls for computing F,  $\bar{F}$ , etc. This trades memory, plus a one-time setup cost, for speed. In addition to the non-static methods, the distribution classes also provide static methods that do not require the creation of an object.

The distribution classes extend one of the (abstract) classes DiscreteDistribution and ContinuousDistribution (which both implement the interface Distribution) for discrete and continuous distributions over the real numbers, or DiscreteDistributionInt, for discrete distributions over the non-negative integers.

For example, the class PoissonDist extends DiscreteDistributionInt. Calling a static method from this class will compute the corresponding probability from scratch. Constructing a PoissonDist object, on the other hand, will precompute tables that contain the probability terms and the distribution function for a given parameter  $\lambda$  (the mean of the Poisson distribution). These tables will then be used whenever a method is called for the corresponding object. This second approach is recommended if some of F,  $\bar{F}$ , etc., has to be computed several times for the same parameter  $\lambda$ . As a rule of thumb, creating objects and using their methods is faster than just using static methods as soon as two or three calls are made, unless the parameters are large.

In fact, only the non-negligible probability terms (those that exceed the threshold DiscreteDistributionInt.EPSILON) are stored in the tables. For F and  $\bar{F}$ , a single table actually contains F(x) for  $F(x) \leq 1/2$  and 1 - F(x) for F(x) > 1/2. When the distribution parameters are so large that the tables would take too much space, these are not created and the methods automatically call their static equivalents instead of using tables.

Objects that implement the interface Distribution (and sometimes ContinuousDistribution) are required by some methods in package randvar and also in the classes GofStat and GofFormat, in package gof.

Some of the classes also provide methods that compute parameter estimators of the corresponding distribution from a set of empirical observations, in most cases based on the maximum likelihood method.

# Distribution

This interface should be implemented by all classes supporting discrete and continuous distributions. It specifies the signature of methods that compute the distribution function F(x), the complementary distribution function  $\bar{F}(x)$ , and the inverse distribution function  $F^{-1}(u)$ . It also specifies the signature of methods that returns the mean, the variance and the standard deviation.

```
package umontreal.iro.lecuyer.probdist;
public interface Distribution
   public double cdf (double x);
      Returns the distribution function F(x).
   public double barF (double x);
      Returns \bar{F}(x) = 1 - F(x).
   public double inverseF (double u);
      Returns the inverse distribution function F^{-1}(u), defined in (5).
   public double getMean();
      Returns the mean of the distribution function.
   public double getVariance();
      Returns the variance of the distribution function.
   public double getStandardDeviation();
      Returns the standard deviation of the distribution function.
   public double[] getParams();
      Returns the parameters of the distribution function in the same order as in the constructors.
```

# DiscreteDistribution

Classes implementing discrete distributions over a *finite set of real numbers* should inherit from this class. For discrete distributions over integers, see DiscreteDistributionInt.

We assume that the random variable X of interest can take one of the n values  $x_0 < \cdots < x_{n-1}$  (which are *sorted* by increasing order). It takes the value  $x_k$  with probability  $p_k = P[X = x_k]$ . In addition to the methods specified in the interface Distribution, a method that returns the probability  $p_k$  is supplied.

Note that the default implementation of the complementary distribution function returns 1.0 - cdf(x - 1), which is not accurate when F(x) is near 1.

```
package umontreal.iro.lecuyer.probdist;
```

public class DiscreteDistribution implements Distribution

#### Constructors

```
public DiscreteDistribution (double[] obs, double[] prob, int n)
```

Constructs a discrete distribution over the n values contained in array obs, with probabilities given in array prob. Both arrays must have at least n elements, the probabilities must sum to 1, and the observations are assumed to be sorted by increasing order.

```
@Deprecated
```

```
public DiscreteDistribution (int n, double[] obs, double[] prob)
Same as DiscreteDistribution(obs, prob, n).
```

```
public DiscreteDistribution (double[] params)
```

Constructs a discrete distribution whose parameters are given in a single ordered array: params[0] contains n, the number of values to consider. Then the next n values of params are the observation values, and the last n values of params are the probabilities values.

#### Methods

```
public double prob (int k)
```

Returns  $p_k$ , the probability of the k-th observation, for  $0 \le k < n$ . The result should be a real number in the interval [0,1].

```
public double getMean()
```

Computes the mean  $E[X] = \sum_{i=1}^{n} p_i x_i$  of the distribution.

```
public double getVariance()
```

Computes the variance  $Var[X] = \sum_{i=1}^{n} p_i(x_i - E[X])^2$  of the distribution.

March 31, 2009 Discrete Distribution 6

# public double getStandardDeviation()

Computes the standard deviation of the distribution.

# public double[] getParams()

Returns a table containing the parameters of the current distribution. This table is built in regular order, according to constructor DiscreteDistribution(double[] params) order.

#### public double getXinf()

Returns the lower limit  $x_a$  of the support of the distribution. The probability is 0 for all  $x < x_a$ .

### public double getXsup()

Returns the upper limit  $x_b$  of the support of the distribution. The probability is 0 for all  $x > x_b$ .

# public String toString()

Returns a String containing information about the current distribution.

# DiscreteDistributionInt

Classes implementing discrete distributions over the integers should inherit from this class. It specifies the signatures of methods for computing the mass function (or probability) p(x) = P[X = x], distribution function F(x), complementary distribution function  $\bar{F}(x)$ , and inverse distribution function  $F^{-1}(u)$ , for a random variable X with a discrete distribution over the integers.

WARNING: the complementary distribution function is defined as  $\bar{F}(j) = P[X \ge j]$  (for integers j, so that for discrete distributions in SSJ,  $F(j) + \bar{F}(j) \ne 1$  since both include the term P[X = j].

The implementing classes provide both static and non-static methods to compute the above functions. The non-static methods require the creation of an object of class DiscreteDistributionInt; all the non-negligible terms of the mass and distribution functions will be precomputed by the constructor and kept in arrays. Subsequent accesses will be very fast. The static methods do not require the construction of an object. These static methods are not specified in this abstract class because the number and types of their parameters depend on the distribution. When methods have to be called several times with the same parameters for the distributions, it is usually more efficient to create an object and use its non-static methods instead of the static ones. This trades memory for speed.

package umontreal.iro.lecuyer.probdist;

```
public abstract class DiscreteDistributionInt implements Distribution
  public static double EPSILON = 1.0e-16;
    Environment variable that determines what probability terms can be considered as negligible when building precomputed tables for distribution and mass functions. Probabilities smaller than EPSILON are not stored in the DiscreteDistribution objects (such as those of class PoissonDist, etc.), but are computed directly each time they are needed (which should be very seldom). The default value is set to 10<sup>-16</sup>.

public abstract double prob (int x);
    Returns p(x), the probability of x, which should be a real number in the interval [0,1].

public double cdf (double x)
    Returns the distribution function F evaluated at x (see (2)). Calls the cdf(int) method.

public double barF (double x)
    Returns F(x), the complementary distribution function. Calls the barF(int) method.
```

March 31, 2009 Discrete Distribution Int 8

#### public double barF (int x)

Returns  $\bar{F}(x)$ , the complementary distribution function. See the WARNING above.

### public int getXinf()

Returns the lower limit  $x_a$  of the support of the probability mass function. The probability is 0 for all  $x < x_a$ .

### public int getXsup()

Returns the upper limit  $x_b$  of the support of the probability mass function. The probability is 0 for all  $x > x_b$ .

### public double inverseF (double u)

Returns the inverse distribution function  $F^{-1}(u)$ , where  $0 \le u \le 1$ . Calls the inverseFint method.

### public int inverseFInt (double u)

Returns the inverse distribution function  $F^{-1}(u)$ , where  $0 \le u \le 1$ . The default implementation uses binary search.

# ContinuousDistribution

Classes implementing continuous distributions should inherit from this base class. Such distributions are characterized by a *density* function f(x), thus the signature of a **density** method is supplied here. This class also provides default implementations for  $\bar{F}(x)$  and for  $F^{-1}(u)$ , the latter using the Brent-Dekker method to find the inverse of a generic distribution function F.

```
package umontreal.iro.lecuyer.probdist;
public abstract class ContinuousDistribution implements Distribution
   public abstract double density (double x);
      Returns f(x), the density evaluated at x.
   public double barF (double x)
      Returns the complementary distribution function. The default implementation computes
      F(x) = 1 - F(x), which is not accurate when F(x) \to 1.
   public double inverseBrent (double a, double b, double u, double tol)
      Computes the inverse distribution function x = F^{-1}(u), using the Brent-Dekker method.
      The interval [a, b] must contain the root x such that F(a) \le u \le F(b), where u = F(x).
      The calculations are done with an approximate precision of tol. Returns x = F^{-1}(u).
      Restrictions: u \in [0, 1].
   public double inverseBisection (double u)
      Computes and returns the inverse distribution function x = F^{-1}(u), using bisection. Re-
      strictions: u \in [0, 1].
   public double inverseF (double u)
      Computes and returns the inverse distribution function x = F^{-1}(u), by calling the method
      inverseBrent. Restrictions: u \in [0, 1].
   public double getMean()
      Returns the mean.
   public double getVariance()
      Returns the variance.
   public double getStandardDeviation()
      Returns the standard deviation.
   public double getXinf()
      Returns x_a such that the probability density is 0 everywhere outside the interval [x_a, x_b].
```

# public double getXsup()

Returns  $x_b$  such that the probability density is 0 everywhere outside the interval  $[x_a, x_b]$ .

# public void setXinf (double xa)

Sets the value  $x_a = xa$ , such that the probability density is 0 everywhere outside the interval  $[x_a,x_b].$ 

# public void setXsup (double xb)

Sets the value  $x_b = xb$ , such that the probability density is 0 everywhere outside the interval  $[x_a, x_b].$ 

# DistributionFactory

This class implements a string API for the package probdist. It uses Java Reflection to allow the creation of probability distribution objects from a string. This permits one to obtain distribution specifications from a file or dynamically from user input during program execution. This string API is similar to that of UNURAN [30].

The (static) methods of this class invoke the constructor specified in the string. For example,

d = DistributionFactory.getContinuousDistribution ("NormalDist (0.0, 2.5)");
is equivalent to

d = NormalDist (0.0, 2.5);

The string that specifies the distribution (i.e., the formal parameter str of the methods) must be a valid call of the constructor of a class that extends ContinuousDistribution or DiscreteDistribution, and all parameter values must be numerical values (variable names are not allowed).

The distribution parameters can also be estimated from a set of observations instead of being passed to the constructor. In that case, one passes the vector of observations, and the constructor estimates the parameters by the maximum likelihood method.

package umontreal.iro.lecuyer.probdist;

public class DistributionFactory

Uses the Java Reflection API to construct a ContinuousDistribution object by estimating parameters of the distribution using the maximum likelihood method based on the n observations in table x[i],  $i = 0, 1, \ldots, n-1$ .

Uses the Java Reflection API to construct a DiscreteDistributionInt object by estimating parameters of the distribution using the maximum likelihood method based on the n observations in table x[i], i = 0, 1, ..., n - 1.

Uses the Java Reflection API to construct a ContinuousDistribution object by estimating parameters of the distribution using the maximum likelihood method based on the n observations in table x[i], i = 0, 1, ..., n-1.

March 31, 2009 DistributionFactory 12

Uses the Java Reflection API to construct a DiscreteDistributionInt object by estimating parameters of the distribution using the maximum likelihood method based on the n observations in table x[i], i = 0, 1, ..., n-1.

public static ContinuousDistribution getContinuousDistribution (String str)

Uses the Java Reflection API to construct a ContinuousDistribution object by executing the code contained in the string str. This code should be a valid invocation of the constructor of a ContinuousDistribution object. This method throws exceptions if it cannot parse the given string and returns null if the distribution object could not be created due to a Java-specific instantiation problem.

- public static DiscreteDistribution getDiscreteDistribution (String str)

  Same as getContinuousDistribution, but for discrete distributions over the real numbers.
- public static DiscreteDistributionInt getDiscreteDistributionInt (String str)
  Same as getContinuousDistribution, but for discrete distributions over the integers.

# **BinomialDist**

Extends the class DiscreteDistributionInt for the binomial distribution [27, page 321] with parameters n and p, where n is a positive integer and  $0 \le p \le 1$ . Its mass function is given by

$$p(x) = \binom{n}{x} p^x (1-p)^{n-x} = \frac{n!}{x!(n-x)!} p^x (1-p)^{n-x} \quad \text{for } x = 0, 1, 2, \dots n,$$
 (6)

and its distribution function is

$$F(x) = \sum_{j=0}^{x} \binom{n}{j} p^{j} (1-p)^{n-j} \quad \text{for } x = 0, 1, 2, \dots n,$$
 (7)

package umontreal.iro.lecuyer.probdist;

public class BinomialDist extends DiscreteDistributionInt

#### Constructor

public BinomialDist (int n, double p)

Creates an object that contains the binomial terms (6), for  $0 \le x \le n$ , and the corresponding cumulative function. These values are computed and stored in dynamic arrays, unless n exceeds MAXN.

#### Methods

public static double prob (int n, double p, int x)

Computes and returns the binomial probability p(x) in eq. (6).

public static double prob (int n, double p, double q, int x)

A generalization of the previous method. Computes and returns the binomial term

$$f(x) = \binom{n}{x} p^x q^{n-x} = \frac{n!}{x!(n-x)!} p^x q^{n-x},$$
(8)

where p and q are arbitrary real numbers (q is not necessarily equal to 1-p). In the case where  $0 \le p \le 1$  and q = 1-p, the returned value is a probability term for the binomial distribution.

public static double cdf (int n, double p, int x)

Computes F(x), the distribution function of a binomial random variable with parameters n and p, evaluated at x.

March 31, 2009 BinomialDist 14

# public static int inverseF (int n, double p, double u)

Computes the inverse of the binomial distribution,  $x = F^{-1}(u)$ , using a linear search starting at the mode if n is small. If n is larger than 10000, the linear search starts from 0 and the cdf static method is used to compute F(x) at different values of x, which much is less efficient.

### public static double[] getMLE (int[] x, int m)

Estimates the parameters (n, p) of the binomial distribution using the maximum likelihood method, from the m observations x[i], i = 0, 1, ..., m - 1. The estimates are returned in a two-element array, in regular order: [n, p].

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (int[] x, int m)
Same as getMLE.

#### public static BinomialDist getInstanceFromMLE (int[] x, int m)

Creates a new instance of a binomial distribution with both parameters n and p estimated using the maximum likelihood method, from the m observations x[i], i = 0, 1, ..., m - 1.

# public static double[] getMLE (int[] x, int m, int n)

Estimates the parameter p of the binomial distribution with given (fixed) parameter n, by the maximum likelihood method, from the m observations x[i], i = 0, 1, ..., m-1. Returns the estimator in an array with a single element.

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (int[] x, int m, int n)
 Same as getMLE.

# public static BinomialDist getInstanceFromMLE (int[] x, int m, int n)

Creates a new instance of a binomial distribution with given (fixed) parameter n, and with parameter p estimated by the maximum likelihood method based on the m observations x[i],  $i = 0, 1, \ldots, m-1$ .

#### public static double getMean (int n, double p)

Computes the mean E[X] = np of the binomial distribution with parameters n and p.

### public static double getVariance (int n, double p)

Computes the variance Var[X] = np(1-p) of the binomial distribution with parameters n and p.

#### public static double getStandardDeviation (int n, double p)

Computes the standard deviation of the Binomial distribution with parameters n and p.

#### public int getN()

Returns the parameter n of this object.

March 31, 2009 BinomialDist 15

# public double getP()

Returns the parameter p of this object.

# public double[] getParams ()

Returns a table that contains the parameters (n, p) of the current distribution, in regular order: [n, p].

# public void setParams (int n, double p)

Resets the parameters to these new values and recomputes everything as in the constructor. From the performance viewpoint, it is essentially the same as constructing a new BinomialDist object.

# GeometricDist

Extends the class DiscreteDistributionInt for the geometric distribution [27, page 322] with parameter p, where 0 . Its mass function is

$$p(x) = p(1-p)^x$$
, for  $x = 0, 1, 2, ...$  (9)

The distribution function is given by

$$F(x) = 1 - (1 - p)^{x+1}, \quad \text{for } x = 0, 1, 2, \dots$$
 (10)

and its inverse is

$$F^{-1}(u) = \left\lfloor \frac{\ln(1-u)}{\ln(1-p)} \right\rfloor, \quad \text{for } 0 \le u < 1.$$
 (11)

package umontreal.iro.lecuyer.probdist;

public class GeometricDist extends DiscreteDistributionInt

#### Constructor

public GeometricDist (double p)

Constructs a geometric distribution with parameter p.

#### Methods

public static double prob (double p, int x)

Computes the geometric probability p(x) given in (9).

public static double cdf (double p, int x)

Computes the distribution function F(x).

public static double barF (double p, int x)

Computes the complementary distribution function. WARNING: The complementary distribution function is defined as  $\bar{F}(x) = P[X \ge x]$ .

public static int inverseF (double p, double u)

Computes the inverse of the geometric distribution, given by (11).

public static double[] getMLE (int[] x, int n)

Estimates the parameter p of the geometric distribution using the maximum likelihood method, from the n observations x[i], i = 0, 1, ..., n - 1. The estimate is returned in element 0 of the returned array.

March 31, 2009 GeometricDist 17

# @Deprecated public static double[] getMaximumLikelihoodEstimate (int[] x, int n) Same as getMLE.

# public static GeometricDist getInstanceFromMLE (int[] x, int n)

Creates a new instance of a geometric distribution with parameter p estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n - 1.

### public static double getMean (double p)

Computes and returns the mean E[X] = (1 - p)/p of the geometric distribution with parameter p.

# public static double getVariance (double p)

Computes and returns the variance  $Var[X] = (1 - p)/p^2$  of the geometric distribution with parameter p.

# public static double getStandardDeviation (double p)

Computes and returns the standard deviation of the geometric distribution with parameter p.

### public double getP()

Returns the p associated with this object.

#### public void setP (double p)

Resets the value of p associated with this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution.

# HypergeometricDist

Extends the class DiscreteDistributionInt for the hypergeometric distribution [18, page 101] with k elements chosen among l, m being of one type, and l-m of the other. The parameters m, k and l are positive integers where  $1 \le m \le l$  and  $1 \le k \le l$ . Its mass function is given by

$$p(x) = \frac{\binom{m}{x} \binom{l-m}{k-x}}{\binom{l}{k}} \qquad \text{for } \max(0, k-l+m) \le x \le \min(k, m).$$
 (12)

package umontreal.iro.lecuyer.probdist;

public class HypergeometricDist extends DiscreteDistributionInt

#### Constructor

public HypergeometricDist (int m, int l, int k)

Constructs an hypergeometric distribution with parameters m, l and k.

#### Methods

public static double prob (int m, int 1, int k, int x)

Computes the hypergeometric probability p(x) given by (12).

public static double cdf (int m, int l, int k, int x)

Computes the distribution function F(x).

public static double barF (int m, int l, int k, int x)

Computes the complementary distribution function. WARNING: The complementary distribution function is defined as  $\bar{F}(x) = P[X \ge x]$ .

public static int inverseF (int m, int l, int k, double u)

Computes  $F^{-1}(u)$  for the hypergeometric distribution without using precomputed tables. The inversion is computed using the chop-down algorithm [24].

public static double getMean (int m, int 1, int k)

Computes and returns the mean E[X] = km/l of the Hypergeometric distribution with parameters m, l and k.

public static double getVariance (int m, int l, int k)

Computes and returns the variance  $\operatorname{Var}[X] = \frac{(km/l)(1-m/l)(l-k)}{l-1}$  of the hypergeometric distribution with parameters m, l and k.

### public static double getStandardDeviation (int m, int 1, int k)

Computes and returns the standard deviation of the hypergeometric distribution with parameters m, l and k.

#### public int getM()

Returns the m associated with this object.

# public int getL()

Returns the l associated with this object.

### public int getK()

Returns the k associated with this object.

### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order: [m, l, k].

### public void setParams (int m, int 1, int k)

Resets the parameters of this object to m, l and k.

March 31, 2009 20

# LogarithmicDist

Extends the class DiscreteDistributionInt for the logarithmic distribution. It has shape parameter  $\theta$ , where  $0 < \theta < 1$ . Its mass function is

$$p(x) = \frac{-1}{\log(1-\theta)} \frac{\theta^x}{x}$$
 for  $x = 1, 2, 3, ...$  (13)

Its distribution function is

$$F(x) = \frac{-1}{\log(1-\theta)} \sum_{i=1}^{x} \frac{\theta^{i}}{i}, \quad \text{for } x = 1, 2, 3, \dots$$
 (14)

and is 0 for x < 0.

package umontreal.iro.lecuyer.probdist;

public class LogarithmicDist extends DiscreteDistributionInt

#### Constructor

public LogarithmicDist (double theta)

Constructs a logarithmic distribution with parameter  $\theta =$  theta.

#### Methods

public static double prob (double theta, int x)

Computes the logarithmic probability p(x) given in (13).

public static double cdf (double theta, int x)

Computes the distribution function F(x).

public static double barF (double theta, int x)

Computes the complementary distribution function. WARNING: The complementary distribution function is defined as  $\bar{F}(x) = P[X \ge x]$ .

public static double[] getMLE (int[] x, int n)

Estimates the parameter  $\theta$  of the logarithmic distribution using the maximum likelihood method, from the n observations x[i],  $i=0,1,\ldots,n-1$ . The estimate is returned in element 0 of the returned array.

```
@Deprecated
```

public static double[] getMaximumLikelihoodEstimate (int[] x, int n)

Same as getMLE.

# public static LogarithmicDist getInstanceFromMLE (int[] x, int n)

Creates a new instance of a logarithmic distribution with parameter  $\theta$  estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n - 1.

# public static double getMean (double theta)

Computes and returns the mean

$$E[X] = \frac{-1}{\ln(1-\theta)} \frac{\theta}{(1-\theta)}$$

of the logarithmic distribution with parameter  $\theta = \text{theta}$ .

# public static double getVariance (double theta)

Computes and returns the variance

$$Var[X] = \frac{-\theta(\theta + \ln(1 - \theta))}{[(1 - \theta)\ln(1 - \theta)]^2}$$

of the logarithmic distribution with parameter  $\theta = \text{theta}$ .

# public static double getStandardDeviation (double theta)

Computes and returns the standard deviation of the logarithmic distribution with parameter  $\theta = \mathtt{theta}$ .

# public double getTheta()

Returns the  $\theta$  associated with this object.

#### public void setTheta (double theta)

Sets the  $\theta$  associated with this object.

### public double[] getParams ()

Return a table containing the parameters of the current distribution.

March 31, 2009 22

# NegativeBinomialDist

Extends the class DiscreteDistributionInt for the negative binomial distribution [27, page 324] with real parameters  $\gamma$  and p, where  $\gamma > 0$  and  $0 \le p \le 1$ . Its mass function is

$$p(x) = \frac{\Gamma(\gamma + x)}{x! \Gamma(\gamma)} p^{\gamma} (1 - p)^x, \quad \text{for } x = 0, 1, 2, \dots$$
 (15)

where  $\Gamma$  is the gamma function.

If  $\gamma$  is an integer, p(x) can be interpreted as the probability of having x failures before the  $\gamma$ -th success in a sequence of independent Bernoulli trials with probability of success p. This special case is implemented as the Pascal distribution (see PascalDist).

package umontreal.iro.lecuyer.probdist;

public class NegativeBinomialDist extends DiscreteDistributionInt

#### Constructor

public NegativeBinomialDist (double gamma, double p)

Creates an object that contains the probability terms (15) and the distribution function for the negative binomial distribution with parameters  $\gamma$  and p.

#### Methods

public static double prob (double gamma, double p, int x) Computes the probability p(x) defined in (15).

public static double cdf (double gamma, double p, int x)
Computes the distribution function.

public static int inverseF (double gamma, double p, double u)

Computes the inverse function without precomputing tables. This method computes the CDF at the mode (maximum term) and performs a linear search from that point.

public static double[] getMLE (int[] x, int n, double gamma)

Estimates the parameter p of the negative binomial distribution using the maximum likelihood method, from the n observations x[i],  $i=0,1,\ldots,n-1$ . The parameter  $\gamma=$  gamma is assumed known. The estimate  $\hat{p}$  is returned in element 0 of the returned array. The maximum likelihood estimator  $\hat{p}$  satisfies the equation  $\hat{p}=\gamma/(\gamma+\bar{x}_n)$ , where  $\bar{x}_n$  is the average of  $x[0],\ldots,x[n-1]$ .

Same as getMLE.

Creates a new instance of a negative binomial distribution with parameters  $\gamma = \text{gamma}$  given and  $\hat{p}$  estimated using the maximum likelihood method, from the n observations x[i],  $i = 0, 1, \ldots, n-1$ .

# public static double[] getMLE (int[] x, int n)

Estimates the parameter  $(\gamma, p)$  of the negative binomial distribution using the maximum likelihood method, from the n observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\gamma, p]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (int[] x, int n)
 Same as getMLE.

public static NegativeBinomialDist getInstanceFromMLE (int[] x, int n)

Creates a new instance of a negative binomial distribution with parameters  $\gamma$  and p estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n-1.

### public static double getMean (double gamma, double p)

Computes and returns the mean  $E[X] = \gamma(1-p)/p$  of the negative binomial distribution with parameters  $\gamma$  and p.

#### public static double getVariance (double gamma, double p)

Computes and returns the variance  $Var[X] = \gamma(1-p)/p^2$  of the negative binomial distribution with parameters  $\gamma$  and p.

#### public static double getStandardDeviation (double gamma, double p)

Computes and returns the standard deviation of the negative binomial distribution with parameters  $\gamma$  and p.

#### public double getGamma()

Returns the parameter  $\gamma$  of this object.

# public double getP()

Returns the parameter p of this object.

# public void setParams (double gamma, double p)

Sets the parameter  $\gamma$  and p of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\gamma, p]$ .

March 31, 2009 24

# **PascalDist**

The *Pascal* distribution is a special case of the *negative binomial* distribution [27, page 324] with parameters n and p, where n is a positive integer and  $0 \le p \le 1$ . Its mass function is

$$p(x) = \binom{n+x-1}{x} p^n (1-p)^x, \quad \text{for } x = 0, 1, 2, \dots$$
 (16)

This p(x) can be interpreted as the probability of having x failures before the nth success in a sequence of independent Bernoulli trials with probability of success p. For n = 1, this gives the geometric distribution.

package umontreal.iro.lecuyer.probdist;

public class PascalDist extends NegativeBinomialDist

#### Constructor

```
public PascalDist (int n, double p)
```

Creates an object that contains the probability terms (16) and the distribution function for the Pascal distribution with parameter n and p.

#### Methods

```
public static double[] getMLE (int[] x, int m)
```

Estimates the parameter (n, p) of the Pascal distribution using the maximum likelihood method, from the m observations x[i], i = 0, 1, ..., m - 1. The estimates are returned in a two-element array, in regular order: [n, p].

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (int[] x, int m)
 Same as getMLE.

```
public static PascalDist getInstanceFromMLE (int[] x, int m)
```

Creates a new instance of a Pascal distribution with parameters n and p estimated using the maximum likelihood method based on the m observations x[i], i = 0, 1, ..., m - 1.

#### public int getN()

Returns the parameter n of this object.

#### public void setParams (int n, double p)

Sets the parameter n and p of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order: [n, p].

March 31, 2009 25

# **PoissonDist**

Extends the class DiscreteDistributionInt for the *Poisson* distribution [27, page 325] with mean  $\lambda \geq 0$ . The mass function is

$$p(x) = \frac{e^{-\lambda}\lambda^x}{x!}, \quad \text{for } x = 0, 1, \dots$$
 (17)

and the distribution function is

$$F(x) = e^{-\lambda} \sum_{j=0}^{x} \frac{\lambda^{j}}{j!}, \quad \text{for } x = 0, 1, \dots$$
 (18)

If one has to compute p(x) and/or F(x) for several values of x with the same  $\lambda$ , where  $\lambda$  is not too large, then it is more efficient to instantiate an object and use the non-static methods, since the functions will then be computed once and kept in arrays.

For the static methods that compute F(x) and  $\bar{F}(x)$ , we exploit the relationship  $F(x) = 1 - G_{x+1}(\lambda)$ , where  $G_{x+1}$  is the *gamma* distribution function with parameters  $(\alpha, \lambda) = (x+1,1)$ .

package umontreal.iro.lecuyer.probdist;

public class PoissonDist extends DiscreteDistributionInt

#### Constructor

public PoissonDist (double lambda)

Creates an object that contains the probability and distribution functions, for the Poisson distribution with parameter lambda, which are computed and stored in dynamic arrays inside that object.

#### Methods

public static double prob (double lambda, int x)

Computes and returns the Poisson probability p(x) for  $\lambda = \texttt{lambda}$ , as defined in (17).

public static double cdf (double lambda, int x)

Computes and returns the value of the Poisson distribution function F(x) for  $\lambda = \mathtt{lambda}$ , as defined in (18).

public static double barF (double lambda, int x)

Computes and returns the value of the complementary Poisson distribution function, for  $\lambda = \mathtt{lambda}$ . WARNING: The complementary distribution function is defined as  $\bar{F}(x) = P[X \geq x]$ .

March 31, 2009 PoissonDist **26** 

public static int inverseF (double lambda, double u)

Performs a linear search to get the inverse function without precomputed tables.

public static double[] getMLE (int[] x, int n)

Estimates the parameter  $\lambda$  of the Poisson distribution using the maximum likelihood method, from the n observations x[i],  $i=0,1,\ldots,n-1$ . The maximum likelihood estimator  $\hat{\lambda}$  satisfy the equation  $\hat{\lambda} = \bar{x}_n$ , where  $\bar{x}_n$  is the average of  $x[0],\ldots,x[n-1]$  (see [27, page 326]).

@Deprecated

public static double[] getMaximumLikelihoodEstimate (int[] x, int n)
Same as getMLE.

public static PoissonDist getInstanceFromMLE (int[] x, int n)

Creates a new instance of a Poisson distribution with parameter  $\lambda$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

public static double getMean (double lambda)

Computes and returns the mean  $E[X] = \lambda$  of the Poisson distribution with parameter  $\lambda$ .

public static double getVariance (double lambda)

Computes and returns the variance =  $\lambda$  of the Poisson distribution with parameter  $\lambda$ .

public static double getStandardDeviation (double lambda)

Computes and returns the standard deviation of the Poisson distribution with parameter  $\lambda$ .

public double getLambda()

Returns the  $\lambda$  associated with this object.

public void setLambda (double lambda)

Sets the  $\lambda$  associated with this object.

public double[] getParams ()

Return a table containing the parameter of the current distribution.

March 31, 2009 27

# **UniformIntDist**

Extends the class DiscreteDistributionInt for the discrete uniform distribution over the range [i, j]. Its mass function is given by

$$p(x) = \frac{1}{j - i + 1}$$
 for  $x = i, i + 1, \dots, j$  (19)

and 0 elsewhere. The distribution function is

$$F(x) = \begin{cases} 0, & \text{for } x < i \\ \frac{\lfloor x \rfloor - i + 1}{j - i + 1}, & \text{for } i \le x < j \\ 1, & \text{for } x \ge j. \end{cases}$$
 (20)

and its inverse is

$$F^{-1}(u) = i + |(j - i + 1)u| \quad \text{for } 0 \le u \le 1.$$
 (21)

package umontreal.iro.lecuyer.probdist;

public class UniformIntDist extends DiscreteDistributionInt

#### Constructor

```
public UniformIntDist (int i, int j)
```

Constructs a discrete uniform distribution over the interval [i, j].

#### Methods

public static double prob (int i, int j, int x)

Computes the discrete uniform probability p(x) defined in (19).

public static double cdf (int i, int j, int x)

Computes the discrete uniform distribution function defined in (20).

public static double barF (int i, int j, int x)

Computes the discrete uniform complementary distribution function  $\bar{F}(x)$ . WARNING: The complementary distribution function is defined as  $\bar{F}(x) = P[X \ge x]$ .

public static int inverseF (int i, int j, double u)

Computes the inverse of the discrete uniform distribution function (21).

March 31, 2009 UniformIntDist 28

```
public static double[] getMLE (int[] x, int n)
```

Estimates the parameters (i, j) of the uniform distribution over integers using the maximum likelihood method, from the n observations x[k], k = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order: [i, j].

### @Deprecated

public static double[] getMaximumLikelihoodEstimate (int[] x, int n)
 Same as getMLE.

```
public static UniformIntDist getInstanceFromMLE (int[] x, int n)
```

Creates a new instance of a discrete uniform distribution over integers with parameters i and j estimated using the maximum likelihood method based on the n observations x[k],  $k = 0, 1, \ldots, n-1$ .

```
public static double getMean (int i, int j)
```

Computes and returns the mean E[X] = (i + j)/2 of the discrete uniform distribution.

```
public static double getVariance (int i, int j)
```

Computes and returns the variance  $Var[X] = [(j-i+1)^2 - 1]/12$  of the discrete uniform distribution.

```
public static double getStandardDeviation (int i, int j)
```

Computes and returns the standard deviation of the discrete uniform distribution.

```
public int getI()
```

Returns the parameter i.

```
public int getJ()
```

Returns the parameter j.

```
public void setParams (int i, int j)
```

Sets the parameters i and j for this object.

```
public double[] getParams ()
```

Return a table containing the parameters of the current distribution. This table is put in regular order: [i, j].

March 31, 2009 29

# **EmpiricalDist**

Extends DiscreteDistribution to an *empirical* distribution function, based on the observations  $X_{(1)}, \ldots, X_{(n)}$  (sorted by increasing order). The distribution is uniform over the n observations, so the distribution function has a jump of 1/n at each of the n observations.

```
package umontreal.iro.lecuyer.probdist;
public class EmpiricalDist extends DiscreteDistribution
```

#### Constructors

```
public EmpiricalDist (double[] obs)
```

Constructs a new empirical distribution using all the observations stored in obs, and which are assumed to have been sorted in increasing numerical order. <sup>1</sup> These observations are copied into an internal array.

```
public EmpiricalDist (Reader in) throws IOException
```

Constructs a new empirical distribution using the observations read from the reader in. This constructor will read the first double of each line in the stream. Any line that does not start with a +, -, or a decimal digit, is ignored. One must be careful about lines starting with a blank. This format is the same as in UNURAN. The observations read are assumed to have been sorted in increasing numerical order.

#### Methods

```
public double getMedian ()
```

Returns the  $n/2^{\text{th}}$  item of the sorted observations when the number of items is odd, and the mean of the  $n/2^{\text{th}}$  and the  $(n/2+1)^{\text{th}}$  items when the number of items is even.

```
public static double getMedian (double obs[], int n)
```

Returns the  $n/2^{th}$  item of the array obs when the number of items is odd, and the mean of the  $n/2^{th}$  and the  $(n/2+1)^{th}$  items when the number of items is even. The array does not have to be sorted.

```
public int getN()
```

Returns n, the number of observations.

```
public double getObs (int i)
```

Returns the value of  $X_{(i)}$ .

```
public double getSampleMean()
```

Returns the sample mean of the observations.

<sup>&</sup>lt;sup>1</sup>The method java.util.Arrays.sort may be used to sort the observations.

March 31, 2009 EmpiricalDist 30

### public double getSampleVariance()

Returns the sample variance of the observations.

## public double getSampleStandardDeviation()

Returns the sample standard deviation of the observations.

# public double getInterQuartileRange()

Returns the *interquartile range* of the observations, defined as the difference between the third and first quartiles.

### public double[] getParams ()

Return a table containing parameters of the current distribution.

### public String toString ()

Returns a String containing information about the current distribution.

# BetaDist

Extends the class Continuous Distribution for the beta distribution [23, page 210] with shape parameters  $\alpha > 0$  and  $\beta > 0$ , over the interval (a, b), where a < b. This distribution has density

$$f(x) = \frac{(x-a)^{\alpha-1}(b-x)^{\beta-1}}{\mathcal{B}(\alpha,\beta)(b-a)^{\alpha+\beta-1}}, \quad \text{for } a < x < b, \text{ and } 0 \text{ elsewhere},$$
 (22)

and distribution function

$$F(x) = I_{\alpha,\beta}(x) = \int_{a}^{x} \frac{(\xi - a)^{\alpha - 1} (b - \xi)^{\beta - 1}}{\mathcal{B}(\alpha, \beta)(b - a)^{\alpha + \beta - 1}} d\xi, \quad \text{for } a < x < b,$$
 (23)

where  $\mathcal{B}(\alpha,\beta)$  is the *beta* function defined by

$$\mathcal{B}(\alpha,\beta) = \frac{\Gamma(\alpha)\Gamma(\beta)}{\Gamma(\alpha+\beta)},\tag{24}$$

and  $\Gamma(x)$  is the gamma function defined in (44).

package umontreal.iro.lecuyer.probdist;

public class BetaDist extends ContinuousDistribution

#### Constructors

public BetaDist (double alpha, double beta)

Constructs a BetaDist object with parameters  $\alpha = \text{alpha}$  and  $\beta = \text{beta}$  and default domain (0,1).

public BetaDist (double alpha, double beta, double a, double b)

Constructs a BetaDist object with parameters  $\alpha = \text{alpha}$  and  $\beta = \text{beta}$ , and domain (a, b).

public BetaDist (double alpha, double beta, int d)

Constructs a BetaDist object with parameters  $\alpha = \text{alpha}$  and  $\beta = \text{beta}$ , and approximations of roughly d decimal digits of precision when computing the distribution, complementary distribution, and inverse functions. The default domain (0,1) is used.

public BetaDist (double alpha, double beta, double a, double b, int d)

Constructs a BetaDist object with parameters  $\alpha = \text{alpha}$  and  $\beta = \text{beta}$ , and approximations of roughly d decimal digits of precision when computing distribution, complementary distribution, and inverse functions. The domain (a, b) is used.

March 31, 2009 BetaDist **32** 

#### Methods

public static double density (double alpha, double beta, double x) Same as density (alpha, beta, 0, 1, x).

Computes the density function of the *beta* distribution.

public static double cdf (double alpha, double beta, int d, double x)
 Same as cdf (alpha, beta, 0, 1, d, x).

Computes an approximation of the distribution function, with roughly d decimal digits of precision.

public static double barF (double alpha, double beta, int d, double x)
 Same as barF (alpha, beta, 0, 1, d, x).

Computes the complementary distribution function.

public static double inverseF (double alpha, double beta, int d, double u) Same as inverseF (alpha, beta, 0, 1, d, u).

Returns the inverse beta distribution function using the algorithm implemented in [36]. The method performs interval halving or Newton iterations to compute the inverse. The precision depends on the accuracy of the cdf method. The argument d gives a good idea of the precision attained.

public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \beta)$  of the beta distribution over the interval [0, 1] using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n-1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \beta]$ .

@Deprecated
public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

public static BetaDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a beta distribution with parameters  $\alpha$  and  $\beta$  over the interval [0,1] estimated using the maximum likelihood method based on the n observations x[i],  $i=0,1,\ldots,n-1$ .

March 31, 2009 BetaDist **33** 

# public static double getMean (double alpha, double beta)

Computes and returns the mean  $E[X] = \alpha/(\alpha + \beta)$  of the beta distribution with parameters  $\alpha$  and  $\beta$ , over the interval [0,1].

#### 

Computes and returns the mean  $E[X] = (b\alpha + a\beta)/(\alpha + \beta)$  of the beta distribution with parameters  $\alpha$  and  $\beta$  over the interval [a, b].

# public static double getVariance (double alpha, double beta)

Computes and returns the variance  $Var[X] = \frac{\alpha\beta}{(\alpha+\beta)^2(\alpha+\beta+1)}$  of the beta distribution with parameters  $\alpha$  and  $\beta$ , over the interval [0, 1].

#### 

Computes and returns the variance  $\operatorname{Var}[X] = \frac{\alpha\beta(b-a)^2}{(\alpha+\beta)^2(\alpha+\beta+1)}$  of the beta distribution with parameters  $\alpha$  and  $\beta$ , over the interval [a,b].

# public static double getStandardDeviation (double alpha, double beta)

Computes the standard deviation of the beta distribution with parameters  $\alpha$  and  $\beta$ , over the interval [0,1].

#### 

Computes the standard deviation of the beta distribution with parameters  $\alpha$  and  $\beta$ , over the interval [a, b].

# public double getAlpha()

Returns the parameter  $\alpha$  of this object.

#### public double getBeta()

Returns the parameter  $\beta$  of this object.

#### public double getA()

Returns the parameter a of this object.

#### public double getB()

Returns the parameter b of this object.

#### public double[] getParams ()

Return a table containing parameters of the current distribution. This table is put in regular order:  $[\alpha, \beta]$ .

March 31, 2009 34

# BetaSymmetricalDist

Specializes the class BetaDist to the case of a symmetrical beta distribution over the interval [0,1], with shape parameters  $\alpha=\beta$ . A faster inversion method is implemented here for this special case. Because of the symmetry around 1/2, four series are used to compute the cdf, two around x=0 and two around x=1/2. Given u, one then solves each series for x by using the Newton-Raphson method which shows quadratic convergence when the starting iterate is close enough to the solution x.

```
package umontreal.iro.lecuyer.probdist;
public class BetaSymmetricalDist extends BetaDist
```

#### Constructors

```
public BetaSymmetricalDist (double alpha)
```

Constructs a BetaSymmetricalDist object with parameters  $\alpha = \beta = \text{alpha}$ , over the unit interval (0,1).

```
public BetaSymmetricalDist (double alpha, int d)
```

Same as BetaSymmetricalDist (alpha), but using approximations of roughly d decimal digits of precision when computing the distribution, complementary distribution, and inverse functions.

#### Methods

```
public static double density (double alpha, double x)
  Returns the density evaluated at x.

public static double cdf (double alpha, int d, double x)
  Same as cdf (alpha, alpha, d, x).

public static double barF (double alpha, int d, double x)
  Same as barF (alpha, beta, d, x).

public static double inverseF (double alpha, double u)
```

Returns the inverse distribution function evaluated at u, for the symmetrical beta distribution over the interval [0,1], with shape parameters  $0<\alpha=\beta=$  alpha. Uses four different hypergeometric series to compute the distribution u=F(x) (for the four cases x close to 0 and  $\alpha<1$ , x close to 0 and  $\alpha>1$ , x close to 1/2 and  $\alpha<1$ , and x close to 1/2 and  $\alpha>1$ ), which are then solved by Newton's method for the solution of equations. For  $\alpha>100000$ , uses a normal approximation given in [38].

# public static double[] getMLE (double[] x, int n)

Estimates the parameter  $\alpha$  of the symmetrical beta distribution over the interval [0, 1] using the maximum likelihood method, from the n observations  $x[i], i = 0, 1, \ldots, n-1$ . The estimate is returned in element 0 of the returned array.

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n) Same as getMLE.

# public static BetaSymmetricalDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a symmetrical beta distribution with parameter  $\alpha$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

# public static double getMean (double alpha)

Computes and returns the mean E[X] = 1/2 of the symmetrical beta distribution with parameter  $\alpha$ .

#### public static double getVariance (double alpha)

Computes and returns the variance,  $Var[X] = 1/(8\alpha + 4)$ , of the symmetrical beta distribution with parameter  $\alpha$ .

# public static double getStandardDeviation (double alpha)

Computes and returns the standard deviation of the symmetrical beta distribution with parameter  $\alpha$ .

#### public double[] getParams ()

Return a table containing the parameter of the current distribution.

# CauchyDist

Extends the class Continuous Distribution for the Cauchy distribution [22, page 299] with location parameter  $\alpha$  and scale parameter  $\beta > 0$ . The density function is given by

$$f(x) = \frac{\beta}{\pi[(x-\alpha)^2 + \beta^2]}, \quad \text{for } -\infty < x < \infty.$$
 (25)

The distribution function is

$$F(x) = \frac{1}{2} + \frac{\arctan((x - \alpha)/\beta)}{\pi}, \quad \text{for } -\infty < x < \infty,$$
 (26)

and its inverse is

$$F^{-1}(u) = \alpha + \beta \tan(\pi(u - 1/2)). \quad \text{for } 0 < u < 1.$$
 (27)

package umontreal.iro.lecuyer.probdist;

public class CauchyDist extends ContinuousDistribution

#### Constructors

public CauchyDist()

Constructs a CauchyDist object with parameters  $\alpha = 0$  and  $\beta = 1$ .

public CauchyDist (double alpha, double beta)

Constructs a CauchyDist object with parameters  $\alpha = \text{alpha}$  and  $\beta = \text{beta}$ .

### Methods

public static double density (double alpha, double beta, double x) Computes the density function.

public static double cdf (double alpha, double beta, double x)
 Computes the distribution function.

public static double barF (double alpha, double beta, double x) Computes the complementary distribution.

public static double inverseF (double alpha, double beta, double u) Computes the inverse of the distribution.

March 31, 2009 CauchyDist 37

# public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \beta)$  of the Cauchy distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \beta]$ .

### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static CauchyDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a Cauchy distribution with parameters  $\alpha$  and  $\beta$  estimated using the maximum likelihood method based on the *n* observations x[i], i = 0, 1, ..., n-1.

# public static double getMean (double alpha, double beta)

Throws an exception since the mean does not exist.

# public static double getVariance (double alpha, double beta)

Returns  $\infty$  since the variance does not exist.

# public static double getStandardDeviation (double alpha, double beta)

Returns  $\infty$  since the standard deviation does not exist.

# public double getAlpha()

Returns the value of  $\alpha$  for this object.

# public double getBeta()

Returns the value of  $\beta$  for this object.

#### public void setParams (double alpha, double beta)

Sets the value of the parameters  $\alpha$  and  $\beta$  for this object.

#### public double[] getParams ()

Return a table containing parameters of the current distribution. This table is put in regular order:  $[\alpha, \beta]$ .

# ChiDist

Extends the class ContinuousDistribution for the *chi* distribution [22, page 417] with shape parameter  $\nu > 0$ , where the number of degrees of freedom  $\nu$  is a positive integer. The density function is given by

$$f(x) = \frac{e^{-x^2/2}x^{\nu-1}}{2^{(\nu/2)-1}\Gamma(\nu/2)}, \quad \text{for } x > 0,$$
 (28)

where  $\Gamma(x)$  is the gamma function defined in (44). The distribution function is

$$F(x) = \frac{1}{\Gamma(\nu/2)} \int_0^{x^2/2} t^{\nu/2 - 1} e^{-t} dt.$$
 (29)

It is equivalent to the gamma distribution function with parameters  $\alpha = \nu/2$  and  $\lambda = 1$ , evaluated at  $x^2/2$ .

package umontreal.iro.lecuyer.probdist;

public class ChiDist extends ContinuousDistribution

#### Constructor

public ChiDist (int nu)

Constructs a ChiDist object.

#### Methods

public static double density (int nu, double x)

Computes the density function.

public static double cdf (int nu, double x)

Computes the distribution function by using the gamma distribution function.

public static double barF (int nu, double x)

Computes the complementary distribution.

public static double inverseF (int nu, double u)

Returns the inverse distribution function computed using the gamma inversion.

public static double[] getMLE (double[] x, int n)

Estimates the parameter  $\nu$  of the chi distribution using the maximum likelihood method, from the n observations  $x[i], i = 0, 1, \dots, n-1$ . The estimate is returned in element 0 of the returned array.

March 31, 2009 ChiDist **39** 

@Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
Same as getMLE.

# public static ChiDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a chi distribution with parameter  $\nu$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \dots, n-1$ .

#### public static double getMean (int nu)

Computes and returns the mean

$$E[X] = \frac{\sqrt{2}\,\Gamma(\frac{\nu+1}{2})}{\Gamma(\frac{\nu}{2})}$$

of the chi distribution with parameter  $\nu$ .

# public static double getVariance (int nu)

Computes and returns the variance

$$\operatorname{Var}[X] = \frac{2\Gamma(\frac{\nu}{2})\Gamma(1+\frac{\nu}{2}) - \Gamma^2(\frac{\nu+1}{2})}{\Gamma(\frac{\nu}{2})}$$

of the chi distribution with parameter  $\nu$ .

#### public static double getStandardDeviation (int nu)

Computes and returns the standard deviation of the chi distribution with parameter  $\nu$ .

#### public int getNu()

Returns the value of  $\nu$  for this object.

# public void setNu (int nu)

Sets the value of  $\nu$  for this object.

#### public double[] getParams ()

Return a table containing parameters of the current distribution.

# ChiSquareDist

Extends the class Continuous Distribution for the *chi-square* distribution with n degrees of freedom, where n is a positive integer [22, page 416]. Its density is

$$f(x) = \frac{x^{(n/2)-1}e^{-x/2}}{2^{n/2}\Gamma(n/2)}, \quad \text{for } x > 0$$
 (30)

where  $\Gamma(x)$  is the gamma function defined in (44). The *chi-square* distribution is a special case of the *gamma* distribution with shape parameter n/2 and scale parameter 1/2. Therefore, one can use the methods of GammaDist for this distribution.

The non-static versions of the methods cdf, barF, and inverseF call the static version of the same name.

package umontreal.iro.lecuyer.probdist;

public class ChiSquareDist extends ContinuousDistribution

#### Constructor

```
public ChiSquareDist (int n)
```

Constructs a chi-square distribution with n degrees of freedom.

#### Methods

public static double density (int n, double x)

Computes the density function (30) for a *chi-square* distribution with n degrees of freedom.

public static double cdf (int n, int d, double x)

Computes the chi-square distribution function with n degrees of freedom, evaluated at x. The method tries to return d decimals digits of precision, but there is no guarantee.

```
public static double barF (int n, int d, double x)
```

Computes the complementary chi-square distribution function with n degrees of freedom, evaluated at x. The method tries to return d decimals digits of precision, but there is no guarantee.

public static double inverseF (int n, double u)

Computes an approximation of  $F^{-1}(u)$ , where F is the chi-square distribution with n degrees of freedom. Uses the approximation given in [2] and in Figure L.23 of [7]. It gives at least 6 decimal digits of precision, except far in the tails (that is, for  $u < 10^{-5}$  or  $u > 1 - 10^{-5}$ ) where the function calls the method GammaDist.inverseF (n/2, 7, u) and multiplies the result by 2.0. To get better precision, one may call GammaDist.inverseF, but this method

March 31, 2009 ChiSquareDist 41

is slower than the current method, especially for large n. For instance, for n = 16, 1024, and 65536, the GammaDist.inverseF method is 2, 5, and 8 times slower, respectively, than the current method.

```
public static double[] getMLE (double[] x, int m)
```

Estimates the parameter n of the chi-square distribution using the maximum likelihood method, from the m observations x[i], i = 0, 1, ..., m - 1. The estimate is returned in element 0 of the returned array.

#### @Deprecated

```
public static double[] getMaximumLikelihoodEstimate (double[] x, int m)
Same as getMLE.
```

```
public static ChiSquareDist getInstanceFromMLE (double[] x, int m)
```

Creates a new instance of a chi-square distribution with parameter n estimated using the maximum likelihood method based on the m observations x[i], i = 0, 1, ..., m-1.

```
public static double getMean (int n)
```

Computes and returns the mean E[X] = n of the chi-square distribution with parameter n.

```
public static double[] getMomentsEstimate (double[] x, int m)
```

Estimates and returns the parameter  $[\hat{n}]$  of the chi-square distribution using the moments method based on the m observations in table x[i], i = 0, 1, ..., m-1.

```
public static double getVariance (int n)
```

Returns the variance Var[X] = 2n of the chi-square distribution with parameter n.

```
public static double getStandardDeviation (int n)
```

Returns the standard deviation of the chi-square distribution with parameter n.

```
public int getN()
```

Returns the parameter n of this object.

```
public void setN (int n)
```

Sets the parameter n of this object.

```
public double[] getParams ()
```

Return a table containing the parameters of the current distribution.

# ChiSquareDistQuick

Provides a variant of ChiSquareDist with faster but less accurate methods. The non-static version of inverseF calls the static version. This method is not very accurate for small n but becomes better as n increases. The other methods are the same as in ChiSquareDist.

```
package umontreal.iro.lecuyer.probdist;
public class ChiSquareDistQuick extends ChiSquareDist
```

#### Constructor

```
public ChiSquareDistQuick (int n)
```

Constructs a chi-square distribution with n degrees of freedom.

#### Methods

```
public static double inverseF (int n, double u)
```

Computes a quick-and-dirty approximation of  $F^{-1}(u)$ , where F is the *chi-square* distribution with n degrees of freedom. Uses the approximation given in Figure L.24 of [7] over most of the range. For u < 0.02 or u > 0.98, it uses the approximation given in [19] for  $n \ge 10$ , and returns 2.0 \* GammaDist.inverseF (n/2, 6, u) for n < 10 in order to avoid the loss of precision of the above approximations. When  $n \ge 10$  or 0.02 < u < 0.98, it is between 20 to 30 times faster than the same method in ChiSquareDist for n between 10 and 1000 and even faster for larger n.

Note that the number d of decimal digits of precision generally increases with n. For n=3, we only have d=3 over most of the range. For n=10, d=5 except far in the tails where d=3. For n=100, one has more than d=7 over most of the range and for n=1000, at least d=8. The cases n=1 and n=2 are exceptions, with precision of about d=10.

# ChiSquareNoncentralDist

Extends the class ContinuousDistribution for the noncentral chi-square distribution with  $\nu$  degrees of freedom and noncentrality parameter  $\lambda$ , where  $\nu > 0$  and  $\lambda > 0$  [23, page 436]. Its density is

$$f(x) = \frac{e^{-(x+\lambda)/2}}{2} \left(\frac{x}{\lambda}\right)^{(\nu-2)/4} I_{\nu/2-1} \left(\sqrt{\lambda x}\right) \quad \text{for } x > 0, \tag{31}$$

where  $I_{\nu}(x)$  is the modified Bessel function of the first kind of order  $\nu$  given by

$$I_{\nu}(z) = \sum_{j=0}^{\infty} \frac{(z/2)^{\nu+2j}}{j! \Gamma(\nu+j+1)},$$
(32)

where  $\Gamma(x)$  is the gamma function. Notice that this distribution is more general than the *chi-square* distribution since its number of degrees of freedom can be any positive real number. For  $\lambda = 0$  and  $\nu$  a positive integer, we have the ordinary *chi-square* distribution.

The cumulative probability function can be written as

$$P[X \le x] = \sum_{j=0}^{\infty} \frac{e^{-\lambda/2} (\lambda/2)^j}{j!} P[\chi_{\nu+2j}^2 \le x], \tag{33}$$

where  $\chi^2_{\nu+2j}$  is the *central chi-square* distribution with  $\nu$  degrees of freedom.

package umontreal.iro.lecuyer.probdist;

public class ChiSquareNoncentralDist extends ContinuousDistribution

#### Constructor

public ChiSquareNoncentralDist (double nu, double lambda)

Constructs a noncentral chi-square distribution with  $\nu = nu$  degrees of freedom and noncentrality parameter  $\lambda = lambda$ .

#### Methods

public static double density (double nu, double lambda, double x)

Computes the density function (31) for a noncentral chi-square distribution with  $\nu = nu$  degrees of freedom and parameter  $\lambda = lambda$ .

public static double cdf (double nu, double lambda, double x)

Computes the noncentral chi-square distribution function (33) with  $\nu = \text{nu}$  degrees of freedom and parameter  $\lambda = \text{lambda}$ .

# public static double barF (double nu, double lambda, double x)

Computes the complementary noncentral chi-square distribution function with  $\nu = nu$  degrees of freedom and parameter  $\lambda = lambda$ .

#### public static double inverseF (double nu, double lambda, double u)

Computes the inverse of the noncentral chi-square distribution with  $\nu = nu$  degrees of freedom and parameter  $\lambda = lambda$ .

#### public static double getMean (double nu, double lambda)

Computes and returns the mean  $E[X] = \nu + \lambda$  of the noncentral chi-square distribution with parameters  $\nu = \text{nu}$  and  $\lambda = \text{lambda}$ .

#### public static double getVariance (double nu, double lambda)

Computes and returns the variance  $Var[X] = 2(\nu + 2\lambda)$  of the noncentral chi-square distribution with parameters  $\nu = \text{nu}$  and  $\lambda = \text{lambda}$ .

## public static double getStandardDeviation (double nu, double lambda)

Computes and returns the standard deviation of the noncentral chi-square distribution with parameters  $\nu = \text{nu}$  and  $\lambda = \text{lambda}$ .

# public double getNu()

Returns the parameter  $\nu$  of this object.

#### public double getLambda()

Returns the parameter  $\lambda$  of this object.

#### public void setParams (double nu, double lambda)

Sets the parameters  $\nu = \text{nu}$  and  $\lambda = \text{lambda}$  of this object.

## public double[] getParams ()

Returns a table containing the parameters of the current distribution.

# **ErlangDist**

Extends the class GammaDist for the special case of the *Erlang* distribution with shape parameter k > 0 and scale parameter  $\lambda > 0$ . This distribution is a special case of the gamma distribution for which the shape parameter  $k = \alpha$  is an integer.

```
package umontreal.iro.lecuyer.probdist;
public class ErlangDist extends GammaDist
Constructors
   public ErlangDist (int k)
      Constructs a ErlangDist object with parameters k = k and \lambda = 1.
   public ErlangDist (int k, double lambda)
      Constructs a ErlangDist object with parameters k = k and \lambda = lambda.
Methods
   public static double density (int k, double lambda, double x)
      Computes the density function.
   public static double cdf (int k, double lambda, int d, double x)
      Computes the distribution function using the gamma distribution function.
   public static double barF (int k, double lambda, int d, double x)
      Computes the complementary distribution function.
   public static double inverseF (int k, double lambda, int d, double u)
      Returns the inverse distribution function.
   public static double[] getMLE (double[] x, int n)
      Estimates the parameters (k,\lambda) of the Erlang distribution using the maximum likelihood
      method, from the n observations x[i], i = 0, 1, \dots, n-1. The estimates are returned in a
      two-element array, in regular order: [k, \lambda].
   @Deprecated
   public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
      Same as getMLE.
```

public static ErlangDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of an Erlang distribution with parameters k and  $\lambda$  estimated using

the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

March 31, 2009 ErlangDist **46** 

# public static double getMean (int k, double lambda)

Computes and returns the mean,  $E[X] = k/\lambda$ , of the Erlang distribution with parameters k and  $\lambda$ .

# public static double getVariance (int k, double lambda)

Computes and returns the variance,  $Var[X] = k/\lambda^2$ , of the Erlang distribution with parameters k and  $\lambda$ .

# public static double getStandardDeviation (int k, double lambda)

Computes and returns the standard deviation of the Erlang distribution with parameters k and  $\lambda$ .

#### public int getK()

Returns the parameter k for this object.

### public void setParams (int k, double lambda, int d)

Sets the parameters k and  $\lambda$  of the distribution for this object. Non-static methods are computed with a rough target of d decimal digits of precision.

# public double[] getParams ()

Return a table containing parameters of the current distribution. This table is put in regular order:  $[k, \lambda]$ .

# **ExponentialDist**

Extends the class Continuous Distribution for the exponential distribution [22, page 494] with mean  $1/\lambda$  where  $\lambda > 0$ . Its density is

$$f(x) = \lambda e^{-\lambda x}$$
 for  $x \ge 0$ , (34)

its distribution function is

$$F(x) = 1 - e^{-\lambda x}, \quad \text{for } x \ge 0,$$
 (35)

and its inverse distribution function is

$$F^{-1}(u) = -\ln(1-u)/\lambda$$
, for  $0 < u < 1$ .

package umontreal.iro.lecuyer.probdist;

public class ExponentialDist extends ContinuousDistribution

#### Constructors

public ExponentialDist()

Constructs an Exponential Dist object with parameter  $\lambda = 1$ .

public ExponentialDist (double lambda)

Constructs an Exponential Dist object with parameter  $\lambda = lambda$ .

#### Methods

public static double density (double lambda, double x)
 Computes the density function.

public static double cdf (double lambda, double x) Computes the distribution function.

public static double barF (double lambda, double x) Computes the complementary distribution function.

public static double inverseF (double lambda, double u) Computes the inverse distribution function.

public static double[] getMLE (double[] x, int n)

Estimates the parameter  $\lambda$  of the exponential distribution using the maximum likelihood method, from the n observations x[i],  $i=0,1,\ldots,n-1$ . The estimate is returned in a one-element array, as element 0.

March 31, 2009 ExponentialDist 48

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
Same as getMLE.

# public static ExponentialDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of an exponential distribution with parameter  $\lambda$  estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n - 1.

## public static double getMean (double lambda)

Computes and returns the mean,  $E[X] = 1/\lambda$ , of the exponential distribution with parameter  $\lambda$ .

# public static double getVariance (double lambda)

Computes and returns the variance,  $Var[X] = 1/\lambda^2$ , of the exponential distribution with parameter  $\lambda$ .

# public static double getStandardDeviation (double lambda)

Computes and returns the standard deviation of the exponential distribution with parameter  $\lambda$ .

# public double getLambda()

Returns the value of  $\lambda$  for this object.

#### public void setLambda (double lambda)

Sets the value of  $\lambda$  for this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution.

# ${\bf Exponential Dist From Mean}$

Extends the ExponentialDist class with a constructor accepting as argument the mean  $1/\lambda$  instead of the rate  $\lambda$ .

```
package umontreal.iro.lecuyer.probdist;
public class ExponentialDistFromMean extends ExponentialDist
```

#### Constructors

```
public ExponentialDistFromMean (double mean)
```

Constructs a new exponential distribution with mean mean.

#### Methods

```
public void setMean (double mean)
```

Calls setLambda with argument 1/mean to change the mean of this distribution.

# ExtremeValueDist

Extends the class Continuous Distribution for the extreme value (or Gumbel) distribution [23, page 2], with location parameter  $\alpha$  and scale parameter  $\lambda > 0$ . It has density

$$f(x) = \lambda e^{-\lambda(x-\alpha)} e^{-e^{-\lambda(x-\alpha)}}, \quad \text{for } -\infty < x < \infty,$$
 (36)

distribution function

$$F(x) = e^{-e^{-\lambda(x-\alpha)}} \qquad \text{for } -\infty < x < \infty, \tag{37}$$

and inverse distribution function

$$F^{-1}(u) = -\ln(-\ln(u))/\lambda + \alpha, \quad \text{for } 0 \le u \le 1.$$
 (38)

package umontreal.iro.lecuyer.probdist;

public class ExtremeValueDist extends ContinuousDistribution

#### Constructors

public ExtremeValueDist()

Constructs a ExtremeValueDist object with parameters  $\alpha = 0$  and  $\lambda = 1$ .

public ExtremeValueDist (double alpha, double lambda)

Constructs a ExtremeValueDist object with parameters  $\alpha =$  alpha and  $\lambda =$  lambda.

#### Methods

public static double density (double alpha, double lambda, double x) Computes the density function.

public static double cdf (double alpha, double lambda, double x) Computes the distribution function.

public static double barF (double alpha, double lambda, double x) Computes the complementary distribution function.

public static double inverseF (double alpha, double lambda, double u) Computes the inverse distribution function.

public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \lambda)$  of the extreme value distribution using the maximum likelihood method, from the n observations x[i],  $i = 0, 1, \ldots, n-1$ . The estimates are returned in a two-element array, in regular order:  $[\alpha, \lambda]$ .

March 31, 2009 ExtremeValueDist 51

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
Same as getMLE.

# public static ExtremeValueDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of an extreme value distribution with parameters  $\alpha$  and  $\lambda$  estimated using the maximum likelihood method based on the n observations x[i],  $i = 0, 1, \ldots, n-1$ .

## public static double getMean (double alpha, double lambda)

Computes and returns the mean,  $E[X] = \alpha + \gamma/\lambda$ , of the extreme value distribution with parameters  $\alpha$  and  $\lambda$ , where  $\gamma = 0.5772156649$  is the Euler-Mascheroni constant.

# public static double getVariance (double alpha, double lambda)

Computes and returns the variance,  $Var[X] = \pi^2/(6\lambda^2)$ , of the extreme value distribution with parameters  $\alpha$  and  $\lambda$ .

# public static double getStandardDeviation (double alpha, double lambda)

Computes and returns the standard deviation of the extreme value distribution with parameters  $\alpha$  and  $\lambda$ .

### public double getAlpha()

Returns the parameter  $\alpha$  of this object.

## public double getLambda()

Returns the parameter  $\lambda$  of this object.

#### public void setParams (double alpha, double lambda)

Sets the parameters  $\alpha$  and  $\lambda$  of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \lambda]$ .

# FatigueLifeDist

Extends the class Continuous Distribution for the fatigue life distribution [4] with location parameter  $\mu$ , scale parameter  $\beta$  and shape parameter  $\gamma$ . Its density is

$$f(x) = \left[ \frac{\sqrt{\frac{x-\mu}{\beta}} + \sqrt{\frac{\beta}{x-\mu}}}{2\gamma(x-\mu)} \right] \phi \left( \frac{\sqrt{\frac{x-\mu}{\beta}} - \sqrt{\frac{\beta}{x-\mu}}}{\gamma} \right), \quad \text{for } x > \mu,$$
 (39)

where  $\phi$  is the probability density of the standard normal distribution. The distribution function is given by

$$F(x) = \Phi\left(\frac{\sqrt{\frac{x-\mu}{\beta}} - \sqrt{\frac{\beta}{x-\mu}}}{\gamma}\right), \quad \text{for } x > \mu,$$
 (40)

where  $\Phi$  is the standard normal distribution function. Restrictions:  $\beta > 0, \gamma > 0$ .

The non-static versions of the methods cdf, barF, and inverseF call the static version of the same name.

package umontreal.iro.lecuyer.probdist;

public class FatigueLifeDist extends ContinuousDistribution

#### Constructor

public FatigueLifeDist (double mu, double beta, double gamma) Constructs a fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

#### Methods

Computes the density (39) for the fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

public static double cdf (double mu, double beta, double gamma, double x) Computes the fatigue life distribution function with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

Computes the complementary distribution function of the fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

March 31, 2009 FatigueLifeDist 53

Computes the inverse of the fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

public static double[] getMLE (double[] x, int n, double mu)

Estimates the parameters  $(\mu, \beta, \gamma)$  of the fatigue life distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a three-element array, in regular order:  $[\mu, \beta, \gamma]$ .

@Deprecated

Same as getMLE.

public static double getMean (double mu, double beta, double gamma)

Computes and returns the mean  $E[X] = \mu + \beta(1 + \gamma^2/2)$  of the fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

public static double getVariance (double mu, double beta, double gamma)

Computes and returns the variance  $Var[X] = \beta^2 \gamma^2 (1 + 5\gamma^2/4)$  of the fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

Computes and returns the standard deviation of the fatigue life distribution with parameters  $\mu$ ,  $\beta$  and  $\gamma$ .

public double getBeta()

Returns the parameter  $\beta$  of this object.

public double getGamma()

Returns the parameter  $\gamma$  of this object.

public double getMu()

Returns the parameter  $\mu$  of this object.

public void setParams (double mu, double beta, double gamma)

Sets the parameters  $\mu$ ,  $\beta$  and  $\gamma$  of this object.

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \beta, \gamma]$ .

# **FisherFDist**

Extends the class Continuous Distribution for the Fisher F distribution with n and m degrees of freedom, where n and m are positive integers. Its density is

$$f(x) = \frac{\Gamma(\frac{n+m}{2})n^{\frac{n}{2}}m^{\frac{m}{2}}}{\Gamma(\frac{n}{2})\Gamma(\frac{m}{2})} \frac{x^{\frac{n-2}{2}}}{(m+nx)^{\frac{n+m}{2}}}, \quad \text{for } x > 0$$
 (41)

where  $\Gamma(x)$  is the gamma function defined in (44).

The non-static versions of the methods cdf, barF, and inverseF call the static version of the same name.

package umontreal.iro.lecuyer.probdist;

public class FisherFDist extends ContinuousDistribution

#### Constructor

public FisherFDist (int n, int m)

Constructs a Fisher F distribution with n and m degrees of freedom.

#### Methods

public static double density (int n, int m, double x)

Computes the density function (41) for a Fisher F distribution with n and m degrees of freedom.

public static double cdf (int n, int m, int d, double x)

Computes the distribution function of the Fisher F distribution with parameters n and m, evaluated at x, with roughly d decimal digits of precision.

public static double barF (int n, int m, int d, double x)

Computes the complementary distribution function of the Fisher F distribution with parameters n and m, evaluated at x, with roughly d decimal digits of precision.

public static double inverseF (int n, int m, int d, double u)

Computes the inverse of the Fisher F distribution with parameters n and m, evaluated at x, with roughly d decimal digits of precision.

public static double getMean (int n, int m)

Computes and returns the mean E[X] = m/(m-2) of the Fisher F distribution with parameters n and m.

March 31, 2009 FisherFDist 55

public static double getVariance (int n, int m)

Computes and returns the variance

$$Var[X] = \frac{2m^2(m+n-2)}{n(m-2)^2(m-4)}$$

of the Fisher F distribution with parameters n and m.

public static double getStandardDeviation (int n, int m)

Computes and returns the standard deviation of the Fisher F distribution with parameters n and m.

public int getN()

Returns the parameter n of this object.

public int getM()

Returns the parameter m of this object.

public void setParams (int n, int m)

Sets the parameters n and m of this object.

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order: [n, m].

# FoldedNormalDist

Extends the class ContinuousDistribution for the folded normal distribution with parameters  $\mu \geq 0$  and  $\sigma > 0$ . The density is

$$f(x) = \phi\left(\frac{x-\mu}{\sigma}\right) + \phi\left(\frac{-x-\mu}{\sigma}\right) \quad \text{for } x \ge 0,$$

$$f(x) = 0, \quad \text{for } x < 0,$$
(42)

where  $\phi$  denotes the density function of a standard normal distribution.

package umontreal.iro.lecuyer.probdist;

public class FoldedNormalDist extends ContinuousDistribution

#### Constructors

public FoldedNormalDist (double mu, double sigma)

Constructs a FoldedNormalDist object with parameters  $\mu = \text{mu}$  and  $\sigma = \text{sigma}$ .

#### Methods

public static double density (double mu, double sigma, double x) Computes the density function of the *folded normal* distribution.

public static double cdf (double mu, double sigma, double x) Computes the distribution function.

public static double barF (double mu, double sigma, double x)
Computes the complementary distribution function.

public static double inverseF (double mu, double sigma, double u) Computes the inverse of the distribution function.

public static double getMean (double mu, double sigma)
Computes and returns the mean

$$E[X] = \sigma \sqrt{\frac{2}{\pi}} e^{-\mu^2/(2\sigma^2)} + \mu \operatorname{erf}\left(\frac{\mu}{\sigma\sqrt{2}}\right),$$

where  $\operatorname{erf}(z)$  is the error function.

March 31, 2009 FoldedNormalDist 57

public static double getVariance (double mu, double sigma)

Computes and returns the variance

$$Var[X] = \mu^2 + \sigma^2 - E[X]^2.$$

public static double getStandardDeviation (double mu, double sigma)

Computes the standard deviation of the folded normal distribution with parameters  $\mu$  and  $\sigma$ .

public static double[] getMLE (double[] x, int n)

NOT IMPLEMENTED. Les formules pour le MLE sont données dans [28].

public double getMu()

Returns the parameter  $\mu$  of this object.

public double getSigma()

Returns the parameter  $\sigma$  of this object.

public void setParams (double mu, double sigma)

Sets the parameters  $\mu$  and  $\sigma$  for this object.

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \sigma]$ .

public String toString ()

Returns a String containing information about the current distribution.

# GammaDist

Extends the class Continuous Distribution for the gamma distribution [22, page 337] with shape parameter  $\alpha > 0$  and scale parameter  $\lambda > 0$ . The density is

$$f(x) = \frac{\lambda^{\alpha} x^{\alpha - 1} e^{-\lambda x}}{\Gamma(\alpha)}, \quad \text{for } x > 0,$$
(43)

where  $\Gamma$  is the gamma function, defined by

$$\Gamma(\alpha) = \int_0^\infty x^{\alpha - 1} e^{-x} dx. \tag{44}$$

In particular,  $\Gamma(n) = (n-1)!$  when n is a positive integer.

package umontreal.iro.lecuyer.probdist;

public class GammaDist extends ContinuousDistribution

#### Constructors

public GammaDist (double alpha)

Constructs a GammaDist object with parameters  $\alpha =$  alpha and  $\lambda = 1$ .

public GammaDist (double alpha, double lambda)

Constructs a GammaDist object with parameters  $\alpha = \text{alpha}$  and  $\lambda = \text{lambda}$ .

public GammaDist (double alpha, double lambda, int d)

Constructs a GammaDist object with parameters  $\alpha = \text{alpha}$  and  $\lambda = \text{lambda}$ , and approximations of roughly d decimal digits of precision when computing functions.

#### Methods

public static double density (double alpha, double lambda, double x) Computes the density function (43) at x.

public static double cdf (double alpha, double lambda, int d, double x)

Returns an approximation of the gamma distribution function with parameters  $\alpha = \mathtt{alpha}$  and  $\lambda = \mathtt{lambda}$ , whose density is given by (43). The approximation is an improved version of the algorithm in [3]. The function tries to return d decimals digits of precision. For  $\alpha$  not too large (e.g.,  $\alpha \leq 1000$ ), d gives a good idea of the precision attained.

public static double cdf (double alpha, int d, double x)
 Equivalent to cdf (alpha, 1.0, d, x).

March 31, 2009 GammaDist **59** 

public static double barF (double alpha, double lambda, int d, double x) Computes the complementary distribution function.

public static double barF (double alpha, int d, double x)
 Same as barF (alpha, 1.0, d, x).

Computes the inverse distribution function using the algorithm implemented in [36]. Starting with the approximation  $x = \alpha t^3$ , where  $t = 1 - z - \Phi^{-1}(u)\sqrt{z}$ ,  $z = \alpha/9$ , and  $\Phi^{-1}$  is the inverse of the standard normal distribution, the method uses Newton iterations to estimate the inverse. The precision of the algorithm depends on the accuracy of the barF function. The argument d gives a good idea of the precision attained.

public static double inverseF (double alpha, int d, double u)
 Same as inverseF (alpha, 1, d, u).

# public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \lambda)$  of the gamma distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \lambda]$ .

# @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

# public static GammaDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a gamma distribution with parameters  $\alpha$  and  $\lambda$  estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n-1.

# public static double getMean (double alpha, double lambda)

Computes and returns the mean  $E[X] = \alpha/\lambda$  of the gamma distribution with parameters  $\alpha$  and  $\lambda$ .

# public static double getVariance (double alpha, double lambda)

Computes and returns the variance  $Var[X] = \alpha/\lambda^2$  of the gamma distribution with parameters  $\alpha$  and  $\lambda$ .

# public static double getStandardDeviation (double alpha, double lambda)

Computes and returns the standard deviation of the gamma distribution with parameters  $\alpha$  and  $\lambda$ .

#### public double getAlpha()

Return the parameter  $\alpha$  for this object.

#### public double getLambda()

Return the parameter  $\lambda$  for this object.

March 31, 2009 GammaDist **60** 

public void setParams (double alpha, double lambda, int d)
public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \lambda]$ .

# **GammaDistFromMoments**

Extends the GammaDist distribution with constructors accepting the mean  $\mu$  and variance  $\sigma^2$  as arguments instead of a shape parameter  $\alpha$  and a scale parameter  $\lambda$ . Since  $\mu = \alpha/\lambda$ , and  $\sigma^2 = \alpha/\lambda^2$ , the shape and scale parameters are  $\alpha = \mu^2/\sigma^2$ , and  $\lambda = \mu/\sigma^2$ , respectively.

```
package umontreal.iro.lecuyer.probdist;
```

public class GammaDistFromMoments extends GammaDist

#### Constructors

public GammaDistFromMoments (double mean, double var, int d)

Constructs a gamma distribution with mean mean, variance var, and d decimal of precision.

public GammaDistFromMoments (double mean, double var)

Constructs a gamma distribution with mean mean, and variance var.

# **HalfNormalDist**

Extends the class Continuous Distribution for the half-normal distribution with parameters  $\mu$  and  $\sigma > 0$ . Its density is

$$f(x) = \frac{1}{\sigma} \sqrt{\frac{2}{\pi}} e^{-(x-\mu)^2/2\sigma^2}, \quad \text{for } x \ge \mu.$$

$$f(x) = 0, \quad \text{for } x < \mu.$$

$$(45)$$

package umontreal.iro.lecuyer.probdist;

public class HalfNormalDist extends ContinuousDistribution

#### Constructors

public HalfNormalDist (double mu, double sigma)

Constructs a HalfNormalDist object with parameters  $\mu = \text{mu}$  and  $\sigma = \text{sigma}$ .

#### Methods

public static double density (double mu, double sigma, double x) Computes the density function of the *half-normal* distribution.

public static double cdf (double mu, double sigma, double x) Computes the distribution function.

public static double barF (double mu, double sigma, double x)
Computes the complementary distribution function.

public static double inverseF (double mu, double sigma, double u)
Computes the inverse of the distribution function.

public static double[] getMLE (double[] x, int n)

Estimates the parameters  $\mu$  and  $\sigma$  of the half-normal distribution using the maximum likelihood method from the n observations x[i],  $i=0,1,\ldots,n-1$ . The estimates are returned in a two-element array:  $[\mu, \sigma]$ .

public static double[] getMLE (double[] x, int n, double mu)

Estimates the parameter  $\sigma$  of the half-normal distribution using the maximum likelihood method from the n observations x[i],  $i=0,1,\ldots,n-1$  and the parameter  $\mu=\text{mu}$ . The estimate is returned in a one-element array:  $[\sigma]$ .

March 31, 2009 HalfNormalDist 63

public static double getMean (double mu, double sigma)

Computes and returns the mean  $E[X] = \mu + \sigma \sqrt{2/\pi}$ .

public static double getVariance (double mu, double sigma)

Computes and returns the variance  $Var[X] = (1 - 2/\pi) \sigma^2$ .

public static double getStandardDeviation (double mu, double sigma)

Computes the standard deviation of the half-normal distribution with parameters  $\mu$  and  $\sigma$ .

public double getMu()

Returns the parameter  $\mu$  of this object.

public double getSigma()

Returns the parameter  $\sigma$  of this object.

public void setParams (double mu, double sigma)

Sets the parameters  $\mu$  and  $\sigma$ .

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \sigma]$ .

public String toString ()

Returns a String containing information about the current distribution.

# **HyperbolicSecantDist**

Extends the class ContinuousDistribution for the *Hyperbolic Secant* distribution with location parameter  $\mu$  and scale parameter  $\sigma > 0$ . Its density is

$$f(x) = \frac{1}{2\sigma} \operatorname{sech}\left(\frac{\pi}{2} \frac{(x-\mu)}{\sigma}\right) \tag{46}$$

The distribution function is given by

$$F(x) = \frac{2}{\pi} \tan^{-1} \left[ \exp\left(\frac{\pi}{2} \frac{(x-\mu)}{\sigma}\right) \right]$$
 (47)

The non-static versions of the methods cdf, barF, and inverseF call the static version of the same name.

package umontreal.iro.lecuyer.probdist;

public class HyperbolicSecantDist extends ContinuousDistribution

#### Constructor

public HyperbolicSecantDist (double mu, double sigma)

Constructs a hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

#### Methods

public static double density (double mu, double sigma, double x)

Computes the density function (46) for a hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

public static double cdf (double mu, double sigma, double x)

Computes the distribution function of the hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

public static double barF (double mu, double sigma, double x)

Computes the complementary distribution function of the hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

public static double inverseF (double mu, double sigma, double u)

Computes the inverse of the hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\mu, \sigma)$  of the hyperbolic secant distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\mu, \sigma]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

# public static HyperbolicSecantDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$  estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n-1.

## public static double getMean (double mu, double sigma)

Computes and returns the mean  $E[X] = \mu$  of the hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

# public static double getVariance (double mu, double sigma)

Computes and returns the variance  $Var[X] = \sigma^2$  of the hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

# public static double getStandardDeviation (double mu, double sigma)

Computes and returns the standard deviation of the hyperbolic secant distribution with parameters  $\mu$  and  $\sigma$ .

### public double getMu()

Returns the parameter  $\mu$  of this object.

#### public double getSigma()

Returns the parameter  $\sigma$  of this object.

#### public void setParams (double mu, double sigma)

Sets the parameters  $\mu$  and  $\sigma$  of this object.

# public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \sigma]$ .

# InverseGaussianDist

Extends the class Continuous Distribution for the *inverse Gaussian* distribution with location parameter  $\mu > 0$  and scale parameter  $\lambda > 0$ . Its density is

$$f(x) = \sqrt{\frac{\lambda}{2\pi x^3}} e^{-\lambda(x-\mu)^2/(2\mu^2 x)}, \quad \text{for } x > 0.$$
 (48)

The distribution function is given by

$$F(x) = \Phi\left(\sqrt{\frac{\lambda}{x}}\left(\frac{x}{\mu} - 1\right)\right) + e^{(2\lambda/\mu)}\Phi\left(-\sqrt{\frac{\lambda}{x}}\left(\frac{x}{\mu} + 1\right)\right),\tag{49}$$

where  $\Phi$  is the standard normal distribution function.

The non-static versions of the methods cdf, barF, and inverseF call the static version of the same name.

package umontreal.iro.lecuyer.probdist;

public class InverseGaussianDist extends ContinuousDistribution

#### Constructor

public InverseGaussianDist (double mu, double lambda)

Constructs the *inverse Gaussian* distribution with parameters  $\mu$  and  $\lambda$ .

#### Methods

public static double density (double mu, double lambda, double x)

Computes the density function (48) for the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ , evaluated at x.

public static double cdf (double mu, double lambda, double x)

Computes the distribution function (49) of the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ , evaluated at x.

public static double barF (double mu, double lambda, double x)

Computes the complementary distribution function of the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ , evaluated at x.

public static double inverseF (double mu, double lambda, double u)

Computes the inverse of the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ .

March 31, 2009 InverseGaussianDist 67

# public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\mu, \lambda)$  of the inverse gaussian distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\mu, \lambda]$ .

### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

# public static InverseGaussianDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of an inverse gaussian distribution with parameters  $\mu$  and  $\lambda$  estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n-1.

# public static double getMean (double mu, double lambda)

Returns the mean  $E[X] = \mu$  of the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ .

# public static double getVariance (double mu, double lambda)

Computes and returns the variance  $Var[X] = \mu^3/\lambda$  of the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ .

# public static double getStandardDeviation (double mu, double lambda)

Computes and returns the standard deviation of the inverse gaussian distribution with parameters  $\mu$  and  $\lambda$ .

#### public double getLambda()

Returns the parameter  $\lambda$  of this object.

#### public double getMu()

Returns the parameter  $\mu$  of this object.

#### public void setParams (double mu, double lambda)

Sets the parameters  $\mu$  and  $\lambda$  of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \lambda]$ .

# **JohnsonSBDist**

Extends the class ContinuousDistribution for the Johnson  $S_B$  distribution (see [27, page 314]) with shape parameters  $\gamma$  and  $\delta > 0$ , location parameter  $\xi$ , and scale parameter  $\lambda > 0$ . Denoting  $y = (x - \xi)/\lambda$ , the density is

$$f(x) = \frac{\delta}{\lambda y (1 - y)\sqrt{2\pi}} \exp(-(1/2) \left[\gamma + \delta \ln \left(y/(1 - y)\right)\right]^2) \text{ for } \xi < x < \xi + \lambda,$$
 (50)

and 0 elsewhere. The distribution function is

$$F(x) = \Phi[\gamma + \delta \ln(y/(1-y))], \text{ for } \xi < x < \xi + \lambda, \tag{51}$$

where  $\Phi$  is the standard normal distribution function. The inverse distribution function is

$$F^{-1}(u) = \xi + \lambda(1/(1 + e^{-v(u)})) \quad \text{for } 0 \le u \le 1,$$
 (52)

where

$$v(u) = [\Phi^{-1}(u) - \gamma]/\delta. \tag{53}$$

This class relies on the methods NormalDist.cdf01 and NormalDist.inverseF01 of NormalDist to approximate  $\Phi$  and  $\Phi^{-1}$ .

package umontreal.iro.lecuyer.probdist;

public class JohnsonSBDist extends ContinuousDistribution

#### Constructor

Constructs a JohnsonSBDist object with shape parameters  $\gamma$  and  $\delta$ , location parameter  $\xi$  and scale parameter  $\lambda$ .

#### Methods

Computes the density function (50).

Computes the distribution function (51).

March 31, 2009 JohnsonSBDist 69

Computes the complementary distribution.

Computes the inverse of the distribution (52).

### public double getGamma()

Returns the value of  $\gamma$  for this object.

## public double getDelta()

Returns the value of  $\delta$  for this object.

## public double getXi()

Returns the value of  $\xi$  for this object.

# public double getLambda()

Returns the value of  $\lambda$  for this object.

Sets the value of the parameters  $\gamma$ ,  $\delta$ ,  $\xi$  and  $\lambda$  for this object.

### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\gamma, \delta, \xi, \lambda]$ .

March 31, 2009

# **JohnsonSUDist**

Extends the class Continuous Distribution for the Johnson  $S_U$  distribution (see [27, page 316]). It has shape parameters  $\gamma$  and  $\delta > 0$ , location parameter  $\xi$ , and scale parameter  $\lambda > 0$ . Denoting  $y = (x - \xi)/\lambda$ , the distribution has density

$$f(x) = \frac{\delta}{\lambda \sqrt{y^2 + 1} \sqrt{2\pi}} \exp\left(-(1/2) \left[\gamma + \delta \ln\left[y + \sqrt{y^2 + 1}\right]\right]^2\right) \quad \text{for } -\infty < x < \infty,$$
(54)

and distribution function

$$F(x) = \Phi\left\{\gamma + \delta \ln\left[y + \sqrt{y^2 + 1}\right]\right\}, \quad \text{for } -\infty < x < \infty,$$
 (55)

where  $\Phi$  is the standard normal distribution function. The inverse distribution function is

$$F^{-1}(u) = \xi + \lambda (e^{t(u)} - e^{-t(u)})/2, \quad \text{for } 0 \le u < 1,$$
 (56)

where

$$t(u) = [\Phi^{-1}(u) - \gamma]/\delta. \tag{57}$$

This class relies on the methods NormalDist.cdf01 and NormalDist.inverseF01 of NormalDist to approximate  $\Phi$  and  $\Phi^{-1}$ .

package umontreal.iro.lecuyer.probdist;

public class JohnsonSUDist extends ContinuousDistribution

# Constructors

public JohnsonSUDist (double gamma, double delta) Same as JohnsonSUDist (gamma, delta, 0.0, 1.0).

Constructs a JohnsonSUDist object with shape parameters  $\gamma$  and  $\delta$ , location parameter  $\xi$ , and scale parameter  $\lambda$ .

#### Methods

Computes the density function f(x).

March 31, 2009 JohnsonSUDist 71

Computes the distribution function F(x).

Computes the complementary distribution function 1 - F(x).

Computes the inverse distribution function  $F^{-1}(u)$ .

Computes and returns the mean  $E[X] = \xi - \lambda e^{1/(2\delta^2)} \sinh(\frac{\gamma}{\delta})$  of the Johnson  $S_U$  distribution with parameters  $\gamma$ ,  $\delta$ ,  $\xi$  and  $\lambda$ .

Computes and returns the variance  $\operatorname{Var}[X] = \lambda^2[(e^{1/\delta^2} - 1)(e^{1/\delta^2}\cosh(2\frac{\gamma}{\delta}) + 1)]/2$  of the Johnson  $S_U$  distribution with parameters  $\gamma$ ,  $\delta$ ,  $\xi$  and  $\lambda$ .

Computes and returns the standard deviation of the Johnson  $S_U$  distribution with parameters  $\gamma$ ,  $\delta$ ,  $\xi$  and  $\lambda$ .

public double getGamma()

Returns the value of  $\gamma$  for this object.

public double getDelta()

Returns the value of  $\delta$  for this object.

public double getXi()

Returns the value of  $\xi$  for this object.

public double getLambda()

Returns the value of  $\lambda$  for this object.

Sets the value of the parameters  $\gamma$ ,  $\delta$ ,  $\xi$  and  $\lambda$  for this object.

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\gamma, \delta, \xi, \lambda]$ .

# LaplaceDist

Extends the class ContinuousDistribution for the Laplace distribution (see, e.g., [23, page 165]). It has location parameter  $\mu$  and scale parameter  $\beta > 0$ . The density function is given by

$$f(x) = \frac{e^{-|x-\mu|/\beta}}{2\beta} \quad \text{for } -\infty < x < \infty.$$
 (58)

The distribution function is

$$F(x) = \begin{cases} \frac{1}{2}e^{(x-\mu)/\beta} & \text{if } x \le \mu, \\ 1 - \frac{1}{2}e^{(\mu-x)/\beta} & \text{otherwise,} \end{cases}$$
 (59)

and its inverse is

$$F^{-1}(u) = \begin{cases} \beta \log(2u) + \mu & \text{if } 0 \le u \le \frac{1}{2}, \\ \mu - \beta \log(2(1-u)) & \text{otherwise.} \end{cases}$$
 (60)

package umontreal.iro.lecuyer.probdist;

import umontreal.iro.lecuyer.util.Num;

public class LaplaceDist extends ContinuousDistribution

#### Constructors

public LaplaceDist()

Constructs a LaplaceDist object with default parameters  $\mu = 0$  and  $\beta = 1$ .

public LaplaceDist (double mu, double beta)

Constructs a LaplaceDist object with parameters  $\mu = mu$  and  $\beta = beta$ .

#### Methods

public static double density (double mu, double beta, double x) Computes the Laplace density function.

public static double cdf (double mu, double beta, double x) Computes the Laplace distribution function.

public static double barF (double mu, double beta, double x) Computes the Laplace complementary distribution function.

public static double inverseF (double mu, double beta, double u) Computes the inverse Laplace distribution function. March 31, 2009 LaplaceDist 73

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\mu, \beta)$  of the Laplace distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\mu, \beta]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static LaplaceDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a Laplace distribution with parameters  $\mu$  and  $\beta$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

#### public static double getMean (double mu, double beta)

Computes and returns the mean  $E[X] = \mu$  of the Laplace distribution with parameters  $\mu$  and  $\beta$ .

#### public static double getVariance (double mu, double beta)

Computes and returns the variance  $Var[X] = 2\beta^2$  of the Laplace distribution with parameters  $\mu$  and  $\beta$ .

#### public static double getStandardDeviation (double mu, double beta)

Computes and returns the standard deviation of the Laplace distribution with parameters  $\mu$  and  $\beta$ .

#### public double getMu()

Returns the parameter  $\mu$ .

#### public double getBeta()

Returns the parameter  $\beta$ .

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \beta]$ .

March 31, 2009 74

# LogisticDist

Extends the class Continuous Distribution for the *logistic* distribution (e.g., [23, page 115]). It has location parameter  $\alpha$  and scale parameter  $\lambda > 0$ . The density is

$$f(x) = \frac{\lambda e^{-\lambda(x-\alpha)}}{(1 + e^{-\lambda(x-\alpha)})^2} \quad \text{for } -\infty < x < \infty,$$
 (61)

and the distribution function is

$$F(x) = \frac{1}{1 + e^{-\lambda(x - \alpha)}} \qquad \text{for } -\infty < x < \infty.$$
 (62)

For  $\lambda = 1$  and  $\alpha = 0$ , one can write

$$F(x) = \frac{1 + \tanh(x/2)}{2}. (63)$$

The inverse distribution function is given by

$$F^{-1}(u) = \ln(u/(1-u))/\lambda + \alpha$$
 for  $0 \le u < 1$ .

package umontreal.iro.lecuyer.probdist;

public class LogisticDist extends ContinuousDistribution

#### Constructors

public LogisticDist()

Constructs a Logistic Dist object with default parameters  $\alpha = 0$  and  $\lambda = 1$ .

public LogisticDist (double alpha, double lambda)

Constructs a Logistic Dist object with parameters  $\alpha =$  alpha and  $\lambda =$  lambda.

#### Methods

public static double density (double alpha, double lambda, double x) Computes the density function f(x).

public static double cdf (double alpha, double lambda, double x) Computes the distribution function F(x).

public static double barF (double alpha, double lambda, double x) Computes the complementary distribution function 1 - F(x).

March 31, 2009 LogisticDist 75

public static double inverseF (double alpha, double lambda, double u) Computes the inverse distribution function  $F^{-1}(u)$ .

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \lambda)$  of the logistic distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \lambda]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static LogisticDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a logistic distribution with parameters  $\alpha$  and  $\lambda$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

#### public static double getMean (double alpha, double lambda)

Computes and returns the mean  $E[X] = \alpha$  of the logistic distribution with parameters  $\alpha$  and  $\lambda$ .

#### public static double getVariance (double alpha, double lambda)

Computes and returns the variance  $Var[X] = \pi^2/(3\lambda^2)$  of the logistic distribution with parameters  $\alpha$  and  $\lambda$ .

#### public static double getStandardDeviation (double alpha, double lambda)

Computes and returns the standard deviation of the logistic distribution with parameters  $\alpha$  and  $\lambda$ .

#### public double getAlpha()

Return the parameter  $\alpha$  of this object.

#### public double getLambda()

Returns the parameter  $\lambda$  of this object.

#### public void setParams (double alpha, double lambda)

Sets the parameters  $\alpha$  and  $\lambda$  of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \lambda]$ .

March 31, 2009 76

# LoglogisticDist

Extends the class ContinuousDistribution for the Log-Logistic distribution with shape parameter  $\alpha > 0$  and scale parameter  $\beta > 0$ . Its density is

$$f(x) = \frac{\alpha(x/\beta)^{\alpha-1}}{\beta[1 + (x/\beta)^{\alpha}]^2} \qquad \text{for } x > 0$$
 (64)

and its distribution function is

$$F(x) = \frac{1}{1 + \left(\frac{x}{\beta}\right)^{-\alpha}} \qquad \text{for } x > 0.$$
 (65)

The complementary distribution is

$$\bar{F}(x) = \frac{1}{1 + (\frac{x}{\beta})^{\alpha}} \qquad \text{for } x > 0.$$
 (66)

package umontreal.iro.lecuyer.probdist;

public class LoglogisticDist extends ContinuousDistribution

#### Constructor

public LoglogisticDist (double alpha, double beta)

Constructs a log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

#### Methods

public static double density (double alpha, double beta, double x)

Computes the density function (64) for a log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

public static double cdf (double alpha, double beta, double x)

Computes the distribution function (65) of the log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

public static double barF (double alpha, double beta, double x)

Computes the complementary distribution function (66) of the log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

public static double inverseF (double alpha, double beta, double u)

Computes the inverse of the log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

March 31, 2009 LoglogisticDist 77

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \beta)$  of the log-logistic distribution using the maximum likelihood method, from the n observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \beta]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static LoglogisticDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a log-logistic distribution with parameters  $\alpha$  and  $\beta$  estimated using the maximum likelihood method based on the *n* observations x[i], i = 0, 1, ..., n-1.

#### public static double getMean (double alpha, double beta)

Computes and returns the mean  $E[X] = \beta \theta \csc(\theta)$ , where  $\theta = \pi/\alpha$ , of the log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

#### public static double getVariance (double alpha, double beta)

Computes and returns the variance  $\operatorname{Var}[X] = \beta^2 \theta(2\operatorname{cosec}(2\theta) - \theta[\operatorname{cosec}(\theta)]^2)$ , where  $\theta = \pi/\alpha$ , of the log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

#### public static double getStandardDeviation (double alpha, double beta)

Computes and returns the standard deviation of the log-logistic distribution with parameters  $\alpha$  and  $\beta$ .

#### public double getAlpha()

Return the parameter  $\alpha$  of this object.

#### public double getBeta()

Returns the parameter  $\beta$  of this object.

#### public void setParams (double alpha, double beta)

Sets the parameters  $\alpha$  and  $\beta$  of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \beta]$ .

March 31, 2009 78

# LognormalDist

Extends the class Continuous Distribution for the lognormal distribution [22]. It has scale parameter  $\mu$  and shape parameter  $\sigma > 0$ . The density is

$$f(x) = \frac{1}{\sqrt{2\pi}\sigma x} e^{-(\ln(x) - \mu)^2/(2\sigma^2)} \qquad \text{for } x > 0,$$
 (67)

and 0 elsewhere. The distribution function is

$$F(x) = \Phi\left(\left(\ln(x) - \mu\right)/\sigma\right) \quad \text{for } x > 0,$$
(68)

where  $\Phi$  is the standard normal distribution function. Its inverse is given by

$$F^{-1}(u) = e^{\mu + \sigma \Phi^{-1}(u)}$$
 for  $0 \le u < 1$ . (69)

If ln(Y) has a normal distribution, then Y has a lognormal distribution with the same parameters.

This class relies on the methods NormalDist.cdf01 and NormalDist.inverseF01 of NormalDist to approximate  $\Phi$  and  $\Phi^{-1}$ .

package umontreal.iro.lecuyer.probdist;

public class LognormalDist extends ContinuousDistribution

#### Constructors

public LognormalDist()

Constructs a LognormalDist object with default parameters  $\mu = 0$  and  $\sigma = 1$ .

public LognormalDist (double mu, double sigma)

Constructs a LognormalDist object with parameters  $\mu = mu$  and  $\sigma = sigma$ .

#### Methods

public static double density (double mu, double sigma, double x)

Computes the lognormal density function f(x) in (67).

public static double cdf (double mu, double sigma, double x)

Computes the lognormal distribution function, using cdf01.

public static double barF (double mu, double sigma, double x)

Computes the lognormal complementary distribution function F(x), using NormalDist.barF01.

March 31, 2009 LognormalDist 79

#### public static double inverseF (double mu, double sigma, double u)

Computes the inverse of the lognormal distribution function, using NormalDist.inverseF01.

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\mu, \sigma)$  of the lognormal distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\mu, \sigma]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static LognormalDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a lognormal distribution with parameters  $\mu$  and  $\sigma$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

#### public static double getMean (double mu, double sigma)

Computes and returns the mean  $E[X] = e^{\mu + \sigma^2/2}$  of the lognormal distribution with parameters  $\mu$  and  $\sigma$ .

#### public static double getVariance (double mu, double sigma)

Computes and returns the variance  $Var[X] = e^{2\mu + \sigma^2}(e^{\sigma^2} - 1)$  of the lognormal distribution with parameters  $\mu$  and  $\sigma$ .

#### public static double getStandardDeviation (double mu, double sigma)

Computes and returns the standard deviation of the lognormal distribution with parameters  $\mu$  and  $\sigma$ .

#### public double getMu()

Returns the parameter  $\mu$  of this object.

#### public double getSigma()

Returns the parameter  $\sigma$  of this object.

#### public void setParams (double mu, double sigma)

Sets the parameters  $\mu$  and  $\sigma$  of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \sigma]$ .

# ${\bf Lognormal Dist From Moments}$

Extends the LognormalDist class with a constructor accepting the mean m and the variance v of the distribution as arguments. The mean and variance of a lognormal random variable with parameters  $\mu$  and  $\sigma$  are  $e^{\mu+\sigma^2/2}$  and  $e^{2\mu+\sigma^2}(e^{\sigma^2}-1)$  respectively, so the parameters are given by  $\sigma = \sqrt{\ln(v/m^2+1)}$  and  $\mu = \ln(m) - \sigma^2/2$ .

```
package umontreal.iro.lecuyer.probdist;
```

public class LognormalDistFromMoments extends LognormalDist

#### Constructor

public LognormalDistFromMoments (double mean, double var)

# NakagamiDist

Extends the class ContinuousDistribution for the *Nakagami* distribution with location parameter a, scale parameter  $\lambda > 0$  and shape parameter c > 0. The density is

$$f(x) = \frac{2\lambda^{c}}{\Gamma(c)} (x - a)^{2c - 1} e^{-\lambda(x - a)^{2}} \quad \text{for } x > a,$$
 (70)

$$f(x) = 0$$
 for  $x \le a$ ,

where  $\Gamma$  is the gamma function.

package umontreal.iro.lecuyer.probdist;

public class NakagamiDist extends ContinuousDistribution

#### Constructors

public NakagamiDist (double a, double lambda, double c) Constructs a NakagamiDist object with parameters a = a,  $\lambda = lambda$  and c = c.

#### Methods

public static double density (double a, double lambda, double c, double x)

Computes the density function of the Nakagami distribution.

public static double cdf (double a, double lambda, double c, double x)
 Computes the distribution function.

public static double barF (double a, double lambda, double c, double x) Computes the complementary distribution function.

Computes the inverse of the distribution function.

public static double getMean (double a, double lambda, double c)
 Computes and returns the mean

$$E[X] = a + \frac{1}{\sqrt{\lambda}} \frac{\Gamma(c+1/2)}{\Gamma(c)}.$$

March 31, 2009 NakagamiDist 82

public static double getVariance (double a, double lambda, double c)

Computes and returns the variance

$$\operatorname{Var}[X] = \frac{1}{\lambda} \left[ c - \left( \frac{\Gamma(c+1/2)}{\Gamma(c)} \right)^2 \right].$$

Computes the standard deviation of the Nakagami distribution with parameters a,  $\lambda$  and c.

#### public double getA()

Returns the location parameter a of this object.

#### public double getLambda()

Returns the scale parameter  $\lambda$  of this object.

#### public double getC()

Returns the shape parameter c of this object.

public void setParams (double a, double lambda, double c)

Sets the parameters a,  $\lambda$  and c of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[a, \lambda, c]$ .

#### public String toString ()

Returns a String containing information about the current distribution.

### NormalDist

Extends the class Continuous Distribution for the *normal* distribution (e.g., [22, page 80]). It has mean  $\mu$  and variance  $\sigma^2$ . Its density function is

$$f(x) = \frac{1}{\sqrt{2\pi}\sigma} e^{-(x-\mu)^2/(2\sigma^2)} \quad \text{for } -\infty < x < \infty, \tag{71}$$

where  $\sigma > 0$ . When  $\mu = 0$  and  $\sigma = 1$ , we have the standard normal distribution, with corresponding distribution function

$$F(x) = \Phi(x) = \frac{1}{\sqrt{2\pi}} \int_{-\infty}^{x} e^{-t^2/2} dt$$
 for  $-\infty < x < \infty$ . (72)

The non-static methods cdf, barF, and inverseF are implemented via cdf01, barF01, and inverseF01, respectively.

package umontreal.iro.lecuyer.probdist;

public class NormalDist extends ContinuousDistribution

#### Constructors

public NormalDist()

Constructs a NormalDist object with default parameters  $\mu = 0$  and  $\sigma = 1$ .

public NormalDist (double mu, double sigma)

Constructs a NormalDist object with mean  $\mu = mu$  and standard deviation  $\sigma = sigma$ .

#### Methods

```
public static double density01 (double x)
```

Same as density (0, 1, x).

public static double density (double mu, double sigma, double x)

Computes the normal density function (71).

public static double cdf01 (double x)

Same as cdf (0, 1, x).

public static double cdf (double mu, double sigma, double x)

Computes the normal distribution function with mean  $\mu$  and variance  $\sigma^2$ . Uses the Chebyshev approximation proposed in [41], which gives 16 decimals of precision.

```
public static double barF01 (double x)
Same as barF (0, 1, x).
```

#### public static double barF (double mu, double sigma, double x)

Computes the complementary normal distribution function  $\bar{F}(x) = 1 - \Phi((x - \mu)/\sigma)$ , with mean  $\mu$  and variance  $\sigma^2$ . Uses a Chebyshev series giving 16 decimal digits of precision [41].

### public static double inverseF01 (double u)

Same as inverseF (0, 1, u).

#### public static double inverseF (double mu, double sigma, double u)

Computes the inverse normal distribution function with mean  $\mu$  and variance  $\sigma^2$ . Uses rational Chebyshev approximations giving at least 16 decimal digits of precision (see [5]).

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\mu, \sigma)$  of the normal distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\hat{\mu}, \hat{\sigma}]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static NormalDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a normal distribution with parameters  $\mu$  and  $\sigma$  estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, 1, \ldots, n-1$ .

#### public static double getMean (double mu, double sigma)

Computes and returns the mean  $E[X] = \mu$  of the normal distribution with parameters  $\mu$  and  $\sigma$ .

#### public static double getVariance (double mu, double sigma)

Computes and returns the variance  $Var[X] = \sigma^2$  of the normal distribution with parameters  $\mu$  and  $\sigma$ .

#### public static double getStandardDeviation (double mu, double sigma)

Computes and returns the standard deviation  $\sigma$  of the normal distribution with parameters  $\mu$  and  $\sigma$ .

#### public double getMu()

Returns the parameter  $\mu$ .

#### public double getSigma()

Returns the parameter  $\sigma$ .

March 31, 2009 NormalDist 85

public void setParams (double mu, double sigma)

Sets the parameters  $\mu$  and  $\sigma$  of this object.

### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\mu, \sigma]$ .

# NormalDistQuick

A variant of the class NormalDist (for the *normal* distribution with mean  $\mu$  and variance  $\sigma^2$ ). The difference is in the implementation of the methods cdf01, barF01 and inverseF01, which are faster but less accurate than those of the class NormalDist.

```
package umontreal.iro.lecuyer.probdist;
public class NormalDistQuick extends NormalDist
```

Same as inverseF (0.0, 1.0, u).

#### Constructors

```
public NormalDistQuick()
Constructs a NormalDistQuick object with default parameters \mu=0 and \sigma=1.

public NormalDistQuick (double mu, double sigma)
Constructs a NormalDistQuick object with mean \mu= mu and standard deviation \sigma= sigma.
```

#### Methods

```
public static double cdf01 (double x) Same as cdf (0.0, 1.0, x).  
public static double cdf (double mu, double sigma, double x) Returns an approximation of \Phi(x), where \Phi is the standard normal distribution function, with mean 0 and variance 1. Uses Marsaglia et al's [34] fast method with table lookups. Returns 15 decimal digits of precision. This method is approximately 60% faster than NormalDist.cdf.  
public static double barF01 (double x) Same as barF (0.0, 1.0, x).  
public static double barF (double mu, double sigma, double x) Returns an approximation of 1-\Phi(x), where \Phi is the standard normal distribution function, with mean 0 and variance 1. Uses Marsaglia et al's [34] fast method with table lookups. Returns 15 decimal digits of precision. This method is approximately twice faster than NormalDist.barF.
```

Returns an approximation of  $\Phi^{-1}(u)$ , where  $\Phi$  is the standard normal distribution function, with mean 0 and variance 1. Uses the method of Marsaglia, Zaman, and Marsaglia [34], with table lookups. Returns 6 decimal digits of precision. This method is approximately 20% faster than NormalDist.inverseF.

public static double inverseF (double mu, double sigma, double u)

# NormalInverseGaussianDist

Extends the class Continuous Distribution for the normal inverse gaussian distribution with location parameter  $\mu$ , scale parameter  $\delta > 0$ , tail heavyness  $\alpha > 0$ , and asymmetry parameter  $\beta$  such that  $0 \le |\beta| < \alpha$ . Its density is

$$f(x) = \frac{\alpha \delta e^{\delta \gamma + \beta(x-\mu)} K_1 \left( \alpha \sqrt{\delta^2 + (x-\mu)^2} \right)}{\pi \sqrt{\delta^2 + (x-\mu)^2}}, \quad \text{for } -\infty < x < \infty,$$
 (73)

where  $K_1$  is the modified Bessel function of the second kind of order 1, and  $\gamma = \sqrt{\alpha^2 - \beta^2}$ . The distribution function is given by

$$F(x) = \int_{-\infty}^{x} dt f(t), \tag{74}$$

package umontreal.iro.lecuyer.probdist;

public class NormalInverseGaussianDist extends ContinuousDistribution

#### Constructor

Constructor for a normal inverse gaussian distribution with parameters  $\alpha = \text{alpha}$ ,  $\beta = \text{beta}$ ,  $\mu = \text{mu}$  and  $\delta = \text{delta}$ .

#### Methods

Computes the density function (73) for the normal inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ , evaluated at x.

NOT IMPLEMENTED. Computes the distribution function (74) of the normal inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ , evaluated at x.

NOT IMPLEMENTED. Computes the complementary distribution function of the *normal* inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ , evaluated at x.

public static double inverseF (double alpha, double beta, double mu, double delta, double u)

NOT IMPLEMENTED. Computes the inverse of the normal inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ .

public static double[] getMLE (double[] x, int n) NOT IMPLEMENTED.

public static NormalInverseGaussianDist getInstanceFromMLE (double[] x, int n)

NOT IMPLEMENTED.

public static double getMean (double alpha, double beta, double mu, double delta)

Returns the mean  $E[X] = \mu + \delta \beta / \gamma$  of the normal inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ .

public static double getVariance (double alpha, double beta, double mu, double delta)

Computes and returns the variance  $Var[X] = \delta \alpha^2 / \gamma^3$  of the normal inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ .

public static double getStandardDeviation (double alpha, double beta, double mu, double delta)

Computes and returns the standard deviation of the normal inverse gaussian distribution with parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$ .

#### public double getAlpha()

Returns the parameter  $\alpha$  of this object.

#### public double getBeta()

Returns the parameter  $\beta$  of this object.

#### public double getMu()

Returns the parameter  $\mu$  of this object.

#### public double getDelta()

Returns the parameter  $\delta$  of this object.

public void setParams (double alpha, double beta, double mu, double delta)

Sets the parameters  $\alpha$ ,  $\beta$ ,  $\mu$  and  $\delta$  of this object.

#### public double[] getParams ()

Returns a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \beta, \mu, \delta]$ .

### **ParetoDist**

Extends the class ContinuousDistribution for a distribution from the *Pareto* family, with shape parameter  $\alpha > 0$  and location parameter  $\beta > 0$  [22, page 574]. The density for this type of Pareto distribution is

$$f(x) = \frac{\alpha \beta^{\alpha}}{r^{\alpha+1}}$$
 for  $x \ge \beta$ , (75)

and 0 otherwise. The distribution function is

$$F(x) = 1 - (\beta/x)^{\alpha} \qquad \text{for } x \ge \beta, \tag{76}$$

and the inverse distribution function is

$$F^{-1}(u) = \beta (1-u)^{-1/\alpha}$$
 for  $0 \le u < 1$ .

package umontreal.iro.lecuyer.probdist;

public class ParetoDist extends ContinuousDistribution

#### Constructors

public ParetoDist (double alpha)

Constructs a ParetoDist object with parameters  $\alpha =$  alpha and  $\beta = 1$ .

public ParetoDist (double alpha, double beta)

Constructs a ParetoDist object with parameters  $\alpha =$  alpha and  $\beta =$  beta.

#### Methods

public static double density (double alpha, double beta, double x) Computes the density function.

public static double cdf (double alpha, double beta, double x) Computes the distribution function.

public static double barF (double alpha, double beta, double x) Computes the complementary distribution function.

public static double inverseF (double alpha, double beta, double u) Computes the inverse of the distribution function.

March 31, 2009 ParetoDist **90** 

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \beta)$  of the Pareto distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \beta]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static ParetoDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a Pareto distribution with parameters  $\alpha$  and  $\beta$  estimated using the maximum likelihood method based on the *n* observations x[i],  $i = 0, 1, \ldots, n-1$ .

#### public static double getMean (double alpha, double beta)

Computes and returns the mean  $E[X] = \alpha \beta / (\alpha - 1)$  of the Pareto distribution with parameters  $\alpha$  and  $\beta$ .

#### public static double getVariance (double alpha, double beta)

Computes and returns the variance  $\operatorname{Var}[X] = \frac{\alpha\beta^2}{(\alpha-2)(\alpha-1)}$  of the Pareto distribution with parameters  $\alpha$  and  $\beta$ .

#### public static double getStandardDeviation (double alpha, double beta)

Computes and returns the standard deviation of the Pareto distribution with parameters  $\alpha$  and  $\beta$ .

#### public double getAlpha()

Returns the parameter  $\alpha$ .

#### public double getBeta()

Returns the parameter  $\beta$ .

#### public void setParams (double alpha, double beta)

Sets the parameter  $\alpha$  and  $\beta$  for this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \beta]$ .

March 31, 2009 91

### Pearson5Dist

Extends the class Continuous Distribution for the Pearson type V distribution with shape parameter  $\alpha > 0$  and scale parameter  $\beta > 0$ . The density function is given by

$$f(x) = \begin{cases} \frac{x^{-(\alpha+1)}e^{-\beta/x}}{\beta^{-\alpha}\Gamma(\alpha)} & \text{for } x > 0\\ 0 & \text{otherwise,} \end{cases}$$
 (77)

where  $\Gamma$  is the gamma function. The distribution function is given by

$$F(x) = 1 - F_G\left(\frac{1}{x}\right) \qquad \text{for } x > 0, \tag{78}$$

and F(x) = 0 otherwise, where  $F_G(x)$  is the distribution function of a gamma distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

package umontreal.iro.lecuyer.probdist;

public class Pearson5Dist extends ContinuousDistribution

#### Constructor

public Pearson5Dist (double alpha, double beta)

Constructs a Pearson5Dist object with parameters  $\alpha =$  alpha and  $\beta =$  beta.

#### Methods

public static double density (double alpha, double beta, double x)

Computes the density function of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

public static double cdf (double alpha, double beta, double x)

Computes the density function of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

public static double barF (double alpha, double beta, double x)

Computes the complementary distribution function of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

public static double inverseF (double alpha, double beta, double u)

Computes the inverse distribution function of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

March 31, 2009 Pearson5Dist **92** 

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \beta)$  of the Pearson V distribution using the maximum likelihood method, from the n observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order:  $[\alpha, \beta]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static Pearson5Dist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a Pearson V distribution with parameters  $\alpha$  and  $\beta$  estimated using the maximum likelihood method based on the n observations x[i],  $i = 0, 1, \ldots, n-1$ .

#### public static double getMean (double alpha, double beta)

Computes and returns the mean  $E[X] = \beta/(\alpha - 1)$  of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

#### public static double getVariance (double alpha, double beta)

Computes and returns the variance  $\operatorname{Var}[X] = \beta^2/((\alpha-1)^2(\alpha-2))$  of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

#### public static double getStandardDeviation (double alpha, double beta)

Computes and returns the standard deviation of a Pearson V distribution with shape parameter  $\alpha$  and scale parameter  $\beta$ .

#### public double getAlpha()

Returns the  $\alpha$  parameter of this object.

#### public double getBeta()

Returns the  $\beta$  parameter of this object.

#### public void setParam (double alpha, double beta)

Sets the parameters  $\alpha$  and  $\beta$  of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \beta]$ .

### Pearson6Dist

Extends the class ContinuousDistribution for the Pearson type VI distribution with shape parameters  $\alpha_1 > 0$  and  $\alpha_2 > 0$ , and scale parameter  $\beta > 0$ . The density function is given by

$$f(x) = \begin{cases} \frac{(x/\beta)^{\alpha_1 - 1}}{\beta \mathcal{B}(\alpha_1, \alpha_2)(1 + x/\beta)^{\alpha_1 + \alpha_2}} & \text{for } x > 0, \\ 0 & \text{otherwise,} \end{cases}$$
(79)

where  $\mathcal{B}$  is the beta function. The distribution function is given by

$$F(x) = F_B\left(\frac{x}{x+\beta}\right) \qquad \text{for } x > 0, \tag{80}$$

and F(x) = 0 otherwise, where  $F_B(x)$  is the distribution function of a beta distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ .

package umontreal.iro.lecuyer.probdist;

public class Pearson6Dist extends ContinuousDistribution

#### Constructor

public Pearson6Dist (double alpha1, double alpha2, double beta)

Constructs a Pearson6Dist object with parameters  $\alpha_1 = \text{alpha1}$ ,  $\alpha_2 = \text{alpha2}$  and  $\beta = \text{beta}$ .

#### Methods

Computes the density function of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

Computes the distribution function of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

Computes the complementary distribution function of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

March 31, 2009 Pearson6Dist **94** 

#### 

Computes the inverse distribution function of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

#### public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha_1, \alpha_2, \beta)$  of the Pearson VI distribution using the maximum likelihood method, from the *n* observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a three-element array, in regular order:  $[\alpha_1, \alpha_2, \beta]$ .

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
 Same as getMLE.

#### public static Pearson6Dist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a Pearson VI distribution with parameters  $\alpha_1$ ,  $\alpha_2$  and  $\beta$ , estimated using the maximum likelihood method based on the n observations x[i], i = 0, 1, ..., n-1.

#### 

Computes and returns the mean  $E[X] = (\beta \alpha_1)/(\alpha_2 - 1)$  of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

#### 

Computes and returns the variance  $Var[X] = [\beta^2 \alpha_1(\alpha_1 + \alpha_2 - 1)]/[(\alpha_2 - 1)^2(\alpha_2 - 2)]$  of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

#### 

Computes and returns the standard deviation of a Pearson VI distribution with shape parameters  $\alpha_1$  and  $\alpha_2$ , and scale parameter  $\beta$ .

#### public double getAlpha1()

Returns the  $\alpha_1$  parameter of this object.

#### public double getAlpha2()

Returns the  $\alpha_2$  parameter of this object.

#### public double getBeta()

Returns the  $\beta$  parameter of this object.

# public void setParam (double alpha1, double alpha2, double beta) Sets the parameters $\alpha_1$ , $\alpha_2$ and $\beta$ of this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha_1, \alpha_2, \beta]$ .

# PiecewiseLinearEmpiricalDist

Extends the class ContinuousDistribution for a piecewise-linear approximation of the *empirical* distribution function, based on the observations  $X_{(1)}, \ldots, X_{(n)}$  (sorted by increasing order), and defined as follows (e.g., [27, page 318]). The distribution function starts at  $X_{(1)}$  and climbs linearly by 1/(n-1) between any two successive observations. The density is

$$f(x) = \frac{1}{(n-1)(X_{(i+1)} - X_{(i)})} \text{ for } X_{(i)} \le x < X_{(i+1)} \text{ and } i = 1, 2, \dots, n-1.$$
 (81)

The distribution function is

$$F(x) = \begin{cases} 0 & \text{for } x < X_{(1)}, \\ \frac{i-1}{n-1} + \frac{x - X_{(i)}}{(n-1)(X_{(i+1)} - X_{(i)})} & \text{for } X_{(i)} \le x < X_{(i+1)} \text{ and } i < n, \\ 1 & \text{for } x \ge X_{(n)}, \end{cases}$$
(82)

whose inverse is

$$F^{-1}(u) = X_{(i)} + ((n-1)u - i + 1)(X_{(i+1)} - X_{(i)})$$
(83)

for 
$$(i-1)/(n-1) \le u \le i/(n-1)$$
 and  $i = 1, ..., n-1$ .

package umontreal.iro.lecuyer.probdist;

public class PiecewiseLinearEmpiricalDist extends ContinuousDistribution

#### public PiecewiseLinearEmpiricalDist (double[] obs)

Constructs a new piecewise-linear distribution using all the observations stored in obs. These observations are copied into an internal array and then sorted.

#### public PiecewiseLinearEmpiricalDist (Reader in) throws IOException

Constructs a new empirical distribution using the observations read from the reader in. This constructor will read the first double of each line in the stream. Any line that does not start with a +, -, or a decimal digit, is ignored. The file is read until its end. One must be careful about lines starting with a blank. This format is the same as in UNURAN.

#### public int getN()

Returns n, the number of observations.

public double getObs (int i)

Returns the value of  $X_{(i)}$ .

#### public double getSampleMean()

Returns the sample mean of the observations.

#### public double getSampleVariance()

Returns the sample variance of the observations.

### public double getSampleStandardDeviation()

Returns the sample standard deviation of the observations.

### public double[] getParams ()

Return a table containing parameters of the current distribution.

#### public String toString ()

Returns a String containing information about the current distribution.

March 31, 2009 97

### **PowerDist**

Extends the class Continuous Distribution for the *power* distribution [14, page 161] with shape parameter c > 0, over the interval [a, b], where a < b. This distribution has density

$$f(x) = \frac{c(x-a)^{c-1}}{(b-a)^c}, \quad \text{for } a \le x \le b,$$
 (84)

and f(x) = 0 elsewhere. Its distribution function is

$$F(x) = \frac{(x-a)^c}{(b-a)^c}, \quad \text{for } a \le x \le b,$$
(85)

with F(x) = 0 for  $x \le a$  and F(x) = 1 for  $x \ge b$ .

package umontreal.iro.lecuyer.probdist;

public class PowerDist extends ContinuousDistribution

#### Constructors

public PowerDist (double a, double b, double c)

Constructs a PowerDist object with parameters a = a, b = b and c = c.

public PowerDist (double b, double c)

Constructs a PowerDist object with parameters a = 0, b = b and c = c.

public PowerDist (double c)

Constructs a PowerDist object with parameters a = 0, b = 1 and c = c.

#### Methods

public static double density (double a, double b, double c, double x) Computes the density function (84).

public static double cdf (double a, double b, double c, double x) Computes the distribution function (85).

public static double barF (double a, double b, double c, double x)

Computes the complementary distribution function.

public static double inverseF (double a, double b, double c, double u)

Computes the inverse of the distribution function.

March 31, 2009 PowerDist 98

public static double[] getMLE (double[] x, int n, double a, double b) Estimates the parameter c of the power distribution from the n observations x[i], i = $0, 1, \ldots, n-1$ , using the maximum likelihood method and assuming that a and b are known. The estimate is returned in a one-element array: [c]. public static PowerDist getInstanceFromMLE (double[] x, int n, double a, double b) Creates a new instance of a power distribution with parameters a and b, with c estimated using the maximum likelihood method based on the n observations  $x[i], i = 0, \ldots, n-1$ . public static double getMean (double a, double b, double c) Returns the mean a + (b-a)c/(c+1) of the power distribution with parameters a, b and c. public static double getVariance (double a, double b, double c) Computes and returns the variance  $(b-a)^2c/[(c+1)^2(c+2)]$  of the power distribution with parameters a, b and c. public static double getStandardDeviation (double a, double b, double c) Computes and returns the standard deviation of the power distribution with parameters a, b and c. public double getA() Returns the parameter a. public double getB() Returns the parameter b. public double getC() Returns the parameter c. public void setParams (double a, double b, double c) Sets the parameters a, b and c for this object.

Return a table containing the parameters of the current distribution. This table is put in

public double[] getParams ()

regular order: [a, b, c].

# RayleighDist

This class extends the class Continuous Distribution for the Rayleigh distribution [14] with location parameter a, and scale parameter  $\beta > 0$ . The density function is

$$f(x) = \frac{(x-a)}{\beta^2} e^{-(x-a)^2/(2\beta^2)} \quad \text{for } x \ge a,$$
 (86)

and f(x) = 0 for x < a. The distribution function is

$$F(x) = 1 - e^{-(x-a)^2/(2\beta^2)}$$
 for  $x \ge a$ , (87)

and the inverse distribution function is

$$F^{-1}(u) = x = a + \beta \sqrt{-2\ln(1-u)} \quad \text{for } 0 \le u \le 1.$$
 (88)

package umontreal.iro.lecuyer.probdist;

public class RayleighDist extends ContinuousDistribution

#### Constructors

```
public RayleighDist (double beta)
```

Constructs a RayleighDist object with parameters a=0 and  $\beta=$  beta.

public RayleighDist (double a, double beta)

Constructs a RayleighDist object with parameters a = a, and  $\beta = beta$ .

#### Methods

public static double density (double a, double beta, double x) Computes the density function (86).

public static double density (double beta, double x)
 Same as density (0, beta, x).

public static double cdf (double a, double beta, double x) Computes the distribution function (87).

public static double cdf (double beta, double x)
 Same as cdf (0, beta, x).

public static double barF (double a, double beta, double x)
Computes the complementary distribution function.

March 31, 2009 RayleighDist 100

```
public static double barF (double beta, double x)
  Same as barf (0, beta, x).
public static double inverseF (double a, double beta, double u)
  Computes the inverse of the distribution function (88).
public static double inverseF (double beta, double u)
  Same as inverseF (0, beta, u).
public static double[] getMLE (double[] x, int n, double a)
  Estimates the parameter \beta of the Rayleigh distribution using the maximum likelihood
  method, assuming that a is known, from the n observations x[i], i = 0, 1, \dots, n-1. The
  estimate is returned in a one-element array: [\beta].
public static RayleighDist getInstanceFromMLE (double[] x, int n,
  Creates a new instance of a Rayleigh distribution with parameters a and \beta. This last is
  estimated using the maximum likelihood method based on the n observations x[i], i =
  0, \ldots, n-1.
public static double getMean (double a, double beta)
  Returns the mean a + \beta \sqrt{\pi/2} of the Rayleigh distribution with parameters a and \beta.
public static double getVariance (double beta)
  Returns the variance of the Rayleigh distribution with parameter \beta.
public static double getStandardDeviation (double beta)
  Returns the standard deviation \beta \sqrt{2-\pi/2} of the Rayleigh distribution with parameter \beta.
public double getA()
  Returns the parameter a.
public double getSigma()
  Returns the parameter \beta.
public void setParams (double a, double beta)
  Sets the parameters a and \beta for this object.
public double[] getParams ()
  Return an array containing the parameters of the current distribution in the order: [a, \beta].
```

March 31, 2009 101

# StudentDist

Extends the class ContinuousDistribution for the Student-t distribution [23, page 362] with n degrees of freedom, where n is a positive integer. Its density is

$$f(x) = \frac{\Gamma((n+1)/2)}{\Gamma(n/2)\sqrt{\pi n}} \left(1 + \frac{x^2}{n}\right)^{-(n+1)/2} \quad \text{for } -\infty < x < \infty,$$
 (89)

where  $\Gamma(x)$  is the gamma function defined in (44).

The non-static methods cdf and barF use the same algorithm as in cdf.

package umontreal.iro.lecuyer.probdist;

public class StudentDist extends ContinuousDistribution

#### Constructors

public StudentDist (int n)

Constructs a StudentDist object with n degrees of freedom.

#### Methods

public static double density (int n, double x)

Computes the density function (89) for a Student-t distribution with n degrees of freedom.

public static double cdf (int n, double x)

Returns the approximation of [25, page 96] for the Student-t distribution function with n degrees of freedom. Gives at least 12 decimals of precision for  $n \leq 10^3$ , and at least 10 decimals for  $10^3 < n \leq 10^5$ .

public static double cdf2 (int n, int d, double x)

Returns an approximation of the Student-t distribution function with n degrees of freedom. Uses the relationship (see [22])

$$2F(x) = \begin{cases} I_{n/2,1/2}(n/(n+x^2)) & \text{for } x < 0, \\ I_{1/2,n/2}(x^2/(n+x^2)) & \text{for } x \ge 0, \end{cases}$$
(90)

where  $I_{\alpha,\beta}$  is the beta distribution function with parameters  $\alpha$  and  $\beta$  (also called the incomplete *beta* ratio) defined in (23), which is approximated by calling BetaDist.cdf. The function tries to return d decimals digits of precision (but there is no guarantee). This method is much slower (twenty to forty times, depending on parameters) than cdf, but could be used if precision is important.

March 31, 2009 StudentDist 102

#### public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}(x)$ .

#### public static double inverseF (int n, double u)

Returns an approximation of  $F^{-1}(u)$ , where F is the Student-t distribution function with n degrees of freedom. Uses an approximation giving at least 5 decimal digits of precision when  $n \geq 8$  or  $n \leq 2$ , and 3 decimal digits of precision when  $3 \leq n \leq 7$  (see [20] and Figure L.28 of [7]).

#### public static double[] getMLE (double[] x, int m)

Estimates the parameter n of the Student-t distribution using the maximum likelihood method, from the m observations x[i], i = 0, 1, ..., m - 1. The estimate is returned in a one-element array.

#### @Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int m)
Same as getMLE.

#### public static StudentDist getInstanceFromMLE (double[] x, int m)

Creates a new instance of a Student-t distribution with parameter n estimated using the maximum likelihood method based on the m observations x[i], i = 0, 1, ..., m - 1.

#### public static double getMean (int n)

Returns the mean E[X] = 0 of the Student-t distribution with parameter n.

#### public static double getVariance (int n)

Computes and returns the variance Var[X] = n/(n-2) of the Student-t distribution with parameter n.

#### public static double getStandardDeviation (int n)

Computes and returns the standard deviation of the Student-t distribution with parameter n.

#### public int getN()

Returns the parameter n associated with this object.

#### public void setN (int n)

Sets the parameter n associated with this object.

#### public double[] getParams ()

Return a table containing the parameter of the current distribution.

# **TriangularDist**

Extends the class ContinuousDistribution for the triangular distribution (see [23, page 297] and [27, page 317]) with domain [a, b] and mode (or shape parameter) m, where  $a \le m \le b$ . The density function is

$$f(x) = \begin{cases} \frac{2(x-a)}{(b-a)(m-a)} & \text{if } a \le x \le m, \\ \frac{2(b-x)}{(b-a)(b-m)} & \text{if } m \le x \le b, \\ 0 & \text{elsewhere,} \end{cases}$$
(91)

the distribution function is

$$F(x) = \begin{cases} 0 & \text{for } x < a, \\ \frac{(x-a)^2}{(b-a)(m-a)} & \text{if } a \le x \le m, \\ 1 - \frac{(b-x)^2}{(b-a)(b-m)} & \text{if } m \le x \le b, \\ 1 & \text{for } x > b, \end{cases}$$
(92)

and the inverse distribution function is given by

$$F^{-1}(u) = \begin{cases} a + \sqrt{(b-a)(m-a)u} & \text{if } 0 \le u \le \frac{m-a}{b-a}, \\ b - \sqrt{(b-a)(b-m)(1-u)} & \text{if } \frac{m-a}{b-a} \le u \le 1. \end{cases}$$
(93)

package umontreal.iro.lecuyer.probdist;

public class TriangularDist extends ContinuousDistribution

#### Constructors

public TriangularDist()

Constructs a TriangularDist object with default parameters a = 0, b = 1, and m = 0.5.

public TriangularDist (double m)

Constructs a TriangularDist object with parameters a=0, b=1 and m=m.

public TriangularDist (double a, double b, double m)

Constructs a TriangularDist object with parameters a, b and m.

March 31, 2009 Triangular Dist 104

#### Methods

public static double density (double a, double b, double m, double x) Computes the density function.

public static double cdf (double a, double b, double m, double x) Computes the distribution function.

public static double barF (double a, double b, double m, double x)

Computes the complementary distribution function.

public static double inverseF (double a, double b, double m, double u) Computes the inverse distribution function.

public static double getMean (double a, double b, double m) Computes and returns the mean E[X] = (a+b+m)/3 of the triangular distribution with parameters a, b, m.

public static double getVariance (double a, double b, double m) Computes and returns the variance  $Var[X] = (a^2 + b^2 + m^2 - ab - am - bm)/18$  of the triangular distribution with parameters a, b, m.

public static double getStandardDeviation (double a, double b, double m) Computes and returns the standard deviation of the triangular distribution with parameters a, b, m.

#### public double getA()

Returns the value of a for this object.

#### public double getB()

Returns the value of b for this object.

#### public double getM()

Returns the value of m for this object.

public void setParams (double a, double b, double m)

Sets the value of the parameters a, b and m for this object.

#### public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order: [a, b, m].

#### public String toString ()

Returns a String containing information about the current distribution.

March 31, 2009 105

### UniformDist

Extends the class Continuous Distribution for the uniform distribution [23, page 276] over the interval [a, b]. Its density is

$$f(x) = 1/(b-a) \qquad \text{for } a \le x \le b \tag{94}$$

and 0 elsewhere. The distribution function is

$$F(x) = (x - a)/(b - a) \qquad \text{for } a \le x \le b \tag{95}$$

and its inverse is

$$F^{-1}(u) = a + (b - a)u \qquad \text{for } 0 \le u \le 1.$$
 (96)

package umontreal.iro.lecuyer.probdist;

public class UniformDist extends ContinuousDistribution

#### Constructors

public UniformDist()

Constructs a uniform distribution over the interval (a, b) = (0, 1).

public UniformDist (double a, double b)

Constructs a uniform distribution over the interval (a, b).

#### Methods

public static double density (double a, double b, double x)

Computes the uniform density function f(x) in (94).

public static double cdf (double a, double b, double x)

Computes the uniform distribution function as in (95).

public static double barF (double a, double b, double x)

Computes the uniform complementary distribution function  $\bar{F}(x)$ .

public static double inverseF (double a, double b, double u)

Computes the inverse of the uniform distribution function (96).

public static double[] getMLE (double[] x, int n)

Estimates the parameter (a, b) of the uniform distribution using the maximum likelihood method, from the n observations x[i], i = 0, 1, ..., n - 1. The estimates are returned in a two-element array, in regular order: [a, b].

March 31, 2009 UniformDist 106

@Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
Same as getMLE.

public static UniformDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a uniform distribution with parameters a and b estimated using the maximum likelihood method based on the n observations x[i],  $i = 0, 1, \ldots, n-1$ .

public static double getMean (double a, double b)

Computes and returns the mean E[X] = (a + b)/2 of the uniform distribution with parameters a and b.

public static double getVariance (double a, double b)

Computes and returns the variance  $Var[X] = (b-a)^2/12$  of the uniform distribution with parameters a and b.

public static double getStandardDeviation (double a, double b)

Computes and returns the standard deviation of the uniform distribution with parameters a and b.

public double getA()

Returns the parameter a.

public double getB()

Returns the parameter b.

public void setParams (double a, double b)

Sets the parameters a and b for this object.

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order: [a, b].

## WeibullDist

This class extends the class ContinuousDistribution for the Weibull distribution [22, page 628] with shape parameter  $\alpha > 0$ , location parameter  $\delta$ , and scale parameter  $\lambda > 0$ . The density function is

$$f(x) = \alpha \lambda^{\alpha} (x - \delta)^{\alpha - 1} e^{-(\lambda(x - \delta))^{\alpha}} \qquad \text{for } x > \delta,$$
(97)

the distribution function is

$$F(x) = 1 - e^{-(\lambda(x-\delta))^{\alpha}} \qquad \text{for } x > \delta, \tag{98}$$

and the inverse distribution function is

$$F^{-1}(u) = (-\ln(1-u))^{1/\alpha}/\lambda + \delta$$
 for  $0 \le u < 1$ .

package umontreal.iro.lecuyer.probdist;

public class WeibullDist extends ContinuousDistribution

## Constructors

```
public WeibullDist (double alpha)
```

Constructs a WeibullDist object with parameters  $\alpha = \text{alpha}$ ,  $\lambda = 1$ , and  $\delta = 0$ .

public WeibullDist (double alpha, double lambda, double delta)

Constructs a WeibullDist object with parameters  $\alpha = \text{alpha}$ ,  $\lambda = \text{lambda}$ , and  $\delta = \text{delta}$ .

### Methods

Computes the density function.

public static double density (double alpha, double x)

Same as density (alpha, 1, 0, x).

Computes the distribution function.

public static double cdf (double alpha, double x)

Same as cdf (alpha, 1, 0, x).

Computes the complementary distribution function.

public static double barF (double alpha, double x)
Same as barF (alpha, 1, 0, x).

Computes the inverse of the distribution function.

public static double inverseF (double alpha, double x)
 Same as inverseF (alpha, 1, 0, x).

public static double[] getMLE (double[] x, int n)

Estimates the parameters  $(\alpha, \lambda)$  of the Weibull distribution, assuming that  $\delta = 0$ , using the maximum likelihood method, from the *n* observations x[i],  $i = 0, 1, \ldots, n-1$ . The estimates are returned in a two-element array, in regular order:  $[\alpha, \lambda]$ .

@Deprecated

public static double[] getMaximumLikelihoodEstimate (double[] x, int n)
Same as getMLE.

public static WeibullDist getInstanceFromMLE (double[] x, int n)

Creates a new instance of a Weibull distribution with parameters  $\alpha$ ,  $\lambda$  and  $\delta = 0$  estimated using the maximum likelihood method based on the n observations x[i],  $i = 0, 1, \ldots, n-1$ .

public static double getMean (double alpha, double lambda, double delta) Computes and returns the mean  $E[X] = \delta + \Gamma(1+1/\alpha)/\lambda$  of the Weibull distribution with parameters  $\alpha$ ,  $\lambda$  and  $\delta$ .

Computes and returns the variance  $\operatorname{Var}[X] = |\Gamma(2/\alpha + 1) - \Gamma^2(1/\alpha + 1)|/\lambda^2$  of the Weibull distribution with parameters  $\alpha$ ,  $\lambda$  and  $\delta$ .

Computes and returns the standard deviation of the Weibull distribution with parameters  $\alpha$ ,  $\lambda$  and  $\delta$ .

public double getAlpha()

Returns the parameter  $\alpha$ .

public double getLambda()

Returns the parameter  $\lambda$ .

March 31, 2009 WeibullDist 109

public double getDelta()

Returns the parameter  $\delta$ .

public void setParams (double alpha, double lambda, double delta) Sets the parameters  $\alpha$ ,  $\lambda$  and  $\delta$  for this object.

public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in regular order:  $[\alpha, \lambda, \delta]$ .

## **TruncatedDist**

This container class takes an arbitrary continuous distribution and truncates it to an interval [a, b], where a and b can be finite or infinite. If the original density and distribution function are f and F, the new ones are  $f^*$  and  $F^*$ , defined by

$$f^*(x) = f(x)/(F(b) - F(a))$$
 for  $a \le x \le b$ 

and  $f^*(x) = 0$  and zero elsewhere, and

$$F^*(x) = F(x)/(F(b) - F(a)) \qquad \text{for } a \le x \le b.$$

The inverse distribution function of the truncated distribution is

$$F^{-1*}(u) = F^{-1}(F(a) + (F(b) - F(a))u)$$

where  $F^{-1}$  is the inverse distribution function of the original distribution.

package umontreal.iro.lecuyer.probdist;

public class TruncatedDist extends ContinuousDistribution

#### Constructor

public TruncatedDist (ContinuousDistribution dist, double a, double b)

Constructs a new distribution by truncating distribution dist to the interval [a,b]. If a = Double.NEGATIVE\_INFINITY, F(a) is assumed to be 0. If b = Double.POSITIVE\_INFINITY, F(b) is assumed to be 1.

### Methods

public double getA()

Returns the value of a.

public double getB()

Returns the value of b.

public double getFa()

Returns the value of F(a).

public double getFb()

Returns the value of F(b).

public double getArea()

Returns the value of F(b) - F(a), the area under the truncated density function.

March 31, 2009 TruncatedDist 111

public void setParams (ContinuousDistribution dist, double a, double b) Sets the parameters dist, a and b for this object. See the constructor for details.

## public double[] getParams ()

Return a table containing the parameters of the current distribution. This table is put in order: [a, b, F(a), F(b), F(b) - F(a)].

## public String toString ()

Returns a String containing information about the current distribution.

# AndersonDarlingDist

Extends the class Continuous Distribution for the Anderson-Darling distribution (see [1, 29, 32, 43]). Given a sample of n independent uniforms  $U_i$  over (0, 1), the Anderson-Darling statistic  $A_n^2$  is defined by

$$A_n^2 = -n - \frac{1}{n} \sum_{j=1}^n \left\{ (2j-1) \ln(U_{(j)}) + (2n+1-2j) \ln(1-U_{(j)}) \right\},\,$$

where the  $U_{(j)}$  are the  $U_i$  sorted in increasing order. The distribution function (the cumulative probabilities) is defined as  $F_n(x) = P[A_n^2 \le x]$ .

package umontreal.iro.lecuyer.probdist;

public class AndersonDarlingDist extends ContinuousDistribution

#### Constructor

public AndersonDarlingDist (int n)

Constructs an Anderson-Darling distribution for a sample of size n.

## Methods

public static double density (int n, double x)

Computes the density of the Anderson-Darling distribution with parameter n.

public static double cdf (int n, double x)

Computes the Anderson-Darling distribution function  $F_n(x)$ , with parameter n, using Marsaglia's and al. algorithm [32]. First the asymptotic distribution for  $n \to \infty$  is computed. Then an empirical correction obtained by simulation is added for finite n.

public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}_n(x)$  with parameter n.

public static double inverseF (int n, double u)

Computes the inverse  $x = F_n^{-1}(u)$  of the Anderson-Darling distribution with parameter n.

public int getN()

Returns the parameter n of this object.

public void setN (int n)

Sets the parameter n of this object.

public double[] getParams ()

Return an array containing the parameter n of the current distribution.

# AndersonDarlingDistQuick

Extends the class AndersonDarlingDist for the *Anderson-Darling* distribution (see [1, 29, 43]). This class implements a faster version than class AndersonDarlingDist.

```
package umontreal.iro.lecuyer.probdist;
```

public class AndersonDarlingDistQuick extends AndersonDarlingDist

### Constructor

```
public AndersonDarlingDistQuick (int n)
```

Constructs an Anderson-Darling distribution for a sample of size n.

### Methods

```
public static double density (int n, double x)
```

Computes the density of the Anderson-Darling distribution with parameter n.

```
public static double cdf (int n, double x)
```

Computes the Anderson-Darling distribution function  $F_n(x)$  with parameter n. The asymptotic distribution  $F_{\infty}(x) = \lim_{n \to \infty} F_n(x)$  was first computed by numerical integration. Then a linear correction O(1/n) obtained by simulation was added. The absolute error on  $F_n(x)$  is estimated to be less than 0.001 for n > 6, except far in the tails. For n = 2, 3, 4, 6, it is estimated to be less than 0.04, 0.01, 0.005, 0.002, respectively. For n = 1, the method returns the exact value  $F_1(x) = \sqrt{1 - 4e^{-x-1}}$ , for  $x \ge \ln(4) - 1$ .

```
public static double barF (int n, double x)
```

Computes the complementary distribution function  $\bar{F}_n(x)$  with parameter n.

```
public static double inverseF (int n, double u)
```

Computes the inverse  $x = F_n^{-1}(u)$  of the Anderson-Darling distribution with parameter n.

## CramerVonMisesDist

Extends the class ContinuousDistribution for the Cramér-von Mises distribution (see [13, 42, 43]). Given a sample of n independent uniforms  $U_i$  over [0, 1], the Cramér-von Mises statistic  $W_n^2$  is defined by

$$W_n^2 = \frac{1}{12n} + \sum_{j=1}^n \left( U_{(j)} - \frac{(j-0.5)}{n} \right)^2, \tag{99}$$

where the  $U_{(j)}$  are the  $U_i$  sorted in increasing order. The distribution function (the cumulative probabilities) is defined as  $F_n(x) = P[W_n^2 \le x]$ .

package umontreal.iro.lecuyer.probdist;

public class CramerVonMisesDist extends ContinuousDistribution

## Constructor

public CramerVonMisesDist (int n)

Constructs a  $Cram\'{e}r$ - $von\ Mises$  distribution for a sample of size n.

### Methods

public static double density (int n, double x)

Computes the density function for a  $Cram\'er-von\ Mises$  distribution with parameter n.

public static double cdf (int n, double x)

Computes the Cramér-von Mises distribution function with parameter n. Returns an approximation of  $P[W_n^2 \leq x]$ , where  $W_n^2$  is the Cramér von Mises statistic (see [42, 43, 1, 26]). The approximation is based on the distribution function of  $W^2 = \lim_{n \to \infty} W_n^2$ , which has the following series expansion derived by Anderson and Darling [1]:

$$P(W^2 \le x) = \frac{1}{\pi \sqrt{x}} \sum_{j=0}^{\infty} (-1)^j \binom{-1/2}{j} \sqrt{4j+1} \exp\left\{-\frac{(4j+1)^2}{16x}\right\} K_{1/4} \left(\frac{(4j+1)^2}{16x}\right),$$

where  $K_{\nu}$  is the modified Bessel function of the second kind. To correct for the deviation between  $P(W_n^2 \le x)$  and  $P(W^2 \le x)$ , we add a correction in 1/n, obtained empirically by simulation. For n = 10, 20, 40, the error is less than 0.002, 0.001, and 0.0005, respectively, while for  $n \ge 100$  it is less than 0.0005. For  $n \to \infty$ , we estimate that the method returns at least 6 decimal digits of precision. For n = 1, the method uses the exact distribution:  $P(W_1^2 \le x) = 2\sqrt{x - 1/12}$  for  $1/12 \le x \le 1/3$ .

public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}_n(x)$  with parameter n.

March 31, 2009 CramerVonMisesDist 115

```
public static double inverseF (int n, double u)
   Computes x = F_n^{-1}(u), where F_n is the Cram\'er-von\ Mises distribution with parameter n.

public static double getMean (int n)
   Returns the mean of the distribution with parameter n.

public static double getVariance (int n)
   Returns the variance of the distribution with parameter n.

public static double getStandardDeviation (int n)
   Returns the standard deviation of the distribution with parameter n.

public int getN()
   Returns the parameter n of this object.

public void setN (int n)
   Sets the parameter n of this object.
```

Return an array containing the parameter n of this object.

# KolmogorovSmirnovPlusDist

Extends the class ContinuousDistribution for the Kolmogorov-Smirnov+ distribution (see [11, 13, 8]). Given a sample of n independent uniforms  $U_i$  over [0, 1], the Kolmogorov-Smirnov+ statistic  $D_n^+$  and the Kolmogorov-Smirnov- statistic  $D_n^-$ , are defined by

$$D_n^+ = \max_{1 \le j \le n} (j/n - U_{(j)}), \qquad (100)$$

$$D_n^- = \max_{1 \le j \le n} \left( U_{(j)} - (j-1)/n \right), \tag{101}$$

where the  $U_{(j)}$  are the  $U_i$  sorted in increasing order. Both statistics follows the same distribution function, i.e.  $F_n(x) = P[D_n^+ \le x] = P[D_n^- \le x]$ .

package umontreal.iro.lecuyer.probdist;

public class KolmogorovSmirnovPlusDist extends ContinuousDistribution

### Constructor

public KolmogorovSmirnovPlusDist (int n)

Constructs an Kolmogorov-Smirnov+ distribution for a sample of size n.

### Methods

public static double density (int n, double x)

Computes the density of the Kolmogorov-Smirnov+ distribution with parameter n.

public static double cdf (int n, double x)

Computes the Kolmogorov-Smirnov+ distribution function  $F_n(x)$  with parameter n. The distribution function can be approximated via the following expressions:

$$P[D_n^+ \le x] = 1 - x \sum_{i=0}^{\lfloor n(1-x) \rfloor} {n \choose i} \left( \frac{i}{n} + x \right)^{i-1} \left( 1 - \frac{i}{n} - x \right)^{n-i}$$
 (102)

$$= x \sum_{j=0}^{\lfloor nx \rfloor} {n \choose j} \left( \frac{j}{n} - x \right)^j \left( 1 - \frac{j}{n} + x \right)^{n-j-1}$$
 (103)

$$\approx 1 - e^{-2nx^2} \left[ 1 - \frac{2x}{3} \left( 1 - x \left( 1 - \frac{2nx^2}{3} \right) \right) \right]$$

$$-\frac{2}{3n}\left(\frac{1}{5} - \frac{19nx^2}{15} + \frac{2n^2x^4}{3}\right) + O(n^{-2})\right]. \tag{104}$$

Formula (102) and (103) can be found in [13], equations (2.1.12) and (2.1.16), while (104) can be found in [11]. Formula (103) becomes numerically unstable as nx increases. The

approximation (104) is simpler to compute and excellent when nx is large. The relative error on  $F_n(x) = P[D_n^+ \le x]$  is always less than  $10^{-5}$ .

## public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}_n(x)$  with parameter n.

## public static double inverseF (int n, double u)

Computes the inverse  $x = F^{-1}(u)$  of the distribution with parameter n.

## public int getN()

Returns the parameter n of this object.

## public void setN (int n)

Sets the parameter n of this object.

## public double[] getParams ()

Returns an array containing the parameter n of this object.

# KolmogorovSmirnovDist

Extends the class Continuous Distribution for the Kolmogorov-Smirnov distribution with parameter n [13]. Given an empirical distribution  $F_n$  with n independent observations and a continuous distribution F(x), the two-sided Kolmogorov-Smirnov statistic is defined as

$$D_n = \sup_{-\infty \le x \le \infty} |F_n(x) - F(x)| = \max\{D_n^+, D_n^-\},$$
 (105)

where  $D_n^+$  and  $D_n^-$  are the Kolmogorov-Smirnov+ and Kolmogorov-Smirnov- statistics as defined in equations 100 and 101 on page 116 of this guide. This class implements a high precision version of the Kolmogorov-Smirnov distribution  $P[D_n \leq x]$ ; it is a Java translation of the C program written in [33]. According to its authors, it should give at least seven decimal digits of precision. It may be astronomically slow for large values of n.

package umontreal.iro.lecuyer.probdist;

public class KolmogorovSmirnovDist extends ContinuousDistribution

### Constructor

public KolmogorovSmirnovDist (int n)

Constructs a Kolmogorov-Smirnov distribution with parameter n. Restriction:  $n \ge 1$ .

## Methods

```
public static double density (int n, double x)
```

Computes the density for the Kolmogorov-Smirnov distribution with parameter n.

public static double cdf (int n, double x)

Computes the Kolmogorov-Smirnov distribution function F(x) with parameter n.

public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}(x)$  with parameter n.

public static double inverseF (int n, double u)

Computes the inverse  $x = F^{-1}(u)$  of the Kolmogorov-Smirnov distribution F(x) with parameter n.

public int getN()

Returns the parameter n of this object.

public void setN (int n)

Sets the parameter n of this object.

public double[] getParams ()

Returns an array containing the parameter n of this object.

# KolmogorovSmirnovDistQuick

Extends the class KolmogorovSmirnovDist for the Kolmogorov-Smirnov distribution. This class uses quick approximations to compute the probabilities for n > 50; these approximations are much faster than the methods of KolmogorovSmirnovDist. For  $n \leq 50$ , it simply calls the methods in KolmogorovSmirnovDist.

```
package umontreal.iro.lecuyer.probdist;
```

public class KolmogorovSmirnovDistQuick extends KolmogorovSmirnovDist

## Constructor

```
public KolmogorovSmirnovDistQuick (int n)
```

Constructs a Kolmogorov-Smirnov distribution with parameter n.

## Methods

```
public static double density (int n, double x)
```

Computes the density for the Kolmogorov-Smirnov distribution with parameter n.

```
public static double cdf (int n, double x)
```

Computes the Kolmogorov-Smirnov distribution function F(x) with parameter n.

```
public static double barF (int n, double x)
```

Computes the complementary distribution function  $\bar{F}(x)$  with parameter n.

```
public static double inverseF (int n, double u)
```

Computes the inverse  $x = F^{-1}(u)$  of the Kolmogorov-Smirnov distribution F(x) with parameter n.

## WatsonGDist

Extends the class Continuous Distribution for the Watson G distribution (see [12, 45]). Given a sample of n independent uniforms  $U_i$  over [0, 1], the G statistic is defined by

$$G_n = \sqrt{n} \max_{1 \le j \le n} \left\{ j/n - U_{(j)} + \bar{U}_n - 1/2 \right\}$$

$$= \sqrt{n} \left( D_n^+ + \bar{U}_n - 1/2 \right),$$
(106)

where the  $U_{(j)}$  are the  $U_i$  sorted in increasing order,  $\bar{U}_n$  is the average of the observations  $U_i$ , and  $D_n^+$  is the Kolmogorov-Smirnov+ statistic. The distribution function (the cumulative probabilities) is defined as  $F_n(x) = P[G_n \leq x]$ .

package umontreal.iro.lecuyer.probdist;

public class WatsonGDist extends ContinuousDistribution

#### Constructor

public WatsonGDist (int n)

Constructs a Watson distribution for a sample of size n.

### Methods

public static double density (int n, double x)

Computes the density function for a Watson G distribution with parameter n.

public static double cdf (int n, double x)

Computes the Watson G distribution function  $F_n(x)$ , with parameter n. A cubic spline interpolation is used for the asymptotic distribution when  $n \to \infty$ , and an empirical correction of order  $1/\sqrt{n}$ , obtained empirically from  $10^7$  simulation runs with n=256 is then added. The absolute error is estimated to be less than 0.01, 0.005, 0.002, 0.0008, 0.0005, 0.0005, 0.0005 for n=16, 32, 64, 128, 256, 512, 1024, respectively.

public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}_n(x)$  with parameter n.

public static double inverseF (int n, double u)

Computes  $x = F_n^{-1}(u)$ , where  $F_n$  is the Watson G distribution with parameter n.

public int getN()

Returns the parameter n of this object.

March 31, 2009 WatsonGDist 121

public void setN (int n)

Sets the parameter n of this object.

public double[] getParams ()

Return an array containing the parameter n of this object.

## WatsonUDist

Extends the class Continuous Distribution for the Watson U distribution (see [13, 42, 43]). Given a sample of n independent uniforms  $u_i$  over [0, 1], the Watson statistic  $U_n^2$  is defined by

$$W_n^2 = \frac{1}{12n} + \sum_{j=1}^n \left\{ u_{(j)} - \frac{(j-1/2)}{n} \right\}^2,$$
  
$$U_n^2 = W_n^2 - n \left( \bar{u}_n - 1/2 \right)^2.$$

where the  $u_{(j)}$  are the  $u_i$  sorted in increasing order, and  $\bar{u}_n$  is the average of the observations  $u_i$ . The distribution function (the cumulative probabilities) is defined as  $F_n(x) = P[U_n^2 \le x]$ .

package umontreal.iro.lecuyer.probdist;

public class WatsonUDist extends ContinuousDistribution

### Constructor

public WatsonUDist (int n)

Constructs a Watson U distribution for a sample of size n.

### Methods

public static double density (int n, double x)

Computes the density of the Watson U distribution with parameter n.

public static double cdf (int n, double x)

Computes the Watson U distribution function, i.e. returns  $P[U_n^2 \leq x]$ , where  $U_n^2$  is the Watson statistic defined in (107). We use the asymptotic distribution for  $n \to \infty$ , plus a correction in O(1/n), as given in [10].

public static double barF (int n, double x)

Computes the complementary distribution function  $\bar{F}_n(x)$ , where  $F_n$  is the Watson U distribution with parameter n.

public static double inverseF (int n, double u)

Computes  $x = F_n^{-1}(u)$ , where  $F_n$  is the Watson U distribution with parameter n.

public static double getMean (int n)

Returns the mean of the Watson U distribution with parameter n.

March 31, 2009 WatsonUDist 123

public static double getVariance (int n)

Returns the variance of the  $Watson\ U$  distribution with parameter n.

public static double getStandardDeviation (int n)

Returns the standard deviation of the  $Watson\ U$  distribution with parameter n.

public int getN()

Returns the parameter n of this object.

public void setN (int n)

Sets the parameter n of this object.

public double[] getParams ()

Return an array containing the parameter n of this object.

March 31, 2009 REFERENCES 124

## References

[1] T. W. Anderson and D. A. Darling. Asymptotic theory of certain goodness of fit criteria based on stochastic processes. *Annals of Mathematical Statistics*, 23:193–212, 1952.

- [2] D. J. Best and D. E. Roberts. Algorithm AS 91: The percentage points of the  $\chi^2$  distribution. Applied Statistics, 24:385–388, 1975.
- [3] G. P. Bhattacharjee. The incomplete gamma integral. *Applied Statistics*, 19:285–287, 1970. AS32.
- [4] Z. W. Birnbaum and S. C. Saunders. A new family of life distributions. *Journal of Applied Probability*, 6:319–327, 1969.
- [5] J. M. Blair, C. A. Edwards, and J. H. Johnson. Rational Chebyshev approximations for the inverse of the error function. *Mathematics of Computation*, 30:827–830, 1976.
- [6] L. N. Bol'shev. Some applications of Pearson transformations. Review of the Internat. Stat. Institute, 32:14–16, 1964.
- [7] P. Bratley, B. L. Fox, and L. E. Schrage. A Guide to Simulation. Springer-Verlag, New York, NY, second edition, 1987.
- [8] J. R. Brown and M. E. Harvey. Rational arithmetic MATHEMATICA functions to evaluate the one-sided one-sample K-S cumulative sample distribution. *Journal of Statistical Software*, 19(i06):1–32, 2007.
- [9] B. H. Camp. Approximation to the point binomial. Ann. Math. Stat., 22:130–131, 1951.
- [10] S. Csörgő and J. J. Faraway. The exact and asymptotic distributions of Cramér-von mises statistics. *Journal of the Royal Statistical Society, Series B*, 58:221–234, 1996.
- [11] D. A. Darling. On the theorems of Kolmogorov-Smirnov. Theory of Probability and Its Applications, V(4):356–360, 1960.
- [12] D. A. Darling. On the asymptotic distribution of Watson's statistic. *The Annals of Statistics*, 11(4):1263–1266, 1983.
- [13] J. Durbin. Distribution Theory for Tests Based on the Sample Distribution Function. SIAM CBMS-NSF Regional Conference Series in Applied Mathematics. SIAM, Philadelphia, PA, 1973.
- [14] M. Evans, N. Hastings, and B. Peacock. *Statistical Distributions*. Wiley, 3rd edition, 2000.
- [15] M. Evans and T. Swartz. Approximating Integrals via Monte Carlo and Deterministic Methods. Oxford University Press, Oxford, UK, 2000.
- [16] W. Gautschi. Algorithm 222: Incomplete beta function ratios. Communications of the ACM, 7(3):143–144, 1964.

March 31, 2009 REFERENCES 125

[17] W. Gautschi. Certification of algorithm 222: Incomplete beta function ratios. Communications of the ACM, 7(3):244, 1964.

- [18] J. E. Gentle. Random Number Generation and Monte Carlo Methods. Springer, New York, NY, 1998.
- [19] R. B. Goldstein. Algorithm 451: Chi-square quantiles. Communications of the ACM, 16:483–485, 1973.
- [20] G. W. Hill. Algorithm 395: Student's t-distribution. Communications of the ACM, 13:617–619, 1970.
- [21] N. L. Johnson and S. Kotz. *Distributions in Statistics: Discrete Distributions*. Houghton Mifflin, Boston, 1969.
- [22] N. L. Johnson, S. Kotz, and N. Balakrishnan. *Continuous Univariate Distributions*, volume 1. Wiley, 2nd edition, 1994.
- [23] N. L. Johnson, S. Kotz, and N. Balakrishnan. *Continuous Univariate Distributions*, volume 2. Wiley, 2nd edition, 1995.
- [24] V. Kachitvichyanukul and B. Schmeiser. Computer generation of hypergeometric random variates. *J. Statist. Comput. Simul.*, 22:127–145, 1985.
- [25] W. J. Kennedy Jr. and J. E. Gentle. *Statistical Computing*. Dekker, New York, NY, 1980.
- [26] M. Knott. The distribution of the Cramér-von Mises statistic for small sample sizes. Journal of the Royal Statistical Society B, 36:430–438, 1974.
- [27] A. M. Law and W. D. Kelton. Simulation Modeling and Analysis. McGraw-Hill, New York, NY, third edition, 2000.
- [28] F. C. Leone, L. S. Nelson, and R. B. Nottingham. The folded normal distribution. *Technometrics*, 3(4):543–550, 1961.
- [29] P. A. W. Lewis. Distribution of the Anderson-Darling statistic. *Annals of Mathematical Statistics*, 32:1118–1124, 1961.
- [30] J. Leydold and W. Hörmann. *UNURAN—A Library for Universal Non-Uniform Ran-dom Number Generators*, 2002. Available at http://statistik.wu-wien.ac.at/unuran.
- [31] K. V. Mardia and P. J. Zemroch. Tables of the F and Related Distributions with Algorithms. Academic Press, London, 1978.
- [32] G. Marsaglia and J. Marsaglia. Evaluating the Anderson-Darling distribution. *Journal of Statistical Software*, 9(2):1–5, 2004. See http://www.jstatsoft.org/v09/i02/.

March 31, 2009 REFERENCES 126

[33] G. Marsaglia, W. W. Tsang, and J. Wang. Evaluating Kolmogorov's distribution. *Journal of Statistical Software*, 8(18):1–4, 2003. See http://www.jstatsoft.org/v08/i18/.

- [34] G. Marsaglia, A. Zaman, and J. C. W. Marsaglia. Rapid evaluation of the inverse normal distribution function. *Statistics and Probability Letters*, 19:259–266, 1994.
- [35] W. Molenaar. Approximations to the Poisson, Binomial and Hypergeometric Distribution Functions, volume 31 of Mathematical Center Tract. Mathematisch Centrum, Amsterdam, 1970.
- [36] S. L. Moshier. Cephes math library, 2000. See http://www.moshier.net.
- [37] E. S. Pearson. Note on an approximation to the distribution of non-central  $\chi^2$ . Biometrika, 46:364, 1959.
- [38] D. B. Peizer and J. W. Pratt. A normal approximation for binomial, F, beta, and other common related tail probabilities. *Journal of the American Statistical Association*, 63:1416–1456, 1968.
- [39] S. Penev and T. Raykov. A Wiener germ approximation of the noncentral chi square distribution and of its quantiles. *Computational Statistics*, 15(2):219–228, 2000.
- [40] R. B. Schnabel. *UNCMIN—Unconstrained Optimization Package*, *FORTRAN*. University of Colorado at Boulder. See http://www.ici.ro/camo/unconstr/uncmin.htm.
- [41] J. L. Schonfelder. Chebyshev expansions for the error and related functions. *Mathematics of Computation*, 32:1232–1240, 1978.
- [42] M. A. Stephens. Use of the Kolmogorov-Smirnov, Cramér-Von Mises and related statistics without extensive tables. *Journal of the Royal Statistical Society, Series B*, 33(1):115–122, 1970.
- [43] M. S. Stephens. Tests based on EDF statistics. In R. B. D'Agostino and M. S. Stephens, editors, *Goodness-of-Fit Techniques*. Marcel Dekker, New York and Basel, 1986.
- [44] S. P. Verrill. *UNCMIN—Unconstrained Optimization Package*, *Java*. US Forest Service, Forest Products Laboratory. Available at http://www1.fpl.fs.fed.us/optimization.html.
- [45] G. S. Watson. Optimal invariant tests for uniformity. In *Studies in Probability and Statistics*, pages 121–127. North Holland, Amsterdam, 1976.