

Device	Interface	IP Address	Subnet Mask
RED	S0/0/0	30.30.30.1	255.255.255.252
	G0/0	192.168.1.1	255.255.255.0
	G0/1.10	99.99.10.1	255.255.255.0
	G0/1.20	99.99.20.1	255.255.255.0
	G0/1.99	99.99.99.1	255.255.255.0

Yellow	S0/0/0	30.30.30.2	255.255.255.252
	SO/0/1	30.30.30.5	255.255.255.252
	G0/0	192.168.2.1	255.255.255.0
	G0/1.30	99.99.30.1	255.255.255.0
	G0/1.99	99.99.100.1	255.255.255.0
	Lo1	15.15.15.15	255.255.255.255

Orange	S0/0/1	30.30.30.6	255.255.255.252
	G0/0	192.168.3.1	255.255.255.0
	G0/1.40	99.99.40.1	255.255.255.0
	G0/1.50	99.99.50.1	255.255.255.0
	G0/1.99	99.99.101.1	255.255.255.0
Maroon	VLAN 10	99.99.10.10	255.255.255.0
	VLAN 20	99.99.20.10	255.255.255.0
	VLAN 99	99.99.99.10	255.255.255.0
Scarlet	VLAN 10	99.99.10.11	255.255.255.0
	VLAN 20	99.99.20.11	255.255.255.0
	VLAN 99	99.99.99.11	255.255.255.0
	•	•	•
Purple	VLAN 30	99.99.30.10	255.255.255.0
	VLAN 99	99.99.100.10	255.255.255.0
	·	•	•

Green	VLAN 40	99.99.40.10	255.255.255.0
	VLAN 50	99.99.50.10	255.255.255.0
	VLAN 99	99.99.101.10	255.255.255.0

Brown	VLAN 40	99.99.40.11	255.255.255.0
	VLAN 50	99.99.50.11	255.255.255.0
	VLAN 99	99.99.101.11	255.255.255.0
			,
DHCP Server (A)	NIC	192.168.1.100	255.255.255.0
DHCP Server (B)	NIC	192.168.2.100	255.255.255.0
DHCP Server (C)	NIC	192.168.3.100	255.255.255.0
		1	
Maroon	F0/1-11	VLAN 10	Emerald
	F0/12-24	VLAN 20	Silver
	N/A	VLAN 99	Management
Scarlet	F0/1-12	VLAN 20	Silver
	F0/13-24	VLAN 10	Emerald
	N/A	VLAN 99	Management
Purple	F0/1-24	VLAN 30	Fusion
	N/A	VLAN 99	Management
•	1		1
Green	F0/1-10	VLAN 40	Sunburst
	F0/11-24	VLAN 50	Blue
	N/A	VLAN 99	Management

Brown	F0/1-10	VLAN 50	Blue
	F0/11-24	VLAN 40	Sunburst
	N/A	VLAN 99	Management

DHCP Server (A)

- Set the Static IP address, Subnet mask and Default Gateway
- Use the address table from above.
- Enable the DHCP Service
- Pool Name: Sunburst
- Set the default-gateway for the Sunburst network.
- Set the DNS server to 8.8.8.8
- Use the Sunburst network for your DHCP pool.
- Exclude the first 39 Usable IP addresses.
- Set the Subnet mask or Set the Maximum users to 110.
- Set the Static IP address, Subnet mask and Default Gateway
- Use the address table from above.
- Enable the DHCP Service
- Pool Name: Blue
- Set the default-gateway for the blue network.
- Set the DNS server to 8.8.8.8
- Use the Blue network for your DHCP pool.
- Exclude the first 39 Usable IP addresses.
- Set the Subnet mask or Set the Maximum users to 110.

DHCP Server (B)

- Set the Static IP address, Subnet mask and Default Gateway
- Use the address table from above.
- Enable the DHCP Service
- Pool Name: Emerald
- Set the default-gateway for the Emerald network.
- Set the DNS server to 8.8.8.8
- Use the Emerald network for your DHCP pool.
- Exclude the first 39 Usable IP addresses.

- Set the Subnet mask or Set the Maximum users to 110.
- Set the Static IP address, Subnet mask and Default Gateway
- Use the address table from above.
- Enable the DHCP Service
- Pool Name: Silver
- Set the default-gateway for the silver network.
- Set the DNS server to 8.8.8.8
- Use the Silver network for your DHCP pool.
- Exclude the first 39 Usable IP addresses.
- Set the Subnet mask or Set the Maximum users to 110.

DHCP Server (C)

- Set the Static IP address, Subnet mask and Default Gateway
- Use the address table from above.
- Enable the DHCP Service
- Pool Name: Fusion
- Set the default-gateway for the Fusion network.
- Set the DNS server to 8.8.8.8
- Use the fusion network for your DHCP pool.
- Exclude the first 39 Usable IP addresses.
- Set the Subnet mask.
- Set the Maximum users to 110.

RED

- Assign the Hostname
- Disable DNS lookup.
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console.
- Encrypt all clear text passwords in current running configuration.
- Set a MOTD banner to "Configured by Briseno."
- Configure SSH
 - o Domain-Name: GitHub.com
 - o Create a username of admin encrypted password of adminpass
 - o Generate an RSA key with 1024 bits

- o Allow authentication with only the local database o Enable only SSH access on VTY line
- Apply IP addresses according to the Addressing Table
- Disable CDP on S0/0/0
- Use a clock rate of 128000 on DCE interface.
- Configure Single-Area OSPFv2
 - o Process ID 100
 - o Area 0
 - o Router ID: 1.1.1.1
 - o Advertise all networks configured
 - o Apply passive interface on appropriate interfaces if applicable

Yellow

- Assign the hostname.
- Disable DNS lookup.
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console password.
- Encrypt all clear text passwords in current running configuration.
- Set a MOTD banner to "Configured by Briseno" o Configure SSH
- Domain-Name: NETACAD.com
- Create a username of admin with an encrypted password of adminpass.
- Generate an RSA key with 1024 bits.
- Allow authentication with only the local database.
- Enable only SSH access on VTY line.
- Encrypt all plain text passwords.
- Apply IP addresses according to the Addressing Table
- Create loopback 1.
- Create a default route out of Lo1.
- Configure Single-Area OSPFv2
 - o Process ID 100
 - o Area 0
 - o Router ID: 2.2.2.2
 - o Advertise all networks configured
 - o Do not send OSPF updates out appropriate interfaces

o Propagate the default route

- Configure NAT
- Configure a standard ACL numbered 20 to allow only the IP address within the 99.99.30.0/24 network.
- Configure NAT with a pool named AIT with the following range of public IP addresses:
- 200.56.53.200 to 200.56.53.250 with a subnet mask of 255.255.255.128
- Apply to the correct NAT interfaces.

Orange

- Assign the Hostname
- Disable DNS lookup.
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console password.
- Encrypt all clear text passwords in current running configuration.
- Set a MOTD banner to "Configured by Briseno."
- Configure SSH
- Domain-Name: NETACAD.com
- Create a username of admin with an encrypted password of adminpass.
- Generate an RSA key with 1024 bits.
- Allow authentication with only the local database.
- Enable only SSH access on VTY line.
- Apply IP addresses according to the Addressing Table
- Use a clock rate of 128000 on DCE interface.
- Configure Single-Area OSPFv2
 - o Process ID 100
 - o Area 0
 - o Router ID: 3.3.3.3
 - o Advertise all networks configured
 - o Apply passive interface on appropriate interfaces if applicable
- Configure an Access Control List (ACL)
 o Create a standard ACL 65 to deny VLAN 50 from accessing VLAN 40

o Permit all other traffic o Apply to correct interface

Maroon

- Assign the Hostname
- Disable DNS lookup.
- Create a banner stating "Configured by Briseno."
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console and vty password.
- Enable Telnet access only on VTY line.
- Encrypt all clear text passwords in current running configuration.
- Configure, name, and assign VLANs.
- Configure trunking.
- Set the default gateway with VLAN 99
- Configure Port Security
- Interface F0/1 only allow PC-B
- Configure Port Security on all other ports.
- DO NOT APPLY TO TRUNK INTERFACES
- Set maximum allowed MAC addresses to 3.
- Disable all unused interfaces.

Scarlet

- Assign the Hostname
- Disable DNS lookup.
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console and vty password.
- Enable Telnet access only on VTY line.
- Encrypt all clear text passwords in current running configuration.
- Set clock to current time.
- Create a banner stating "Configured by Briseno."
- Configure, name, and assign VLANs.
- Configure trunking.
- Set the default gateway with VLAN 99
- Configure all ports assigned to VLANs as access ports.
- Configure Port Security o Interface F0/1 only allow PC-A

- Configure Port Security on all other ports:
- DO NOT APPLY TO TRUNK INTERFACES
- o Set maximum allowed MAC addresses to three
- Disable all unused interfaces.

Purple

- Assign the Hostname
- Disable DNS lookup.
- Create a banner stating "Configured by Briseno."
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console and vty password.
- Enable Telnet access only on VTY line.
- Encrypt all clear text passwords in current running configuration.
- Configure, name, and assign VLANs.
- Configure trunking.
- Set the default gateway with VLAN 99
- Configure Port Security
- Interface F0/1 only allow PC-C
- Configure Port Security on all other ports.
- DO NOT APPLY TO TRUNK INTERFACES
- Set maximum allowed MAC addresses to 3.
- Disable all unused interfaces.

Green

- Assign the Hostname
- Disable DNS lookup.
- Create a banner stating "Configured by Briseno."
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console and vty password.
- Enable Telnet access only on VTY line.
- Encrypt all clear text passwords in current running configuration.
- Configure, name, and assign VLANs.
- Configure trunking.
- Set the default gateway with VLAN 99

- Configure Port Security
- Interface F0/1 only allow PC-D
- Configure Port Security on all other ports.
- DO NOT APPLY TO TRUNK INTERFACES
- Set maximum allowed MAC addresses to 3.
- Disable all unused interfaces.

Brown

- Assign the Hostname
- Disable DNS lookup.
- Create a banner stating "Configured by Briseno."
- Assign class as the Encrypted privileged EXEC mode password.
- Assign cisco as the console and vty password.
- Enable Telnet access only on VTY line.
- Encrypt all clear text passwords in current running configuration.
- Configure, name, and assign VLANs.
- Configure trunking.
- Set the default gateway with VLAN 99
- Configure Port Security
- Interface F0/1 only allow PC-E
- Configure Port Security on all other ports.
- DO NOT APPLY TO TRUNK INTERFACES
- Set maximum allowed MAC addresses to 3.
- Disable all unused interfaces.