MATLAB code for a distortion measure based on human auditory masking

Dimme de Groot ver0.0-Draft

May 15, 2024

Abstract

This report provides a short overview on the distortion measure implemented in the MATLAB code provided on this GitHub project. Effectively, the code represents my interpretation of the work presented by Van de Par et al. in $[1]^1$. The distortion measure is used to estimate if a human observer can notice an acoustic distortion in the presence of some other acoustic signal. The major advantage of the implemented distortion measure is that it is computationally inexpensive and can be represented as a weighted l_2 norm on the distortion for a fixed masker.

1 Introduction

The distortion measure implemented on this GitHub was introduced by Van de Par et al. in [1] and will hereafter be referred to as the Par-measure. The measure predicts if a human can detect an acoustic disturbance ϵ in the presence of a different acoustic signal s. Signal s is called the masker, since it influences the audibility of the disturbance². Let's illustrate this with a simple example.

Suppose I am playing a piece of music which ideally is given by signal s. However, my washing machine is making some noise in the background so I do not hear s but I hear the noisy audio \hat{s} . The difference $\epsilon = \hat{s} - s$ is the disturbance and would, in this example, be the noise of the washing machine. The Par-measure would take the disturbance ϵ and the received signal (the masker) \hat{s} and compute the perceived distortion as a single number d. Mathematically, this is

$$D(\hat{s}, \epsilon) = d,\tag{1}$$

where $D(\cdot)$ represents the Par-measure. If d > 1, it is predicted that I can hear the difference between my original music s and what I actually hear \hat{s} . If $d \leq 1$, the Par-measure thinks that I can not notice the difference between the two. That is, I do not notice the washing machine! But how does this work?

In the following, I first describe the basic auditory model employed in the Par-measure and than give the equations resulting in the actual distortion measure D. After this, the functions in the code are briefly explained and an example in which the Par-measure is used to increase the loudness of acoustic signals is given. This example is based on [2]. I want to stress that none

 $^{^1{\}rm The\ article\ is\ an\ open\ access\ article, see\ https://link.springer.com/content/pdf/10.1155/ASP.2005.1292.pdf}$

²It should be mentioned that the Par-measure was developed for sinusoidal audio coding. So, "officially" it expects the distortions to be sinusoids. In my experience, it works quite well even for more complex distortions.

of the theoretical work given below is my own, so I tried to be complete in giving the references. Additionally, the content of this small report is mostly adapted from my master's thesis³.

2 Auditory Model

The Par-measure is based on a very simple model of the human auditory system. The effect of the outer- and middle-ear is modelled by the inverse of the threshold in quiet⁴ h_{om} . The effect of the inner-ear (cochlea) is modelled by a gammatone filterbank consisting of N_g filters $h_1, h_2, \ldots, h_{N_g}$. Lastly, the inability of humans to detect very soft tones is modelled by adding a constant c_1 , which can be interpreted as the internal noise of the hearing system. The model is illustrated in Fig. 1.




Figure 1: The model of the human hearing system used in the Par-measure. From left to right, we have an audio signal s which arrives at the ear of the listener. The outer-and middle-ear filter this signal by with a time-domain filter $h_{\rm om}$. The inner-ear is modelled by a gammatone filterbank consisting of N_g time-domain filters $h_1, h_2, \ldots, h_{N_g}$. Lastly, the constant c_1 is added and models the inability of humans to hear very soft tones. The * represents the convolution operator.

In sections 2.1 and 2.2 the expressions for the frequency-domain outer- and middle-ear filter \hat{h}_{om} and for the frequency domain gammatone filter \hat{h}_g with $g \in \{1, 2, \dots, N_g\}$ are given. The hat on top of the symbols simply indicates that we are in the frequency domain instead of in the time domain. In Section 2.3, the full equation defining the Par-measure is given and Fig. 2b of [1] is recreated.

2.1 The outer- and middle-ear filter

The first filter used in the Par-measure is referred to as the outer- and middle-ear filter. In my opinion, this is a bit of a weird name, since in practice the filter is taken to be the inverse of the threshold in quiet. The threshold in quiet, measured in dB SPL (sound pressure level), can be approximated as [4, Eq. (1)]

$$T_q(f) = 3.64 \left(\frac{f}{1000}\right)^{-0.8} - 6.5 \exp\left\{-0.6 \left(\frac{f}{1000} - 3.3\right)^2\right\} + 10^{-3} \left(\frac{f}{1000}\right)^4 \quad [\text{dB SPL}] \quad (2)$$

with f the frequency in hertz, which for human hearing ranges from about 20 Hz to 20 kHz⁵. There is a problem here! Namely, we need to work with digital presentations of the audio

 $^{{}^3{\}rm Accessible\ from\ http://resolver.tudelft.nl/uuid:ee669571-b15a-4f0d-99cd-4c6c35acbd45}$

⁴The threshold in quiet is a curve showing what is the minimum sound pressure that is needed for a human to be able to detect a given tone when there is no sound otherwise. See Chapter 2 of [3].

⁵I'm not entirely sure what is the frequency range of the measurements on which this curve was fitted. Anyway, it is likely correct at least approximately over the mentioned range and simply gives very large values outside that range, which is also fine!

signals, but human hearing is based on a physical representation: the sound pressure level. To circumvent this, I assume to know that a certain value in the digital domain (say s=1) corresponds to a sound pressure level of a certain amount, say $s_{\rm SPL}=70$ dB SPL. We can than compute a constant $\frac{\alpha}{p_0}$ which allows to map the digital number to a physical sound pressure level. This is explained in more detail in Appendix A. For now, it suffices to note that

$$s_{\rm SPL} = 20 \log_{10} \left(\frac{\alpha}{p_0} |s| \right) \quad [\text{dB SPL}],$$
 (3)

which allows to compute the frequency-domain outer- and middle-ear filter as

$$\hat{h}_{\text{om}}(f) = \left(\frac{\alpha}{p_0}\right)^{-1} 10^{-T_q(f)/20}.$$
(4)

Note that a hat was added on top of $h_{\rm om}$. This hat represents frequency domain variables and will be used to distinguish between variables when there is both a time- and frequency domain version of them.

2.2 The Gammatone filterbank

The inner-ear filter used in the Par-measure is a gammatone filterbank⁶ consisting of N_g filters. The magnitude spectrum of a gammatone filter centered at frequency f_g (in Hz) is approximated as [1, Eq. 2],

$$\hat{h}_g(f) = \left(1 + \left(\frac{f - f_g}{\kappa \text{ERB}(f_g)}\right)^2\right)^{-\eta/2},\tag{5}$$

with $g \in \{1, 2, ..., N_g\}$. In the equation, κ is a normalising constant, η is the order of the filter and $ERB(f_g)$ is the equivalent rectangular bandwidth⁷ of the gammatone filter centered at f_g (see (7)). The filter order is assumed to be $\eta = 4$ [1]. The corresponding normalising constant is given by

$$\kappa = \frac{2^{\eta - 1}(\eta - 1)!}{\pi (2\eta - 3)!!} \tag{6}$$

with! the factorial and!! the double factorial. The double factorial n!! equals $2 \cdot 4 \cdot \ldots \cdot n$ for even positive numbers n, and $1 \cdot 3 \cdot 5 \cdot \ldots \cdot n$ for odd positive numbers n. Lastly, the value $ERB(f_g)$ is approximated using [5]

$$ERB(f_g) = 24.7 \left(\frac{4.37 f_g}{1000} + 1 \right). \tag{7}$$

Par et al. choose the N_g center frequencies f_g such that they linearly divide the ERB-rate scale⁸ on the interval $[E(0), E(f_s/2)]$ in N_g steps [1]. Here, f_s is the sampling frequency. The ERB-rate scale is approximated as [5]

$$E(f_g) = 21.4 \log_{10} \left(\frac{4.37 f_g}{1000} + 1 \right). \tag{8}$$

⁶A filterbank is just a bunch of filters placed in parallel. The gammatone filterbank is often used as a simple model for the cochlea (the "snailhouse" in your ear).

⁷The Equivalent Rectangular Bandwidth (ERB) of some reference filter is the bandwidth of a rectangular filter which has the same maximum magnitude as the reference filter and transmits the same power when white noise is given as input [3]. Even though they are not rectangular, auditory filters are often characterised using their ERB. Intuitively, you can interpret ERB(f_g) as the sensitivity of our hearing to distortions at frequencies around f_g : a higher ERB means that our ears are less sensitive.

⁸The ERB-rate scale measures how much ERBs are below a given frequency.

2.3 The distortion measure

We now have expressions for the gammatone filterbank h_g with $g \in \{1, ..., N_g\}$ (Eq. (4)) and for the outer- and middle-ear filter h_{om} (Eq. (5)). Together with Fig. 1, it can be found that the masking power corresponding to filter g and masker s is given by [1, Eq. 3]

$$P_{\text{mask}}^{(g)} = \frac{1}{N} \sum_{f} |\hat{h}_{\text{om}}(f)|^2 |\hat{h}_i(f)|^2 ||\hat{s}(f)|^2 + \frac{1}{N} c_1$$
 (9)

and, similarly, the distortion power corresponding to filter g and disturbance ϵ is given by

$$P_{\text{dist}}^{(g)} = \frac{1}{N} \sum_{f} |\hat{h}_{\text{om}}(f)|^2 |\hat{h}_i(f)|^2 ||\hat{\epsilon}(f)|^2.$$
 (10)

There are three things to note in these equations. Firstly, the value N is the length of a single audio-frame⁹: the Par-measure operates on frames of about 20 to 40 ms, so that for a sample frequency of 16 kHz the frame length ranges from N=320 to N=640. A little bit more information on the framing of audio signals is given in Section B. Secondly, the distortion power does not $P_{\text{dist}}^{(g)}$ does not have the constant c_1 added. This is because c_1 can be considered as part of the masking signal. Thirdly, the summation is over all N frequency bins¹⁰ f.

The distortion $D_q(s,\epsilon)$ per filter g is found as the ratio between (10) and (9). That is

$$D_g(s,\epsilon) = \frac{P_{\text{dist}}^{(g)}}{P_{\text{mask}}^{(g)}} = \frac{\sum_f |\hat{h}_{\text{om}}(f)|^2 |\hat{h}_i(f)|^2 ||\hat{\epsilon}(f)|^2}{\sum_{f_m} |\hat{h}_{\text{om}}(f_m)|^2 |\hat{h}_i(f_m)|^2 ||\hat{s}(f_m)|^2 + c_1},\tag{11}$$

so that the total distortion $D(s,\epsilon)$ is given as

$$D(s,\epsilon) = c_2 \sum_{g=1}^{N_g} D_g(s,\epsilon) = c_2 \sum_{g=1}^{N_g} \frac{\sum_f |\hat{h}_{om}(f)|^2 |\hat{h}_i(f)|^2 ||\hat{\epsilon}(f)|^2}{\sum_{f_m} |\hat{h}_{om}(f_m)|^2 |\hat{h}_i(f_m)|^2 ||\hat{s}(f_m)|^2 + c_1},$$
(12)

where c_2 is a weighting factor which is set to ensure that $D(s, \epsilon) = 1$ when the distortion is just noticeable. The values c_1 and c_2 are set through a calibration procedure, of which I won't go into detail. The calibration is based on the reference value in digital domain s and the corresponding physical sound pressure level $s_{\rm SPL}$. For the calibration, [1] references [6], who proofs that the calibration always converges. However, the proof contains an error, which luckily in practice is not that much of an issue.

With (12) we have a nice but pretty complicated expression for $D(s, \epsilon)$. Let's see if it can be made a bit more simple. Eq. (12) can be rewritten as

$$D(s,\epsilon) = c_2 \sum_{g=1}^{N_g} \sum_{f} |\hat{\epsilon}(f)|^2 \frac{|\hat{h}_{om}(f)|^2 |\hat{h}_{i}(f)|^2}{\sum_{f_m} |\hat{h}_{om}(f_m)|^2 |\hat{h}_{i}(f_m)|^2 |\hat{s}(f_m)|^2 + c_1}$$

$$= \sum_{f} |\hat{\epsilon}(f)|^2 c_2 \sum_{g=1}^{N_g} \frac{|\hat{h}_{om}(f)|^2 |\hat{h}_{i}(f)|^2}{\sum_{f_m} |\hat{h}_{om}(f_m)|^2 |\hat{h}_{i}(f_m)|^2 |\hat{s}(f_m)|^2 + c_1},$$
(13)

⁹The reason that this N shows up in the equations is due to a property of the discrete Fourier transform, which is typically defined such that $||\hat{s}||^2 = N||s||^2$. I.e. if we want the discrete time-domain and discrete frequency-domain signals to have equal power, there needs to be a correction by dividing by the signal length N. See https://en.wikipedia.org/wiki/Parseval%27s_theorem

¹⁰A frequency bin is similar to a 'normal' frequency but for discrete signals. Since the signal is discrete, there is only a finite number of frequencies which are not connected. A single frequency bin thus represents a small range of frequencies, which is why it is called a frequency bin.

which still looks pretty complicated! However, note that the right summation (including c_2) is only dependent on the masker s and not on the disturbance ϵ . It follows that we may write

$$D(s,\epsilon) = \sum_{f} \frac{|\hat{\epsilon}(f)|^2}{(v(f))^2},\tag{14}$$

where $\frac{1}{(v(f))^2}$ is given by

$$\frac{1}{(v(f))^2} = c_2 \sum_{g=1}^{N_g} \frac{|\hat{h}_{om}(f)|^2 |\hat{h}_i(f)|^2}{\sum_{f_m} |\hat{h}_{om}(f_m)|^2 |\hat{h}_i(f_m)|^2 ||\hat{s}(f_m)|^2 + c_1}.$$
(15)

which can be computed based on the masker s only! Thus, if the masker remains constant, we can evaluate a lot of distortions without having to recompute (15) all the time. In fact, [1] shows that $(v(f))^2$ estimates the masking curve for sinusoidal distortions. A sinusoidal acoustic distortion can be considered inaudible if it lies below the masking curve. In Fig. 2, an example masking curve is shown where the masker is a sinusoid at a frequency of 1 kHz and with a sound pressure level of 50 dB SPL. This figure reproduces Fig. 2b of [1].




Figure 2: The estimated masking curve $(v(f))^2$ for a 1 kHz 50 dB SPL. Note that the masking curve is only affected in the frequency range around the masker and reduces to the threshold in quiet at all other frequencies. All sinusoidal distortions which lie below the dashed red line can be considered inaudible. This figure reproduces Fig. 2b of [1].

This finalises background of the Par-measure. In the next section, the MATLAB code is discussed briefly.

3 The MATLAB Par-measure object

The Par-measure is implemented as a MATLAB object and constructed by calling par_measure (Fs, Tframe, x_ref, x_dB_ref, F_cal, Ng). Here, F_s is the sampling frequency, Tframe the length of a single frame in seconds, x_ref the reference value in the digital domain, x_dB_ref the corresponding value in dB SPL, F_cal the frequency at which the Par-measure is calibrated (i.e. for which the constants c_1 and c_2 are calculated) and N_g is the number of gammatone filters in the gammatone filterbank. A typical input is

The value x_dB_ref = 65 dB SPL was taken because this is a typical value in conversational speech [3]. For N_g, 32 or 64 are typical values. For Fs, 48000, 44100, 16000 and 8000 are typical values. For Tframe, anything from 20 to 40 ms is typical. For F_cal, 1000 Hz is the typical value. Please not that, for most parameters, I did not test a wide range of values. In case you notice any issues, feel free to leave a comment (or whatever it is called) in the GitHub. The object Par_measure comes with a few functions, which are listed below.

Firstly, to plot the masking curve (i.e. a figure which is similar to Fig. 2), you can use Par_measure.plot_maskcurve(masker), where masker is the discrete time-domain masker of the proper length (i.e. of length Tframe. When you create the object, the expected length of the masker is printed in the MATLAB command window! In case you also want to plot the disturbance, you can use Par_measure.plot_maskcurve(masker, disturbance).

Secondly, to convert from a physical sound pressure level in dB SPL to the digital amplitude, you can use A_digital = Par_measure.physical_to_digital(A_physical). There is also the inverse function A_physical = Par_measure.digital_to_physical(A_digital).

Lastly, to obtain the masking curve $(v(f))^2$ (see (15)) you can use [maskcurve, maskcurve_spl, p_par] = Par_measure.comp_maskcurve(masker). Here, masker is again the discrete time-domain masker with a length Tframe. Up to some normalisations, maskcurve represents v(f) and p_par represents 1/v(f). Here, f are frequency bins ranging from $f = -f_s/2$ to $f = f_s/2$. Variable maskcurve_spl is simply the masking curve v(f) expressed in dB SPL and has a frequency ranging from f = 0 to $f = f_s/2$. Note that f_s is the sample frequency.

4 Examples

On the GitHub, I added two example files. The first file, example1_basics.m, shows most of the functionality mentioned above. In my opinion, this is not a very interesting example, as you don't really see how the Par-measure can be used. In the second example, the loudness of acoustic signals is increased by making use of the Par-measure. This example is based entirely on the work of Jeannerot et al. [2] and clearly shows why measuring distortion based on human perception is useful. To run this example you need CVX¹¹, which is a free MATLAB package with which you can do a lot of cool stuff (solving convex optimisation problems, you might find it boring...). The example is described in detail in the following subsection.

4.1 Example 2: loudness increase of acoustic signals

Describe example

¹¹At the time of writing CVX is available from https://cvxr.com

A The sound pressure level

The Sound Pressure Level (SPL) gives the intensity of an acoustic stimuli with respect to a reference value. It is given by

$$L_{\rm SPL} = 20 \log_{10} \left(\frac{p}{p_0} \right) \quad [\text{dB SPL}], \tag{16}$$

with p the absolute sound pressure in Pascals and p_0 a reference value equal to $20 \mu Pa$ [7].

To determine $L_{\rm SPL}$, one needs to have access to the sound pressure p. In most applications, this value is not straightforwardly known since only a digital representation x is available. However, a false but, in my experience, satisfactory assumptions is to assume the sound pressure level to be a linear function of the input signal, i.e. $p = \alpha |x|$. Thus, we can write (16) as

$$L_{\rm SPL} = 20 \log_{10} \left(\frac{\alpha |x|}{p_0} \right) = 20 \log_{10} (|x|) + 20 \log_{10} \left(\frac{\alpha}{p_0} \right) \quad [\text{dB SPL}]$$
 (17)

where α depends on environmental factors such as the loudspeaker, cables, amplifier, and room.

To find α , prior information on the sound level needs to be available or an estimate needs to be made. To be specific, let us have access to a value $|x| = x_{\text{ref}}$ for which the received sound pressure level is $x_{\text{dB, ref}}$ (in dB SPL). Substituting this into (17) yields

$$20\log_{10}\left(\frac{\alpha}{p_0}\right) = x_{\text{dB,ref}} - 20\log_{10}\left(x_{\text{ref}}\right),\tag{18}$$

which can straightforwardly be solved for α (or $\frac{\alpha}{p_0}).$

As an example, consider a normalised digital representation, so $\max(|x|) = 1$. Suppose that this corresponds to 70 dB SPL. Solving (18) results in $\alpha = 0.0632$, or, equivalently, $\alpha/p_0 \approx 3162$. Once α is available, it is straightforward to find the amplitude corresponding to a different sound pressure level and vice versa using

$$L_{\text{SPL}} = 20\log_{10}(|x|) + 20\log_{10}\left(\frac{\alpha}{p_0}\right) \Leftrightarrow |x| = \left(\frac{\alpha}{p_0}\right)^{-1} 10^{\frac{L_{\text{SPL}}}{20}} \tag{19}$$

For this example, the value $A_{70}=1$ and $A_{52}\approx 0.1259$. The value $A_{\rm Tq}(f_m)$ is slightly more involved. For $f_m=1000$ Hz, $T_q(f_m)\approx 3.37$ dB SPL. Thus, $A_{\rm Tq}(f_m)\approx 0.466\times 10^{-3}$.

B The framing of audio signals

First of all, there are probably a lot of sources who explain this a lot better than me (for example [8]), but for the sake of completeness, below is a small section which explains the framing of audio signals. Framing is often done in signal processing applications since audio signals can be arbitrary long and since some statistical properties are only present in short frames. Similarly, the Par-measure operates on frames of about 20 to 40 ms.

Consider an audio signal x, this signal could, for example, be a music or speech signal. Let's take Europapa by Joost Klein as an example 12 . If it is sampled at 48 kHz (i.e. 48000 samples per second), we have a total of $221 \times 48000 = 10608000$ samples, which is a lot! The individual samples are referred to as x[n], with $n = 0, 1, \ldots, 10608000 - 1$. The -1 is because I started counting at zero. Because x consists of so many samples, we want to do the processing in frames.

¹²https://www.youtube.com/watch?v=gT2wY0DjYGo

Let's take a frame of 20 ms. This corresponds to frames of length L = 960 samples. Let's call the first frame s_1 , the second frame s_2 , etc. If we take frames without overlap, the frames are given by

$$s_{1}[n] = \begin{cases} x[n] & \text{for } n = 0, 1, \dots 959 \\ 0 & \text{otherwise} \end{cases}$$

$$s_{2}[n] = \begin{cases} x[n] & \text{for } n = 960, 961, \dots 1919 \\ 0 & \text{otherwise} \end{cases}$$

$$s_{3}[n] = \begin{cases} x[n] & \text{for } n = 1920, 1921, \dots 2879 \\ 0 & \text{otherwise} \end{cases}$$

$$(20)$$

and so on and so forth.

Using frame index l, we may write this a bit more compact as

$$s_l[n] = \begin{cases} x[n] & \text{for } n = lL, lL+1, \dots, lL+L-1 \\ 0 & \text{otherwise.} \end{cases}$$
 (21)

Note that we can recover x from the individual frames by simply summing over them

$$x[n] = \sum_{l} s_{l}[n]. \tag{22}$$

In practice, the frames are chosen to have some overlap. The amount of overlap is defined by the "hop length" $R \leq L$. Let us consider a hop length R = 480. Eq. (20) becomes

$$s_{1}[n] = \begin{cases} x[n] & \text{for } n = 0, 1, \dots 959 \\ 0 & \text{otherwise} \end{cases}$$

$$s_{2}[n] = \begin{cases} x[n] & \text{for } n = 480, 481, \dots 1439 \\ 0 & \text{otherwise} \end{cases}$$

$$s_{3}[n] = \begin{cases} x[n] & \text{for } n = 960, 961, \dots 1919 \\ 0 & \text{otherwise} \end{cases}$$

$$(23)$$

and so on and so forth.

We may again write this more compact as

$$s_l[n] = \begin{cases} x[n] & \text{for } n = lR, lR + 1, \dots, lR + L - 1\\ 0 & \text{otherwise.} \end{cases}$$
 (24)

Note that we lost the property that the frames sum to x[n], i.e.

$$x[n] \neq \sum_{l} s_{l}[n], \tag{25}$$

for this reason, the signals are often multiplied with a window $w_1[n]$ which has a nonzero value for $n \in \{0, 1, ..., L-1\}$ and is zero outside this range. Using this window in (24) gives

$$s_l[n] = \begin{cases} w_1[n-lR]x[n] & \text{for } n = lR, lR+1, \dots, lR+L-1 \\ 0 & \text{otherwise,} \end{cases}$$
 (26)

where the shift by -lR is to shift the support of the window¹³ to the correct set of samples. Note that, since the window is zero outside its support, (26) simplifies to

$$s_l[n] = w_1[n - lR]x[n]$$
 for $n = lR, lR + 1, \dots, lR + L - 1.$ (27)

We now have that

$$x[n] = \sum_{l} s_{l}[n] \tag{28}$$

if

$$\sum_{l} w_1[n - lR] = 1 \quad \text{for all } n.$$
(29)

Eq. (29) is known as the constant overlap add condition. Recall that n are integers. To see that (29) is important, let us rewrite (28) using (27). This gives

$$x[n] = \sum_{l} s_{l}[n] = \sum_{l} w_{1}[n - lR]x[n] = x[n] \sum_{l} w_{1}[n - lR],$$
(30)

so if $\sum_l w_1[n-lR] = 1$, we indeed get that the frames sum to x[n] again! This might all look kind of complicated, so let's have a look at what the frames look like in a simple example shown in Fig. 3. In this example, a so called "Hanning" window is used with a length L = 20 and a hop length of R = 10. The windows $w_1[n-lR]$ are plotted for l = 0 up to and including l = 9. The sum of the windows is plotted as well. Note that the constant overlap add condition is




Figure 3: An illustration of a window satisfying the constant overlap add condition with a length of L=20 and a hop length R=10. The window is a Hanning window. The colored lines are the individual frames and the black line is the sum of the frames.

satisfied everywhere apart from at the boundaries. This is typically not a problem, since at the boundaries the audio signal is typically very soft. The Hanning window of length L is given by [8]

$$\operatorname{hann}_{L}(n) = \begin{cases} \frac{1}{2} + \frac{1}{2} \cos\left(\frac{2\pi}{L} \left(n - \frac{L}{2}\right)\right) & \text{for } n = 0, 1, \dots, L - 1\\ 0 & \text{otherwise.} \end{cases}$$
(31)

 $^{^{13}}$ The support of the window is the range of n where the window its value is nonzero.

As a final note, when doing nonlinear processing on the frames, it is often better to also use a window when gluing the frames back together. I.e.

$$x[n] = \sum_{l} w_2[n - lR]s_l[n]. \tag{32}$$

In this case, the constant overlap add condition (Eq. (29)) becomes

$$\sum_{l} w_2[n - lR]w_1[n - lR] = 1 \quad \text{for all } n.$$
 (33)

A simple example of a set of windows for which this holds is the square root Hanning window, i.e.

$$w_1[n] = w_2[n] = \sqrt{\operatorname{hann}_L[n]} \tag{34}$$

with an overlap R = L/2. Note that this assumes the windows have even length L.

References

- [1] S. van de Par, A. Kohlrausch, R. Heusdens, J. Jensen, and S. H. Jensen, "A Perceptual Model for Sinusoidal Audio Coding Based on Spectral Integration," *EURASIP Journal on Advances in Signal Processing*, vol. 2005, p. 317529, June 2005.
- [2] A. Jeannerot, N. de Koeijer, P. Martínez-Nuevo, M. B. Møller, J. Dyreby, and P. Prandoni, "Increasing loudness in audio signals: A perceptually motivated approach to preserve audio quality," in *ICASSP 2022 2022 IEEE International Conference on Acoustics, Speech and Signal Processing (ICASSP)*, pp. 1001–1005, 2022.
- [3] B. Moore, An Introduction to the Psychology of Hearing: Sixth Edition. Leiden, The Netherlands: Brill, 2013.
- [4] E. Terhardt, "Calculating virtual pitch," Hear Res, vol. 1, pp. 155–182, Mar. 1979.
- [5] B. R. Glasberg and B. C. Moore, "Derivation of auditory filter shapes from notched-noise data," *Hearing Research*, vol. 47, no. 1, pp. 103–138, 1990.
- [6] G. Charestan, R. Heusdens, and S. van de Par, "A gammatone-based psychoacoustical modeling approach for speech and audio coding," in SAFE ProRISC SeSens 2001: proceedings. Semiconductor Advances for Future Electronics Program for Research on Integrated Systems and Circuits Semiconductor Sensor and Actuator Technology, pp. 321–326, STW Technology Foundation, 2001.
- [7] T. Painter and A. Spanias, "Perceptual coding of digital audio," *Proceedings of the IEEE*, vol. 88, no. 4, pp. 451–515, 2000.
- [8] J. O. Smith, Spectral Audio Signal Processing. http://ccrma.stanford.edu/~jos/sasp/, accessed 03-03-2023. online book, 2011 edition.