## Bits, Bytes, and Integers


15-213: Introduction to Computer Systems 2<sup>nd</sup> and 3<sup>rd</sup> Lectures, Sep. 3 and Sep. 8, 2015

# Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings

# **Everything is bits**

- Each bit is 0 or 1
- By encoding/interpreting sets of bits in various ways
  - Computers determine what to do (instructions)
  - ... and represent and manipulate numbers, sets, strings, etc...
- Why bits? Electronic Implementation
  - Easy to store with bistable elements
  - Reliably transmitted on noisy and inaccurate wires



## For example, can count in binary

## Base 2 Number Representation

- Represent 15213<sub>10</sub> as 11101101101101<sub>2</sub>
- Represent 1.20<sub>10</sub> as 1.0011001100110011[0011]...<sub>2</sub>
- Represent 1.5213 X 10<sup>4</sup> as 1.1101101101101<sub>2</sub> X 2<sup>13</sup>

# **Encoding Byte Values**

- Byte = 8 bits
  - Binary 000000002 to 111111112
  - Decimal: 010 to 25510
  - Hexadecimal 00<sub>16</sub> to FF<sub>16</sub>
    - Base 16 number representation
    - Use characters '0' to '9' and 'A' to 'F'
    - Write FA1D37B<sub>16</sub> in C as
      - 0xFA1D37B
      - 0xfa1d37b

الم	۱ .	in ary
He	, De,	Binary
0	0	0000
1	1 2 3 4 5 6 7	0001
2	2	0010
3	3	0011
4	4	0100
5	5	0101
6	6	0110
7	7	0111
8	8	1000
9	9	1001
А	10	1010
В	11	1011
С	12	1100
0 1 2 3 4 5 6 7 8 9 A B C	13	1101
E F	14	1110
F	15	1111

# **Example Data Representations**

C Data Type	Typical 32-bit	Typical 64-bit	x86-64
char	1	1	1
short	2	2	2
int	4	4	4
long	4	8	8
float	4	4	4
double	8	8	8
long double	-	-	10/16
pointer	4	8	8

# Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings

# **Boolean Algebra**

## Developed by George Boole in 19th Century

- Algebraic representation of logic
  - Encode "True" as 1 and "False" as 0

And

Or

■ A&B = 1 when both A=1 and B=1

<b>■</b> A	B = 1	when	either	Δ=1	or B=	1
	1 D — I	VVIICII	CILICI	$\neg$	OI D-	_

&	0	1
0	0	0
1	0	1

ı	0	1
0	0	1
1	1	1

Not

Exclusive-Or (Xor)

■ ~A = 1 when A=0

■ A^B = 1 when either A=1 or B=1, but not both

~	
0	1
1	0

٨	0	1
0	0	1
1	1	0

## **General Boolean Algebras**

- Operate on Bit Vectors
  - Operations applied bitwise

```
01101001 01101001 01101001

& 01010101 | 01010101 ^ 01010101 ~ 01010101

01000001 01111101 00111100 1010101
```

All of the Properties of Boolean Algebra Apply

# **Example: Representing & Manipulating Sets**

#### Representation

- Width w bit vector represents subsets of {0, ..., w-1}
- $a_j = 1$  if  $j \in A$ 
  - 01101001 { 0, 3, 5, 6 }
  - **76543210**
  - 01010101 { 0, 2, 4, 6 }
  - **76543210**

## Operations

<b>-</b> &	Intersection	01000001	{ 0, 6 }
•	Union	01111101	{ 0, 2, 3, 4, 5, 6 }
^	Symmetric difference	00111100	{ 2, 3, 4, 5 }
■ ~	Complement	10101010	{ 1, 3, 5, 7 }

## **Bit-Level Operations in C**

- Operations &, |, ~, ^ Available in C
  - Apply to any "integral" data type
    - long, int, short, char, unsigned
  - View arguments as bit vectors
  - Arguments applied bit-wise

## Examples (Char data type)

- ~Ox41 → OxBE
  - ~010000012 → 101111102
- ~OXOO → OXFF
  - ~000000002 → 1111111112
- Ox69 & Ox55 → Ox41
  - 011010012 & 010101012 → 010000012
- 0x69 | 0x55 → 0x7D
  - 011010012 | 010101012 → 011111012

## **Contrast: Logic Operations in C**

## Contrast to Logical Operators

- **■** &&, ||, !
  - View 0 as "False"
  - Anything nonzero as "True"
  - Always return 0 or 1
  - Early termination

## Examples (char data type)

- !Ox41 → Ox00
- !OXOO → OXO1
- !!Ox41 → Ox01
- Ox69 && Ox55 → Ox01
- 0x69 | 0x55 → 0x01
- p && \*p (avoids null pointer access)

## **Contrast: Logic Operations in C**

- Contrast to Logical Operators
  - &&, ||, !
    - View 0 as "Fall
    - Anything ponzo
    - Alway
    - Early
- Example
  - !0x41
  - !OxOO
  - !!Ox41

Watch out for && vs. & (and || vs. |)...
one of the more common oopsies in
C programming

- Ox69 && Ox55 → Ox01
- 0x69 | 0x55 → 0x01
- p && \*p (avoids null pointer access)

# **Shift Operations**

- Left Shift: x << y
  - Shift bit-vector x left y positions
    - Throw away extra bits on left
    - Fill with 0's on right
- Right Shift: x >> y
  - Shift bit-vector x right y positions
    - Throw away extra bits on right
  - Logical shift
    - Fill with 0's on left
  - Arithmetic shift
    - Replicate most significant bit on left
- Undefined Behavior
  - Shift amount < 0 or ≥ word size</p>

Argument x	01100010	
<< 3	00010000	
<b>Log.</b> >> 2	00011000	
<b>Arith.</b> >> 2	00011000	

Argument x	10100010
<< 3	00010000
<b>Log.</b> >> 2	00101000
<b>Arith.</b> >> 2	11101000

# Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings
- Summary

## **Encoding Integers**

## **Unsigned**

$$B2U(X) = \sum_{i=0}^{w-1} x_i \cdot 2^i$$

## Two's Complement

$$B2T(X) = -x_{w-1} \cdot 2^{w-1} + \sum_{i=0}^{w-2} x_i \cdot 2^i$$

## Sign Bit

## C short 2 bytes long

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
У	-15213	C4 93	11000100 10010011

## Sign Bit

- For 2's complement, most significant bit indicates sign
  - 0 for nonnegative
  - 1 for negative

# **Two-complement Encoding Example (Cont.)**

x = 15213: 00111011 01101101y = -15213: 11000100 10010011

Weight	152	.13	-152	213
1	1	1	1	1
2	0	0	1	2
4	1	4	0	0
8	1	8	0	0
16	0	0	1	16
32	1	32	0	0
64	1	64	0	0
128	0	0	1	128
256	1	256	0	0
512	1	512	0	0
1024	0	0	1	1024
2048	1	2048	0	0
4096	1	4096	0	0
8192	1	8192	0	0
16384	0	0	1	16384
-32768	0	0	1	-32768

## **Numeric Ranges**

#### Unsigned Values

$$UMax = 2^w - 1$$

$$111...1$$

#### **■ Two's Complement Values**

■ 
$$TMin = -2^{w-1}$$
100...0

TMax = 
$$2^{w-1} - 1$$
  
011...1

#### Other Values

Minus 1111...1

#### Values for W = 16

	Decimal	Hex	Binary
UMax	65535	FF FF	11111111 11111111
TMax	32767	7F FF	01111111 11111111
TMin	-32768	80 00	10000000 00000000
-1	-1	FF FF	11111111 11111111
0	0	00 00	00000000 00000000

## Values for Different Word Sizes

	W			
	8	16	32	64
UMax	255	65,535	4,294,967,295	18,446,744,073,709,551,615
TMax	127	32,767	2,147,483,647	9,223,372,036,854,775,807
TMin	-128	-32,768	-2,147,483,648	-9,223,372,036,854,775,808

#### Observations

- $\blacksquare$  | TMin | = TMax + 1
  - Asymmetric range
- UMax = 2 \* TMax + 1

## C Programming

- #include <limits.h>
- Declares constants, e.g.,
  - ULONG\_MAX
  - LONG\_MAX
  - LONG\_MIN
- Values platform specific

## **Unsigned & Signed Numeric Values**

Χ	B2U( <i>X</i> )	B2T( <i>X</i> )
0000	0	0
0001	1	1
0010	2	2
0011	3	3
0100	4	4
0101	5	5
0110	6	6
0111	7	7
1000	8	-8
1001	9	<b>-</b> 7
1010	10	-6
1011	11	<b>-</b> 5
1100	12	<b>–</b> 4
1101	13	-3
1110	14	-2
1111	15	-1

## Equivalence

Same encodings for nonnegative values

### Uniqueness

- Every bit pattern represents unique integer value
- Each representable integer has unique bit encoding


## ■ ⇒ Can Invert Mappings

- $U2B(x) = B2U^{-1}(x)$ 
  - Bit pattern for unsigned integer
- $T2B(x) = B2T^{-1}(x)$ 
  - Bit pattern for two's comp integer

# Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings

# **Mapping Between Signed & Unsigned**




Mappings between unsigned and two's complement numbers: Keep bit representations and reinterpret

# Mapping Signed ↔ Unsigned

Bits
0000
0001
0010
0011
0100
0101
0110
0111
1000
1001
1010
1011
1100
1101
1110
1111

Signed
0
1
2
3
4
5
6
7
-8
-7
-6
<b>-</b> 5
-4
-3
-2
-1




Unsigned	
0	
1	
2	
3	
4	
5	
6	
7	
8	
9	
10	
11	
12	
13	
14	
15	

# Mapping Signed ↔ Unsigned


Bits
0000
0001
0010
0011
0100
0101
0110
0111
1000
1001
1010
1011
1100
1101
1110
1111


r	
	Signed
	0
	1
	2
	3
	4
	5
	6
	7
	-8
	-7
	-6
	<b>-</b> 5
	-4
	-3
	-2
	-1



ı	<b>Jnsigned</b>
	0
	1
	2
	3
	4
	5
	6
	7
	8
	9
	10
	11
	12
	13
	14
	15

# **Relation between Signed & Unsigned**





Large negative weight becomes

Large positive weight

## **Conversion Visualized**

2's Comp.  $\rightarrow$  Unsigned **UMax Ordering Inversion** UMax - 1Negative  $\rightarrow$  Big Positive TMax + 1Unsigned TMax **TMax** Range 2's Complement Range

## Signed vs. Unsigned in C

#### Constants

- By default are considered to be signed integers
- Unsigned if have "U" as suffixOU, 4294967259U

## Casting

Explicit casting between signed & unsigned same as U2T and T2U

```
int tx, ty;
unsigned ux, uy;
tx = (int) ux;
uy = (unsigned) ty;
```

Implicit casting also occurs via assignments and procedure calls

```
tx = ux;

uy = ty;
```

## **Casting Surprises**

## Expression Evaluation

- If there is a mix of unsigned and signed in single expression, signed values implicitly cast to unsigned
- Including comparison operations <, >, ==, <=, >=
- **Examples for** W = 32: **TMIN = -2,147,483,648**, **TMAX = 2,147,483,647**

■ Constant <sub>1</sub>	Constant <sub>2</sub>	Relation	<b>Evaluation</b>
0	0U	==	unsigned
-1	0	<	signed
-1	OU	>	unsigned
2147483647	-2147483647-1	>	signed
2147483647U	-2147483647-1	<	unsigned
-1	-2	>	signed
(unsigned)-1	-2	>	unsigned
2147483647	2147483648U	<	unsigned
2147483647	(int) 2147483648U	>	signed

# Summary Casting Signed ↔ Unsigned: Basic Rules

- Bit pattern is maintained
- But reinterpreted
- Can have unexpected effects: adding or subtracting 2<sup>w</sup>
- Expression containing signed and unsigned int
  - int is cast to unsigned!!

# Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings


## **Sign Extension**


#### Task:

- Given w-bit signed integer x
- Convert it to w+k-bit integer with same value

#### Rule:

Make k copies of sign bit:





## **Sign Extension Example**

```
short int x = 15213;
int     ix = (int) x;
short int y = -15213;
int     iy = (int) y;
```

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
ix	15213	00 00 3B 6D	00000000 00000000 00111011 01101101
У	-15213	C4 93	11000100 10010011
iy	-15213	FF FF C4 93	11111111 11111111 11000100 10010011

- Converting from smaller to larger integer data type
- C automatically performs sign extension

# **Summary: Expanding, Truncating: Basic Rules**

- Expanding (e.g., short int to int)
  - Unsigned: zeros added
  - Signed: sign extension
  - Both yield expected result
- Truncating (e.g., unsigned to unsigned short)
  - Unsigned/signed: bits are truncated
  - Result reinterpreted
  - Unsigned: mod operation
  - Signed: similar to mod
  - For small numbers yields expected behavior

# Today: Bits, Bytes, and Integers


- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
- Representations in memory, pointers, strings
- Summary

# **Unsigned Addition**

Operands: w bits

u

True Sum: w+1 bits



u + v

Discard Carry: w bits

 $UAdd_{w}(u, v)$ 



- Ignores carry output
- **Implements Modular Arithmetic**


$$s = UAdd_w(u, v) = u + v \mod 2^w$$

# Visualizing (Mathematical) Integer Addition

## Integer Addition

- 4-bit integers u, v
- Compute true sum  $Add_4(u, v)$
- Values increase linearly with u and v
- Forms planar surface

## $Add_4(u, v)$





### **Visualizing Unsigned Addition**

#### Wraps Around

- If true sum  $\ge 2^w$
- At most once

#### **True Sum**





# **Two's Complement Addition**

Operands: w bits

True Sum: w+1 bits

Discard Carry: w bits

u



 $TAdd_{w}(u, v)$ 

#### TAdd and UAdd have Identical Bit-Level Behavior

Signed vs. unsigned addition in C:

```
int s, t, u, v;
s = (int) ((unsigned) u + (unsigned) v);
t = u + v
```


Will give s == t

#### **TAdd Overflow**

#### Functionality

- True sum requires w+1 bits
- Drop off MSB
- Treat remaining bits as 2's comp. integer

#### **True Sum**




## Visualizing 2's Complement Addition

#### Values

- 4-bit two's comp.
- Range from -8 to +7

#### Wraps Around


- If sum  $\geq 2^{w-1}$ 
  - Becomes negative
  - At most once
- If sum  $< -2^{w-1}$ 
  - Becomes positive
  - At most once



### Multiplication

- Goal: Computing Product of w-bit numbers x, y
  - Either signed or unsigned
- But, exact results can be bigger than w bits
  - Unsigned: up to 2w bits
    - Result range:  $0 \le x * y \le (2^w 1)^2 = 2^{2w} 2^{w+1} + 1$
  - Two's complement min (negative): Up to 2w-1 bits
    - Result range:  $x * y \ge (-2^{w-1})*(2^{w-1}-1) = -2^{2w-2} + 2^{w-1}$
  - Two's complement max (positive): Up to 2w bits, but only for  $(TMin_w)^2$ 
    - Result range:  $x * y \le (-2^{w-1})^2 = 2^{2w-2}$
- So, maintaining exact results...
  - would need to keep expanding word size with each product computed
  - is done in software, if needed
    - e.g., by "arbitrary precision" arithmetic packages

# **Unsigned Multiplication in C**



Discara W Sits. W Sits

- Standard Multiplication Function
  - Ignores high order w bits
- Implements Modular Arithmetic

$$UMult_w(u, v) = u \cdot v \mod 2^w$$

# Signed Multiplication in C

O		u			• • •		
Operands: w bits	* v				• • •		
True Product: $2*w$ bits $u \cdot v \square$	• • •				• • •	Ш	]
Discard w bits: w bits	$TMult_{\scriptscriptstyle{w}}(u)$	<i>, v)</i>			• • •	Ш	]

#### Standard Multiplication Function

- Ignores high order w bits
- Some of which are different for signed vs. unsigned multiplication
- Lower bits are the same


k

### Power-of-2 Multiply with Shift

#### **Operation**

- $\mathbf{u} \ll \mathbf{k}$  gives  $\mathbf{u} * \mathbf{2}^k$
- Both signed and unsigned

Operands: w bits




#### **Examples**

- u << 3
- (u << 5) (u << 3) == u \* 24
- Most machines shift and add faster than multiply
  - Compiler generates this code automatically

### **Unsigned Power-of-2 Divide with Shift**

- Quotient of Unsigned by Power of 2
  - $\mathbf{u} \gg \mathbf{k}$  gives  $\left[ \mathbf{u} / 2^k \right]$
  - Uses logical shift



	Division	Computed	Hex	Binary	
x	15213	15213	3B 6D	00111011 01101101	
x >> 1	7606.5	7606	1D B6	00011101 10110110	
x >> 4	950.8125	950	03 в6	00000011 10110110	
x >> 8	59.4257813	59	00 3B	00000000 00111011	

## Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings

#### **Arithmetic: Basic Rules**

#### Addition:

- Unsigned/signed: Normal addition followed by truncate, same operation on bit level
- Unsigned: addition mod 2<sup>w</sup>
  - Mathematical addition + possible subtraction of 2<sup>w</sup>
- Signed: modified addition mod 2<sup>w</sup> (result in proper range)
  - Mathematical addition + possible addition or subtraction of 2<sup>w</sup>

#### Multiplication:

- Unsigned/signed: Normal multiplication followed by truncate, same operation on bit level
- Unsigned: multiplication mod 2<sup>w</sup>
- Signed: modified multiplication mod 2<sup>w</sup> (result in proper range)

## Why Should I Use Unsigned?

- Don't use without understanding implications
  - Easy to make mistakes

```
unsigned i;
for (i = cnt-2; i >= 0; i--)
  a[i] += a[i+1];
```

Can be very subtle

```
#define DELTA sizeof(int)
int i;
for (i = CNT; i-DELTA >= 0; i-= DELTA)
. . . .
```

### **Counting Down with Unsigned**

Proper way to use unsigned as loop index

```
unsigned i;
for (i = cnt-2; i < cnt; i--)
  a[i] += a[i+1];</pre>
```

- See Robert Seacord, Secure Coding in C and C++
  - C Standard guarantees that unsigned addition will behave like modular arithmetic
    - $0-1 \rightarrow UMax$
- Even better

```
size_t i;
for (i = cnt-2; i < cnt; i--)
   a[i] += a[i+1];</pre>
```

- Data type size\_t defined as unsigned value with length = word size
- Code will work even if cnt = UMax
- What if cnt is signed and < 0?</p>


# Why Should I Use Unsigned? (cont.)

- Do Use When Performing Modular Arithmetic
  - Multiprecision arithmetic
- Do Use When Using Bits to Represent Sets
  - Logical right shift, no sign extension

## Today: Bits, Bytes, and Integers

- Representing information as bits
- Bit-level manipulations
- Integers
  - Representation: unsigned and signed
  - Conversion, casting
  - Expanding, truncating
  - Addition, negation, multiplication, shifting
  - Summary
- Representations in memory, pointers, strings

### **Byte-Oriented Memory Organization**



#### Programs refer to data by address

- Conceptually, envision it as a very large array of bytes
  - In reality, it's not, but can think of it that way
- An address is like an index into that array
  - and, a pointer variable stores an address

#### ■ Note: system provides private address spaces to each "process"


- Think of a process as a program being executed
- So, a program can clobber its own data, but not that of others

#### **Machine Words**

- Any given computer has a "Word Size"
  - Nominal size of integer-valued data
    - and of addresses
  - Until recently, most machines used 32 bits (4 bytes) as word size
    - Limits addresses to 4GB (2<sup>32</sup> bytes)
  - Increasingly, machines have 64-bit word size
    - Potentially, could have 18 EB (exabytes) of addressable memory
    - That's 18.4 X 10<sup>18</sup>
    - Machines still support multiple data formats
      - Fractions or multiples of word size
      - Always integral number of bytes

## **Word-Oriented Memory Organization**

- Addresses Specify Byte Locations
  - Address of first byte in word
  - Addresses of successive words differ by 4 (32-bit) or 8 (64-bit)



# **Example Data Representations**

C Data Type	Typical 32-bit	Typical 64-bit	x86-64
char	1	1	1
short	2	2	2
int	4	4	4
long	4	8	8
float	4	4	4
double	8	8	8
long double	-	-	10/16
pointer	4	8	8


## **Byte Ordering**

- So, how are the bytes within a multi-byte word ordered in memory?
- Conventions
  - Big Endian: Sun, PPC Mac, Internet
    - Least significant byte has highest address
  - Little Endian: x86, ARM processors running Android, iOS, and Windows
    - Least significant byte has lowest address

## **Byte Ordering Example**

#### Example

- Variable x has 4-byte value of 0x01234567
- Address given by &x is 0x100




### **Representing Integers**

Decimal: 15213


Binary: 0011 1011 0110 1101

**Hex:** 3 B 6 D


int A = 15213;



int B = -15213;



long int C = 15213;



Two's complement representation

#### **Examining Data Representations**

- Code to Print Byte Representation of Data
  - Casting pointer to unsigned char \* allows treatment as a byte array

```
typedef unsigned char *pointer;

void show_bytes(pointer start, size_t len) {
    size_t i;
    for (i = 0; i < len; i++)
        printf("%p\t0x%.2x\n",start+i, start[i]);
    printf("\n");
}</pre>
```

#### **Printf directives:**

%p: Print pointer

%x: Print Hexadecimal

# show bytes Execution Example

```
int a = 15213;
printf("int a = 15213;\n");
show_bytes((pointer) &a, sizeof(int));
```

#### Result (Linux x86-64):

```
int a = 15213;

0x7fffb7f71dbc 6d


0x7fffb7f71dbd 3b

0x7fffb7f71dbe 00

0x7fffb7f71dbf 00
```

### **Representing Pointers**

int 
$$B = -15213$$
;  
int \*P = &B



Different compilers & machines assign different locations to objects

## **Representing Strings**


char S[6] = "18213";

#### Strings in C

- Represented by array of characters
- Each character encoded in ASCII format
  - Standard 7-bit encoding of character set
  - Character "0" has code 0x30
    - Digit i has code 0x30+i
- String should be null-terminated
  - Final character = 0

#### Compatibility

Byte ordering not an issue




# **Integer C Puzzles**

#### Initialization

#### **Bonus extras**

### **Application of Boolean Algebra**

- Applied to Digital Systems by Claude Shannon
  - 1937 MIT Master's Thesis
  - Reason about networks of relay switches
    - Encode closed switch as 1, open switch as 0



### **Binary Number Property**

#### Claim

$$1 + 1 + 2 + 4 + 8 + \dots + 2^{w-1} = 2^{w}$$
$$1 + \sum_{i=0}^{w-1} 2^{i} = 2^{w}$$

- w = 0:
  - **■** 1 = 2<sup>0</sup>
- Assume true for w-1:

$$1 + 1 + 2 + 4 + 8 + \dots + 2^{w-1} + 2^w = 2^w + 2^w = 2^{w+1}$$

$$= 2^w$$

### **Code Security Example**

```
/* Kernel memory region holding user-accessible data */
#define KSIZE 1024
char kbuf[KSIZE];

/* Copy at most maxlen bytes from kernel region to user buffer */
int copy_from_kernel(void *user_dest, int maxlen) {
    /* Byte count len is minimum of buffer size and maxlen */
    int len = KSIZE < maxlen ? KSIZE : maxlen;
    memcpy(user_dest, kbuf, len);
    return len;
}</pre>
```

- Similar to code found in FreeBSD's implementation of getpeername
- There are legions of smart people trying to find vulnerabilities in programs

## **Typical Usage**

```
/* Kernel memory region holding user-accessible data */
#define KSIZE 1024
char kbuf[KSIZE];

/* Copy at most maxlen bytes from kernel region to user buffer */
int copy_from_kernel(void *user_dest, int maxlen) {
    /* Byte count len is minimum of buffer size and maxlen */
    int len = KSIZE < maxlen ? KSIZE : maxlen;
    memcpy(user_dest, kbuf, len);
    return len;
}</pre>
```

```
#define MSIZE 528

void getstuff() {
    char mybuf[MSIZE];
    copy_from_kernel(mybuf, MSIZE);
    printf("%s\n", mybuf);
}
```

### Malicious Usage /\* Declaration of library function memcpy \*/

```
void *memcpy(void *dest, void *src, size t n);
```

```
/* Kernel memory region holding user-accessible data */
#define KSIZE 1024
char kbuf[KSIZE];
/* Copy at most maxlen bytes from kernel region to user buffer */
int copy from kernel(void *user dest, int maxlen) {
    /* Byte count len is minimum of buffer size and maxlen */
    int len = KSIZE < maxlen ? KSIZE : maxlen;</pre>
   memcpy(user dest, kbuf, len);
   return len;
}
```

```
#define MSIZE 528
void getstuff() {
    char mybuf[MSIZE];
    copy from kernel(mybuf, -MSIZE);
```

### **Mathematical Properties**

#### Modular Addition Forms an Abelian Group

Closed under addition

$$0 \leq \mathsf{UAdd}_{w}(u, v) \leq 2^{w} - 1$$

Commutative

$$UAdd_{w}(u, v) = UAdd_{w}(v, u)$$

Associative

$$UAdd_{w}(t, UAdd_{w}(u, v)) = UAdd_{w}(UAdd_{w}(t, u), v)$$

0 is additive identity

$$UAdd_{w}(u, 0) = u$$

- Every element has additive inverse
  - Let  $UComp_w(u) = 2^w u$  $UAdd_w(u, UComp_w(u)) = 0$

# **Mathematical Properties of TAdd**

#### Isomorphic Group to unsigneds with UAdd

- TAdd<sub>w</sub>(u, v) = U2T(UAdd<sub>w</sub>(T2U(u), T2U(v)))
  - Since both have identical bit patterns

#### Two's Complement Under TAdd Forms a Group


- Closed, Commutative, Associative, 0 is additive identity
- Every element has additive inverse

$$TComp_{w}(u) = \begin{cases} -u & u \neq TMin_{w} \\ TMin_{w} & u = TMin_{w} \end{cases}$$

# **Characterizing TAdd**

#### Functionality

- True sum requires w+1 bits
- Drop off MSB
- Treat remaining bits as 2's comp. integer



$$TAdd_{w}(u,v) = \begin{cases} u+v+2^{w} & u+v < TMin_{w} \text{ (NegOver)} \\ u+v & TMin_{w} \le u+v \le TMax_{w} \\ u+v-2^{w} & TMax_{w} < u+v \text{ (PosOver)} \end{cases}$$

# **Negation: Complement & Increment**

Claim: Following Holds for 2's Complement

$$\sim x + 1 == -x$$

Complement

```
• Observation: \sim x + x == 1111...111 == -1

x = 10011101

+ \sim x = 01100010

-1 = 111111111
```

Complete Proof?

# **Complement & Increment Examples**

$$x = 15213$$

	Decimal	Hex	Binary
x	15213	3B 6D	00111011 01101101
~x	-15214	C4 92	11000100 10010010
~x+1	-15213	C4 93	11000100 10010011
У	-15213	C4 93	11000100 10010011

$$x = 0$$


	Decimal	Hex	Binary
0	0	00 00	0000000 00000000
~0	-1	FF FF	11111111 11111111
~0+1	0	00 00	00000000 00000000

## **Code Security Example #2**

## SUN XDR library

Widely used library for transferring data between machines

```
void* copy_elements(void *ele_src[], int ele_cnt, size_t ele_size);
```



malloc(ele\_cnt \* ele\_size)



## **XDR Code**

```
void* copy elements(void *ele src[], int ele cnt, size t ele size) {
    /*
     * Allocate buffer for ele cnt objects, each of ele size bytes
     * and copy from locations designated by ele src
     */
    void *result = malloc(ele cnt * ele size);
    if (result == NULL)
       /* malloc failed */
       return NULL;
    void *next = result;
    int i;
    for (i = 0; i < ele cnt; i++) {
        /* Copy object i to destination */
        memcpy(next, ele src[i], ele size);
       /* Move pointer to next memory region */
       next += ele size;
    return result;
```

# **XDR Vulnerability**

malloc(ele\_cnt \* ele\_size)

What if:

```
• ele_cnt = 2<sup>20</sup> + 1
• ele_size = 4096 = 2<sup>12</sup>
```

• Allocation = ??

How can I make this function secure?

## **Compiled Multiplication Code**

#### **C** Function

```
long mul12(long x)
{
  return x*12;
}
```

#### **Compiled Arithmetic Operations**

```
leaq (%rax,%rax,2), %rax
salq $2, %rax
```

#### **Explanation**

```
t <- x+x*2
return t << 2;
```

 C compiler automatically generates shift/add code when multiplying by constant

# **Compiled Unsigned Division Code**

#### **C** Function

```
unsigned long udiv8
      (unsigned long x)
{
   return x/8;
}
```

#### **Compiled Arithmetic Operations**

```
shrq $3, %rax
```


#### **Explanation**

```
# Logical shift
return x >> 3;
```

- Uses logical shift for unsigned
- For Java Users
  - Logical shift written as >>>

# Signed Power-of-2 Divide with Shift


- Quotient of Signed by Power of 2
  - $x \gg k$  gives  $\lfloor x / 2^k \rfloor$
  - Uses arithmetic shift
  - Rounds wrong direction when u < 0</li>



	Division	Computed	Hex	Binary
У	-15213	-15213	C4 93	11000100 10010011
y >> 1	-7606.5	-7607	E2 49	<b>1</b> 1100010 01001001
y >> 4	-950.8125	-951	FC 49	11111100 01001001
y >> 8	-59.4257813	-60	FF C4	1111111 11000100

## **Correct Power-of-2 Divide**


- Quotient of Negative Number by Power of 2
  - Want  $\lceil x / 2^k \rceil$  (Round Toward 0)
  - Compute as  $\lfloor (x+2^k-1)/2^k \rfloor$ 
    - In C: (x + (1 << k) -1) >> k
    - Biases dividend toward 0



## Biasing has no effect

# **Correct Power-of-2 Divide (Cont.)**

### **Case 2: Rounding**



Biasing adds 1 to final result

# **Compiled Signed Division Code**

#### **C** Function

```
long idiv8(long x)
{
  return x/8;
}
```

#### **Compiled Arithmetic Operations**

```
testq %rax, %rax
  js L4
L3:
  sarq $3, %rax
  ret
L4:
  addq $7, %rax
  jmp L3
```

#### **Explanation**

```
if x < 0
   x += 7;
# Arithmetic shift
return x >> 3;
```

- Uses arithmetic shift for int
- For Java Users
  - Arith. shift written as >>

## **Arithmetic: Basic Rules**

Unsigned ints, 2's complement ints are isomorphic rings: isomorphism = casting

#### Left shift

- Unsigned/signed: multiplication by 2<sup>k</sup>
- Always logical shift

## Right shift

- Unsigned: logical shift, div (division + round to zero) by 2<sup>k</sup>
- Signed: arithmetic shift
  - Positive numbers: div (division + round to zero) by 2<sup>k</sup>
  - Negative numbers: div (division + round away from zero) by 2<sup>k</sup>
     Use biasing to fix

# **Properties of Unsigned Arithmetic**

- Unsigned Multiplication with Addition Forms Commutative Ring
  - Addition is commutative group
  - Closed under multiplication

$$0 \leq \mathsf{UMult}_w(u, v) \leq 2^w - 1$$

Multiplication Commutative

$$UMult_{w}(u, v) = UMult_{w}(v, u)$$

Multiplication is Associative

$$UMult_{w}(t, UMult_{w}(u, v)) = UMult_{w}(UMult_{w}(t, u), v)$$

1 is multiplicative identity

$$UMult_{w}(u, 1) = u$$

Multiplication distributes over addtion

$$UMult_{w}(t, UAdd_{w}(u, v)) = UAdd_{w}(UMult_{w}(t, u), UMult_{w}(t, v))$$

# Properties of Two's Comp. Arithmetic

## Isomorphic Algebras

- Unsigned multiplication and addition
  - Truncating to w bits
- Two's complement multiplication and addition
  - Truncating to w bits

### Both Form Rings

■ Isomorphic to ring of integers mod 2<sup>w</sup>

## Comparison to (Mathematical) Integer Arithmetic

- Both are rings
- Integers obey ordering properties, e.g.,

$$u > 0$$
  $\Rightarrow u + v > v$   
 $u > 0, v > 0$   $\Rightarrow u \cdot v > 0$ 

These properties are not obeyed by two's comp. arithmetic

$$TMax + 1 == TMin$$

## **Reading Byte-Reversed Listings**

### Disassembly

- Text representation of binary machine code
- Generated by program that reads the machine code

#### Example Fragment

Address	Instruction Code	Assembly Rendition
8048365:	5b	pop %ebx
8048366:	81 c3 ab 12 00 00	add \$0x12ab,%ebx
804836c:	83 bb 28 00 00 00 00	cmpl \$0x0,0x28(%ebx)

## Deciphering Numbers

- Value:
- Pad to 32 bits:
- Split into bytes:
- Reverse:

0x12ab 0x000012ab 00 00 12 ab ab 12 00 00