The Markuspline Fortran Module

Francesco Calcavecchia

November 21, 2014

The markuspline Fortran module follows the recipe of Ref. [HB05] for representing a spline.

The module markuspline depends on the LAPACK library.

The following is a short user's documentation.

1 Declaration of the module

First of all one has to declare the utilization of the markuspline module, using the instruction

USE markuspline

which has to be inserted just before the IMPLICIT NONE command in any PROGRAM, SUBROUTINE, FUNCTION, or MODULE.

2 Spline's declaration

In the following we will use the variable name spl in our examples. A spline spl must be declared as

TYPE(MSPLINE) :: spl

3 Spline's initialization

As first step, the spline should be initialized, by using the command

```
spl=new_MSPL(M= , NKNOTS= , LA= , LB= , CUTOFF= )
```

where M and NKNOTS are two INTEGERs which refer to m and $N_{\rm spline}$ in [HB05], while LA and LB are two REAL(KIND=8) which represent the range on which the spline is defined (typically LA=0.d0). Finally, CUTOFF is a LOGICAL which specifies whether the spline should smoothly goes to zero at LB or not. Alternatively, one can use the subroutine

```
CALL MSPL_new(M= , NKNOTS= , LA= , LB= , SPL=spl, CUTOFF= )
```

After the initialization, the spline can be used. One has access to the following internal variables:

- LOGICAL :: spl%flag_init, it indicates whether the MSPLINE has been initialized or not (by using new_MSPLINE or MSPLINE_new);
- INTEGER :: spl%m;
- INTEGER :: spl%Nknots;
- REAL(KIND=8) :: spl%La;
- REAL(KIND=8) :: spl%Lb;
- REAL(KIND=8) :: spl%x(-1:spl%Nknots+1)

The grid of the spline. The index 0 corresponds to spl%La and the index spl%Nknots to spl%Lb;

- REAL(KIND=8) :: spl%delta

 The distance between two consecutive points in the grid;
- REAL(KIND=8) :: sp1%t(0:sp1%m,0:sp1%Nknots)

 The t matrix in reference [HB05] but with exchanged indexes (or, in other words, is the transposed matrix), which by default is initialized to zero by new_MSPLINE and MSPLINE_new;
- LOGICAL :: spl%cutoff.

4 Fit a function

At this point one can set the t matrix. The markuspline module provide a tool to fit any given function of the form:

```
FUNCTION f(i,x)
  REAL(KIND=8) :: f
  INTEGER, INTENT(IN) :: i
  REAL(KIND=8), INTENT(IN) :: x
END FUNCTION f
```

To accomplish this, it is sufficient to invoke the following subroutine

```
CALL MSPL_fit_function(SPL=spl,F=f)
```

5 Compute the spline and its derivatives

After that the spline has been set, its value in any $r \in [spl\%La, spl\%Lb]$ can be computed by invoking the function

```
compute_MSPL(SPL=spl, DERIV=0, R=r)
```

which returns a REAL(KIND=8). The derivatives of the spline can be computed simply by setting the value of DERIV accordingly (DERIV=1 for the first derivative, DERIV=2 for the second derivative, etc.). Alternatively, the value of the spline function and of its derivatives can be computed by means of the subroutine

```
CALL MSPL_compute(SPL=spl, DERIV= , R=r, VAL=val)
```

where val is a REAL(KIND=8). If one wants to accumulate the computed value in the variable val, one can add the optional argument RESET=.FALSE., e.g.

```
CALL MSPL_compute(SPL=spl,DERIV= ,R=r,VAL=val,RESET=.FALSE.)
```

This is equivalent to the instruction

val=val+compute_MSPL(SPL=spl,DERIV=0,R=r)

6 Print on file

It is possible to print on file the values of the spline or its derivatives. This can be useful in order to visualize it. To do so, use

```
CALL MSPL_print_on_file(SPL= , DERIV= , FILENAME= , NPOINTS= )
```

where DERIV and NPOINTS are INTEGERS, and FILENAME is a string containing the name of the file where the spline values should be stored. As a result, a file with NPOINTS rows containing the position $r \in [SPL\%La, SPL\%Lb]$ and the value of the spline SPL(r).

7 Parameter derivative of the spline

It is also possible to compute the parameter (or variational) derivatives with respect to the t matrix. In particular, the subroutine

```
CALL MSPL_t_deriv(SPL=spl,R=r,T_DERIV=td)
```

assigns to the matrix td, defined as

```
REAL(KIND=8) :: td(0:spl%m,0:spl%Nknots)
```

the derivatives' matrix

$$exttt{td(i,j)} = rac{\partial}{\partial t_{ij}} exttt{spl}(exttt{r})$$

If one wants to accumulate the derivatives on top of the pre-existing td matrix, it is sufficient to add the optional variable RESET=.FALSE. to the arguments of the subroutine, e.g

CALL MSPL_t_deriv(SPL=spl,R=r,T_DERIV=td,RESET=.FALSE.)

In this way

$$\mathtt{td(i,j)} := \mathtt{td(i,j)} + \frac{\partial}{\partial t_{ij}}\mathtt{spl(r)}$$

7.1 Parameter derivative for particles in a simulation box

The markuspline module contains a subroutine which computes the variational derivatives for all the distances between n particles in a d dimensional space simulation box with sizes $L=(\Lx, Ly, \ldots)$. If we label the particles coordinates as X, the invocation reads

where n and d are INTEGERS, whereas X(1:d,1:n) and L(1:d) are of type REAL(KIND=8). Also in this case it is possible to accumulate the values of the variational derivatives by adding the optional argument RESET=.FALSE.

8 Gradient of the parameter derivative

Suppose that the spline is computed on the distance between two particles i and j, whose coordinates are represented in \mathbb{R}^d :

$$\mathbf{r} = ||\mathbf{r}_j - \mathbf{r}_i||$$

It is possible to compute the quantities

$$\texttt{grad(m,n,1:d)} = \nabla_{\mathbf{j}} \frac{\partial}{\partial t_{mn}} \texttt{spl}(r)$$

for all the m and n by invoking

where dist(0:d) is of type REAL(KIND=8) and RESET is the usual LOGICAL optional argument. It is important to know that dist(1:d) contains the vector $\mathbf{r}_j - \mathbf{r}_i$, whereas dist(0) contains the distance (i.e. r).

8.1 Gradient of the parameter derivative for particles in a simulation box

As in Sec. 7.1, also in this case it is possible to compute the gradient for a simulation box. This is done with

```
CALL MSPL_boxNpart_grad_t_deriv(SPL=spl, R=X, NDIM=d, NPART=n, LBOX=L, GRAD_T_DERIV=grad [, RESET= ])
```

However, in this case the argument has different dimension:

grad(0:spl\m,0:spl\%Nknots,1:d,1:n)

9 Laplacian of the parameter derivative

Suppose that, similarly to Sec. 8, we are now interested in the laplacian

$$\mathrm{lapl(m,n,1:d)} = \nabla_{\mathbf{j}}^2 \frac{\partial}{\partial t_{mn}} \mathrm{spl}(r)$$

This can be computed with

where LAPL_T_DERIV(0:spl%m,0:spl%Nknots) is of type REAL(KIND=8).

10 Gradient and laplacian of the parameter derivative

One can simultaneously obtain the results from both Sec. 8 and 9 with (i.e. both the gradient and the laplacian) with the command

```
CALL MSPL_grad_and_lapl_t_deriv(SPL= , R_VEC= , NDIM= , GRAD_T_DERIV , LAPL_T_DERIV [, RESET= ])
```

10.1 Gradient and laplacian of the parameter derivative for particles in a simulation box

As in Sec. 7.1 and 8.1, we can compute all the gradients and laplacians in a simulation box with

```
CALL MSPL_boxNpart_grad_and_lapl_t_deriv(SPL= , R= , NDIM= ,
NPART= , LBOX= , GRAD_T_DERIV= , LAPL_T_DERIV= [, RESET= ])
```

where one has to be aware of the dimensionality of the two following arrays:

```
GRAD_T_DERIV(0:SPL%m,0:SPL%Nknots,1:NDIM,1:NPART)
LAPL_T_DERIVO:SPL%m,0:SPL%Nknots,1:NPART)
```

11 Carbon-copy

A spline can be transposed to another spline with different m and N_{spline} , by doing a "carbon-copy". This can be accomplished by invoking

CALL MSPL_carbon_copy(ORIGINAL_SPL=spl_in,CC_SPL=spl_out)

where spl_in and spl_out have type TYPE(MSPL).

12 Deallocate the spline's allocated memory

When the spline is of no use any more, its allocated memory can be freed by invoking

CALL MSPL_deallocate(SPL=spl)

13 Notes on the efficiency

If an instruction is called a lot of times, using the subroutine instead of the function will drastically increase the performance.

14 Debugging mode

A final note about the routine checks that are performed internally. By default, the markuspline module checks the input values provided by the user, in order avoid possible mistake (for example, if the user provides a $LA \geq LB$). However, these checks can be disabled with the command

CALL MSPL_change_debug_mode(DEBUG_MODE=.FALSE.)

which changes the internal variable MSPL_DEBUG_MODE accordingly. This might slightly enhance the performance. The current value of MSPL_DEBUG_MODE can be obtained with the function

get_debug_mode_MSPL()

References

[HB05] Markus Holzmann and Bernard Bernu. Optimized periodic 1/r coulomb potential in two dimensions. *Journal of Computational Physics*, 206(1):111 – 121, 2005.