

Thanks for purchasing **Terrain To Mesh** converter package.

Please consider writing a review or just rate the asset:

For any question or help use forum:

http://forum.unity3d.com/threads/terrain-to-mesh.358472/

Editor tool

Menu/Window/VacuumShaders/Terrain To Mesh

| TerrainToMesh | |
|--|-------------------|
| Terrain To Mesh | |
| Source | |
| Drag and drop terrain objects from Hierarchy and Project windows here. | |
| ▼ Selection: 1 | 0 |
| rentani | Show All Hide All |
| Sub-folder Name | |
| Assets/(Temporary) | |
| ☑ Export Maps | |
| Splatmap | PNG ‡ |
| Resolution | Original + |
| Basemap | PNG ‡ |
| Resolution | 1K ‡ |
| Export Per-Chunk | <u> </u> |
| Heightmap | Remap + |
| Resolution | Original # |
| Export Trees | |
| ☑ Export Unity Mesh | |
| Chunk Count Horizontal | 4 |
| Vertical | 4 |
| Vertex Count Horizontal Vertical | 100 |
| Add 'Skirt' | |
| Default Shader | Default ‡ |
| Chunk Count | 16 |
| Mesh Vertex Count | 10,000 |
| Mesh Triangle Count | 19,602 |
| Mesh Compression | Off ‡ |
| Attach MeshCollider | ✓ |
| Vertex Density Vertex Count | 2,500 |
| | -, |
| ✓ Export OBJ Mesh | 25 |
| Vertex Count Horizontal Vertical | 25 |
| | |
| Vertex Count Triangle Count | 1,152 |
| mangie count | 1,100 |
| ☑ Hide Source Object(s) After Convert | |
| | Generate |

Source tab

For converting terrain assets into mesh just drag and drop them from Hierarchy and Project windows here.

Only Unity Terrain assets are supported.

Show/Hide All buttons enable/disable terrain visibility in the Scene window. Have no effect if selected terrains are assets from Project.

After converting terrain prefab file is created at location Assets/(Temporary)/#Sub-folder Name#

If selection contains multiple objects they all will be saved inside one Sub-Folder.

Each prefab is saved in separate folder with the same name as prefab file.

Export Maps tab

Enables exporting terrain Splatmaps, Basemap and Heightmap textures. Files are saved in the same folder as the main prefab.

- Splatmap –Uncompressed RGBA texture used by Unity Terrain engine for blending paint textures. One splatmap can blend 4 paint textures. Splatmaps can be exported in PNG and TGA formats.
- Basemap All paint textures used by Unity Terrain engine are baked into one final texture.
 Diffuse and Normal textures are exported separately.
 Basemap can be baked only if terrain uses Unity's built-in terrain shaders.
- Heightmap Grayscale texture with terrain height data.
 - 1. Original Exports original heightmap.
 - 2. Remap Before exporting terrain heightmap data is remapped to be inside [0, 1] range.

Export Trees tab

Exports tree prefabs used by Unity Terrain asset. Exported trees are original tree prefabs and have no Unity Terrain LOD system like: billboard, distance fade, etc.

Export Unity Mesh tab

Converts source terrain into Unity mesh (.asset file)


- Chunk count horizontal/vertical Source terrain can be split in any amount of chunks. Chunk count defines generated mesh asset count. Mesh asset files are saved in the same folder as the main prefab.
- Vertex count horizontal/vertical Defines vertex count per chunk. Max allowed vertex count is
 65.000
- Mesh Compression Compressing meshes saves space in the built game, but more compression
 introduces more artifacts in vertex data. For multi-chunk meshes editor automatically adds
 CompressedMeshLoader script for fixing visible edge artifacts (high compressed meshes) in run-time.
- Attach MeshCollider Generates separate mesh file to be used as MeshCollider. Mesh vertex density
 is calculated from the main mesh's Vertex Count Horizontal/Vertical value.
 Depending on mesh resolution loading it into Unity's Physics core may be time consuming.

Export OBJ Mesh tab

Converts terrain into .obj file format. Can be imported into any 3d modeling software for additional editing.

 Vertex count horizontal/vertical – OBJ file has no limit on vertex count, if submesh has more than 65.000 vertices it will be split by Unity automatically. UV and normals are generated by default, tangents are calculated by Unity after file importing. OBJ file is saved inside same folder as the main asset, in OBJ subfolder.

Editor window supports context menu



- Add selected object(s) Picks up active game object with terrain component from the Scene or if they are selected inside Project window.
- Reset Resets editor window parameters to their defaults.
- Clear selection Remove all terrains from the selection.