


**MERC 2025 - Session 2**  
**PHYSICAL**  
**PROPERTIES AND**  
**APPLICATION**




# Session 2 - Outline

- What are Physical Properties and their importance
- Methods to obtain them
- Types and Applications
- Borehole Survey Parameters
  - Density
  - Neutron
    - Coal Example Exercise
  - Gamma
  - Electrical and Magnetic parameters
  - Full Wave Sonic
  - Caliper and others
- Exercise



# What Are Physical Properties

- A measurable property which describes a physical system's state/matter
- Independent of geological names
- Interdisciplinary – geology, geophysics, geochemistry, physics, engineering etc.



# Importance of Physical Rock Properties



- Geophysics is the measurement of the physical properties of the earth
  - The science of exploiting physical rock property contrasts
- Physical rock properties are the quantitative link between geology and geophysics
- Respond to lithology, mineralization, alteration, porosity, and mechanical rock properties
- Quantitative physical rock properties are essential to map geology with geophysics
- Capable of providing key insights into ore grade, ore delineation, geometallurgy, geotechnical properties and hydrogeology

# Methods to obtain Physical Properties

- Textbook/Google
- Rock Property Database System  
Led by Mira Geoscience  
[rpds.mirageoscience.com](http://rpds.mirageoscience.com)
- Lab
- Core analysis
- Core scanner on site
- ***In-situ - Boreholes***



# Methods to Obtain Physical Properties

## Textbook/Literature

- Pros
  - Inexpensive
  - Fast
- Cons
  - Representative?
  - Data range
  - Out of date?



# Methods to Obtain Physical Properties

The screenshot shows the 'Rock Property Database System' interface from [rpds.mirageoscience.com](http://rpds.mirageoscience.com). The map displays various geological features and locations in Northern Ontario, including Lake Superior, Lake Huron, and several provincial parks. A callout box highlights 'Available Data Locations' with entries: GSC-ON-SU-LV-93647, GSC-ON-SU-LV-93653, and GSC-ON-SU-LV-97103. The left sidebar includes sections for 'Rock Properties', 'Profiles', 'Maps', and 'Location Info'. The 'Parameters' section lists various geophysical properties like Density, Gamma ray count, Magnetic susceptibility, Resistivity, Spectral gamma-gamma ratio, Self potential gradient, Self potential, and Single point resistivity, with Density checked. The 'Download' section allows for file formats like LAS File, LogView, Gocad Well Object, ASCII, Excel Report, and XML. The 'Query Results' table at the bottom shows data for 22 locations, with the first few rows listed below:

Location ID	Parameter	Country	Province/State	Area	Location Type	# Distinct Lithologies
GSC-ON-SU-LE-NRD18	MS	CANADA	ONTARIO	SUDBURY	BH	7
GSC-ON-SU-FA-F5501	MS	CANADA	ONTARIO	SUDBURY	BH	7
GSC-ON-SU-FA-F5507	MS	CANADA	ONTARIO	SUDBURY	BH	7
GSC-ON-SU-IN-52845	MS	CANADA	ONTARIO	SUDBURY	BH	7
GSC-ON-SU-FA-B4301	MS	CANADA	ONTARIO	SUDBURY	BH	2
GSC-ON-SU-IN-60064	MS	CANADA	ONTARIO	SUDBURY	BH	16

**Rock Property  
Database  
System Led by  
Mira  
Geoscience  
[rpds.mirageoscience.co  
m](http://rpds.mirageoscience.com)**

# Methods to Obtain Physical Properties

## Lab

- **Pros**
  - Highly accurate
  - Rigorous controls
- **Cons**
  - Time & logistics
  - Sample Selection Bias
  - Sample Statistics
  - Sampling Procedure
  - Sample handling
  - Sample Scale



Powertech Labs, 2013

## Core Analysis

- Hand Held - Measure directly on core/outcrop
  - Magnetic Susceptibility e.g. KT –20
  - Gamma Ray Spectrometry
- **Pros**
  - Fast
  - Accurate
- **Cons**
  - Orientation/contact
  - Calibration
  - Location



## Core Scanner On Site

- E.g. Geotek can measure;
  - P wave
  - Density
  - Magnetic Susceptibility
  - Resistivity
- **Pros**
  - On site
- **Cons**
  - Slow
  - Calibrations
  - Nuclear licence



## In Situ - Borehole

- **Pros**

- Relatively Inexpensive
- Fast
- Continuous
- Repeatable and Robust Measurements
- Multi-parameter
- Suited for statistical analysis


- **Cons**

- Capital intensive to purchase equipment with long lead times and training
- Rental
- Hire contractor
- Logistics – timing, camp costs, standby




# Types of Borehole Geophysical Measurements


Near Hole



Off-Hole



Cross-hole



# Physical Properties Constraining Geophysics to Geology




Geophysical Method	Parameter Measured	Physical Property
Gravity	Earth's Gravity Field	Density
Magnetic	Magnetic Field of Earth	Magnetic Susceptibility
Electromagnetic	Induced Electromagnetic Field	Conductivity
Radiometrics	Natural Gamma Radiation	Radioactivity
Seismic/Sonic	Velocity of Waves	Acoustic Impedance
Resistivity	Apparent Resistivity	Resistivity
Induced Polarization	Transient Voltage	Chargeability

Geological Survey of Canada, 2008


# Lithology, Alteration and Mineralization Characterization

- As with other geophysical methods, you often want to run multiple types in the same area/borehole.
- A single lithology can have a wide geophysical response range – multiparameter approach
- Alteration changes the physical properties of a lithology. E.g.
  - Potassic alteration – natural gamma response
  - Argillic alteration – electrical response



# Applications of In-situ Data – What to do with it?


- Improve Geological Understanding
  - Rock properties to improve / assist / QA-QC core logging
  - Maximize information from non-cored drill holes
  - Lithology and alteration mapping
- Rock Property Characterizations of Lithology / Domains
  - Quantify and prioritize contrasts worth exploiting
  - Forward modeling with known (quantified) contrasts
  - Constrained Inversions - less assumptions = better results
- Data Integration and Cross Correlation
  - Establish relationships between disparate data set
  - Predict assay values from rock properties
  - Ore delineation



# Borehole Physical Properties Surveys



- Induction Logs
- Magnetic Susceptibility
- Natural Radioactivity
- Electrical Logs
- Nuclear
- Mechanical Calipers
- Fluid Properties



# Density

- **Purpose**

- Records variation in rock density.

- **Method**


- Radioactive source emits gamma rays into formation.
- Gamma rays interact with electrons in formation (Compton scattering).
- Two detectors measure Compton scattering: near and far.
- Proper calibration essential.

- **Applications**

- Lithological characterization
- Geotechnical calculations (when combined with full wave sonic data)



**X** in casing

**✓** above water



# Density for Resource Estimation

- Important for: ore tonnage calculations, geotechnical engineering and rock mechanics.
- Can affect the total resource and reserve estimate, mine design and planning.
- Downhole density:
  - Radioactive source emits gamma rays into formation; measure backscattering (returned radiation in CPS)
  - High density = lower backscattering/more absorption
  - CPS = electron density
  - Electron density can be calibrated to bulk density.
  - CPS calibrated to known density
- Infill sparse core measurements. Quality Control. Continuous profile.



# Density In Drill Rods



- Acquiring density data though drill rods:
  - Eliminates probe loss risk.
  - Allows for logging through regions of bad ground and highly weathered zones.


**Challenge:** Your volume of investigation now includes steel. How to compensate for the density of the drill rods?

# Density In Drill Rods



**Solution:** Establish a calibration borehole.

1. Acquire density measurements through rods.
2. Acquire density measurements open hole on the same borehole.
3. Calculate a compensation for the steel that can be used on other boreholes.




# Density In Drill Rods

**Solution:** Establish a calibration borehole.

1. Acquire density measurements through rods.
2. Acquire density measurements open hole on the same borehole.
3. Calculate a compensation for the steel that can be used on other boreholes.

Min: 0 g/cc  
Max: 0.25 g/cc  
Avg: 0.037 g/cc



## • Purpose

- Determine the porosity of the formation.

## • Method


- Radioactive source emits neutrons into the formation.
- Neutrons collide with hydrogen nuclei in formation, losing energy and creating “thermal neutron”.
- Returning thermal neutron strikes neutron detector (Helium-3) in probe.
- High thermal neutron number: high porosity (hydrogen)
- Low thermal neutron number: low porosity (hydrogen)
- Qualitative v. quantitative

## • Applications

- Porosity estimate
- Can reflect changes in lithology

✓ \* in casing   X above water

\* Casing must be below water level; some signal attenuation occurs.



# Natural Gamma

- **Purpose**

- Measure variation in radioactivity of formation

- **Method**


- Rocks emit gamma rays because of the decay of K, U & Th.
- Gamma rays strike sodium iodide crystal in probe, creating a pulse of light.
- Light is captured by a photo multiplier tube, which outputs a current that reflects the amount of radiation.
- CPS converted to API measurement

- **Applications**

- Lithological mapping
- Detection of alteration zones
- Grain size indicator

✓ in casing

✓ above water



# Density and Gamma – Working Example



- This example is from a coal exploration project
- **Aim** is to identify coal seams
- Use several parameters in conjunction with one another



# Find the Coal Seams


- HINT:

- Coal is defined, in this example, as having LOW Density and LOW Gamma
- Use all parameters to find them




# Find the Coal Seams

- Low Density, Low Gamma zones



# Find the Coal Seams

- Potentially 5-6 seems
- Low Density, Low Gamma zones
- Check with Acoustic Televiewer



- Measures K, U, Th but able to distinguish energy windows
- Measures daughter products, Potassium 40, Bismuth 214, Thallium 208
- Static Measurements
- Disequilibrium
- Temperature/Hole Size Considerations
- Calibration
- Used for mineral identification and clay typing (e.g., smectite)
- Spectrometric Ratios can be used as they are less sensitive to borehole environment.

# Chargeability

DGI

- **Purpose**

- Calculate chargeability of formation.

- **Method**



- Probe injects current into the formation.
- Current is switched off.
- Potential difference is measured over time.
- Chargeability is equal to the integrated area under the decay waveform divided by the injection voltage.

- **Applications**


- Lithological characterization
- Certain minerals (eg. sulphides) have high chargeability

X in casing

X above water



# In-situ Chargeability and Sulphide Zones



# Magnetic Susceptibility



## • Purpose

- Measure magnetic susceptibility; reflection of the amount of magnetic materials in the formation.

## • Method


- Magnetic field varies in borehole due to amount of magnetic minerals in formation.
- Varying magnetic field induces an electrical current in probe sensor (coil of wire).
- Pre/Post Calibration checks are paramount
- Corrections: Temperature, hole size and drift

## • Applications


- Magnetite assay estimates
- Lithological characterization
- Measure abundance of magnetic materials; location of magnetic ore body.

in casing

above water



# In-situ Assay for Magnetite



# Full Wave Sonic (FWS)

DGI

## • Purpose




- Record acoustic waveform of the formation.

## • Method

- Waves are transmitted into the formation.
- Determine compressional (P) and shear (S) waves**
- Allows for an estimate of the velocity of the formation (dependent on porosity and lithology type).

✓ in pvc casing


✗ above water



# Full Wave Sonic (FWS)

## • Applications

- Rock strength and porosity
- Locations of fractures
- Geotechnical calculations (when combined with density information): Poisson's Ration, Young's modulus, bulk and shear modulus
- Cement bond logs



# Derived Rock Mechanics

DGI

Using full waveform sonic (P & S wave velocity) and focused density:

$$\text{Poisson's Ratio : } \nu = \frac{R^2 - 2}{2(R^2 - 1)} \text{ where } R = \frac{V_p}{V_s}$$

$$\text{Young's Modulus : } E = \nu V_p^2 \frac{(1+\nu)(1-2\nu)}{(1-\nu)}$$

$$\text{Shear Modulus : } G = \nu V_s^2$$


$$\text{Bulk Modulus : } K = \nu V_p^2 - \frac{4}{3}G$$

Where:

Compressional wave velocity  $V_p$

Shear wave velocity  $V_s$

Density  $\rho$



# Electrical Resistivity

DGI

## • Purpose

- Measure the combined resistivity of rock and pore fluid

## • Method



- Transmit current into the formation
- Measure voltage between transmitter and receiver
- 4 different receiver distances measured; different volume of investigation
- Calculate formation resistivity based on known current output and measured voltage

## • Applications

- Lithological characterization and identification
- Fracture identification
- Quantitative measurement

X in casing

X above water



# Mechanical Caliper

- **Purpose**

- Record variation in the diameter of the borehole

- **Method**

- Arm on probe opens and measures borehole size
- More arms
- Single arm caliper
  - Side walling device
- 3-arm caliper
  - 3 arms linked together
  - Does not account for shape
- 4-arm Caliper
  - X-Y measurement

- **Applications**


- Detection of large open fractures
- Changes in hole size



in casing



above water



# 3-Arm Caliper


**DGI**  
GEOSCIENCE



# Synthetic Caliper

DGI

- Acoustic Televiewer can create a synthetic caliper
- Good QAQC of caliper or back up if caliper is broken
- Faster and therefore cheaper



# Temperature

- **Purpose**

- Measure temperature of borehole fluid.

- **Method**


- Thermal sensor on bottom of probe measures the temperature of the fluid.
- Used in conjunction with other parameters; multi-parameter

- **Applications**


- Indicative of fracturing and groundwater flow

X in casing

X above water



# Hydrogeological - Flowmeters



- Measure L/min in-situ
- Dynamic or static measurements
  - A) Heatflow
  - B) Electromagnetic
  - C) Spinner



(a)




(b)



(c)

USGS, 2013

# Borehole Magnetic Resonance



- Uses magnetic field to polarize hydrogen nuclei. Once the magnetic field is removed, it measures the time it takes for the nuclei to return to their randomly oriented state.
- **Measure:** porosity and pore size.
- **Calculate:** permeability and hydraulic conductivity using KTIM and KSDR models.
- Formation porosity without radioactive source.
- Continuous vertical profiles of Permeability, Bound Fluid and Specific Yield.
- Packer test complement.






Image courtesy of  
OTEC

# Borehole Magnetic Resonance

DGI  
EO SCIENCE



# Borehole Radar



Plunge +01  
Azimuth 318



0 50 100 150


- Depends on a property called **Diaelectric Permittivity**.
  - A measure of how strongly a material will become electrically polarized while being exposed to an electric field.
  - **Diaelectric Permittivity** is unitless.

# Borehole Radar


Material	Relative Permittivity
Air	1
Fresh Water	80
Sea Water	80
Ice	3-4
Dry Sand	3-5
Saturated Sand	20-30
Limestone	4-8
Shales	5-15
Silts	5-30
Clays	5-40
Granite	4-6
Anhydrites	3-4

# Borehole Radar

- Unlike Ground Penetrating Radar (GPR), Borehole Radar (BHR) is not bound to a single direction.
  - The area of investigation is a cylinder around the borehole axis.
- Can be used to identify:
  - Faulting
  - Bedding
  - Voids




# Borehole Radar



# Borehole Radar

Large sub-parallel to low-angle features that run the length of the survey.



Plunge +01  
Azimuth 318  
S E

0 50 100 150

# Borehole Physical Properties Surveys Cont'd



- Single Point Resistance
  - Measure resistance along the borehole to a surface point
- Laterolog
  - Focused resistivity with minimal fluid impact
- Down-hole Electromagnetics (DHEM)
  - Ideally suited for detecting conductive massive sulphide mineralization.
- MagnetoMetric Resistivity (DHMMR)
  - Ideally suited for detecting poorly conducting mineralization such as sphalerite (zinc sulphide) rich bodies.
- Vertical Seismic Profile (VSP)
  - Correlate with surface seismic data.
- Borehole Gravity
  - Detects mass excesses or mass deficits

# Exercise Physical Properties Click Here to Open