Stacklook User Manual

KernelShark plugin

Intro

This document serves as a simple to grasp manual for the "Stacklook" KernelShark plugin.

For a more technical look, read the doxygen-generated HTML API documentation and source code.




Figure 1 - working Stacklook

"How do I build and install Stacklook?"

Prerequisites

- CMake of version at least 3.1.2
- KernelShark and its dependencies
 - version 2.4.0-couplebreak and higher for custom KernelShark
 - version 2.3.2 for unmodified KernelShark

Compatibility

Plugin is compatible with KernelShark's **custom** version *2.4.0-couplebreak* and higher.

Unmodified KernelShark usage is achievable through a build argument. Unmodified KernelShark removes these features from the plugin:

- Buttons optionally being the same color as the task is in the graph
- Mouse hover showing a preview of the kernel stack with an adjustable stack offset for it in the configuration
- No other dependencies are necessary, except maybe the standard libraries of C and C++.

Build and install only this plugin

- 1. Set your working directory in terminal as the build directory (best created in the project's root directory (see [README](../../README.md)), if not already present).
- 2. Run cmake ... command (if the main CMakeLists.txt file isn't in the parent folder, provide cmake with its valid location).
 - . If using an unmodified KernelShark copy, add -D_UNMODIFIED_KSHARK to the command.
 - . If **Doxygen documentation** is desired, include D_DOXYGEN_DOC=1 in the command.
 - . By default, the **build type** will be RelWithDebInfo to change this, e.g. to Release, use the option -DCMAKE_BUILD_TYPE=Release.
 - If Qt6 files aren't in /usr/include/qt6, use the option
 -D_QT6_INCLUDE_DIR=[PATH], where [PATH] is replaced by the path to the Qt6 files.
 - . Build instructions still expect that the specified directory has same inner structure as the default case (i.e. it contains QtCore, QtWidgets, etc.).
 - . If **KernelShark source files** aren't in the relative path ../KS_fork/src from this directory, use the option -D_KS_INCLUDE_DIR=[PATH], where [PATH] is replaced by the path to KernelShark source files.
 - . If **KernelShark's shared libraries** (.so files) aren't in /usr/local/lib64, use the option -D_KS_SHARED_LIBS_DIR=[PATH], where [PATH] is replaced by the path to KernelShark shared libraries.
- 3. Run make while still in the build directory.
 - . If only a part of building is necessary, select a target of your choice.
 - Just running make builds: **the plugin** (target stacklook), **symlink** to the plugin SO (target stacklook_symlink) and, if specified, the **Doxygen documentation** (target docs).
- 4. (**Installation**) Plug in the plugin into KernelShark either via KernelShark's GUI or when starting it via the CLI with the -p option and location of the symlink or the SO itself.
 - . **IMPORTANT**: Always install/load the plugin before loading a session where said plugin was active! Failure to do so will result in KernelShark not completely loading configuration menus or may even crash the whole program.

Building KernelShark from source and this plugin with it

- 1. Ensure all source files (.c, .cpp, .h) of Naps are in the src/plugins subdirectory of your KernelShark project directory.
- 2. Ensure the CMakeLists.txt file in said subdirectory contains instructions for building the plugin (copy the style of other Qt-using GUI plugins). Adjust the build instructions if _UNMODIFIED_KSHARK build is desired.
- 3. Build KernelShark (plugins are built automatically).
- 4. (**Installation**) Start KernelShark. Plugins built this way will be loaded automatically. If that for some reason failed, look for the SO as for any other default-built KernelShark plugin, again in GUI or via the CLI.

WARNING - loading plugin twice

If you have two or more versions of the plugin, do **NOT** load them at the same time - doing so **WILL CRASH** the program. Use either one or the other, but **NEVER BOTH**.

"How do I enable/disable Stacklook?"

Enabling the plugin is very simple. All one has to do is open KernelShark and navigate to Tools > Manage Plotting plugins toolbar menu button. If the plugin was loaded via the command-line interface, it will be shown in the list of plotting plugins as a checkbox plus the name, checkbox already being ticked.

If not, it is possible to search for the plugin via provded Tools > Add plugin button - it's sufficient to find the symlink, but searching for the actual shared object file is possible too. As you can see, the plugin follows standard KernelShark plugin loading behaviour.




Figure 2 - loaded Stacklook in Manage Plotting plugins window

Ticked checkbox means the plugin is enabled, empty checkbox means the plugin is disabled.

"How do I use Stacklook?"

Configuration

Plugin configuration can be done at any time, even before any trace file is loaded. To change it, simply open the configuration dialog window through

Tools > Stacklook Configuration in the main window. There can be only one configuration window open (figure 3).




Figure 3 - Stacklook's configuration window

If using the unmodified build, the configuration window will be missing the checkbox for task colors and the stack offset for the preview labels (figure 4).



Figure 4 - Configuration window of Stacklook for unmodified KernelShark

Now to explain each of the options and how to control them. In top to bottom order:

- *Histogram entries limit* Decrease this number to force Stacklook to activate only if there are less than or equal to this many entries visible. Lesser the number, greater the zoom necessary to activate Stacklook. Minimum is set to 0, maximum is 1 000 000 (one billion) though this high of a value will hardly ever become useful. By default, the value is 10 000 (ten thousand).
- *Use task colors for Stacklook buttons* Check this box (if present) to color Stacklook's buttons' filling color according to the task which owned the event Stacklook found kernel stack trace for. Keep it disabled to use default Stacklook button colors (figure 6). By default, this option is off.




Figure 5 - Stacklook buttons with default coloring




Figure 6 - Stacklook buttons with task-color fillings

• *Stacklook button & outline colors* - The "Choose" buttons will bring up a color dialog, allowing one to pick a color to be used for Stacklook button's filling or a color its outline. These are effective only if the task color checkbox either is not present or is not checked. Next to this button is a space to show what colors are currently picked for the buttons. By default it is white for filling, black for outline. See example in figure 7 below.




Figure 7 - change default values to a light green filling an magenta-ish outlines

- *Per-event configurations* Each event is assigned a checkbox toggling Stacklook on or off for an event entry and (if present) an spinbox with an offset into the kernel stack, which is used to read the "most interesting" events from the kernel stack trace. The maximum value of the offset is the 100 000 000 (one hundred million), minimum is 0. Again, the maximum value will probably never be used. By default, the values for each event are allowed (checked) and offset of 3.
 - To reiterate, the spinbox will not appear if the unmodified KernelShark version of the plugin is used.

The Apply button will save the changes made an close the dialog - if not pressed, changes made won't take effect. Only active configuration values show up in the control elements - the configuration window doesn't persist changes made to it after closing, unless they were applied. The Close button and top-right corner X button will discard changes made in the window and close the dialog.

There is **no** configuration of:

- Supported events plugin currently only support sched/sched_switch and sched/sched_waking
- The text in stacklook windows
- The text in stacklook buttons
- Stacklook button sizes
- Stacklook button positions

In the graph

After loading (and maybe configuring) the plugin, zoom in until less than the configured number of visible entries are visible in the graph. A button will show up above each supported entry, colored by the default color in the configuration, or if using custom KernelShark and having the corresponding option on, colored like the task in the graph. The task color option is fully compatible with KernelShark's color slider.

The plugin won't show the buttons above event entries that aren't sched/sched_switch or sched/sched_waking, or if such entries are missing their kernel stack trace event.

Hovering over buttons

If using custom KernelShark, hover over any button and look at the top-left quarter of the screen. You will see the preview label's contents change to have:

- Task name as the leftmost (first) entry.
- First item in the kernel stack, offset by configured number for this event type from the stack's top (where the newer entries go)
- Item in the kernel stack after the first item
- · Item in the kernel stack after the second item
- Either three dots "...", signifying that the kernel stack has more entries than these or "(End of stack)" message, signifying there are no more items to display after the ones shown.

See figure 8 on the next page for a small showcase. Included is also the Stacklook window (more on that later below) and the kernel stack trace in the main window's list view of all events - both to really show that the items in the preview are in the kernel stack (chosen offset was the default of 3). There's also a red circle highlighting the entry the mouse cursor hovered over.




Figure 8 - Mouse hover shows three stack items in the preview, offset from the top by the value in configuration

It is possible to set the offset so high that only last one, two, three entries are shown or none at all in the preview. In that case, Stacklook shows just a dash and a the "(End of stack)" message (figure 9).




Figure 9 - Chosen offset was so great that nothing can be shown, so Stacklook shows nothing

Double-clicking on buttons

Upon double-clicking a Stacklook button, a new window will open. This is a *Stacklook window*, which shows a message that we are viewing a kernel stack of a task (whose name is shown at the sentence's end). Below it is a note about whether task has woken up (which shows only for sched/sched_waking events) or about its previous state (only for sched/sched_switch events). Then two radio buttons and the view with the kernel stack taken at the time of the event entry is shown. The radio buttons toggle what kind of view is used for the kernel stack.

- By default, the view is set as raw text, which means the kernel stack is just a string with newlines
 this is useful for copying the stack as a single string or for highlighting only a specific part of a stack item.
- *Alternatively*, the stack can be viewed in list view, which allows for simpler and quicker highlighting of a single line.

Thre can be multiple windows present for a single entry, there can be multiple windows open for different entries and any mix of the two previous situations.

All of the above for this section can be seen below in figure 10.




Figure 10 - Multiple Stacklook winows are opened, with different views shown

Toggle between the raw text view and the list view using two radio buttons above the stack view area.

The window can be closed with the Close button at the very bottom of the window or with the X button of the window's header. Last option is to close the main KernelShark window, which will close all of Stacklook's opened windows.

Using Stacklook as a library

See technical documentation, as this is not intended usage of the plugin and such usage explanations will be omitted.

Bugs & glitches

If multiple stacklook buttons would lay over one another, the one belonging to an *earlier* event will be drawn above a button for an event happening *later*, **BUT** clicking on or hovering over overlaid buttons will select the button for the *later* event. This is, to the author's knowledge, something internal to KernelShark and cannot be fixed on the plugin side.

Opening a KernelShark session where Stacklook was active, but without preloading it will result in a segmentation fault and a **program crash** upon hovering over a Stacklook button.

If more are discovered, contact the author via e-mail djsebofficial@gmail.com.

Recommendations

A few recommendations of usage by the author for the smoothest user experience.

Always preload Stacklook before loading a session. It can save the program from nasty surprises.

Do not open hundreds upon hundreds of stacklook windows, lest you wish your memory to suffer.

It is recommended to not set the histogram limit in the configuration too high as to not make the plugin use too much memory with many of stacklook's buttons being present.

While KernelShark's sessions work, they are a little buggy. This plugin attempts its best to not get in the way of their inner logic, but a warning should be issued that if the plugin isn't loaded beforehand, there might be unexpected behaviours, e.g. loading a session when the plugin was active won't add the plugin's menu to the Tools menu.