# Moment of Inertia © BinaryPhi

Last Edit: June 27, 2022 PDT

#### **Definitions:**

**Moment of Inertia**, often denoted by I (SI Unit:  $kg \cdot m^2$ ), is a quantitative measurement of the inertia for an object to rotate about a specific axis. It can be calculated by the summation of moment of inertia of every infinitesimal part of the rigid body ( $\Longrightarrow$  in other words, a **mass point**). The moment of inertia of a mass point is:

$$I = m r^2, (1)$$

where m is the mass of the mass point and r is the distance between this mass point and the rotational axis. By using summation, the moment of inertia of a system can be written as:

$$I = \sum_{i}^{\infty} m_i \, r_i^2. \tag{2}$$

By using integral, the moment of inertia can be written as:

$$I = \int r^2 dM. \tag{3}$$

Depending on the circumstances, we can transform (3) to the following:

$$I = \int \rho r^2 dV; \tag{4}$$

$$I = \int \sigma r^2 dS; \tag{5}$$

$$I = \int \lambda r^2 dL. \tag{6}$$

In (4) (5) (6), the convention is  $\rho$  denotes the Volume Density,  $\sigma$  denotes the Area Density, and  $\lambda$  denotes the Linear Density. In addition,

$$dL = Rd\theta$$

is also useful in some cases.

# Eq.1: Infinite Thin Rod : Center (Mass: m; Lenght: I)

$$I = \frac{1}{12}ml^2. \tag{7}$$

proof

$$I = \int r^2 dM = \int_0^m r^2 dM$$

$$= \int r^2 (\lambda dL) = \int_{-l/2}^{l/2} \frac{m}{l} L^2 dL$$

$$= \frac{m}{l} \int_{-l/2}^{l/2} L^2 dL = \frac{m}{l} \cdot \left[ \frac{1}{3} L^3 \right]_{-l/2}^{l/2}$$

$$= \frac{m}{l} \left[ \frac{1}{3} \left( \frac{l}{2} \right)^3 - \frac{1}{3} \left( -\frac{l}{2} \right)^3 \right]$$

$$= \frac{1}{12} m l^2.$$

### **Eq.2: Infinite Thin Rod** : **One End** (Mass: **m**; Lenght: **I**)

$$I = \frac{1}{3}ml^2. (8)$$

$$I = \int r^2 dM = \int_0^m r^2 dM$$

$$= \int r^2 (\lambda dL) = \int_0^l \frac{m}{l} L^2 dL$$

$$= \frac{m}{l} \int_0^l L^2 dL$$

$$= \frac{m}{l} \cdot \left[ \frac{1}{3} L^3 \right]_0^l = \frac{m}{l} \left( \frac{1}{3} l^3 - 0 \right)$$

$$= \frac{1}{3} m l^2.$$

#### Theorem.1: Parallel Axis Theorem

The moment of inertia of a rigid body about a rotating axis is:

$$I = I_{cm} + md^2. (9)$$

 $I_{cm}$  is the moment of inertia when rotating about the axis that passes through the center of mass. d is the distance between an arbitrary rotational axis and the axis that passes through the center of mass of the object.

#### proof

For the sake of simplicity, let's imagine the rigid body rotating about the z-axis, which passes through the center of mass of the body. You could use tensor to do a more generalized proof (I will do a tensor version of this whole topic if I have time).

$$I_{cm} = \int r^2 dM$$

$$= \int (x^2 + y^2 + z^2) dM = \int (x^2 + y^2) dM$$

$$I = \int ((x - d_1)^2 + (y - d_2)^2) dM$$

$$= \int (x^2 + y^2 - 2d_1x - 2d_2y + d_1^2 + d_2^2) dM$$

$$= \int (x^2 + y^2) dM + (d_1^2 + d_2^2) \int dM$$

$$- 2d_1 \int x dM - 2d_2 \int y dM$$

$$\therefore \int x dM = \int y dM = 0$$

$$\therefore I = \int (x^2 + y^2) dM + d^2 \cdot \int dM$$

$$= I_{cm} + md^2$$

## **Eq.3:** Circular Thin Loop: Orthogonal Center (Mass: m; Radius: R)

$$I_z = mR^2. (10)$$

proof

$$I_z = \int r^2 dM = \int R^2 dM$$
$$= R^2 \int dM = R^2 \cdot m$$
$$= mR^2$$

# **Eq.4:** Circular Thin Loop : Diameter (Mass: m; Radius: R)

$$I_x = I_y = \frac{1}{2}mR^2. (11)$$

$$I_x = I_y = \int r^2 dM$$

$$= \int r^2 (\lambda dL) = \int_0^{2\pi} r^2 \left(\frac{m}{2\pi R} R d\theta\right)$$

$$= \int_0^{2\pi} (R \cos \theta)^2 \left(\frac{m}{2\pi}\right) d\theta$$

$$= R^2 \frac{m}{2\pi} \int_0^{2\pi} \cos^2 \theta d\theta$$

$$= R^2 \frac{m}{2\pi} \int_0^{2\pi} \frac{1 + \cos 2\theta}{2} d\theta$$

$$= R^2 \frac{m}{2\pi} \left(\left[\frac{1}{2}\theta + \frac{1}{4}\sin 2\theta\right]_0^{2\pi}\right)$$

$$= R^2 \frac{m}{2\pi} (\pi - 0 + 0 - 0)$$

$$= \frac{1}{2} m R^2.$$

## Theorem.2: Perpendicular Axis Theorem

For a flat, thin, and uniform object, the moment of inertia,  $I_z$ , about a rotating axis, say z-axis, that is orthogonal to the center of mass, is equal to the sum of the moments of inertia of the object about two other rotating axes orthogonal to each other,  $I_x$ ,  $I_y$ :

$$I_z = I_x + I_y. (12)$$

 $I_z$  is the moment of inertia when rotating about the z-axis,  $I_x$ ,  $I_y$  are the moments of inertia when rotating about the x-axis and y-axis respectively. Note that the object is flat among the xy surface. We have:

$$I_z = 2I_x = 2I_y; \quad I_x = I_y$$
 (13)

when the rigid body has rotational symmetry in xy surface.

proof

$$I_z = \int r^2 dM$$

$$= \int (x^2 + y^2) dM$$

$$= \int x^2 dM + \int y^2 dM$$

$$= I_y + I_x.$$
Note that: 
$$\int x^2 dM = I_y,$$
and 
$$\int y^2 dM = I_x.$$

Since the circular loop is a flat, thin, and uniform rigid body, we have:

$$(10): I_z = mR^2$$

$$(11): I_x = I_y = \frac{1}{2}mR^2$$

which satisfy

$$I_z = I_x + I_y$$
.

# Eq.5: Circular Thin Disk: Orthogonal Center (Mass: m; Radius: R)

$$I_z = \frac{1}{2}mR^2. (14)$$

proof

$$I_z = \int r^2 dM = \iint r^2 (\sigma dA)$$

$$= \int_0^R \int_{-\pi}^{\pi} r^2 \sigma r d\theta dr = \int_0^R \sigma r^3 \left( \int_{-\pi}^{\pi} d\theta \right) dr$$

$$= 2\pi \sigma \int_0^R r^3 dr$$

$$= 2\pi \sigma \left[ \frac{1}{4} r^4 \right]_0^R = 2\pi \frac{m}{\pi R^2} \left( \frac{1}{4} R^4 - 0 \right)$$

$$= \frac{1}{2} m R^2$$

### Eq.6: Cylinder: Orthogonal Center (Mass: m; Radius: R; Hight: H)

$$I_z = \frac{1}{2}mR^2. (15)$$

$$I_z = \int r^2 dM = \int r^2 (HdM_A)$$

$$= \iint r^2 (H\sigma dA) = H\sigma \int_0^R r^3 \cdot 2\pi \cdot dr$$

$$= H \frac{m}{\pi R^2 H} 2\pi \int_0^R r^2 r dr$$

$$= \frac{2m}{R^2} \left(\frac{1}{4}R^4\right)$$

$$= \frac{1}{2}mR^2$$

# Eq.7: Circular Thin Disk : Diameter (Mass: m; Radius: R)

$$I_x = I_y = \frac{1}{4} mR^2. (16)$$

$$I_x = I_y =$$

$$= \frac{1}{4}mR^2$$