


Packet Tracer - Pinging and Tracing to Test the Path

Topology



Addressing Table

Device	Interface	IPv4 Address	Subnet Mask	Default Gateway
		IPv6 Address/Prefix		Delault Gateway
R1	G0/0	2001:DB8:1:1::1/64		N/A
	G0/1	10.10.1.97	255.255.255.224	N/A
	S0/0/1	10.10.1.6	255.255.255.252	N/A
		2001:DB8:1:2::2/64		N/A
	Link-local	FE80::1		N/A
R2	S0/0/0	10.10.1.5	255.255.255.252	N/A
		2001:DB8:1:2::1/64		N/A
	S0/0/1	10.10.1.9	255.255.255.252	N/A
		2001:DB8:1:3::1/64		N/A
	Link-local	FE80::2		N/A
R3	G0/0	2001:DB8:1:4::1/64		N/A
	G0/1	10.10.1.17	255.255.255.240	N/A
	S0/0/1	10.10.1.10	255.255.255.252	N/A
		2001:DB8:1:3::2/64		N/A
	Link-local	FE80::3		N/A
PC1	NIC			
PC2	NIC			
PC3	NIC			
PC4	NIC			

Objectives

Part 1: Test and Restore IPv4 Connectivity

Part 2: Test and Restore IPv6 Connectivity

Scenario

There are connectivity issues in this activity. In addition to gathering and documenting information about the network, you will locate the problems and implement acceptable solutions to restore connectivity.

Note: The user EXEC password is cisco. The privileged EXEC password is class.

Part 1: Test and Restore IPv4 Connectivity

Step 1: Use ipconfig and ping to verify connectivity.

a. Click **PC1** and click the **Desktop** tab > **Command Prompt**.

- b. Enter the **ipconfig /all** command to collect the IPv4 information. Complete the **Addressing Table** with the IPv4 address, subnet mask, and default gateway.
- c. Click PC3 and click the Desktop tab > Command Prompt.
- d. Enter the **ipconfig /all** command to collect the IPv4 information. Complete the **Addressing Table** with the IPv4 address, subnet mask, and default gateway.
- e. Test connectivity between PC1 and PC3. The ping should fail.

Step 2: Locate the source of connectivity failure.

- a. From PC1, enter the necessary command to trace the route to PC3. What is the last successful IPv4 address that was reached?
- b. The trace will eventually end after 30 attempts. Enter CtrI+C to stop the trace before 30 attempts.
- c. From PC3, enter the necessary command to trace the route to PC1. What is the last successful IPv4 address that was reached?
- d. Enter Ctrl+C to stop the trace.
- e. Click R1 and then the CLI tab. Press ENTER and log in to the router.
- f. Enter the **show ip interface brief** command to list the interfaces and their status. There are two IPv4 addresses on the router. One should have been recorded in Step 2a. What is the other?
- g. Enter the **show ip route** command to list the networks to which the router is connected. Note that there are two networks connected to the **Serial0/0/1** interface. What are they?
- h. Repeat step 2e to 2g with **R3** and record the answers here.
 - Notice how the serial interface for R3 changes.
- i. Run more tests if it helps visualize the problem. Simulation mode is available.

Step 3: Propose a solution to solve the problem.

- a. Compare your answers in Step 2 to the documentation you have available for the network. What is the error?
- b. What solution would you propose to correct the problem?

Step 4: Implement the plan.

Implement the solution you proposed in Step 3b.

Step 5: Verify that connectivity is restored.

- a. From PC1 test connectivity to PC3.
- b. From PC3 test connectivity to PC1. Is the problem resolved?

Step 6: Document the solution.

Part 2: Test and Restore IPv6 Connectivity

Step 1: Use ipv6config and ping to verify connectivity.

- a. Click PC2 and click the Desktop tab > Command Prompt.
- b. Enter the **ipv6config /all** command to collect the IPv6 information. Complete the **Addressing Table** with the IPv6 address, subnet prefix, and default gateway.
- c. Click PC4 and click the Desktop tab > Command Prompt.
- d. Enter the **ipv6config /all** command to collect the IPv6 information. Complete the **Addressing Table** with the IPv6 address, subnet prefix, and default gateway.
- e. Test connectivity between PC2 and PC4. The ping should fail.

Step 2: Locate the source of connectivity failure.

- a. From PC2, enter the necessary command to trace the route to PC4. What is the last successful IPv6 address that was reached?
- b. The trace will eventually end after 30 attempts. Enter Ctrl+C to stop the trace before 30 attempts.
- c. From **PC4**, enter the necessary command to trace the route to **PC2**. What is the last successful IPv6 address that was reached?
- d. Enter Ctrl+C to stop the trace.
- e. Click R3 and then the CLI tab. Press ENTER and log in to the router.
- f. Enter the show ipv6 interface brief command to list the interfaces and their status. There are two IPv6 addresses on the router. One should match the gateway address recorded in Step 1d. Is there a discrepancy?
- g. Run more tests if it helps visualize the problem. Simulation mode is available.

Step 3: Propose a solution to solve the problem.

- a. Compare your answers in Step 2 to the documentation you have available for the network. What is the error?
- b. What solution would you propose to correct the problem?

Step 4: Implement the plan.

Implement the solution you proposed in Step 3b.

Step 5: Verify that connectivity is restored.

- a. From PC2 test connectivity to PC4.
- b. From **PC4** test connectivity to **PC2**. Is the problem resolved?

Step 6: Document the solution.

Suggested Scoring Rubric

Activity Section	Question Location	Possible Points	Earned Points
Part 1: Test and Restore	Step 1b	5	
Connectivity Between PC1 and PC3	Step 1d	5	
	Step 2a	5	
	Step 2c	5	
	Step 2f	5	
	Step 2g	5	
	Step 2h	5	
	Step 3a	5	
	Step 3b	5	
	Part 1 Total	45	
Part 2: Test and Restore Connectivity Between PC2	Step 1b	5	
and PC4	Step 1d	5	
	Step 2a	5	
	Step 2c	5	
	Step 2f	5	
	Step 3a	5	
	Step 3b	5	
	Part 2 Total	35	
Pack	20		
	100		