

webMethods API Gateway Staging and Promotion

Version 10.15

October 2022

WEBMETHODS

This document applies to webMethods API Gateway 10.15 and to all subsequent releases.

Specifications contained herein are subject to change and these changes will be reported in subsequent release notes or new editions.

Copyright © 2016-2023 Software AG, Darmstadt, Germany and/or Software AG USA, Inc., Reston, VA, USA, and/or its subsidiaries and/or its affiliates and/or their licensors.

The name Software AG and all Software AG product names are either trademarks or registered trademarks of Software AG and/or Software AG USA Inc. and/or its subsidiaries and/or its affiliates and/or their licensors. Other company and product names mentioned herein may be trademarks of their respective owners.

Detailed information on trademarks and patents owned by Software AG and/or its subsidiaries is located at https://softwareag.com/licenses/.

Use of this software is subject to adherence to Software AG's licensing conditions and terms. These terms are part of the product documentation, located at https://softwareag.com/licenses/ and/or in the root installation directory of the licensed product(s).

This software may include portions of third-party products. For third-party copyright notices, license terms, additional rights or restrictions, please refer to "License Texts, Copyright Notices and Disclaimers of Third Party Products". For certain specific third-party license restrictions, please refer to section E of the Legal Notices available under "License Terms and Conditions for Use of Software AG Products / Copyright and Trademark Notices of Software AG Products". These documents are part of the product documentation, located at https://softwareag.com/licenses/ and/or in the root installation directory of the licensed product(s).

Document ID: YAI-SPG-1015-20230619

Table of Contents

About this Documentation	5
Document Conventions	
Online Information and Support	6
Data Protection	
I Introduction	o
1 11110uuctioit	٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠٠
	4.4
2 Asset Promotion	
Asset Promotion	12
Promoting Assets Using Promotion Management API	15
Promoting Assets from API Gateway User Interface	
Promoting Assets Using Deployer	
3 Export and Import Assets and Configurations	31
Export and Import Assets and Configurations	
Importing Asset and Configuration Archives	37
Troubleshooting Tips: Import and Export Assets	
Trouble transfer of the Export resocts	

About this Documentation

Document Conventions	6
Online Information and Support	6
Data Protection	7

This documentation describes how you manage Stages, asset promotions and required rollbacks in API Gateway.

Document Conventions

Convention	Description
Bold	Identifies elements on a screen.
Narrowfont	Identifies service names and locations in the format <i>folder.subfolder.service</i> , APIs, Java classes, methods, properties.
Italic	Identifies:
	Variables for which you must supply values specific to your own situation or environment. New terms the first time they occur in the text. References to other documentation sources.
Monospace font	Identifies:
	Text you must type in. Messages displayed by the system. Program code.
{}	Indicates a set of choices from which you must choose one. Type only the information inside the curly braces. Do not type the { } symbols.
T	Separates two mutually exclusive choices in a syntax line. Type one of these choices. Do not type the symbol.
[]	Indicates one or more options. Type only the information inside the square brackets. Do not type the [] symbols.
	Indicates that you can type multiple options of the same type. Type only the information. Do not type the ellipsis ().

Online Information and Support

Product Documentation

You can find the product documentation on our documentation website at https://documentation.softwareag.com.

In addition, you can also access the cloud product documentation via https://www.softwareag.cloud. Navigate to the desired product and then, depending on your solution, go to "Developer Center", "User Center" or "Documentation".

Product Training

You can find helpful product training material on our Learning Portal at https://knowledge.softwareag.com.

Tech Community

You can collaborate with Software AG experts on our Tech Community website at https://techcommunity.softwareag.com. From here you can, for example:

- Browse through our vast knowledge base.
- Ask questions and find answers in our discussion forums.
- Get the latest Software AG news and announcements.
- Explore our communities.
- Go to our public GitHub and Docker repositories at https://github.com/softwareag and https://hub.docker.com/u/softwareag and discover additional Software AG resources.

Product Support

Support for Software AG products is provided to licensed customers via our Empower Portal at https://empower.softwareag.com. Many services on this portal require that you have an account. If you do not yet have one, you can request it at https://empower.softwareag.com/register. Once you have an account, you can, for example:

- Download products, updates and fixes.
- Search the Knowledge Center for technical information and tips.
- Subscribe to early warnings and critical alerts.
- Open and update support incidents.
- Add product feature requests.

Data Protection

Software AG products provide functionality with respect to processing of personal data according to the EU General Data Protection Regulation (GDPR). Where applicable, appropriate steps are documented in the respective administration documentation.

1 Introduction


API Gateway assets are critical to keep a business running. In order to facilitate the migration of assets smoothly across different API Gateway instances and stages, API Gateway supports the movement of assets such as APIs, policies, applications, packages, plans, approval configurations on through staging and promotion, and export and import capabilities.

2 Asset Promotion

Asset Promotion	12
Promoting Assets Using Promotion Management API	15
Promoting Assets from API Gateway User Interface	16
Promoting Assets Using Deployer	27

Asset Promotion

API Gateway supports staging and promotion of assets. In a typical enterprise-level, solutions are separated according to the different stages of Software Development Lifecycle (SDLC) such as development, quality assurance (QA), and production stages. As each organization builds APIs for easy consumption and monetization, continuous integration (CI) and continuous delivery (CD) is an integral part of the solution. CI is a development practice that requires developers to integrate code into a shared repository several times a day and CD is a software engineering approach in which teams produce software in short cycles, ensuring that the software can be reliably released at any time. Development of assets starts at the development stage and once the assets are developed, they are promoted to the QA stage for testing, after testing of the assets is complete, the assets are promoted to the deployment stage.



API Gateway provides tools and features to automate your CI and CD practices. Modifications made to the APIs, policies, and other assets can be efficiently delivered to the application developers with speed and agility. For example, When you publish new applications, the API definitions change. These changes are to be propagated to application developers. The API provider has to update the associated documentation for the API or application. In most cases this process is a tedious manual exercise. You can use API Gateway staging and promotion to address such cases to automate API and policy management that makes deployment faster, introduces continuous innovation with speed and agility. This ensures that new updates and capabilities are automatically, efficiently, and securely delivered to their developers and partners, in a timely fashion and without manual intervention.


API Gateway provides the staging and promotion feature to automate the CI and CD practices. Modifications made to the APIs, policies, and other assets can be efficiently delivered to the application developers with speed and agility.

Staging and promotion allows you to:

- Promote all the run time assets such as API Gateway APIs, aliases, applications, policies, or admin configurations across different stages.
- Select and promote a subset of assets from one stage to another stage. For example, you can promote a single API and its dependencies from one stage to another.
- select dependencies involved while promoting an asset. For example, while selecting a service for promotion, you must also select the dependent policies, applications, and so on.
- modify values of attributes of selected aliases during promotion.
- roll back assets in case of failures.

When you have three stages namely *Dev*, *QA*, and *Prod*, you can promote assets in the given sequence. That is, you can promote assets from stage 1 to stage 2, and from there to stage 3.

To promote assets from first stage, you create aliases of those assets that you want to promote to the second stage and promote them. Similarly, from the second stage you create aliases of assets that you want to promote to the third stage and promote them. The following illustration shows the flow:



Assets can have aliases that are associated to a target stage and aliases without a target stage. When you promote to a target stage, the aliases associated to the particular target stage are promoted to the target stage. If an asset has no alias that is created for the target stage, then aliases that are not associated are included in the promotion.

Note:

During the promotion process ensure that both the source and the target system have the same master password. For more information on promoting assets using the API Gateway, see "Promoting Assets from API Gateway User Interface" on page 16.

Stages

The fundamental phases of assets starts with requirements or needs at the development stage and once the assets are developed, they are promoted to the QA stage for testing, after testing of the assets is complete, the assets are promoted to the production stage.

An asset's overall lifecycle can be split across two or more API Gateway instances. For example, assets that are in the development and test phases of their lifecycle can be maintained in one instance and assets that are deployed (that is, in production) can be maintained in a separate instance.

When the asset's lifecycle is split across multiple API Gateway instances, each participating instance is referred to as a stage. A stage definition in API Gateway describes an API Gateway instance by its name and configuration information.

Note:

Software AG recommends you to have API Gateway instances across stages to be completely independent. For example, the API Gateway instances from the Development stage and the API Gateway instances from the QA stage must not share any resources in common such as databases.

Promotions

Promotion refers to moving API Gateway assets from the source stage to one or more target stages. For example, you might want to promote assets you have developed on servers in a Development stage (the source API Gateway instance) to servers in a QA or Production stage (the target API Gateway instance). When you promote an asset from one stage to another, the asset's metadata is copied from the source instance to the target instance. For the list of assets and configuration settings that can be promoted, see *Assets that can be exported and imported* section in "Export and Import Assets and Configurations" on page 32.

Note:

During the promotion process ensure that both the source and the target system have the same master password.

Assets that are dependencies for the asset are also promoted. The required dependencies of an asset are always promoted with the asset. However, you can choose which optional dependencies are promoted at the time of promoting the asset. For example, at the time of promoting an API, the policies and aliases used by the API are always promoted. However, you can choose which dependent applications are promoted as applications an optional dependency for APIs. You can choose to promote all or no application, or select specific applications that you want to included with the API in the promotion.

When you promote extended settings, the watt settings are not promoted. You have to reconfigure the watt settings in each node.

The following table lists the required and optional dependencies of assets that are supported by promotion management.

Dependencies (Required)	Dependencies (Optional)
Policies, Aliases	Applications
APIs	
APIs, Plans, Policies, Subscriptions	
Policies	
Packages, Plans	Applications
	Group
Teams	
	Policies, Aliases APIs APIs, Plans, Policies, Subscriptions Policies Packages, Plans

Asset	Dependencies (Required)	Dependencies (Optional)
Configuration > Keystore	Keystore, Truststore	
Email destination		Truststore
Group		User
JMS Connection alias	JNDI provider alias	
LDAP configuration	Group	
Password expiry settings		User
Port (https)	Keystore, Truststore	
Service Registry	Keystore, Truststore	
Web service endpoint alias	s Teams, JMS, JNDI, JMS trigger, Keystore, Truststore	
Custom destinations	Keystore, Truststore, Aliases	

Note:

Till API Gateway version 10.3, promotion management supported only the simple and endpoint types of aliases. Starting from API Gateway version 10.4, all types of aliases are supported.

Promoting Assets Using Promotion Management API

The promotion management capabilities allows for moving assets from lower to higher environments. For details, see "Asset Promotion" on page 12.

API Gatewayenables continuous integration (CI) and continuous delivery (CD) practices to be used for development, deployment, and promotion of the APIs, applications, other related assets, and for supporting the use of DevOps tooling. There are different ways in which API Gateway enables continuous integration (CI) and continuous delivery (CD).


The promotion management REST APIs allow for automation for CI/CD. For detail about the promotion management API, see *webMethods API Gateway User's Guide*.

DevOps Use Case using Promotion Management APIs

This example explains a sample DevOps use case using the promotion management APIs. You can promote API Gateway assets from one stage to the other using API Gateway specific scripts provided in GitHub. You can use the continuous integration tools like Jenkins and Azure to deploy user-created assets that reside on source API Gateway instance or repositories to a target API Gateway instance. For example, you might want to deploy assets you have developed on an API Gateway instance in a development environment (the source) to an API Gateway instance in a test or production environment (the target).

The high level steps to achieve this are as follows and are depicted in the illustration:

- 1. Create a stage-specific API Gateway environment.
- 2. Develop APIs.
- 3. Test the APIs.



For details about various API Gateway-specific scripts and their usage, see https://github.com/SoftwareAG/webmethods-api-gateway-devops.

Promoting Assets from API Gateway User Interface

Pre-requisites:

- You must define a stage to represent the asset's lifecycle such as development, test, and production. For details about how to add a stage, see "Adding a Stage" on page 23.
- You must have the Manage promotions functional privilege assigned to perform this task.

Promoting assets from one (source) stage to another (target) stage includes the following high-level steps:

- 1. **Authorization server promotion:** Promote Authorization server in one of the following ways:
 - Export the authorization server from one environment and import it into another, if you want to use the same authorization server across multiple environments.
 - Create the authorization server with the same name as in the current environment, if you want to use a different authorization server instance.

Proceed to the next step once the authorization server is ready.

- 2. **Select assets for promotion:** During this step, you search for assets by using a keyword and by performing a type search that sorts and filters the results.
 - Search using a keyword. You can search for all assets whose string attributes (asset name, description, and so on) contain a certain keyword (character string).
 - **Search using a Type**. You can search for assets on the basis of types.
 - You may use the **Search by type** filter to restrict the types on which the search is conducted. In the **Search by type** panel, API Gateway shows you a list of supported asset types.
 - **Search by team**. You can search for assets assigned to team(s). Click the team(s) to view the assets that are assigned to the selected team(s).
 - **Search using two keywords**. You can provide more than one keyword by separating the keywords using a pipe symbol (|). For example, to search for assets whose names contain *pet* and *test*, you can provide pet|test in the search field.
 - **Search using wild card characters**. You can use wild card characters in your search keyword. For example, to list all assets that start with *graph*, you can provide graph*.
- 3. **Optionally select assets' dependencies for promotion:** During this step, you specify whether the dependencies (for example, a list of applications that are registered for an API, subscriptions for a package, and so on) of the selected assets will be included for the promotion.

Note:

As groups and users are part of the team, if you want to promote the Groups and Users (optional dependencies) of the team that the selected asset belongs to, you have to set the **enableTeamWork** extended setting to true. Only then the **Groups** and **Users** sections appear.

- 4. **Select the stages to promote:** During this step, you specify one or more target stages to which you want to promote the selected assets and their dependencies.
- 5. **Configure the promotion details:** During this step, you provide the promotion-specific information.

6. Ensure that you are promoting the assets from an lower version of API Gateway to a higher version of API Gateway. You cannot promote assets from a higher version to a lower version of API Gateway. For example, if you are using API Gateway v10.11, you can promote the assets from this version to v10,15 and other higher versions. You cannot promote assets back to the v10.7, v10.5, and so on.

Important:

If you plan to perform bulk promotion of assets from a source stage to a target stage, Software AG recommends you to increase the value of the **pg.gateway.elasticsearch.http.socketTimeout** property, located in SAG_Install_Directory/IntegrationServer/instances/IS_Instance_Name/packages/WmAPIGateway/config/resources/elasticsearch/config.properties. The default value of this property is 3000. To bulk promote assets, for example, 50 numbers, you would set the value of this property to 60000. Depending on the number of assets you want to promote, increment the value as 70000, 80000, and so on.


You must restart API Gateway for changes to this property to take effect.

To promote assets

- 1. Expand the menu options icon , in the title bar, and select **Promotion management**.
- 2. Select **Promotions**.

The Promotions page appears.

- 3. Click + Promote.
- 4. In the **Search by keyword** text box, type the keyword to search for assets. You can use one or more wildcards to specify the keywords.



Note:


You can search multiple times for the same type while retaining the previous search results.

API Gateway returns the assets that match the specified keyword.

5. In the **Search by type** drop-down list, select the required type(s). Select the **All** check box to search across all asset types.

Important:

Authorization server, External Authorization server, and Providers are listed under the Aliases category. To select any of these assets, select the Aliases check box and then choose the required asset.



API Gateway returns the assets that match the selected type(s). The number of search results is displayed in the results area, for example, Showing 10 results. If no results are found, the results area is displays a blank page.

6. Optional. Select the **Include admin configurations** check box if you want to include administrative configurations in the promotion.

API Gateway displays the administrative configurations that are supported for promotion.

Important:

Before you configure API Gateway to promote an administrative configuration, make sure that the corresponding administrative settings are already configured in API Gateway. For example, to include the Load balancer configuration in the asset promotion set, the required Load balancer URLs should be configured.

- 7. Select the assets and the administrative configurations that you want to promote.
- 8. Click Next.

The Assets and dependencies page appears.

- 9. Select the referenced assets that you want to promote.
- 10. Click Next.

The Stages page appears.

- 11. Select the target stages to which you want to promote the assets, dependencies, and administrative configurations to.
- 12. Click Next.

The Promote page appears.

13. Provide the following information:

Field	Description
Name	Name of the promotion.
Description	Description of the promotion.
Overwrites assets except alias that already exist on the selected target stages	If you set this field to <i>True</i> , all the assets except for aliases are overwritten.
Overwrites aliases that already exist on the selected target stages.	If you set this field to <i>True</i> , even the aliases are overwritten.
Fix missing version	Select the check box to fix the API version history. The discrepancy between the asset versions in the source and target stages, if any, are fixed.
	For example, consider that you have created an API and have five versions of the API from 1 to 5, in the source. If you select versions 1,2,4, and, 5 for promotion to the target, and if this check box is not selected, versions 1 and 2 are linked separately and versions 4 and 5 are linked separately. However, if you select this check box, version 2 is linked to version 4 and hence all versions 1,2,4, and 5 are now linked in the target.
Include application registrations	Select the checkbox to include the application registrations when you promote an API.

14. Click **Promote**.

The selected assets, dependencies, and administrative configurations are promoted to the selected stages.

The Stage-specific promotion status page displays the status of the asset promotion in each of the selected stages. The available values are:

- Success
- Failure

The page also displays the reason if the promotion fails.

Viewing Promotion List and Promotion Details

The **Promotions** tab displays a list of the available asset promotions in API Gateway. The asset promotions are listed alphabetically by name.

In addition, you can examine the details of an asset promotion history, repromote assets to the configured stages, and delete the promotion history from API Gateway database in the **Promotions** tab.

> To view the promotion list and promotion details

- 1. Expand the menu options icon , in the title bar, and select **Promotion management**.
- 2. Select **Promotions**.

The **Promotions** tab displays a list of available asset promotions.

This tab provides the following information about each promotion:

Column	Description
Name	Name of the promotion.
Description	Description of the promotion.
Promoted by	Name of the user who initiated the asset promotion.
Promotion time	The time at which the asset promotion occurred.
Status	The status report on the asset promotion.

3. Examine the **Report** link in the **Status** column and check for any errors that occurred during the asset promotion.

The Promotion status report displays the following information:

Column	Description	
Asset type	Name of the asset type that was promoted from the source instance.	
Name	Name of the asset that was promoted from the source instance.	
Status	The status of the asset promotion.	
Comments	A descriptive comment on the asset promotion status.	

4. Click the required promotion whose details you want to examine.

The Promote page appears.

Adding a Stage

Pre-requisites:

You must have the Manage promotions functional privilege assigned to perform this task.

API Gateway can contain one or more stages. You define a stage to represent the asset's lifecycle such as development, test, and production.

> To add a stage

- 1. Expand the menu options icon , in the title bar, and select **Promotion management** > **Stages**.
- 2. Click Add Stage.
- 3. Provide the following information in the Basic information section:

Field	Description
Name	Mandatory. Name of the stage.
	Note: A stage name must be unique within API Gateway.
Description	Description of the stage.

4. Provide the following information in the Technical information section:

Field	Description
Stage URL	The URL of the host machine where the stage is deployed on an API Gateway installation.
	The Stage URL value is specified in the format, <code>scheme://host:port</code> . The scheme is http or https. The host is the host name of the machine on which the target API Gateway instance is running. The port is the port number of the target API Gateway instance.
Username	The username of a registered API Gateway user who has the Manage promotions or Manage assets functional privilege in the target API Gateway instance.

Field	Description
Password	A valid password of the API Gateway user identified by the attribute Username .
Keystore alias	The alias of the keystore containing the private key that is used for performing asset promotion from one (source) stage to another (target) stage.
	The Keystore alias field contains a list of the available keystore aliases in API Gateway. If there are no configured keystore aliases, this field lists the default Integration Server keystore, DEFAULT_IS_KEYSTORE.
	Note: This field is required when the Stage URL scheme is set to https with Two-way SSL.
Key alias (signing)	The alias of the private key that is stored in the keystore specified by the keystore alias.
	The Key alias field contains a list of the available aliases in the selected keystore. If there are no configured keystores, this field is empty.
	Note: This field is required when the Stage URL scheme is set to https with Two-way SSL.

5. Click **Save**.

The stage gets created and is displayed in the stages list on the Promotion Management > Stages screen. You can click **Test** to test the configuration before saving the details for creating a stage.

The **Stages** tab displays a list of the available stages in API Gateway. In addition to viewing the list of stages, you can also examine, modify the basic or the technical information of a stage at any time and delete a stage in the **Stages** tab to remove it from API Gateway permanently.

Repromoting Assets

Pre-requisites:

You must have the Manage promotions functional privilege assigned to perform this task.

If you have made recent changes to an asset's information, you can repromote the updated asset to the already promoted target stages.

If you have to update an asset, for example, you want to correct an attribute setting, modify the asset's description, that has already been promoted to a target stage, you can simply make the change directly to the asset in the source target and then repromote the updated asset to the target

stage just as you did with the previous version of the asset. In a multi-stage environment, you have to repromote the updated assets in each of the participating API Gateway instances.

> To repromote assets

1. Expand the menu options icon , in the title bar, and select **Promotion management**.

2. Select **Promotions**.

The **Promotions** tab displays a list of available promotion histories in API Gateway.

3. Click the **Repromote** icon for the required assets' promotion history.

The Stages page appears.

4. Select the target stages to that you want to repromote the assets, dependencies, and administrative configurations.

5. Click **Next**.

The Promote page appears.

6. Provide the following information:

Field	Description
Name	Name of the promotion.
Description	Description of the promotion.

Note:

The **Overwrite assets if exists on selected stages** option allows you to overwrite assets that exist on the target stages. If you do not want to overwrite assets in the target stages, clear this check box.

7. Click **Promote**.

The selected assets, dependencies, and administrative configurations are repromoted to the selected stages.

The Stage-specific promotion status page displays the status of the asset repromotion in each of the selected stages. The available values are:

- Success
- Failure

The page also displays the reason if the repromotion fails.

Rollbacks

Rollback is the process of restoring the asset's metadata in the target API Gateway instance to a previous state.

You might need to rollback assets to revert any promotional data changes being made in the target API Gateway instance.

Rollback Asset Promotions

Pre-requisites:

You must have the Manage promotions functional privilege assigned to perform this task.

You can rollback an asset promotion that is already available in the target stage at any time.

To rollback asset promotion

- 1. Expand the menu options icon , in the title bar, and select **Promotion management**.
- Select Rollbacks.

The **Rollbacks** tab displays a list of available promotion histories.

- 3. Click the **Rollback** icon for the promotion history that you want to rollback.
- 4. Click **Yes** in the confirmation dialog.

Viewing Rollback List and Rollback Details

The **Rollbacks** tab displays a list of the available asset promotion rollbacks in API Gateway. The rollbacks are listed alphabetically by name.

In addition, you can also examine the details of a rollback, and delete the rollback history in the **Rollbacks** tab.

To view the rollback list and rollback details

- 1. Expand the menu options icon , in the title bar, and select **Promotion management**.
- 2. Select Rollbacks.

The **Rollbacks** tab displays a list of available asset promotion rollbacks.

This tab provides the following information about each rollback:

Column	Description
Name	Name of the rollback.
Promotion time	The time at which the asset was promoted.
Rollback time	The time at which the asset promotion was rolled back.
Status	The status report on the rollback operation.

3. Examine the **Report** link in the **Status** column and check for any errors that occurred during the rollback process.

The Promotion status report displays the following information:

Column	Description
Asset Type	Name of the asset type that was promoted from the source instance.
Asset Name	Name of the asset that was promoted from the source instance.


Promoting Assets Using Deployer

You can promote API Gateway assets from one stage to the other using webMethods Deployer. webMethods Deployer is a tool you use to deploy user-created assets that reside on source webMethods runtimes or repositories to target webMethods runtime components (runtimes). For example, you might want to deploy assets you have developed on servers in a development environment (the source) to servers in a test or production environment (the target).

Note:

webMethods Deployer support for API Gateway is deprecated and will be removed in future releases.

The high level steps involved are as follows:



For more information on promoting assets using webMethods Deployer, see *webMethods Deployer User's Guide*.


For details about the automation scripts provided by ABE and Deployer and their usage to promote assets from one stage to another, see http://techcommunity.softwareag.com/pwiki/-/wiki/Main/Staging%2C%20Promotion%20and%20DevOps%20of%20API%20Gateway%20assets.

DevOps Use Case using Asset Build Environment and webMethods Deployer


The API Gateway specific scripts that are provided as part of the Asset Build Environment and webMethods Deployer can be used by continuous integration tools like Jenkins. The sample flow is as follows:

- 1. The developer makes changes to a development API Gateway instance.
- 2. A Jenkins job then uses the build script to pull data from this development instance and push it to a version control system such as GIT.
- 3. Another job is used to pull it from a version control system and then use the webMethods Deployer scripts to directly push it to the test instance. In this way, the test instance always have the APIs.

Sample: Staging workflow



Sample: Staging call flow



For detailed information about promoting assets using webMethods Deployer , see *webMethods Deployer User's Guide*.

3 Export and Import Assets and Configurations

Export and Import Assets and Configurations	32
Importing Asset and Configuration Archives	37
Troubleshooting Tips: Import and Export Assets	39

Export and Import Assets and Configurations

API Gateway supports the import and export of the assets that you create or configure in API Gateway. You can import archives of APIs, global policies, and other related assets that you have exported and re-create them in API Gateway. This enables you to easily export and archive the assets; and when required, import them to a different instance of API Gateway or redeploy them on the same instance.

Each artifact in an archive is associated with a universally unique identifier (UUID) that is unique across all API Gateway installations. When importing an archive, the UUID helps in determining whether the corresponding artifact is already available in API Gateway. You can configure whether you want to overwrite the existing artifact or keep the available artifact during the import process.

Note:

During export or import of assets, ensure that the master password is identical across stages and on different instances of API Gateway.

Considerations while importing assets:

- The APIs, applications, policies, and aliases you import become visible in API Gateway immediately.
- Active APIs are replaced during import with the updated API and the API level policies.
- The updated APIs and updated API level policies do not become effective for ongoing requests.
- Active APIs are replaced during deployment with zero downtime without breaking ongoing requests.
- Imported applications become effective immediately, even the ongoing requests are affected.
- Imported aliases and global policies do not affect the ongoing requests.
- You can not define multiple aliases with the same name in API Gateway as overwriting of aliases based on their names during import is not supported. Aliases, like other assets, are identified based on their UUID. Hence, if you want to overwrite an alias by importing, then ensure that the alias being imported has the same UUID as the one in the target instance.
- You can not update ports through the import process when:
 - the ports are enabled in the target instance.
 - the port has the same alias as in the target instance.
 - the port has the same port ID as in the target instance.

Note:

- Do not attempt to modify and import an archive file because import of modified archive files is not supported.
- You can export archives from an earlier version to a later version of API Gateway. However, you can not import from a later version to an earlier version. For example, you can not import an 10.5 asset into a 10.3 API Gateway.

You can also export and import assets using the API Gateway REST APIs. For more information, see webMethods API Gateway User's Guide.

When you export an asset, the dependent assets are also exported. If any of the exported assets contain secure strings, the user credential information (passwords) associated with the assets is also exported. When you import this exported asset, API Gateway enforces conditions to check the order of import and the dependency evaluation between assets, and the dependent assets along with the user credential data are imported. For example, if you import an API, API Gateway checks and ensures that all associated policies and aliases are imported along with any passwords, if present, before importing the API.

When you export extended settings, the watt settings are not exported. When you import the exported archive, you have to reconfigure the watt settings in the instance.

The **Overwrite** option available for all the assets allows you to decide whether the asset should be imported if an existing version of the asset already exists in the target instance. In scenarios where you select to overwrite the asset in the target instance, API Gateway also checks for any associated passwords and applies the overwrite accordingly. There is no separate overwrite option for the passwords during import. The password uses the overwrite option of the asset it is associated with. For example, if you are importing an alias with a password, the overwrite option provided for the alias is applied for the password as well. If set to true, the password is overwritten if it is already exists in the system.

Functional Privileges

The **Export or Import assets and Purge and Archive events** category on the **Functional privileges** page has the available import and export privileges. You must assign the following functional privileges for the required permissions:

- **Import assets**: To import assets previously exported assets from a local system.
- **Export assets**: To export assets and save them on a local system.

Accessing the Export and Import commands in the API Gateway user interface

The export command is either a button with the label **Export**, or the icon. You can export multiple items within lists, such as APIs in the API page, by using the export command in the list menu.

You can import assets using the user menu () > **Import** command.

Assets that can be exported and imported

Path to Page/Tab	Assets that can be exported and imported
APIs	APIs
Policies > Threat protection	Global denial of service

Path to Page/Tab	Assets that can be exported and imported
	Denial of service by IP
	Rules
	Mobile device and apps
	Alert settings
Policies > Global policies	Global policies
Policies > Policy templates	Policy templates
Applications	Applications
Packages > Packages	Packages
Packages > Plans	Plans
User menu ()>	Load balancer
Administration > General	Extended settings
	API fault
	Approval configuration
	Outbound proxy
	URL Aliases
	Custom content-types
	Cache configuration
	Log level configuration
	Callback processor settings
	Messaging
	Web services
User menu (=) >	■ JNDI Provider Alias
Administration > General > Messaging	JMS Connection Alias
User menu () >	■ Keystore/Truststore
Administration > Security	Ports
	SAML issuer
	Custom assertions

Path to Page/Tab	Assets that can be exported and imported
	■ Kerberos
	JWT/OAuth/OpenID
	Providers
User menu ()>	API Gateway
Administration > Destinations	API Portal (both the Event configurations and Communication configurations are exported)
	■ Transaction logger
	■ Elasticsearch (properties on both tabs—Elasticsearch communication and Events—are exported)
	■ Email (properties on both tabs—Email configuration and Templates—are exported)
	■ SNMP (properties on both tabs—SNMP communication and Events—are exported)
	Custom destinations
Hear many (A)	Configurations
User menu (—) > Administration > System	■ SAML SSO
settings	Note: A change in the SAML SSO configuration from the API Gateway user interface forces the logged in user to log out. However, importing an SAML SSO does not.
User menu () > Administration > Service registries	Service registry
User menu (> > Administration > Aliases	Aliases
User menu () > User	Users
management	Groups
	Teams
	■ Global team assignments
	Account settings

Path to Page/Tab	Assets that can be exported and imported
	Password restrictions
	Password expiry settings
	Account locking settings
	LDAP configuration

Dependencies

Some API Gateway assets use other assets. For example, APIs uses policies, aliases, and other assets. As the configuration of an asset is incomplete without the assets it uses, the export features includes the assets that are used by the asset that you export.

Note:

The association of a user to a group is not exported. After importing a user archive, you must manually link the new users to the required groups.

The following table shows the asset dependencies of each type of asset:

Asset	Dependencies (Required)	Dependencies (Optional)
APIs	Policies, Aliases	Applications, Application registrations
Applications	APIs, Application registrations	_
Packages	APIs, Plans, Policies, Subscriptions	_
Plans	Policies	_
Subscriptions	Packages, Plans	Applications
Teams	_	Group
Approval configurations	Teams	_
Configuration > Keystore	Keystore, Truststore	_
Email destination	_	Trust store
Group	_	User
JMS connection alias	JNDI provider alias	_
LDAP configuration	Group	_
Password expiry settings	_	User
Port (https)	Keystore, Truststore	_

Asset	Dependencies (Required)	Dependencies (Optional)
Service Registry	Keystore, Truststore	_
Web service endpoint alias	Teams, JMS, JNDI, JMS Trigger, Keystore, Truststore	_
Custom destinations	Keystore, Truststore, Aliases	

Importing Asset and Configuration Archives

Importing an exported archive enables you to import the required assets to a different instance of API Gateway or redeploy them on the same instance.

> To import the exported files

- 1. Expand the menu options icon , in the title bar, and select **Import**.
- 2. Provide the following information:

_		
Parameter	Description	
Select archive file	Click Browse to select a file or ZIP format file.	
Overwrite	Select an overwrite option:	
	■ None . If you do not want to overwrite matching objects that exist on the server. Import fails for the object in the archive if a matching object or asset already exists on the server.	
	■ All . If you want to overwrite any matching asset that exists on the server. If a match is not found, then a new asset is created.	
	■ Custom . If you want to select specific types of assets to be overwritten on the server if a match is found. If a matching asset exists on the server for an asset type that is not selected in the Custom overwrite list, the import operation fails.	
	If a duplicate asset is found for any asset type that is not selected in the Custom overwrite list, the import fails.	
	Note: Some assets types have dependencies on other asset types. For example, APIs have a dependency on policies, aliases, and applications. Some of the dependencies are required,	

Parameter	Description
	while others are optional. The required dependencies are always included in the archive when you export the asset. You should consider your requirements and select the assets that need to be overwritten in the Custom list.
API version history	Select the option Fix missing versions to fix the API version history.
	On selecting this option, the API versions are newly linked according to the system version of the APIs.

Note:

API Gateway supports backward compatibility for API Gateway 10.1 version or higher when importing the archives of APIs. In addition, the compatibility of archives across API Gateway fix levels is also maintained. For example, you can import the archives created from lower fix levels of API Gateway into higher fix levels.

The import of an archive created from a higher fix level of API Gateway into a lower fix level can be rejected if the higher fix level's configurations are not supported by the lower fix level.

3. Click **Import**.

The **Import report** displays the following information:

Parameter	Description
Туре	The asset type.
Successful	The number of successful imports for each artifact type.
Unsuccessful	The number of unsuccessful imports for each artifact type.
Replaced	The number of instances replaced for each artifact type.
Warning	The number of warnings displayed during the import of each artifact type. API Gateway displays warning messages when the import is successful but some additional information is required.

To download the detail report, click **Download the detail report here >**. The detail report displays the following information about the imported artifact:

Parameter	Description
Name	The name of the imported artifact.
Туре	The artifact type.
Status	The status of the imported artifact. The available values are:
	Success
	Replaced
	Warning
	■ Failure
Explanation	The reason if the import fails or if a warning occurs.

If you want to take a backup of an API that you want to overwrite during import, you can set the parameter enableImportBackup as true under **Administration** > **General** > **Extended Settings** section. For more information about this extended setting, see *webMethods API Gateway Administration*.

If an API import fails, one of the reasons might be that a configuration that is required by the API is not set up correctly on API Gateway. If something happens unexpectedly while the import is in progress, API Gateway discontinues the import and restores the existing API. This is necessary as parts of the existing API such as policies may already have been overwritten.

Troubleshooting Tips: Import and Export Assets

I see the an error *Error while searching scroll ID* when importing an archive consisting APIs

When you import an archive that has an API where the alias used in the archive is not present in API Gateway, *Error while searching scroll ID* error is displayed.

Sample error is as follows:

Error while searching scroll ID -

DXF1ZXJ5QW5kRmV0Y2gBAAAAAAAAKWEWUjVjczBsaktRbmE4M0RNR2RRdkhfUQ==. Message - No search context found for id [10593]. No search context found for id [10593]

Resolution:

To resolve this issue, increase the heap size of Elasticsearch.

To increase the heap space of Elasticsearch, modify the parameters Xms2g and Xmx2g in the jvm.options file located at SAG_Install_Directory\InternalDataStore\config.