Package 'Rgtsvm'

January 18, 2018

Title The e1071 compatibility SVM package for GPU architecture based on the GTSVM software

Imports graphics, grDevices, bit64, tools, methods, stats, utils, class

Version 0.52

Date 2018-01-18

Suggests	s SparseM, Matrix
tur	tion The e1071 compatibility SVM package is built on the CUDA-enable GPU architecte with the following features, including: binary classification, multiclass classification and epon regression; 4 kernel functions; K-fold cross validation; big matrix handle.
License	GPL(>=3)
LazyLoa	ad yes
Author	Zhong Wang <zw355@cornell.edu></zw355@cornell.edu>
	ner Zhong Wang <zw355@cornell.edu></zw355@cornell.edu>
	ompilation yes
	-
Reposito	ory CRAN
R top.	attach.bigmatrix
Index	\mathbf{R}
	1

2 attach.bigmatrix

attach.bigmatrix

Wrapping a big matrix into a reference class

Description

This function wraps a big matrix into a reference class in order to avoid multiple variable copying when variables are passed into deep calls in R. It seems to become pointer calling in C language.

Usage

```
attach.bigmatrix(data)
```

Arguments

data

matrix object

Value

Return a reference class with the name "BigMatrix.refer". It can be used in svm and predict calling in Rgtsvm.

See Also

```
load.bigmatrix
```

Examples

```
library(mvtnorm);
size=5000;
dimension=100:
covar.mat <- matrix(runif(dimension*dimension), nrow=dimension);</pre>
covar.mat <- t(covar.mat)</pre>
covar.mat <- round( (covar.mat + t(covar.mat))/2, 4);</pre>
zero <- rmvnorm(size, mean=c(1:dimension), sigma= covar.mat);</pre>
one <- rmvnorm(size, mean=c(1:dimension)-5, sigma= covar.mat);</pre>
x <- rbind(zero, one);</pre>
y <- c(rep(0,nrow(zero)),rep(1,nrow(one)));</pre>
i.all <- sample(1:(2*size));</pre>
i.training <- i.all[(1:round(2*size*0.8))];</pre>
i.test <- i.all[-c(1:round(2*size*0.8))];</pre>
bigm.x <- attach.bigmatrix( data = x[ i.training,]);</pre>
model.gpu <- svm(bigm.x,y[ i.training ],type="C-classification");</pre>
y.pred <- predict(model.gpu,x[i.test,]);</pre>
cat("accuracy", sum(y.pred==y[i.test])/length(i.test),"\n");
```

load.bigmatrix 3

load.bigmatrix

Loading a big matrix from RData or RDS file

Description

Creating a big matrix based on the matrix variable in a RData file or a RDS file.

Usage

```
load.bigmatrix(file.data, variable = NULL)
```

Arguments

file.data File name, RData file or RDS file.

variable String, variable name in the RData file. If variable is NULL, the data file should

be in RDS format.

Value

Return a reference class with the name "BigMatrix.refer". It can be used in svm and predict calling in Rgtsvm.

See Also

```
attach.bigmatrix
```

Examples

```
# The example can not be executed!
#
# x0_bm <- load.bigmatrix("X0.RDS")
# x1_bm <- load.bigmatrix("X1.Rdata", "x1")</pre>
```

load.svmlight

Load SVMlight data file into a sparse matrix.

Description

Load SVMlight data file into a sparse matrix.

Usage

```
load.svmlight(filename, .loadbyC = TRUE)
```

Arguments

filename string, SVM light filename.

. loadbyC logical value, indicating whether loading data in C or R.

4 plot.gtsvm

Details

The file must be symlight format.(http://symlight.joachims.org/)

Value

A sparse matrix is returned if the file is loaded or downloaded successfully.

Author(s)

```
Zhong Wang (Rinterface) <zw355@cornell.edu>
```

Examples

```
mat <-load.svmlight("http://www.csie.ntu.edu.tw/~cjlin/libsvmtools/datasets/multiclass/glass.scale")
str(mat);</pre>
```

plot.gtsvm

Scatter plot for classification models

Description

A scatter figure is generated for the classification model trained by the svm. The figure only shows two feature columns within training data. Optionally, a filled contour is predicted and added to the class regions.

Usage

Arguments

X	an object of class gtsvm generated by svm.
data	data frame with the training data.
formula	formula object indicating two feature columns used as the X axis and Y axis if more than two feature columns in the training data.
fill	logical value indicating whether a contour plot for the class regions is added.
grid	integer value indicating the grid number to generating the the contour if fill = TRUE.
slice	a list of feature columns that are constant during the predicting for the grid contour if training data has more than two feature columns. all feature columns but two feature columns used in the X axis and Y axis must be held constant to generate a grid contour prediction. In order to generate a contour, except two feature columns of X axis and Y axis, other feature columns hold constant values for predicting. Default unspecified feature columns use 0 for numeric variables and the first level for factors.

plot.tune 5

symbolPalette	Color palette indicating the color of the class data points and support vectors
	belong to.
svSymbol	character or integer code indicating plot character or symbol for support vectors, check the available values in pch in points function.
dataSymbol	character or integer code indicating plot character or symbol for non-support vectors, check the available values in pch in points function.
	additional graphics parameters passed to filled.contour or plot.

Author(s)

```
David Meyer
<David.Meyer@R-project.org>
```

See Also

svm

Examples

plot.tune

Plot performance of tuning object

Description

Contour or perspective plot to visualize the performace of tuning results. It is limited to two tuning parameters.

Usage

6 plot.tune

Arguments

x	an object of class tune generated by the tune.svm
type	string indicating whether a contour plot or a perspective plot is used if two parameters shall be plotted. Ignored if only one tuning parameter in the x.
theta	numeric value indicating angle of azimuthal direction for perspective plot.
col	the $color(s)$ of the surface facets for the perspective plot. Ignored if transparent colors are specified.
main	string indicating main title.
xlab	string or expression indicating titles for the X axes.
ylab	string or expression indicating titles for the Y axes.
swapxy	logical value indicating whether the parameter axes are swapped, only used in case of two parameters.
transform.x	function indicating how to transform the first parameter in \boldsymbol{X} axis. Ignored if NULL.
transform.y	function indicating how to transform the second parameter in \boldsymbol{Y} axis. Ignored if NULL.
transform.z	function indicating how to transform the error measures in \boldsymbol{Z} axis in the perspective plot or color palette in the contour plot. Ignored if NULL.
color.palette	color palette used in the contour plot.
nlevels	integer value indicating number of levels used in the contour plot.
• • •	additional graphics parameters passed to filled.contour or persp.

Author(s)

```
David Meyer (based on C/C++-code by Chih-Chung Chang and Chih-Jen Lin) 
 \mbox{\tt CDavid.Meyer@R-project.org>}
```

See Also

```
tune.svm
```

Examples

```
data(iris) obj <- tune.svm(Species~., data = iris, sampling = "fix", gamma = 2^c(-8, -4, 0, 4), cost = 2^c(-8, -4, -2, 0)) plot(obj, transform.x = log2, transform.y = log2) plot(obj, type = "perspective", theta = 120, phi = 45)
```

predict.gtsvm 7

predict.gtsvm	Predict method for SVMs on CUDA-enabled GPU	
predict.gtsvm	Predict method for SVMs on CUDA-enabled GPU	

Description

This function performs prediction based on a SVM model trained by svm in package Rgtsvm.

Usage

Arguments

object	an object of class "gtsvm" returned by svm in Rgtsvm package.
newdata	data frame, or matrix, or sparse matrix of the test data. A vector test data must transform to a $n \times 1$ matrix.
decision.values	S
	logical value indicating whether the decision values of binary classification or multiclass classification shall be returned. Only valid for classification.
probability	logical value indicating whether class probabilities should be computed and returned.
verbose	logical value indicating whether some alogrithm information is output into the R console, default is FALSE.
	Unused currently.
na.action	a function to specify the action to be taken if NAs are found. The default action is na.omit, which leads to rejection of cases with missing values on any required variable. An alternative is na.fail, which causes an error if NA cases are found.

Value

A vector of predicted values or labels are returned.

If decision.values is required, the vector has a "decision.values" attribute containing a decision matrix with number of samples in rows and number of classes and in columns.

(NOTE: If given, this argument must be named.

If probability is required, the vector has a "probabilities" attribute containing a decision matrix with number of samples in rows and number of classes and in columns, only valid for C-classification.

8 predict.load

Note

The test data can be an object containing the new input data: data frame, or matrix, or a sparse matrix. The sparse matrix can be defined by the class Matrix provided by the Matrix package, or the class matrix.csr provided by the SparseM package, or the class simple_triplet_matrix provided by the slam package)

If the training data was scaled by the svm calling, this function shall scale the test data accordingly using scale and center of the training data.

Author(s)

```
Zhong Wang (R interface & eps-regression in CUDA) <zw355@cornell.edu> David Meyer (R interface in e1071) <David.Meyer@R-project.org> Andrew Cotter, Nathan Srebro ,Joseph Keshet (C/C++ code in CUDA) http://ttic.uchicago.edu/~cotter/projects/gtsvm/
```

See Also

svm

predict.load

Load and initialize a training model on CUDA-enabled GPU

Description

This function loads and initializes a SVM model trained by svm in package *Rgtsvm*. This function works with predict.run and predict.unload to implement the phased prediction with 3 steps: model loading, multiple predicting call, removing model from GPU. It is suitable for the prediction with huge samples using a big training model.

Usage

```
predict.load(object, n.GPU=1, verbose=FALSE )
```

Arguments

object an object of class "gtsvm" returned by svm in Rgtsvm package.

n.GPU number of GPU cards, indicating multiple GPU cards are available for the pre-

diction in parallel.

verbose logical value indicating whether some alogrithm information is output into the

R console, default is FALSE.

Value

A slim model with one external pointer returned by the C/C++ functions is returned. The feature vectors and fitting information are removed in order to reduce the memory usage.

Author(s)

Zhong Wang (R interface & eps-regression in CUDA) <zw355@cornel1.edu>

predict.run 9

See Also

```
predict.gtsvm
```

predict.run

Run prediction using a loaded model on CUDA-enabled GPU

Description

This function performs the phased prediction using 3 steps, which are model loading, prediction based on model, and model unloading. This prediction step can be called by multiple times.

Usage

```
predict.run(object, newdata,
    decision.values = FALSE,
    probability = FALSE,
    verbose=FALSE,
    ...,
    na.action = na.omit)
```

Arguments

object an object of class "gtsvm" returned by predict.load in Rgtsvm package.

newdata data frame, or matrix, or sparse matrix of the test data. A vector test data must

transform to a n x 1 matrix.

decision.values

logical value indicating whether the decision values of binary classfication or

multiclass classification shall be returned. Only valid for classification.

probability logical value indicating whether class probabilities should be computed and re-

turned.

verbose logical value indicating whether some alogrithm information is output into the

R console, default is FALSE.

... Unused currently.

na.action a function to specify the action to be taken if NAs are found. The default action is

na.omit, which leads to rejection of cases with missing values on any required variable. An alternative is na.fail, which causes an error if NA cases are found.

(NOTE: If given, this argument must be named.

Value

A vector of predicted values or labels are returned. The structue is same as predict.gtsvm.

If decision.values is required, the vector has a "decision.values" attribute containing a decision matrix with number of samples in rows and number of classes and in columns.

If probability is required, the vector has a "probabilities" attribute containing a decision matrix with number of samples in rows and number of classes and in columns, only valid for C-classification.

Note

```
See predict.gtsvm
```

10 predict.unload

Author(s)

Zhong Wang (R interface & eps-regression in CUDA) <zw355@cornel1.edu>

See Also

```
predict.load, predict.unload
```

Examples

```
data(iris)
attach(iris)

## classification training
model <- svm(Species ~ ., data = iris)

object <- predict.load(model);
r <- predict.run(object, newdata = iris, decision.values = TRUE )
predict.unload(object);
show(r);</pre>
```

predict.unload

Unload SVM object allocated on CUDA-enabled GPU

Description

This function is cleanup step in the phased prediction which is suitable for the multiple predicting calls using a big model.

Usage

```
predict.unload(object, verbose=FALSE )
```

Arguments

object an object of class "gtsvm" returned by predict.load in *Rgtsvm* package. verbose logical value indicating whether some alogrithm information is output into the

R console, default is FALSE.

Value

None. The procedure will be interrupted if any errors happen.

Author(s)

Zhong Wang (R interface & eps-regression in CUDA) <zw355@cornel1.edu>

See Also

```
predict.run, predict.load
```

svm 11

svm

Training a model of SVMs on CUDA-enabled GPU

Description

svm in the **Rgtsvm** pakcage is used to train a support vector machine by C-classfication or epsilon regression on CUDA-enabled GPU.

Usage

```
## S3 method for class 'formula'
svm(formula, data = NULL, ..., subset, na.action = na.omit, scale = TRUE);
## Default S3 method:
svm(x,
     y = NOLL,
scale = TRUE,
type = "C-classification",
kernel = "radial",
degree = 3,
if (is.vector(x)) 1
                    = if (is.vector(x)) 1 else 1/ncol(x),
                    = 0,
      coef0
      cost
      class.weights= NULL,
       tolerance = 0.001,
      epsilon = 0.1,
      shrinking = TRUE,
      cross
                  = 0,
      probability = FALSE,
                 = TRUE,
      fitted
      rough.cross = 0,
      no.change.x = TRUE,
      verbose
                 = FALSE,
       . . . ,
      subset,
      na.action = na.omit)
```

Arguments

formula	a formula object describing the training model.
data	an optional data frame containing the variables in the model. By default the variables are taken from the environment which 'svm' is called from.
X	a data matrix, or a vector, or a sparse matrix as training data.
у	a factor (for C-classification) or a numeric vector (for eps-regression) specifying the response for each row of x .
scale	logical value or a logical vector, indicating whether the feature columns are scaled. By default, both x and y variables are scaled to zero mean and unit variance. The center and scale values are returned and can be used for scaling new test data.

12 svm

string indicating the SVM method, only C-classification or eps-regression type available, default is C-classification the kernel function used in training and predicting, four options are available kernel (attached in details), default is radial. degree integer value indicating parameter value used in kernel of type polynomial, default is 3. numerical value indicating parameter value needed for all kernels except linear, gamma default is 1/(number of feature vector)). numerical value indicating parameter value used in kernels of type polynomial coef0 and sigmoid, default is 0. numerical value indicating regularization term in the Lagrange formulation, which cost is cost of constraints violation, default is 1. class.weights a named vector of weights for the different classes, used for asymmetric class sizes. Not all factor levels have to be supplied (default weight: 1). All components have to be named. tolerance numerical value indicating the tolerance of termination criterion for the training algorithm, default is 0.001. epsilon numerical value indicating epsilon in the insensitive-loss function for the eps-regression method, default is 0.1. logical value indicating whether to use the shrinking-heuristics, default is TRUE. shrinking integer value indicating whether a k-fold cross validation on the training data is cross performed to assess the quality of the model. Ignored if corss=0. integer value which is less than cross, indicating how many tests are performed rough.cross for cross-validation. The function will return partial tests for cross-validation rather than all repeated tests in order to reduce the running time. fitted logical value indicating whether the prediction should be performed and returned in the function calling, default is TRUE. logical value indicating whether the model should allow for probability predicprobability logical value indicating whther the function can change the x parameter. It no.change.x would save CPU memory if this parameter is assigned to FALSE for the big matrix x. verbose logical value indicating whether some alogrithm information is output on R console, default is FALSE. additional parameters for the low level fitting function sym.default a vector of index values specifying the cases to be used in the training sample. subset (NOTE: If given, this argument must be named.) na.action a function to specify the action to be taken if NAs are found. The default action is na.omit, which leads to rejection of cases with missing values on any required variable. An alternative is na. fail, which causes an error if NA cases are found. (NOTE: If given, this argument must be named.)

Details

Rgtsvm uses a sparse matrix and regular matrix. The sparse matrix can be defined by the class Matrix provided by the **Matrix** package, or the class matrix.csr provided by the **SparseM** package, or the class simple_triplet_matrix provided by the **slam** package)

svm 13

The kernel function has the following parameters, depending on the kernel type.

linear: u'v

polynomial: $(\gamma u'v + coef0)^{degree}$ radial basis: $e^{(-\gamma|u-v|^2)}$ sigmoid: $tanh(\gamma u'v + coef0)$

plot.gtsvm provides a simple visualization method for the classification model trained by svm.

Value

This function returns a trained model. It is an object of class "gtsvm" with following properties:

total.nSV the total number of support vectors.

nSV the number of support vectors in each group.
SV the resulting support vectors (possibly scaled).

index the index of the resulting support vectors in the data matrix. Note that this index

refers to the preprocessed data (after the possible effect of na.omit and subset)

coefs the corresponding coefficients multiply the training labels.

rho the negative intercept.

fitted the prediction values if fitted=TRUE

fitted.accuracy

The predicted accuracy for C-classification if fitted=TRUE.

fitted.MSE the mean square error for eps-regression if fitted=TRUE.

fitted.r2 the R square for eps-regression if fitted=TRUE.

residuals the difference between the true values and prediction for eps-regression if

fitted=TRUE.

MSE the mean square errors at each cross-validation test for eps-regression if

cross>0.

tot.MSE the mean square error in cross-validation for eps-regression if cross>0.

scorrcoeff the R square in cross-validation for eps-regression if cross>0.

accuracies the accuracies at each cross-validation test for C-classification if cross>0. tot.accuracy the total accuracies in cross-validation for C-classification if cross>0.

compprob logical values if probability is predicted.

probA numerical value indicating (1) the parameter A of the logistic distributions fit-

ted to the decision values of the binary classifiers (2) the \gamma coefficient of the softmax function for the multi-classification in one-agianst-rest mode. (3) the \zeta parameter of the Laplace distributions for the eps-regression if

 $\verb|probability==TRUE|.$

probB numerical value indicating the parameter B of the logistic distributions fitted to

the decision values of the binary classifiers if probability==TRUE.

Author(s)

Zhong Wang (R interface & epe-regression in CUDA) <zw355@cornell.edu> David Meyer (R interface in e1071) <David.Meyer@R-project.org> Andrew Cotter, Nathan Srebro ,Joseph Keshet (C/C++ code in CUDA) http://ttic.uchicago.edu/~cotter/projects/gtsvm/

14 tune.control

References

 Andrew Cotter, Nathan Srebro, Joseph Keshet. "A GPU-Tailored Approach for Training Kernelized SVMs". 17th ACM SIGKDD Conference on Knowledge Discovery and Data Mining. 2011

```
    Chang, Chih-Chung and Lin, Chih-Jen:

    LIBSVM: a library for Support Vector Machines

    http://www.csie.ntu.edu.tw/~cjlin/libsvm
```

See Also

```
predict.gtsvm plot.gtsvm matrix.csr (in package SparseM)
```

Examples

```
data(iris)
attach(iris)
## classification mode
# default with factor response:
model <- svm(Species ~ ., data = iris)</pre>
# alternatively the traditional interface:
x <- subset(iris, select = -Species)</pre>
y <- Species
model <- svm(x, y)
print(model)
summary(model)
# test with train data
pred <- predict(model, x)</pre>
# Check accuracy:
table(pred, y)
# compute decision values and probabilities:
pred <- predict(model, x, decision.values = TRUE)</pre>
attr(pred, "decision.values")[1:4,]
# visualize (classes by color, SV by crosses):
plot(cmdscale(dist(iris[,-5])),
     col = as.integer(iris[,5]),
     pch = c("o","+")[1:150 \%in\% model\$index + 1])
```

tune.control

Control parameters for the tune function

Description

Creates an object of class tune.control to be used with the tune.svm function, containing various control parameters.

tune.control 15

Usage

```
tune.control(random = FALSE,
    nrepeat = 1,
    repeat.aggregate = mean,
    sampling = c("cross", "fix", "bootstrap"),
    sampling.aggregate = mean,
    sampling.dispersion = sd,
    cross = 10,
    fix = 2/3,
    nboot = 10,
    boot.size = 9/10,
    best.model = TRUE,
    performances = TRUE,
    rough.cross = 0,
    error.fun = NULL)
```

Arguments

random FALSE or an integer value, indicating whether or how many parameter combina-

tions are drawn from the parameter space.

nrepeat integer value, specifies how many replication of training and prediction shall be

repeated, default is 1.

repeat.aggregate

function, used to aggregate the replicates results, default is mean.

sampling string value indicating sampling scheme, three sampling methods are available,

default is cross.

sampling.aggregate

function to aggregate the test results for each parameter combination, default is

nean.

sampling.dispersion

function to disperse the test results for each parameter combination, default is

sd.

cross integer value, used if sampling = "cross", indicating the number of partitions

for cross-validation, default is 10.

fix numeric value, used if sampling = "fix", part of the data used for training in

fixed sampling., default is 2/3

nboot integer value, used if sampling = "boot", indicating number of bootstrap

replications.

boot.size numeric value, used if sampling = "boot", indicating size of the bootstrap

samples.

best.model logical value, indicating whether the best model is returned based on the the best

parameter set on the complete training set).

performances logical value, indicating whether the performance results for all parameter com-

binations are returned.

rough.cross integer value if sampling = "cross", indicating how many training and test-

ing for cross-validation are conducted, it is intended to reduce the computation time by decreasing the cross-validation jobs while maintaining the higher cross

number.

16 tune.svm

error.fun

function for the error measure, It takes two arguments: a vector of true values and a vector of predicted values. If NULL, the misclassification error is used for categorical predictions and the mean squared error for numeric predictions.

Details

Three options for sampling are available:

```
1: sampling = "cross", a cross-times cross validation.
```

2: sampling = "boot", sampling with replacement on the nboot training sets of boot.size (part).

3: sampling = "fix", the dataset is split into a training set of size fix and validation set.

Value

An object of class "tune.control" containing all the above parameters (either the defaults or the user specified values).

Author(s)

```
David Meyer
<David.Meyer@R-project.org>
```

See Also

tune.svm

tune.svm

Parameter tuning function using grid search

Description

tune.svm() tunes hyperparameters of statistical methods using a grid search over supplied parameter ranges. best.tune() returns the best model detected by tune.svm.

Usage

```
tune.svm(x, y = NULL, data = NULL, degree = NULL, gamma = NULL,
    coef0 = NULL, cost = NULL, nu = NULL,
    class.weights = NULL, epsilon = NULL,...)
best.tune(...)
```

tune.svm 17

Arguments

X	formula object or training matrix.
У	vector indicating the response variable only if train.x is not a formula object, otherwise ignore.
1.4.	
data	data frame only if the formula interface is used in train.x, otherwise ignore.
degree	a numeric vector indicating the tuning values for the parameter degree.
gamma	a numeric vector indicating the tuning values for the parameter gamma.
coef0	an numeric vector indicating the tuning values for the parameter coef0.
cost	a numeric vector indicating the tuning values for the parameter cost.
nu	a numeric vector indicating the tuning values for the parameter nu.
class.weights	a numeric vector indicating the tuning values for the parameter class.weights.
epsilon	a numeric vector indicating the tuning values for the parameter epsilon.
	Further parameters passed to the training functions, i.e. svm, tune.

Details

To measure performance, classification error and mean squared error can be used for the classification and epsilon regression respectively.

Value

```
This function return an object of class tune, including the components:
```

```
\verb|best.parameters|
```

a 1 x k data frame, k number of parameters.

best.performance

value, best achieved performance.

performances if requested, a data frame of all parameter combinations along with the corre-

sponding performance results.

train.ind list of index vectors used for splits into training and validation sets.

best.model if requested, the model trained on the complete training data using the best pa-

rameter combination.

Author(s)

```
David Meyer
<David.Meyer@R-project.org>
```

See Also

```
tune.control, plot.tune
```

Examples

```
data(iris)
## tune `svm' for classification with RBF-kernel (default in svm),
## using one split for training/validation set
obj <- tune.svm(Species~., data = iris, gamma = 2^(-1:1), cost = 2^(2:4))
summary(obj)
plot(obj)</pre>
```

Index

```
*Topic data loading
    attach.bigmatrix, 2
                                                  sd, 15
    load.bigmatrix, 3
    load.svmlight, 3
*Topic plot
    \verb"plot.gtsvm", 4"
    plot.tune, 5
*Topic predict
    predict.gtsvm, 7
    predict.load, 8
    predict.run, 9
    predict.unload, 10
*Topic svm
    plot.gtsvm, 4
    svm, 11
*Topic tuning
    plot.tune, 5
    tune.control, 14
    tune.svm, 16
attach.bigmatrix, 2, 3
best.tune (tune.svm), 16
filled.contour, 6
load.bigmatrix, 2, 3
load.svmlight, 3
Matrix, 8, 12
matrix.csr, 8, 12, 14
mean, 15
persp, 6
plot.gtsvm, 4, 13, 14
plot.tune, 5, 17
points, 5
predict, 2, 3
predict.gtsvm, 7, 9, 14
predict.load, 8, 9, 10
predict.run, 8, 9, 10
predict.unload, 8, 10, 10
print.gtsvm(svm), 11
print.summary.gtsvm(svm), 11
print.summary.tune (tune.svm), 16
```

18

```
print.tune (tune.svm), 16
simple_triplet_matrix, 8, 12
summary.gtsvm(svm), 11
summary.tune(tune.svm), 16
svm, 2-5, 7, 8, 11, 13, 17
tune.control, 14, 17
tune.svm, 6, 16, 16
```