Building the Spout libraries

Visual Studio 2017 and 2022 projects are available in the "SPOUTSDK\SpoutGL" folder to build the Spout SDK as a dll.

Equivalent projects can also be found in the "SPOUTSDK\SpoutLibrary" folder to create a C-compatible dll that can be used with other compilers. Pre-built binaries for 32 bit and 64 bit are also available in the "SPOUTSDK\SpoutLibrary\Binaries" folder.

CMAKE build

The libraries can also be built using Cmake. (https://cmake.org). This may be preferable, or necessary if you are using a compiler other than Visual Studio.

Installation

- 1) Download and install CMake for Windows. The easiest way is to use the installer. At the time of writing this was "cmake-3.25.1-x86-64.msi". Get it from the downloads page (https://cmake.org/download/).
- 2) Run the installer. Default options are OK, but it's useful to create a Desktop icon. "Finish" to complete.

Generating a project

- 1) On the desktop, find the CMake icon and open the CMake GUI.
- 2) For "Where is the source code:", click "Browse Source", navigate to wherever you saved the Spout repository and select the root folder, usually named "Spout2".
- 3) For "Where to build the binaries:", click "Browse Build" and navigate to "Spout2\BUILD".
- 4) At bottom click "Configure" to open the configuration dialog.
- 5) For "Specify the generator for this project", select your compiler and other options you may require. "Optional platform ..." will be empty. Default build is 32 bit. Leave it at that for now and other defaults. Click "Finish".

After completion you will see various build settings in red.

- ✓ SKIP_INSTALL_ALL do not generate an INSTALL project to produce header and library folders. Default is off. Generally you can leave this checkbox empty because the INSTALL project is a separate build. Default is off for the following two options.
- ✓ SKIP_INSTALL_HEADERS do not generate header files with the INSTALL project.
- ✓ SKIP_INSTALL_LIBRARIES do not generate library files with the INSTALL project.
- ✓ SPOUT_BUILD_CMT for Visual Studio compilers, this sets a project option to include the runtime libraries into the dll. Then the user does not need to install the runtime separately. Check it off if you know what you are doing. Leave it on if you are unsure.
- ✓ SPOUT_BUILD_LIBRARY builds a C-compatible library "SpoutLibrary" which could be of interest if you are not using Visual Studio.
- ✓ SPOUT_BUILD_SPOUTDX builds the Spout DirectX11 support class "SpoutDX" as a dynamic link library. Default is off.
- ✓ SPOUT_BUILD_SPOUTDX_EXAMPLES build the examples for using the SpoutDX support class for DirectX 11. Default is off.

Finally Click "Generate".

Building the projects

When you see "Generating done", click "Open Project". In the compiler IDE you will see the following projects:

ALL_BUILD INSTALL

Spout_static (Spout SDK static library)

SpoutDX (SpoutDX support class - option)
SpoutLibrary (C compatible Spout library - option)

Spout.dll (Spout SDK dll)

Tutorial04 (DirectX11 SpoutDX sender example - option)
Tutorial07 (DirectX11 SpoutDX receiver example - option)
WinSpoutDXreceiver (Windows SpoutDX receiver example - option)
WinSpoutDXsender (Windows SpoutDX sender example - option)

ZERO_CHECK

ALL_BUILD

Build "ALL_BUILD" and, when it has finished, browse to the "BUILD" folder you previously selected. In the "Binaries" folder you will find :

Win32

SpoutSDK.lib SpoutSDK.dll SpoutLibrary.lib SpoutLibrary.dll SpoutDX.lib SpoutDX.dll Spout_static.lib

- SpoutSDK the Spout SDK built as a dynamic link library
- SpoutLibrary a C-compatible library dynamic link library
- SpoutDX Spout DirectX support class as a dynamic link library
- Spout static.lib the Spout SDK built as a static library

SpoutDX examples

Note that when building the SpoutDX examples with Visual Studio project, ALL_BUILD is the default "Startup Project". Right click on the executable project you are interested in and select as "Startup Project" from the context menu.

INSTALL

This is a separate project that produces all the files you need for the libraries in conveniently arranged folders instead of ALL_BUILD or the separate projects :

bin - dll files include - header diles SpoutDX SpoutGL SpoutLibrary lib - library files

Changing the CMake options

- 1) Close compiler IDE
- 2) Start CMake GUI if it has been closed
- 3) Select any of the options available and check ON or OFF
- 4) Click "Generate" again to set the new options.
- 5) "Open Project" and re-build

Changing Platform

For example to build 64 bit instead of the default 32 bit.

- 1) From the CMake GUI select "File > Delete cache" and do it.
- 2) Click "Configure"
- 3) This time, select the "Optional platform" that you want. For Visual Studio there is a drop-down list and the "x64" option.
- 4) "Generate", "Open Project", change to "Release" and build.

In the "Binaries" folder you will find an "x64" folder with the 64 bit versions of the libraries. They have the same names so be careful not to mix them up.

Credit

Thanks and credit for the CMake files which were first developed and contributed by Alexandre Buge (https://github.com/Qlex42) and revisions by Jean-Michaël Celerier (https://github.com/jcelerier).