Lecture8 Demand Paging

1. Demand Paging Mechanisms


How to go beyond physical memory

- How to support large address space?
 - 64-bit machine supports up to 4EB address space
 - Applications may use more space than available in physical memory
- Solution: stash away portions of address spaces that aren't currently in use
 - in the **next-level of storage** (e.g., hard disk drive)
 - slower but much larger

An abstraction of Address Space


- Application: memory overlays
 - Application in charge of moving data between memory and disk
 - e.g., calling a function needs to make sure the code is in memory
- OS: demand paging
 - OS configures page table entries
 - Virtual page maps to physical memory or files in disk
 - **Process** sees an abstraction of address space
 - OS determines where the data is stored

Swap Space



- Swap space is a partition or a file stored on the disk
 - OS swaps pages out of memory to it
 - OS swaps pages from it into memory
- Swap space conceptually divided into page-sized units
 - OS maintains a disk address of each page-sized unit

Example



- 4-page physical memory and an 8-page swap space
 - Proc 0 has three virtual pages
 - Proc1 has four virtual pages
 - Proc 2 and Proc 3 each has two virtual pages


Demand Paging


- Load pages from disk to memory only as they are needed
 - Pages are loaded "on demand"
- Data transferred in the unit of pages
- Two possible on-disk locations
 - Swap space
 - created by OS for temporary storage of pages on disk
 - e.g., pages for stack and heap
 - Program binary files
 - The code pages from this binary are only loaded into memory when they are executed
 - Read-only, thus never write back

Physical Memory as a Cache

- Physical memory can be regarded as a cache of on-disk swap space
- Block size of the cache: 1 page(4 KB)
- Cache organization (direct-mapped, set-associative, fully-associative)
 - Fully associative: any disk page maps to any page frame
- Page replacement policy
 - LRU, Random, FIFO
- Page miss
 - Go to lower level to fill page (i.e. disk)

Present Bit





Page Faults

- Present bit = 0 raises a page fault exception
 - OS gets involved in address translation
- Page fault handler
 - Find free page frame in physical memory
 - Find one free page frame from a free-page list
 - If no free page, trigger page replacement
 - Fetch page from disk and store it in physical memory
 - Determine the faulting virtual address from register
 - Locate the disk address of the page in PTE (where PFN should be stored)
 - Issues a request to disk to fetch the page into memory
 - Wait (could be a very long time, context switch)
 - When I/O completes, update page table entry, PFN, present bit
- After page fault
 - Return from page fault exception
 - CPU re-execute the instruction that accesses the virtual memory
 - No more page fault since present bit is set this time

• TLB entry loaded from PTE


Page Replacement

- find a page frame to be replaced
 - Page replacement policy decides which one to replace
- If page frame to be replaced is dirty, write it back to disk
- Update all PTEs pointing to the page frame
- Invalidate all TLB entries for these PTEs

When to trigger page replacement

- <u>Lecture13 Deadlock.assets</u> Proactive page replacement usually leads to better performance
 - Page replacement even though no one needs free page frames (yet)
 - o Always reserve some free page frames in the system
- Swap daemon
 - background process for reclaiming page frames
 - Low watermark: a threshold to trigger swap daemon
 - **High watermark**: a threshold to stop reclaiming page frames

Put it all together



2. Page Replacement Policy

Effective Access Time (EAT)

- EAT = Hit Rate x Hit Time + Miss Rate x Miss Penalty
- Example
 - Memory access time: 200ns
 - Average page-fault service time: 8 ms
 - Suppose p = Probability of miss, 1 p = Probability of hit

- \circ EAT = (1-p) x 200ns + p x 8ms
- If one access out of 1,000 causes a page fault, then EAT is about 8.2 μs
 - This is a slowdown by a factor of 40
- If we want slowdown by less than 10%
 - which means EAT < 220 ms
 - This is about 1 page fault in 400,000

Types of Cache Misses

- Compulsory Misses
 - Cold-start miss: pages that have never been fetched into memory before
 - o Prefetching: loading them into memory before needed
- Capacity Misses
 - Not enough memory: must somehow increase available memory size
 - One option: Increase amount of DRAM (not quick fix!)
 - Another option: If multiple processes in memory: adjust percentage of memory allocated to each one
- Conflict Misses
 - fully-associative cache (OS page cache) does not have conflict misses

Page Replacement Policies

Suppose we have 3 page frames, 4 virtual pages, and following reference string:

ABCABDADBCB

Optimal / MIN

- Replace page that will not be used for the longest time
- Lead to minimum page faults in theory

Ref: Page:	Α	В	С	Α	В	D	Α	D	В	С	В
Page:											
1	Α									С	
2		В									
3			С			D					

• MIN: 5 faults

FIFO

- Throw out oldest page first
- May throw out heavily used pages instead of infrequently used

Ref:	Α	В	С	Α	В	D	Α	D	В	С	В
Page:											
_	Α					D				C	
2		В					Α				
3			С						В		

RANDOM

- Pick random page for every replacement
- Pretty unpredictable makes it hard to make real-time guarantees

Least Recently Used (LRU)

- Replace page that has not been used for the longest time
- Temporal locality of program
 - If a page has not been used for a while, it is unlikely to be used in the near future

Ref: Page:	Α	В	С	Α	В	D	Α	D	В	С	В
Page:											
I	Α									С	
2		В									
3			С			D					


- LRU is not always the optimal
 - Consider the following reference string: ABCDABCDABCD

Ref: Page:	Α	В	С	D	Α	В	С	D	Α	В	С	D
Ι	Α			D			С			В		
2		В			Α			D			С	
3			С			В			Α			D

Least Frequently Used (LFU)

- Replace page that has not been accessed many times
- Spatial locality of program
 - If a page has been accessed many times, perhaps it should not be replaced as it clearly has some value

Bélády's Anomaly



- One desirable property: When you add memory the miss rate drops
 - Yes for LRU and MIN
 - Not necessarily for FIFO. For FIFO, more page frames may lead to more page faults

Example




Ref: Page:	A	В	U	Δ	Α	В	Ε	Α	В	С	Δ	Е
1	Α						Ε				D	
2		В						Α				Е
3			С						В			
4				D						С		

Page Fault Curve

Page fault curve for FIFO on reference string

• 70120304230321201701




3. LRU Implementation


- Hardware support is necessary
 - Update a data structure in OS upon every memory access
 - E.g., a timestamp counter for each page frame
- Overhead
 - One additional memory write for each memory access
 - TLB hit does not save the extra memory access
 - Scan the entire memory to find the LRU one
 - 4GB physical memory has 1 million page frames
 - sorting is time consuming


LRU Approximation with Reference Bit


- Reference bit
 - One reference bit per page frame
 - All bits are cleared to 0 initially
 - The first time a page is referenced, the reference bit is set by CPU
 - Can be integrate with page table walk
 - The order of page accesses approximated by two clusters: used and unused pages
- Examples
 - Clock algorithm (also called second-chance algorithm)
 - Enhanced clock algorithm with dirty bits

Clock Algorithm









- Arrange physical pages in a circular list
- CPU sets reference bit to 1 upon first access
- OS maintains a pointer
 - When a replacement occur, check reference bit of the current page
 - If 1: the page has been accessed recently, clear the bit (set to 0) and move to the next page
 - If 0: the page has not been accessed recently, good candidate for replacement, stop

With dirty bit

- Enhance clock algorithm with a dirty bit
 - dirty bit = 1: the page has recently been modified
- CPU sets dirty bit to 1 upon write access


• When a replacement occurs, OS checks (ref bit, dirty bit), and selects a candidate page in decreasing order

Reference bit	Dirty bit	Description
0	0	neither recently used nor modified — best page to replace
0	1	not recently used but modified — not quite as good, because the page will need to be written out before replacement
1	0	recently used but clean — probably will be used again soon
1	1	recently used and modified — probably will be used again soon, and the page will be need to be written out to secondary storage before it can be replaced

LRU Approximation with Reference Bit and Counter

- Each physical page frame is associated with one reference bit and a counter
 - Reference bit indicate recent access
 - set by CPU hardware, cleared by OS
 - Counter records history of accesses
 - Maintained by OS

Additional-reference-bits Algorithm



- 8-bit history register associated with each page frame
- Timer interrupt every 100ms
 - reference bit shifts to **highest bit** in the history register
 - o other bits shift right and discard the lowest bit
 - 00000000 unused page in 800ms
- Compare history register as unsigned integer
 - Larger value more recently used
 - 11000100 > 01110111

• Approximate LRU with more bits and more frequent interrupts

Nth-chance Clock Algorithm

- All page frames arranged in a circular list and each page frame is associated with a reference bit and a counter
- CPU hardware sets reference bit upon memory accesses
- OS checks the reference bit of the page pointed to by the clock hand
 - 1 -> clear reference bit and the counter
 - 0 -> increment counter; if count = N, replace page
- How do we pick N
 - Large N: better approximation of LRU
 - If N = 1K, really good approximation
 - Small N: more efficient
 - otherwise might have to look a long way to find free page

4. Page Frame Allocation

- How do we allocate memory among different processes?
 - Does every process get the same fraction of memory? Different fractions
 - Should we completely swap some processes out of memory?
- Minimum number of pages per process
 - Depends on the computer architecture
 - How many pages would one instruction use at one time
 - x86 only allows data movement between memory and register and no indirect reference
 - needs at least one instruction page, one data page, and some page table pages
- Maximum number of pages per process
 - Depends on available physical memory

Global versus Local Allocation

- Global replacement
 - Process selects replacement frame from all page frames
 - One process can take a frame from another process
- Local replacement
 - Each process selects from only its **own set of allocated frames**

Allocation Algorithms

- Equal allocation
 - Every process gets same amount of memory
 - Example: 100 frames, 5 processes -> process gets 20 frames
- Proportional allocation
 - Number of page frames proportional to the size of process
 - $\circ \hspace{0.1in} s_i$ = size of process p_i and m = total number of frame
 - $\circ \ \ a_i$ = allocation for $p_i = m imes rac{s_i}{\sum s_j}$
- · Priority allocation
 - Number of page frames proportional to the priority of process
 - \circ Possible behavior: If process p_i generates a page fault, select for replacement a frame from a process with lower priority number

Trashing

- The **memory demands** of the set of running processes simply **exceeds** the **available physical memory**
- Early OS
 - Working set: the pages used actively of a process
 - Reduce the # of process so their working set fit into memory
- Modern OS
 - Out-of-memory killer when memory is oversubscribed
 - May need a reboot