0 Contents

```
Move Semantics
1.1 Copy . . . .
1.2
     Move . . . . . . .
1.3 Copy Assignment . . . .
1.4 Move Assignment . . . . .
     Rvalue and Lvalue . . . . . . . .
     1.5.1 Convert Ivalue to rvalue .
1.6 Other value types . . . . . . . .
     1.6.1 Temporary Materialization
1 7
    I and rvalue references . . . . . .
1.8 Binds . . . . . . . . . . . . . . . . . .
3
1.10 Default Constructors and user defined Constructors . .
Type Deduction
2.1 Forwarding Reference . . . . . . . . .
                                                                                                                                          3
2.2 Rules for Type Deduction . . . . . . . . . . . .
                                                                                                                                          3
     2.2.1 Deducing Initializer Lists . . . .
     2.2.2
           Deducing auto types . . . . . .
     2.2.3 Type Deduction with Decltype .
     2.2.4 Returns with decltype . . . .
2.3 Checking for r and I-values . . .
     2.3.1 std::move vs std::forward
```

1 Move Semantics

1.1 Сору

By default cpp will always create copies, this is good for memory safety etc, as you will not be returning null values, but it can be a runtime hit! (There are some special types that can't be copied like mutexes etc)

```
// Copy contructor
class something {
   something(const something &other) {
      // copy values from other
   }
}
```

1.2 Move

Move constructor will NOT copy values, instead, it will move these values into the new object, this is better for performance, but it requires more management from the programmer!

Make sure to free the memory at the old object, otherwise you might be dealing with nullpointers!

In short, the move constructor makes a lot of sense when you have *Heap data*, aka if you have something like an array or a vector, then you will want to make sure to always use the move constructor if you can do so.

The default move constructor is as follows:

```
struct S {
   S(S && s) : member{std::move(s.member)}
   {...}
   M member;
}.
```

1.3 Copy Assignment

Default copy assignment constructor:

```
struct S {
  auto operator=(S const& s) -> S& {
    member = s.member;
    return *this;
  }
  M member;
};
```

1.4 Move Assignment

Default move assignment constructor:

```
struct S {
  auto operator=(S&& s) -> S& {
    member = std::move(s.member);
    return *this;
  }
  M member;
};
```

1.5 Rvalue and Lvalue

Ivalue T&: variable with some location in ram, either on the stack or on the heap

rvalue T&&: temporary value that has no variable and no location in memory, it only exists in code

```
int a = 5;
// 5 is an r value, it has no memory location
// a is an lvalue -> some address is set to 5
int b = 10;
int c = a + b;
// a + b is an rvalue -> value is 15, but no memory location for this calculation
// c is an lvalue -> some address is set to 5
```

1.5.1 Convert Ivalue to rvalue


By default you can't just use an Ivalue as an rvalue, however, you can use std::move to explicitly convert an Ivalue to an rvalue.

Note that in this case, you can't use the old variable anymore, as the data has been moved! -> see rust

```
auto consume(Food&& food) -> void;
auto fryBurger() -> Food;
auto fastFood() -> void {
  Food fries{"salty and greasy"};
  consume(fryBurger()); //call with rvalue
  consume(fries); //cannot pass lvalue to rvalue reference
  consume(std::move(fries)); //explicit conversion lvalue to xvalue
  Food&& burger = fryBurger(); //life-extension of temporary
```

1.6 Other value types

has identity?	can be moved from?	Value Category
Yes	No	Ivalue
Yes	Yes	xvalue (expiring value)
No	No (Since C++17)	prvalue (pure rvalue)
No	Yes (Since C++17)	- (doesn't exist anymore)



Ivalue

- address can be taken
- Can be on the left-hand side of an assignment if modifiable
- Can be used to initialize Ivalue references
- Examples: variables, function calls that return reference, increment and decrement operators, array index access if array is Ivalue
- all string literals
- prvalue
 - address can't be taken -> doesn't exist
 - cannot be on the left hand side of assignment
 - temporary "materialization" to xvalue
 - Examples: literals, false, nullptr, function call with non reference return type, postincrement and postdecrement!!
- xvalue
 - address cannot be taken
 - Cannot be used as left-hand operator of built-in assignment
 - Conversion from prvalue through temporary materialization
 - Examples: function calls with rvalue reference return type -> std::move, access of non-references members of an rvalue object, arra index access when array is rvalue

1.6.1 Temporary Materialization

Getting from something imaginary to something you can point to....

When this happens:

- binding a reference to a prvalue
- when accessing a member of prvalue
- when accessing an element of a prvalue array
- when converting a prvalue array to a pointer
- \bullet when initializing an std::initializer_list<T> from a braced-init-list
- Type needs to be complete and needs to have a destructor


```
struct Ghost {
   auto haunt() const -> void {
      std::cout << "bococo!\n";
   }
   //~Ghost() = delete;
};
auto evoke() -> Ghost {
   return Ghost{};
}
auto main() -> int {
   Ghost&& sam = evoke(); // bind reference to a prvalue
   Ghost{}.haunt(); // access member of prvalue
```

1.7 I and rvalue references

- Ivalue reference made only of Ivalues!!
- type: T&
- alias for a variable
- can be used as function member type, local member/variable, return type
- be aware of dangling references when returning!
- rvalue reference made of rvalues, prvalues or xvalues!
- Type: T&&
- when assigned to a name (for example inside of a function), then it is actually an Ivalue!!
- Argument is either a literal or a temporary object

```
std::string createGlass() -> std::string;
void fancyNameForFunction() {
  std::string mug{"cup of coffee"};
  std::string&& glass_ref = createGlass(); //life-extension of temporary
  std::string&& mug_ref = std::move(mug); //explicit conversion lvalue to rvalue
  int&&
  i_ref = 5;
  //binding rvalue reference to prvalue
}
```

1.8 Binds



 Ivalue Reference 	 const Ivalue Reference 	 rvalue Reference 		
■ binds	■ binds	binds		
ohalue rvalue prvalue	glvalue value produce	expr phalue rvalue value produe		
<pre>auto f(Type&) -> void; Type t{}; f(t);</pre>	<pre>auto f(Type const&) -> void; Type t{}; f(t); f(std::move(t)); f(Type{});</pre>	<pre>auto f(Type&&) -> void; Type t{}; f(Type{}); f(std::move(t));</pre>		

	f(S)	f(S &)	f(S const &)	f(S &&)
S s{}; f(s);	√	√ (preferred over const &)	✓	×
<pre>S const s{}; f(s);</pre>	✓	×	✓	×
f(S{});	✓	×	✓	√ (preferred over const &)
<pre>S s{}; f(std::move(s));</pre>	✓	×	✓	√ (preferred over const &)

	S::m()	S::m() const	S::m() &	S::m() const &	S::m() &&
S s{}; s.m();	✓	√	(preferred over const &)	✓	×
<pre>S const s{}; s.m();</pre>	×	✓	×	✓	×
S{}.m();	✓	√	×	√	(preferred over const &)
<pre>S s{}; std::move(s).m();</pre>	1	✓	×	√	(preferred over const &)

1.9 Destructor

Whenever you need to write an explicit destructor, please make sure that you will not throw exeptions here. This can cause memory to not be freed, which... well you guess what heppens In general you should make sure that ANY form of memory management doesn't throw exceptions!!!

1.10 Default Constructors and user defined Constructors

What you get							5	
		default constructor	destructor	copy constructor	copy assignment	move constructor	move assignment	Where
	nothing	defaulted	defaulted	defaulted	defaulted	defaulted	defaulted	you w
0	any constructor	not declared	defaulted	defaulted	defaulted	defaulted	defaulted	want to
What you write	default constructor	user declared	defaulted	defaulted	defaulted	defaulted	defaulted	be
	destructor	defaulted	user declared	defaulted (!)	defaulted (!)	not declared	not declared	
	copy constructor	not declared	defaulted	user declared	defaulted (!)	not declared	not declared	Avoid
	copy assignment	defaulted	defaulted	defaulted (!)	user declared	not declared	not declared	=:
	move constructor	not declared	defaulted	deleted	deleted	user declared	not declared	possible
	move assignment	defaulted	defaulted	deleted	deleted	not declared	user declared	

The ! means that it is a standard library bug, don't use those defaulted ones!!!

Note that deleting a constructor will be the same as "user declared"!!

The problem with func(T const&) When working with const T references, this implies that we can either copy or move it, this means we will not necessarily know what we get.

The only possible way without type deduction is an overload for both.

```
template <typename T>
  auto log_and_do(T const& param) -> void {
  //log
  do_something(param);
} // lvalue
template <typename T>
  auto log_and_do(T&& param) -> void {
  //log
  do_something(std::move(param));
} // lvalue and rvalue!!
```

Note, with more parameters, you would need x amount of overloads for each combination of parameters!!

2 Type Deduction

2.1 Forwarding Reference

A T&& is not always an rvalue! In some cases, it is a forwarding reference, which can be either an Ivalue or an rvalue!!

```
template <typename T>
auto f(T && param) -> void;

// lvalue
int x = 23;
f(x);
// auto f(int & param) -> void; (inferred)

// rvalue
f(23);
// auto f(int && param) -> void; (inferred)
```

2.2 Rules for Type Deduction

```
// base function
template <typename T>
auto f(T param) -> void;
```

```
// type usages with function instances and deduced T
int x = 23; // f(x) = f(int param) -> T = int
int const cx = x; // f(cx) = f(int param) -> T = int
int const& cx = x; // f(cx) = f(int param) -> T = int
char const * const ptr = /* something */; // f(ptr) = f(char const * param) -> T = char const*;
// -- ignore outermost const
// -- ignore reference types
// -- take base type
// base function 2
template <typename T>
auto f(T & param) -> void;
// type usages with function instances and deduced T
              x = 23; // f(x) = f(int& param) -> T = int
cx = x; // f(cx) = f(int const& param) -> T = int const
& crx = x; // f(crx) = f(int const& param) -> T = int const
int
int const
int const& crx = x;
// -- ignore reference type
// base function 3
template <typename T>
auto f(T const& param) -> void;
// type usages with function instances and deduced T
int x = 23; // f(x) = f(int const & param) -> T = int int const <math>cx = x; // f(cx) = f(int const & param) -> T = int int const <math>cx = x; // cx = f(int const & param) -> T = int int const <math>cx = x; // cx = f(int const & param) -> T = int int const <math>cx = x; // cx = f(int const & param) -> T = int int const <math>cx = x; // cx = f(int const & param) -> T = int int const <math>cx = x; // cx = f(int const & param) -> T = int int const <math>cx = x; // cx = f(int const & param) -> T = int int const <math>cx = x;
// -- ignore reference types
// -- take base type
// base function 4
template <typename T>
auto f(T&& param) -> void;
// type usages with function instances and deduced T int x = 23; // f(x) = f(int\& param) \rightarrow T = int\& int const <math>cx = x; // f(cx) = f(int const\& param) \rightarrow T = int const\& int const\& crx = x; // f(crx) = f(int const\& param) \rightarrow T = int const\& // // // // f(27) = f(int\&\& param) \rightarrow T = int
// -- if param is an lvalue, then they become lvalue references
// -- otherwise rvalue, default rules for references
2.2.1 Deducing Initializer Lists
With initializer lists, you can't directly deduce the type as it will think T is the entire list, which is nonsense!
template <typename T>
auto f(T param) -> void;
f({23}); //error
template <typename T>
auto f(std::initializer_list<T> param) -> void;
f({23}); //T = int
//ParamType = std::initializer_list<int>
2.2.2 Deducing auto types
                              //auto is a value type
autox = 23;
auto const cx = x; //auto is a value type
auto& rx = x;
                              //auto is a reference type
auto&& uref1 = x;
                              //x is an lvalue, uref1 is int&
auto&& uref2 = cx;
                             //cx is an lvalue, uref2 is int const&
auto&& uref3 = 23; //23 is an rvalue, uref3 is int&&
   special cases
auto init_list1 = {23}; //std::initializer_list<int>
auto init_list2{23};    //int, was std::initializer_list<int>
auto init_list3{23, 23};    //Error, requires one single argument
Note that auto type deduction works with parameters and return types, with the special cases like initializer list still applying!!
2.2.3 Type Deduction with Decltype
                                 = 23:
                                 = x;
int const
                     сx
decltype(cx) cx_too = cx; //type of cx_too is int const
int&
decltype(rx) rx_too = rx; //type of rx_too is int&
// these two are the only surprises! auto only gives the base type without reference, while the other gives the full reference
      type
auto just_x = rx; //type of just_x is int
decltype(auto) more_rx = rx; //type of more_rx is int&
decltype(auto) etc can also be used for returning something specific:
// auto decltype
template <typename Container, typename Index>
decltype(auto) access(Container & c, Index i) {
return c[i];
// specific decltype
template <typename Container, typename Index>
auto access(Container & c, Index i) -> decltype(c[i]) {
```

Note we can only declare decltype(c[i]) as a trailing type! The reason for this is that c and i are only known AFTER the parameters!

return c[i];

2.2.4 Returns with decitype

```
decltype(auto) funcName() {
  int local = 42;
  return local; // decltype(local) => int
} // lvalue -> T
decltype(auto) funcNameRef() {
  int local = 42;
  int & lref = local;
  return lref; // int & -> bad (dangling)
} // lvalue reference -> T\&
decltype(auto) funcXvalue() {
  int local = 42;
  return std::move(local); // int && -> bad (dangling)
 // rvalue reference -> T&&
decltype(auto) funcLvalue() {
  int local = 42;
return (local); // int & -> bad (dangling) } // lvalue reference -> T&
decltype(auto) funcPrvalue() {
 return 5; // int
} // prvalue \rightarrow T
```

2.3 Checking for r and I-values

We learned that we can solve the issue of multiple overloads with T&&, but what if we want to differentiate after the fact? std::forward!

```
template <typename T>
auto log_and_do(T&& param) -> void {
  //log
  do_something(std::forward<T>(param));
// example for implementation
template <typename T>
  decltype(auto) forward(std::remove_reference_t < T > & param) {
  return static_cast < T&& > (param);
// explanation
// this will check if we have an lvalue or not by trying to cast to an rvalue reference // if & and && are casted, it will always result in &
// this means only an rvalue will result in an rvalue being returned, everything else will result in lvalue being returned
// this is called reference collapsing!
// example -> when T is int& the static cast will be int& && and hence collapsed to int& // when T is int&& the static cast will be int&& && and hence collapsed to int&&
// when T is int, the static cast will be int&&, no collapse is needed here.
// note references are only checked for the type, the actual references are removed, as can be seen by the std::
     remove_reference_t
```

This means that forwards is essentially a conditional cast to an rvalue reference!

Rules for reference collapsing:

- & and & = &
- \bullet && and & = &
- & and && = &
- && and && = &&

2.3.1 std::move vs std::forward

While forward is the conditional cast, std::move is the unconditional cast! This means you will always receive an rvalue!

```
// std::forward
template <typename T>
  decltype(auto) forward(std::remove_reference_t<T>& param) {
  return static_cast<T&&>(param);
} // will collapse dynamically
// std::move
template <typename T>
decltype(auto) move(T&& param) { // param is always T&& !!!
  return static_cast<std::remove_reference_t<T>&&>(param);
} // will always collapse to && and && meaning && is returned
```