

# Boundary Layer Meteorology Reference: Stability Functions Based Upon Shear Functions

Equation Reference Guide (Adapted from England & McNider, 1995)

August 15, 2026

## 1 Exchange Coefficients & Surface Layer Framework

The Monin–Obukhov exchange coefficients for momentum ( $K_m$ ) and heat ( $K_h$ ) are defined as:

$$K_m = \frac{l_m u_*}{\phi_m} = \frac{l_m^2 s}{\phi_m^2} \quad (1)$$

$$K_h = \frac{l_m u_*}{\phi_h} = \frac{l_m^2 s}{\phi_m \phi_h} \quad (2)$$

where friction velocity  $u_*$ , wind shear  $s$ , mixing length  $l_m$ , and temperature scale  $\theta_*$  are:

$$u_* = \frac{l_m s}{\phi_m}, \quad s = \left[ \left( \frac{\partial u}{\partial z} \right)^2 + \left( \frac{\partial v}{\partial z} \right)^2 \right]^{1/2} \quad (3)$$

$$l_m = \kappa z, \quad \theta_* = \frac{l_m}{\phi_h} \frac{\partial \theta}{\partial z} \quad (4)$$

The dimensionless shear functions  $\phi(\zeta)$  depend on stability parameter  $\zeta = z/L$ :

- **Stable branch** ( $\zeta > 0$ ):

$$\phi_m(\zeta) = 1 + \beta_m \zeta, \quad \phi_h(\zeta) = 1 + \beta_h \zeta \quad (5)$$

- **Unstable branch** ( $\zeta < 0$ ):

$$\phi_m(\zeta) = (1 - \beta_m \zeta)^{-1/4}, \quad \phi_h(\zeta) = (1 - \beta_h \zeta)^{-1/2} \quad (6)$$

## 2 Gradient Richardson Number ( $Ri$ ) & Inverse Relations

The gradient Richardson number is related to Monin–Obukhov stability  $\zeta$  via:

$$Ri = \frac{g}{\theta_0} \frac{\partial \theta / \partial z}{s^2} = \zeta \frac{\phi_h(\zeta)}{\phi_m^2(\zeta)} \quad (7)$$

### Stable Boundary Layer ( $\zeta > 0$ )

Substituting stable shear functions into  $Ri(\zeta)$  yields the quadratic equation:

$$(Ri\beta_m^2 - \beta_h)\zeta^2 + (2Ri\beta_m - 1)\zeta + Ri = 0 \quad (8)$$

The physically continuous solution requiring  $\zeta \rightarrow 0$  as  $Ri \rightarrow 0$  (neutral limit) is:

$$\zeta = \frac{1 - 2Ri\beta_m - \sqrt{1 + 4(\beta_h - \beta_m)Ri}}{2(Ri\beta_m^2 - \beta_h)} \quad (9)$$

- **Asymptotic Critical Richardson Number:**  $Ri_c = \frac{\beta_h}{\beta_m^2}$
- **Exact Linear Simplification** ( $\beta_h = \beta_m$ ): When heat and momentum constants match, the discriminant collapses to 1, yielding:

$$\zeta = \frac{Ri}{1 - Ri/Ri_c} \quad \text{where } Ri_c = \frac{1}{\beta_m} \quad (10)$$

### Unstable Boundary Layer ( $\zeta < 0$ )

Squaring and clearing denominators for the unstable branch yields the cubic equation:

$$\beta_m \zeta^3 - \zeta^2 - \beta_h Ri^2 \zeta + Ri^2 = 0 \quad (11)$$

## 3 Stability Functions $f_m(Ri)$ and $f_h(Ri)$

In numerical models, exchange coefficients are expressed directly in terms of  $Ri$ :

$$K_m = f_m(Ri) l_m^2 s, \quad K_h = f_h(Ri) l_m^2 s \quad (12)$$

where:

$$f_m(Ri) = \phi_m^{-2}(\zeta), \quad f_h(Ri) = \phi_m^{-1}(\zeta) \phi_h^{-1}(\zeta) \quad (13)$$

### Stable Layer Formulations ( $0 \leq Ri \leq Ri_c$ )

- **Quadratic Form** ( $Pr = 1, \beta_m = \beta_h$ ):

$$f_m(Ri) = f_h(Ri) = \begin{cases} \left(1 - \frac{Ri}{Ri_c}\right)^2, & 0 \leq Ri \leq Ri_c \\ 0, & Ri > Ri_c \end{cases} \quad (14)$$

- **Blackadar Linear Form (For Comparison):**

$$f_m(Ri) = f_h(Ri) = \begin{cases} 1 - \frac{Ri}{Ri_c}, & 0 \leq Ri \leq Ri_c \\ 0, & Ri > Ri_c \end{cases} \quad (15)$$