EN.601.414/614 Computer Networks

Congestion Control

Xin Jin

Spring 2019 (MW 3:00-4:15pm in Shaffer 301)



Agenda

- TCP congestion control wrap-up
- TCP throughput equation
- Problems with congestion control

Recap

Flow Control

➤ Restrict window to RWND to make sure that the receiver isn't overwhelmed

Congestion Control

➤ Restrict window to CWND to make sure that the network isn't overwhelmed

Together

➤ Restrict window to min{RWND, CWND} to make sure that neither the receiver nor the network are overwhelmed

CC Implementation

States at sender

- CWND (initialized to a small constant)
- ssthresh (initialized to a large constant)
- ➤ dupACKcount and timer

Events

- >ACK (new data)
- dupACK (duplicate ACK for old data)
- **≻**Timeout

Event: ACK (new data)

If CWND < ssthresh

>CWND += 1

- CWND packets per RTT
- Hence, after one RTT with no drops:

CWND = 2xCWND

Event: ACK (new data)

If CWND < ssthresh

-Slow start phase

Else

Congestion avoidance phase

- CWND packets per RTT
- Hence, after one RTT with no drops:

$$CWND = CWND + 1$$


Event: TimeOut

- On Timeout
 - ➤ssthresh ← CWND/2
 - ➤CWND ← 1

Event: dupACK

- dupACKcount ++
- If dupACKcount = 3 /* fast retransmit */
 - >ssthresh = CWND/2
 - >CWND = CWND/2

Example



Slow-start restart: Go back to CWND = 1 MSS, but take advantage of knowing the previous value of CWND

Not done yet!

 Problem: congestion avoidance too slow in recovering from an isolated loss

Example

- Consider a TCP connection with:
 - ➤ CWND=10 packets
 - ➤ Last ACK was for packet # 101
 - i.e., receiver expecting next packet to have seq. no. 101
- 10 packets [101, 102, 103,..., 110] are in flight
 - ➤ Packet 101 is dropped

Timeline: [10, 102, ..., 110]

- ACK 101 (due to 102) cwnd=10 dupACK#1 (no xmit)
- ACK 101 (due to 103) cwnd=10 dupACK#2 (no xmit)
- ACK 101 (due to 104) cwnd=10 dupACK#3 (no xmit)
- RETRANSMIT 101 ssthresh=5 cwnd= 5
- ACK 101 (due to 105) cwnd=5 (no xmit)
- ACK 101 (due to 106) cwnd=5 (no xmit)
- ACK 101 (due to 107) cwnd=5 (no xmit)
- ACK 101 (due to 108) cwnd=5 (no xmit)
- ACK 101 (due to 109) cwnd=5 (no xmit)
- ACK 101 (due to 110) cwnd= 5 (no xmit)
- ACK 111 (due to 101) column{c} only now can we transmit new packets
- Plus no packets in flight so ACK "clocking" (to increase CWND) stalls for another RTT

Solution: Fast recovery

- Idea: Grant the sender temporary "credit" for each dupACK so as to keep packets in flight
- If dupACKcount = 3
 - > ssthresh = CWND/2
 - > CWND = ssthresh + 3
- While in fast recovery
 - >CWND = CWND + 1 for each additional dupACK
- Exit fast recovery after receiving new ACK
 - > set CWND = ssthresh


Example

- Consider a TCP connection with:
 - ➤ CWND=10 packets
 - ➤ Last ACK was for packet # 101
 - i.e., receiver expecting next packet to have seq. no. 101
- 10 packets [101, 102, 103,..., 110] are in flight
 - ➤ Packet 101 is dropped


Timeline: [10, 102, ..., 110]

- ACK 101 (due to 102) cwnd=10 dup#1
- ACK 101 (due to 103) cwnd=10 dup#2
- ACK 101 (due to 104) cwnd=10 dup#3
- RETRANSMIT 101 ssthresh=5 cwnd= 8 (5+3)
- ACK 101 (due to 105) cwnd= 9 (no xmit)
- ACK 101 (due to 106) cwnd=10 (no xmit)
- ACK 101 (due to 107) cwnd=11 (xmit 111)
- ACK 101 (due to 108) cwnd=12 (xmit 112)
- ACK 101 (due to 109) cwnd=13 (xmit 113)
- ACK 101 (due to 110) cwnd=14 (xmit 114)
- ACK 111 (due to 101) cwnd = 5 (xmit 115) exiting fast recovery
- Packets 111-114 already in flight
- ACK 112 (due to 111) cwnd = $5 + 1/5 \leftarrow$ back in congestion avoidance


TCP state machine




Timeouts → Slow Start




dupACKs → Fast Recovery



New ACK changes state ONLY from Fast Recovery



TCP state machine



TCP flavors

- TCP-Tahoe
 - ➤ CWND =1 on 3 dupACKs
- TCP-Reno
 - >CWND =1 on timeout
 - \triangleright CWND = CWND/2 on 3 dupACKs
- TCP-newReno
 - >TCP-Reno + improved fast recovery
- TCP-SACK
 - ➤ Incorporates selective acknowledgements


Our default assumption

How can they coexist?


- All follow the same principle
 - ➤ Increase CWND on good news
 - ➤ Decrease CWND on bad news

TCP Throughput Equation

A simple model for TCP throughput




A simple model for TCP throughput



Implications (1): Different RTTs

Throughput =
$$\sqrt{\frac{3}{2}} \frac{1}{RTT\sqrt{p}}$$

- Flows get throughput inversely proportional to RTT
- TCP unfair in the face of heterogeneous RTTs!



Implications (2): High-speed TCP

Throughput =
$$\sqrt{\frac{3}{2}} \frac{1}{RTT\sqrt{p}}$$

- Assume RTT = 100ms, MSS=1500bytes, BW=100Gbps
- What value of p is required to reach 100Gbps throughput?

How long between drops?

How much data has been sent in this time?

Adapting TCP to high speed

- Once past a threshold speed, increase CWND faster
 - ➤ A proposed standard [Floyd'03]
 - ➤ Let the additive constant in AIMD depend on CWND
- Other approaches?
 - Multiple simultaneous connections (hack but works today)
 - > Router-assisted approaches

Implications (3): Rate-based CC

Throughput =
$$\sqrt{\frac{3}{2}} \frac{1}{RTT\sqrt{p}}$$

- TCP throughput swings between W/2 to W
- Apps may prefer steady rates (e.g., streaming)
- "Equation-Based Congestion Control"
 - ➤ Ignore TCP's increase/decrease rules and just follow the equation
 - Measure drop percentage p, and set rate accordingly
- Following the TCP equation ensures "TCP friendliness"
 - ▶i.e., use no more than TCP does in similar setting

Implications (4): Loss not due to congestion?

- TCP will confuse corruption with congestion
- Flow will cut its rate
 - ➤ Throughput ~ 1/sqrt(p) where p is loss prob.
 - >Applies even for non-congestion losses!

Implications (5): Short flows cannot ramp up

- 50% of flows have < 1500B to send; 80% < 100KB
- Implications
 - ➤ Short flows never leave slow start!
 - They never attain their fair share
 - ➤ Too few packets to trigger dupACKs
 - Isolated loss may lead to timeouts
 - At typical timeout values of ~500ms, might severely impact flow completion time

Implications (6): Short flows share long delays

- A flow deliberately overshoots capacity, until it experiences a drop
- Means that delays are large, and are large for everyone
 - ➤ Consider a flow transferring a 10GB file sharing a bottleneck link with 10 flows transferring 100B
 - Larger flows dominate smaller ones

Implications (7): Cheating

- Three easy ways to cheat
 - ➤Increasing CWND faster than +1 MSS per RTT


Implications (7): Cheating

- Three easy ways to cheat
 - ➤ Increasing CWND faster than +1 MSS per RTT
 - ➤ Using large initial CWND
 - Common practice by many companies

Implications (7): Cheating

- Three easy ways to cheat
 - ➤ Increasing CWND faster than +1 MSS per RTT
 - ➤ Using large initial CWND
 - Common practice by many companies
 - ➤ Opening many connections

Open many connections



Assume

- > A starts 10 connections to B
- >D starts 1 connection to E
- Each connection gets about the same throughput

Then A gets 10 times more throughput than D

Implications (8): CC intertwined with reliability

- CWND adjusted based on ACKs and timeouts
- Cumulative ACKs and fast retransmit/recovery rules
- Complicates evolution
 - Changing from cumulative to selective ACKs is hard
- Sometimes we want CC but not reliability
 - ➤ e.g., real-time applications
- We may also want reliability without CC

Recap: TCP problems

Routers tell endpoints if they're congested

- Misled by non-congestion losses
- Filts up queues leading to high delays
- Short flows complete before discovering available
- AIMD impractical for high speed links
- Saw tooth discovery too choppy for some apps
- Unfair under heterogeneous RTTs
- Tight coupling with reliability mechanisms
- End hosts can cheat

Routers tell endpoints what rate to send at

Routers enforce fair sharing

Could fix many of these with some help from routers!

Summary

- TCP works even though it has many flaws
- Many of them can be fixed via assistance from the network

Next few lectures: The Network Layer

Thanks! Q&A