Reg.No.: 2116220701040

### Practical 8

### AIM: -

a) Simulate Virtual LAN configuration using CISCO Packet Tracer Simulation.

### **Step 1: Set Up Devices in Cisco Packet Tracer**

#### 1. Add Devices

- o Open Cisco Packet Tracer.
- o At the bottom left, find the **Switches** category.
- o Drag 2 switches (S1 and S2) into the workspace.
- Next, find the End Devices category and drag 2 PCs (PC-A and PC-B) into the workspace.

#### 2. Connect Devices

- Click the Connections icon (lightning bolt) at the bottom left to see cable options.
- Select Copper Straight-Through Cable and connect:
  - **PC-A to S1** (PC-A to S1's FastEthernet0/1).
  - **PC-B to S2** (PC-B to S2's FastEthernet0/1).
- o Choose Console Cable (also found under Connections) to connect:
  - PC-A to S1's console port
  - PC-B to S2's console port

# **Step 2: Configure Basic Switch Settings**

- 1. Access Switch CLI via Console Connections
  - $\circ$  Click **PC-A** > **Desktop** > **Terminal**.
  - Click **OK** in the Terminal settings window to access S1's CLI (Command Line Interface).
  - o Repeat this for PC-B to access S2's CLI.

### 2. Enter Configuration Mode on Each Switch

o For each switch, enter the following commands:

```
enable
configure terminal
hostname <SwitchName>
```

#### 3. Set Console and Enable Passwords

o Still in global configuration mode, type:

```
line console 0
password <console_password>
login
exit
enable secret <enable password>
```

### 4. Set IP Address on Switch VLAN Interface

• Type the following commands:

```
interface vlan 1
ip address <IP_address> <subnet_mask>
no shutdown
exit
```

# 5. Save Configuration

- $_{\circ}$  Exit back to privileged EXEC mode by typing exit.
- Save the configuration with write memory or copy running-config startup-config.

# **Step 3: Configure IP Address on PCs**

## 1. Configure PC-A

- $\circ$  Click PC-A > Desktop > IP Configuration.
- Set the IP Address to 192.168.1.2, Subnet Mask to 255.255.255.0, and Default Gateway to 192.168.1.1.

### 2. Configure PC-B

- $\circ$  Click PC-B > Desktop > IP Configuration.
- Set the IP Address to 192.168.1.3, Subnet Mask to 255.255.255.0, and Default Gateway to 192.168.1.1.

### **Step 4: Create VLANs on Each Switch**

### 1. Create VLANs on S1 and S2

 Access each switch's CLI through PC-A and PC-B respectively, and enter the following commands:

enable

configure terminal

vlan 10

name SALES

exit

vlan 20

name HR

exit

### 2. Assign Ports to VLANs

o For **S1**:

interface range fa0/1 - 12

switchport mode access

switchport access vlan 10

exit

interface range fa0/13 - 24

switchport mode access

switchport access vlan 20

#### o For **S2**:

```
interface range fa0/1 – 12
switchport mode access
switchport access vlan 10
exit
interface range fa0/13 - 24
switchport mode access
switchport access vlan 20
exit
```

### 3. Verify VLAN Configuration

 Type show vlan brief on each switch to verify that VLANs 10 and 20 have been created and that ports are correctly assigned.

# **Step 5: Configure Trunking Between Switches**

#### 1. Enable Trunk Ports on Both Switches

- o Access S1 through PC-A and S2 through PC-B.
- Set port FastEthernet0/1 to trunk mode on both switches:

```
interface fa0/1
switchport mode trunk
exit
```

# 2. Verify Trunking

• Type show interfaces trunk to confirm that **FastEthernet0/1** is operating as a trunk port on each switch.

# **Step 6: Testing Connectivity**

# 1. Ping Between PCs

 $\circ$  Click PC-A > Desktop > Command Prompt.

o Type ping 192.168.1.3 (PC-B's IP address) to test connectivity.

# 2. Troubleshooting

 If the ping fails, verify the VLAN and trunk configurations on each switch and ensure the correct IP settings on each PC.

## **OUTPUT:**

Switch#s	show	vlan	brief

VLAN	Name	Status	Ports
1	default	active	Fa0/5, Fa0/6, Fa0/7, Fa0/8 Fa0/9, Fa0/10, Fa0/11, Fa0/12 Fa0/13, Fa0/14, Fa0/15, Fa0/16 Fa0/17, Fa0/18, Fa0/19, Fa0/20 Fa0/21, Fa0/22, Fa0/23, Fa0/24 Gig0/1, Gig0/2
10	Marketing	active	Fa0/1, Fa0/2
20	Sales	active	Fa0/3, Fa0/4
1002	fddi-default	active	
1003	token-ring-default	active	
1004	fddinet-default	active	
1005 Swite	trnet-default ch#	active	