# emftext

# **USER GUIDE**

# Contents

1	Ove	rview 1							
	1.1	Generation features							
	1.2	Specification features							
	1.3	Editor features							
	1.4	Other features							
2	Get	tting Started with EMFText 3							
	2.1	Specifying a Language Metamodel							
	2.2	Specifying the Language's Concrete Syntax							
	2.3	Generating the Language Tooling							
		2.3.1 Generating Resource Plug-ins in Eclipse							
		2.3.2 Generating Resource Plug-ins with ANT							
	2.4	Optionally Customising the Language Tooling							
3	Con	Concrete Syntax Specification Language (CS)							
	3.1	Configuration Block							
		3.1.1 Required General Information							
		3.1.2 Importing other Metamodels and Syntax Specifications							
		3.1.3 Code Generation Options							
	3.2								
		3.2.1 Defining Custom Tokens							
		3.2.2 Composed Tokens							
		3.2.3 Token Priorities							
	3.3	Token Styles							
	3.4	Syntax Rules							
		3.4.1 Simple Syntax							
		3.4.2 Syntax for EAttributes							
		3.4.3 Syntax for EReferences							
		3.4.4 Syntax for Printing Instructions							
		3.4.5 Syntax for Expressions							
	3.5	Suppressing warnings							
4	DSL	. Customization 23							
	4.1	Customization Techniques							
		4.1.1 Overriding Generated Artifacts							
		4.1.2 Overriding Meta Information Classes							
		4.1.3 Using Generated Extension Points							
	4.2	Concrete Customizations							
		4.2.1 Customizing Token Resolving							

# Contents

	4.2.2	Customizing Reference Resolving	26			
	4.2.3	Implementing Post Processors	27			
	4.2.4	Implementing Quick Fixes	29			
	4.2.5	Implementing Builders	30			
	4.2.6	Implementing Interpreters	31			
	4.2.7	Customizing Text Hovers	32			
	4.2.8	Customizing Code Completion Proposals	32			
A Code Generation Options						
В	B Types of Warnings					
Α	A Syntax Dependent Artifacts					
Bi	Bibliography					

## 1 Overview

EMFText is a tool for defining textual syntax for Ecore-based metamodels. It enables developers to define their own textual languages—be it domain specific languages (e.g., a language for describing forms) or general purpose languages (e.g., Java)—and generates accompanying tool support for these languages. It provides a domain specific language (DSL) for syntax specification from which it generates a full-fledged Eclipse editor and components to load and store model instances.

To give a quick overview, some of the most compelling features of EMFText are outlined in the following.

#### 1.1 Generation features

EMFText uses a generative approach where all artifacts that form the tooling for a textual language are generated. This includes a parser for loading textual models, a printer for storing model instances and the editor with all its customizable components.

**Generation of independent code** The code that is generated by EMFText does not contain dependencies to EMFText and is fully customizable. This implies that generated language tooling can be deployed in environments where EMFText is not available and that future compatibility issues are completely avoided.

**Generation of default syntaxes** With EMFText, initial syntaxes for the textual DSL can be generated in one step for any Ecore-based metamodel. One can either generate a syntax that conforms to the HUTN standard [Obj02] or a Java-like syntax. In both cases, the initial, generated specification of the syntax can be further tailored towards specific needs (cf. Section 2.2).

**Highly customizable code generation** EMFText provides many options for tailoring its code generation process to specific needs. For example, manually modified code can be preserved by disabling its generation or custom license headers can be provided if needed (cf. Appendix A).

#### 1.2 Specification features

EMFText comes with a simple but rich syntax specification language—the Concrete Syntax Specification Language (CS). It is based on EBNF and follows the concept of convention over configuration. This allows for very compact and intuitive syntax specifications, but still supports tweaking specifics where needed (cf. Chapter 3).

**Modular specification** EMFText provides an import mechanism that not only supports specification of a single text syntax for multiple related Ecore models, but also allows for modularization and extension of CS specifications (cf. Section 3.1.2).

- **Default reference resolving mechanisms** A default name resolution mechanism for models with globally unique names is available out of the box for any syntax. Also, external references are resolved automatically, if URIs are used to point to the referenced elements. More complex resolution mechanisms can be realized by implementing generated resolving methods (cf. Section 4.2.2).
- **Comprehensive syntax analysis** A number of analyses of CS specifications inform the developer about potential errors in the syntax—like missing syntax for certain metaclasses (cf. Appendix B).

#### 1.3 Editor features

Editors generated by EMFText provide many advanced features that are known from, e.g., the Eclipse Java editor. This includes code completion (with customizable completion proposals cf. Section 4.2.2 and Section 4.2.8), customizable syntax and occurrence highlighting via preference pages, advanced bracket handling, code folding, hyperlinks and text hovers for quick navigation, an outline view and instant error reporting.

#### 1.4 Other features

EMFText provides numerous other interesting features, some of them outlined below.

- **ANT support** Dedicated ANT tasks are provided to allow the generation of text syntax plugins in build scripts (cf. Section 2.3.2).
- **Support for post processors** By default, registered post processors are called by the tooling after parsing. These post processors can be customized to check consistency of models or perform necessary modifications after parsing (cf. Section 4.2.3).
- **Generation of builder stubs** EMFText generates a builder stub that can be used to process model instances on changes and to automatically produce derived resources when needed (cf. Section 4.2.5).
- **Generation of interpreter stubs** Similarly, interpreters are used to execute model instances (cf. Section 4.2.6).
- **Quick fixes** Quick fixes provide actions that can automatically solve problems found during analysis of model instances. EMFText provides means to attach quick fixes to reported problems which then can be fixed by the developer in a convenient way (cf. Section 4.2.4).

# 2 Getting Started with EMFText

Generating an advanced Eclipse editor for a new language with EMFText just requires a few specifications and a generation step. Basically, a language specification for EMFText consists of a language metamodel and a concrete syntax specification. Taking these specifications the EMFText generator derives an advanced textual editor, that uses a likewise generated parser and printer to parse language expressions to EMF models or to print EMF models to languages expressions respectively.




Figure 2.1: Iterative EMFText language development process.

The basic language development process with EMFText is depicted in Fig. 2.1. It is an iterative process that can be passed several times and consists of the following basic tasks:

- (1) Specifying a Language Metamodel,
- (2) Specifying the Language's Concrete Syntax,
- (3) Generating the Language Tooling,
- (4) Optionally Customising the Language Tooling.

Each of the these tasks will be explained and exemplified in the subsequent sections:

To kick-start the development of a new language you can use the EMFText project wizard. Select File > New > Other... > EMFText Project. In the Wizard (cf. Fig. 2.2) you just enter the language name and EMFText will initialise a new EMFText Project containing a metamodel folder that holds an initial metamodel and syntax specification.

#### 2.1 Specifying a Language Metamodel

As EMFText is tightly integrated with the Eclipse Modeling Framework (EMF) [SBPM08] language metamodels are specified using the Ecore Metamodelling Language. The metamodel



Figure 2.2: EMFText Project wizard.

specifies the abstract syntax of a new language. It can be build from classes with attributes that are related using references. References are further distinguished into containment references and non-containment references. It is important to notice this difference, as both reference types have different semantics in EMF and are also handled differently in EMFText. Containment references are used to relate a parent model element and a child model element that is declared in the context of the parent element. An example which can be found for instance in object-oriented programming languages is the declaration of a method within the body of a class declaration. Non-containment references are used to relate a model element with an element that is declared elsewhere (not as one of its children). An example for programming languages is a method call (declared in a statement in the body of a method declaration) that relates to the method that it calls using a non-containment reference. The referenced method, however, is declared elsewhere: In a class the method relates to with a containment reference.

Example. To define a metamodel for a language, we have to consider the concepts this language deals with, how they interrelate and what attributes they have. In the following we discuss the concepts of an exemplary language to specify forms and how they are represented in a forms metamodel.

- A Form (class) has a caption (attribute) and contains (containment reference) a number of question Groups (class).
- Each Group has a name (attribute) and contains (containment reference) a number of question Items (class).

- Each Item has a question text (attribute) and an explanation (attribute).
- There are various Types (class) of question items with regard to the answer values they expect: e.g., Text questions (subclass), Date questions (subclass), Number questions (subclass), Choices (subclass), or Decisions (subclass).
- Choices and Decisions declare (containment reference) a number of selection Options (class).
- There may be question Items that are dependent of (non-containment reference) the selection of a particular Option in another Item, e.g., a question that asks for the age of your children, only if you previously selected that you have some.

Listing 2.1 depicts a textual representation of the according EMF metamodel. Besides the mapping of forms concepts to Ecore it also refines the multiplicities and types. A new text.ecore metamodel is created by selecting File > New > Other... > EMFText. text.ecore file. For a detailed introduction on the basics of Ecore metamodelling we refer to [SBPM08].

Listing 2.1: Metamodel for the exemplary forms language written in text.ecore

```
package forms // this is the package name
        forms // this is the namespace prefix
        "http://org.emftext/language/forms.ecore" // the namespace URI
        class Form {
                attribute EString caption (0..1);
                containment reference Group groups (1..-1) ;
        }
        class Group {
                attribute EString name (1..1);
                containment reference Item items (1..-1);
        }
        class Item {
                attribute EString text (0..1);
                attribute EString explanation (0..1);
                containment reference ItemType itemType (1..1);
                reference Option dependentOf (0..-1);
        }
        abstract class ItemType {}
        class FreeText extends ItemType {}
        class Date extends ItemType {}
        class Number extends ItemType {}
        class Choice extends ItemType {
```

Each Ecore metamodel is accompanied by an .genmodel. You can create the .genmodel by selecting File > New > Other... > EMF Generator Model. The generator model is used to configure various options for EMF code generation (e.g., the targeted Java runtime). From the root element of the .genmodel you can now start the generation of Java code implementing your metamodel specification. By default the generated files can be found in the src folder of the metamodel plug-in, but this can also be configured in the .genmodel. We suggest to change the code generation folder to src-gen to better separate generated code from hand-written.

# 2.2 Specifying the Language's Concrete Syntax

After defining a metamodel, we can start specifying our concrete syntax. The concrete syntax specification defines the textual representation of all metamodel concepts. For that purpose, EMFText provides the cs-language. As a starting point, EMFText provides a syntax generator that can automatically create a cs specification conforming to HUTN (Human-Useable Textual Notation) [Obj02] from the language metamodel. To manually specify the concrete syntax create a new syntax specification by selecting File > New > Other... > EMFText. cs file.

Listing 2.2 depicts a syntax specification for the forms language. It consists of five sections:

- In the first section the language file extension is defined, the syntax specification is bound to the metamodel, and the syntax start symbol is defined.
- In the second section various EMFText code generation options can be configured.
- In the third section basic token types used by the language lexer to tokenise language expressions are defined. If no token definitions are given, default token types are used.
- In the fourth section token styles are defined that customise syntax highlighting for specific token types in the generated editor.
- In the fifth section the syntax rules for the language are specified.

The syntax specification rules used in the cs-language are derived from the EBNF syntax specification language to support arbitrary context-free languages. They are meant to define syntax for EMF-based metamodels and, thus, are specifically related to the Ecore metamodelling concepts. Therefore, it provides Ecore-specific specialisations of classical EBNF constructs like terminals, and non terminals. This specialisation enables EMFText to provide advanced support during syntax specification, e.g., errors and warnings if the syntax specifica-

tion is inconsistent with the metamodel. Furthermore, it enables the EMFText parser generator to derive an parser that directly instantiates EMF models from language expressions.

In the following we conclude the most important syntax specification constructs found in the cs-language and their relation to EBNF and Ecore metamodels. For an extensive overview on the syntax specification language we refer to Sect. 3. Each syntax construct is also related to examples taken from Listing 2.2.

**Rule** An cs rule is always related (by its name) to a specific class from the metamodel. It defines the syntactic representation of this metaclass, its attributes and references. All syntax rules are collected in the rules section of the cs file. Within syntax rules various constructs like keywords, syntax terminals, non-terminals, and EBNF operators as multiplicities (?, +, \*), alternative (|), or rounded brackets to nest sub-rules can be used.

Examples:

```
Form ::= ...;, Group ::= ...;
```

**Keywords** Keywords are purely syntactic elements that are mainly used to structure and markup particular language expressions.

Examples:

```
"FORM", "GROUP", "ONLY" "IF"
```

**Attribute Terminal** Attribute terminals are used in rule bodies to specify the syntactic representation for attributes of the according meta class. They can be recognised by the attribute name that is followed by square brackets. Within these square brackets a token that specifies the syntax allowed for attribute values, or a prefix and a suffix that must surround attribute values can be given. If nothing is given a default text token is assumed.

Examples:

```
name[], mulitple[MULTIPLE], name['"','"']
```

Containment Reference Non-Terminals Containment reference non-terminals are used in rule bodies to specify the syntactic representation for containment references of the according metaclass. They use the reference name and are not followed by brackets. Containment reference non-terminals are derived from EBNF non-terminals, which means that during parsing the parser descends in the syntax rule specified for the class the containment reference points to. This is in line with the semantics of containment references as used in metamodels.

Examples:

groups, questions

Non-Containment Reference Terminals Non-containment reference terminals are used in rule bodies to specify the syntactic representation for non-containment references of the according metaclass. They use the reference name that is followed by square brackets. Within these square brackets a token can be given that specifies the syntax allowed for expressions in the concrete syntax that identify the element the non-containment reference relates to. This symbolic reference is later resolved to the actual element (cf. Sect. 4.2.2). If no token is given, again the default text token is used.

Examples:

#### dependentOf[]

**Printing Markup** Printing Markup is used to customise the behaviour of the generated printer. This is useful to achieve a particular standard layout for printed language expressions. Two forms of printing markup are supported:

- whitespace markup, prints a given number of whitespaces: #<n>
- linebreak markup, introduces a linebreak followed by a given number of tab characters:!<n>

Listing 2.2: Concrete syntax specification for the exemplary forms language written in the cslanguage

```
SYNTAXDEF forms
FOR <http://www.emftext.org/language/forms>
START Form
OPTIONS {
        overrideBuilder = "false";
        additionalDependencies = "org.emftext.language.forms.generator";
}
TOKENS {
        DEFINE MULTIPLE $'multiple'|'MULTIPLE'$;
TOKENSTYLES {
        "TEXT" COLOR #da0000;
        "FORM" COLOR #000000, BOLD;
        "ITEM" COLOR #000000, BOLD;
        "CHOICE" COLOR #000000, BOLD;
        "ONLY" COLOR #da0000, BOLD;
        "IF" COLOR #da0000, BOLD;
        "DATE" COLOR #000000, BOLD;
        "FREETEXT" COLOR #000000, BOLD;
        "NUMBER" COLOR #000000, BOLD;
        "DECISION" COLOR #000000, BOLD;
        "GROUP" COLOR #000000, BOLD;
RULES {
        Form ::= "FORM" caption['"','"'] !1 groups*;
        Group ::= !0 "GROUP" name['"','"'] !0 items*;
        Item ::= "ITEM" text['"','"'] ( explanation['"','"'] )?
                                ("ONLY" "IF" dependentOf[])? ":" itemType !0;
        Choice ::= "CHOICE" (multiple[MULTIPLE])?
                                "(" options ("," options)* ")";
```

```
Option ::= ( id[] ":")? text['"','"'];
Date ::= "DATE";
FreeText ::= "FREETEXT";
Number ::= "NUMBER";
Decision ::= "DECISION" "(" options "," options ")";
}
```

#### 2.3 Generating the Language Tooling

Given a complete syntax specification the EMFText code generator can be used to derive an advanced textual editor and an accompanying customisable language infrastructure. There are two alternative ways to use the code generator: Manually within Eclipse or from an Apache Ant script.

#### 2.3.1 Generating Resource Plug-ins in Eclipse

Manual code generation can be triggered from the context menu of the concrete syntax specification. Therefore, right click the cs file and select *Generate Text Resource*. This starts the EMF code generator that produces a number of plug-ins. Fig. 2.3 depicts the plug-ins generated for our exemplary forms language. In the following we shortly discuss their purpose:

- org.emftext.commons.antrl3\_2\_0 This project contributes the ANTLR parsing runtime that the generated parser for the forms language depends on. As EMFText is meant to be runtime free the ANTLR runtime is generated for every new language, if no runtime is found in the current workspace.
- org.emftext.language.forms This is the basic plug-in of the language. In the folder metamodel it contains the Ecore metamodel and the cs specification defined previously. The src-gen folder contains the Java-based implementation that was generated using the .genmodel. This plug-in will not be altered by the EMFText code generator.
- org.emftext.language.forms.resources.forms This is the plug-in that contains the generated parser, printer and various infrastructure for the forms language. The project contains two source folders (src and src-gen). The contents of src-gen is overridden by every run of EMFText code generation. It is, thus not meant to contain manually customised code. The contents of the src folder contains implementation classes that are meant for manual customisation. By default it only contains reference resolvers that are used to resolve symbolic names of non-containment references to the model element actually meant. For details on reference resolving we refer to Sect. 4.2.2. Various cs options are available to tailor what language implementation artifacts shall be customised and, therefore, put into the src folder. For a detailed discussion of such options we refer to Sect. 4.1.2 and Appendix A.

Besides the files implementing the language tooling, a number of extension points specific for the language are generated to the **schema** folder. They can be used to further customise language tooling. For details we refer to Sect. 4.1.3.

• org.emftext.language.forms.resources.forms.ui This plug-in contains all generated classes related to the Eclipse-based User Interface (UI). Such separation of implementation classes belonging to the UI or not, enables the application of the language backend detached from the Eclipse UI.




Figure 2.3: Projects generated by EMFText to implement language tooling.

#### 2.3.2 Generating Resource Plug-ins with ANT

A second way of starting the EMFText code generator is using Apache Ant scripts. Therefore EMFText contributes a number of tasks for Apache Ant, which are automatically registered to the Eclipse platform using the naming scheme: <code>emftext.taskName</code>. The following task are shipped with EMFText:

**GenerateTextResource** This task can be used to generate all language implementation plugins. The following listing exemplifies the application of this task and its obligatory parameters:

<emftext.GenerateTextResource</pre>

```
syntax="pathToCSSpec"
rootFolder="path/to/project/root"
syntaxProjectName="nameOfTheGeneratedProject"
/>
```

Further parameters are generateANTLRPlugin="[true|false]", which specifies whether the additional plug-in containing the ANTLR parsing runtime should be generated, and pre-processor="[qualified class name]" referring to an implementation of the org.emftext.sdk.-ant.SyntaxProcessor interface, which is provided for realising Java-based syntax specification preprocessors.

**RegisterEcoreResourceFactory** This task registers an Ecore model's resource factory for a certain type. This is especially useful for testing purposes without a running Eclipse platform. The following listing exemplifies its application:

**RegisterURIMapping** This task adds an URI mapping to the EMF URI map, which is useful for mapping symbolic namespace URIs to physical locations, i.e., for locating ecore models. The following listing exemplifies its application:

**RemoveURIMapping** This task removes an URI mapping from the EMF's URI map, which is useful for removing unwanted symbolic URI mappings from the URI map. The following listing exemplifies its application:

To execute an Ant script that uses EMFText tasks from within your Eclipse runtime, you have to adjust the script's run configuration. Therefore, select  $Run > External\ Tools > External\ Tools\ Configurations...$  and select your Ant script's run configuration. In the JRE tab you have to activate the option Run in the same JRE as the workspace to make the EMFText tasks available to the script.

# 2.4 Optionally Customising the Language Tooling

The previous steps are mandatory to generate an initial implementation of basic tooling for your language. The generated text editor already comes with a number of advanced editing features that help editing language expressions a lot. However, there are various ways to make your language tooling more useful. EMFText helps you in customising your language tooling with a number of additional functions ranging from semantic validation of language expressions, language compilation, language interpretation, or editor functions like folding, custom quickfixes, extended code completion, refactoring and more. To discover the full spectrum of possibilities please consider Sect. 4.

# 3 Concrete Syntax Specification Language (CS)

An EMFText syntax specification must be contained in a file with the extension .cs and consists of four main blocks:

- 1. A mandatory configuration block, which specifies the name of the syntax (i.e., the file extension), the generator model where to find the metaclasses, and the root metaclass (start symbol). Optionally, other syntaxes and metamodels can be imported and code generation options can be specified.
- 2. An (optional) TOKENS section. Here, token types like identifiers, numbers etc. for the lexical analyser can be specified.
- 3. An (optional) TOKENSTYLES section. Here, the default style (i.e., color and font style) for tokens and keywords can be specified.
- 4. A RULES section, which defines the syntax for concrete metaclasses.

In the following sections, these four main blocks will be explained in more detail.

#### 3.1 Configuration Block

#### 3.1.1 Required General Information

The first required piece of information is the file extension that shall be used for the files, which will contain your models:

#### SYNTAXDEF yourFileExtension

Note: The file extension must not contain the dot character.

Second, EMFText needs to know the EMF generator model (.genmodel) that contains the metaclasses for which the syntax is specified. EMFText does use the generator model rather than the Ecore model, because it requires information about the code generated from the Ecore model (e.g., the fully qualified names of the classes generated by the EMF). The genmodel can be referred to by its namespace URI:

#### FOR <vourGenModelNamespaceURI>

To find the generator model with the given namespace URI, EMFText tries to load it from the generator model registry. If it is not registered, EMFText looks for a .genmodel file with the same name as the syntax definition. For example, if the syntax specification is contained in a file yourdsl.cs, EMFText looks for a file called yourdsl.genmodel in the same folder.

If your genmodel is not contained in the same folder or is called differently from the syntax file name or if you do not want to use the one in the registry, the optional parameter yourGenmodelLocation can be used:

#### FOR <yourGenModelNamespaceURI> <yourGenmodelLocation>

The value of **yourGenmodelLocation** must be an URI pointing to the generator model. The URI can be absolute or relative to the syntax specification folder.

Third, the root element (start symbol) must be given. The root element must be a metaclass from the metamodel:

#### START YourRootMetaClassName

A CS specification can also have multiple root elements, which must be separated by a comma:

#### START RootMetaClass1, RootMetaClass2, RootMetaClass3

Typical candidates for root elements are metaclasses that do not have incoming containment edges.

Altogether a typical header for a .cs file looks something like:

```
SYNTAXDEF yourFileExtension
FOR <yourGenModelNamespaceURI> <yourGenmodelLocation>
START YourRootMetaClassName
```

#### 3.1.2 Importing other Metamodels and Syntax Specifications

Sometimes it is required to import additional metamodels, e.g., if they are only referenced in the current one and a syntax for some or all of its concepts needs to be specified or reused. Metamodels and syntax specifications can be imported in a dedicated import section, which must follow after the start symbols:

```
IMPORTS {
    // imports go here
}
```

The list of imports must contain at least one entry. If no imports are needed the whole section must be left out. An import entry consists of a prefix, which can be used to refer to imported elements in rules, the metamodel namespace URI and optionally the name of a concrete syntax defined for that metamodel. If a syntax is imported, all its rules are reused and need not to be specified in the current **cs** specification. Importing syntax rules is optional. One can also just import the metamodel contained in the generator model.

```
prefix : <genModelURI> <locationOfTheGenmodel>
    // next line is optional (except the semicolon)
WITH SYNTAX syntaxURI <locationOfTheSyntax>;
```

The two locations are again optional. For resolving the generator model the same rules as for the "main" generator model (declared after the FOR keyword) apply. For locating the syntax, EMFText looks up the registry of registered syntax specifications. If no registered syntax is found, locationOfTheSyntax is used to find the .cs file to import. Again, locationOfTheSyntax must be a relative or absolute URI.

#### 3.1.3 Code Generation Options

EMFText's code generation can be configured using various options. These are specified in a dedicated optional OPTIONS section:

```
OPTIONS {
    // options go here in the following form:
    optionName = "optionValue";
}
```

The list of valid options and their documentation can be found in Appendix A.

#### 3.2 Tokens

EMFText allows to specify custom tokens. Each token type has a name and is defined by a regular expression. This expression is used to convert characters from the DSL files to form groups (i.e., tokens). Tokens are the smallest unit processed by the generated parser. By default, EMFText implicitly uses a set of predefined standard tokens, namingly:

```
TEXT: ('A'..'Z'|'a'..'z'|'0'..'9'|'_'|'-')+,
LINEBREAK: ('\r\n'|'\r'|'\n'),
WHITESPACE: (''|'\t'|'\f').
```

The predefined tokens can be explicitly excluded by using the usePredefinedTokens option:

```
OPTIONS {
    usePredefinedTokens = "false";
}
```

# 3.2.1 Defining Custom Tokens

To define custom tokens, a TOKENS section must be added to the .cs file. This section has the following form:

```
TOKENS {
    // token definitions go here in the form:
    DEFINE YOUR_TOKEN_NAME $yourRegularExpression$;
}
```

Every token name has to start with a capital letter. A regular expression must conform to the ANTLRv3 syntax for regular expressions (without semantic annotations). However, don't worry: EMFText will complain if there is a problem with your regular expressions, such as typos or overlaps of regular expressions.

#### 3.2.2 Composed Tokens

Sometimes, regular expressions are quite repetitive and one wants to reuse simple expressions to compose them to more complex ones. To do so, one can refer to other token definitions by their name. For example:

```
TOKENS {
    // simple token
    DEFINE CHAR $('a'...'z'|'A'...'Z')$;
    // simple token
    DEFINE DIGIT $('0'...'9')$;
    // composed token
    DEFINE IDENTIFIER CHAR + $($ + CHAR + $|$ + DIGIT + $)*$;
}
```

If token definitions are merely used as "helper" tokens, they can be tagged as FRAGMENT. This means the helper token itself is used in other token definitions, but not anywhere else in the syntax specification:

```
TOKENS {
    // simple token
    DEFINE CHAR $('a'...'z'|'A'...'Z')$;
    // helper token - not used on its own
    DEFINE FRAGMENT DIGIT $('0'...'9')$;
    // composed token
    DEFINE IDENTIFIER CHAR + $($ + CHAR + $|$ + DIGIT + $)*$;
}
```

The regular expressions are composed the same way strings are composed in Java programs. Therefore, make sure to put parenthesis around expressions where it is needed.

#### 3.2.3 Token Priorities

EMFText does automatically sort token definitions. However, sometimes token definitions might be ambiguous (i.e., the regular expressions defined for two different tokens are not disjoint). In such cases EMFText will always prefer more specific token over more general tokens. That is, if one token definition includes another one, the latter is preferred over the former. If the automatic token sorting fails, EMFText will report an error. In this case one must turn off the automatic sorting using the <code>disableTokenSorting</code> option and sort the tokens manually. If automatic token sorting is turned off, one can given a higher priority to imported tokens by using the following directive:

```
TOKENS {
         PRIORITIZE NameOfImportedToken;
         DEFINE SOME_CUSTOM_TOKEN $someCustomRegularExpression$;
}
```

The PRIORITIZE directive can also be used with the predefined tokens TEXT, LINEBREAK and WHITESPACE.

#### 3.3 Token Styles

To define the default syntax highlighting for a language, a special section TOKENSTYLES can be used. For each token or keyword the color and style (BOLD, ITALIC, STRIKETHROUGH, UNDERLINE) can be specified as follows:

```
TOKENSTYLES {
    // show YOUR_TOKEN in black
    "YOUR_TOKEN" COLOR #000000;
    // show keyword 'public' in red and bold font face
    "public" COLOR #FF0000, BOLD;
}
```

The default highlighting can still be customized at runtime by using the generated preference pages.

#### 3.4 Syntax Rules

For each concrete metaclass you can define a syntax rule. The rule specifies what the text that represents instances of the class looks like. Rules have two sides—a left and right-hand side. The left side denotes the name of the meta class, while the right-hand side defines the syntax elements. If you have imported additional metamodels you can refer to their metaclasses using the prefix you've defined in the import statement. For example pre.MetaClassA refers to MetaClassA for the metamodel with the prefix pre.

#### 3.4.1 Simple Syntax

The most basic form of a syntax rule is:

```
YourMetaClass ::= "someKeyword" ;
```

This rule states that whenever the text **someKeyword** is found, an instance of **YourMetaClass** must be created. Besides text elements that are expected "as is", parts of the syntax can be optional or repeating. For example the syntax rule:

```
YourMetaClassWithOptionalSyntax ::= ("#")? "someKeyword" ;
```

states that instances of YourMetaClassWithOptionalSyntax can be represented both by #someKeyword and someKeyword. Similar behavior can be defined using a star instead of a question mark. The syntax enclosed in the parenthesis can then be repeated. For example,

```
YourMetaClassWithRepeatingSyntax ::= ("#")* "someKeyword" ;
```

allows to represent instances of metaclass YourMetaClassWithRepeatingSyntax by writing someKeyword, #someKeyword, #someKeyword, or any other number of hash symbols followed by someKeyword. One can also use a plus sign instead of a star or question mark. In this case, the syntax enclosed in the parenthesis can be repeated, but must appear at least once.

#### 3.4.2 Syntax for EAttributes

#### Syntax for EAttributes Having an Arbitrary Type

If metaclasses have attributes, we can also specify syntax for their values. To do so, simply add brackets after the name of the attribute:

```
YourMetaClassWithAttribute ::= yourAttribute[];
```

Optionally, one can specify the name of a token inside the brackets. For example:

```
YourMetaClassWithAttribute ::= yourAttribute[MY_TOKEN] ;
```

If the token name is omitted, as in the first example, EMFText uses the predefined token TEXT, which includes alphanumeric characters (see Sect. 3.2). The found text is automatically converted to the type of the attribute. If this conversion is not successfull, an error is raised when opening a file containing wrong syntax. For details on customizing the conversion of tokens, see Sect. 4.2.1.

Another possibility to specify the token definition that shall be used to match the text for the attribute value is do it inline. For example

```
YourMetaClassWithAttribute ::= yourAttribute['(',')'] ;
```

can be used to express that the text for the value of the attribute yourAttribute must be enclosed in parenthesis. Between the parenthesis arbitrary characters (except the closing parenthesis) are allowed. Other characters can be used as prefix and suffix here as well.

By default, the suffix character (in the example above this was the closing parenthesis) can not be part of the text for the attribute value. To allow this, an escape character needs to be supplied:

```
YourMetaClassWithAttribute ::= yourAttribute['(',')','\'];
```

Here the backslash can be used inside the parenthesis to escape the closing parenthesis. It must then also be used to escape itself. That is, one must write two backslash characters to represent one.

To give an example on how escaping works, consider the following text: (text(more)). After parsing, this yields the attribute value text(more). The character sequence \) is replaced by ). Note that the opening parenthesis does not need to be escaped.

#### Syntax for EAttributes of Type EBoolean

For boolean attributes, EMFText provides a special feature to ease syntax specification. All that is required is to give the two strings that represent **true** and **false**. To give an example consider the following syntax rule:

```
YourMetaClassWithAttribute ::= yourAttribute["yes" : "no"] ;
```

This rules states that **yes** represents the **true** value and **no** represents **false**. You can also use the empty string for one of the values:

```
YourMetaClassWithAttribute ::= yourAttribute["set" : ""] ;
```

This way, the attribute is set to false by default and set to true in the text set is found.

#### 3.4.3 Syntax for EReferences

Metaclasses can have references and consequently there is a way to specify syntax for these. EMF distinguishes between *containment* and *non-containment* references. In an EMF model, the elements that are referenced with the former type are contained in the parent elements. EMFText thus expects the text for the contained elements (children) to be also contained in the parent's text.

The latter (non-containment) references are referenced only and are contained in another (parent) element. Thus, EMFText does not expect text that represents the referenced element, but a symbolic identifier that refers to the element. This is very similar to the declaration and use of variables in Java. The declaration of a variable consists of the complete text that is required to describe a variable (e.g., its type). In contrast, when the variable is used at some other place it is simply referred to by its name. Non-containment references are similar to uses of variables.

#### **Syntax for Containment References**

A basic example for defining a rule for a meta class that has a containment reference looks like this:

```
YourContainerMetaClass ::= "CONTAINER" yourContainmentReference ;
```

It allows to represent instances of YourContainerMetaClass using the keyword CONTAINER followed by one instance of the type that yourContainmentReference points to. If multiple children need to be contained the following rule can be used:

```
YourContainerMetaClass ::= "CONTAINER" yourContainmentReference*;
```

In addition, each containment reference can be restricted to allow only certain types, for example:

```
YourContainerMetaClass ::= "CONTAINER"

yourContainmentReference : SubClass ;
```

does allow only instances of **SubClass** after the keyword **CONTAINER** even though the reference **yourContainmentReference** may have a more general type. One can also add multiple subclass restrictions, which must then be separated by a comma:

```
YourContainerMetaClass ::= "CONTAINER"

yourContainmentReference : SubClassA, SubClassB;
```

#### **Syntax for Non-Containment References**

A basic example for defining a rule for a metaclass that has a non-containment reference looks like this:

```
YourPointerMetaClass ::= "POINTER" yourNonContainmentReference[] ;
```

The rule is very similar to the one for containment references, but uses the additional brackets after the name of the reference. Within the brackets the token that the symbolic name must match can be defined. In the case above, the default token TEXT is used. Therefore, the syntax for an example instance of class YourPointerMetaClass can be POINTER a.

Since a is just a symbolic name that must be resolved to an actual model element, EMF-Text generates a Java class that resolves a to a target model element. This class be customized to specify how symbolic names are resolved to model elements. The default implementation of the resolver looks for all model elements that have the correct type (the type of yourNonContainmentReference) and that have a name or id attribute that matches the symbolic name. For details on how to customize the resolving of references, see Sect. 4.2.2.

#### 3.4.4 Syntax for Printing Instructions

By default, EMFText can print all kinds of models. It does also preserve the layout of the textual representation when models are parsed and printed later on. However, to print models that have been created in memory, additional information can be passed to EMFText to cutomize the print result. This (optional) information includes the number of whitespaces and line breaks to be inserted between keywords, attribute values, references and contained elements. If you do not want to print models to text, printing instructions are not needed in your .cs file.

#### Syntax for Printing Whitespace

To explicitly print whitespace characters, the # operator can be used on the right side of syntax rules:

```
YourMetaclass ::= "keyword" #2 attribute[];
```

It is followed by a number that determines the number of whitespaces to be printed. In the example above, two whitespace characters are printed between the keyword and the attribute value.

#### Syntax for Printing Line Breaks

To explicitly print line breaks, the! operator can be used on the right side of syntax rules:

```
YourMetaclass ::= "keyword" !0 attribute[];
```

It is followed by a number that determines the number of tab characters that shall be printed after the line break. In the example above, a line break is printed after **keyword**. The number of tabs refers to the current model element (i.e., **E0bject**), which is printed. To print contained objects with an indendation of one tab, you can use a rule like this:

```
YourMetaclass ::= "keyword" "{" (!1 containmentRef)* !0 "}";
```

Here, the first line break operator (!1) makes sure that all the contained objects appear on a new line and that they are preceded by one tab character. The second line break operator (!0) tells EMFText to print the closing parenthesis (}) also on a new line, but without a leading tab.

#### 3.4.5 Syntax for Expressions

When defining syntax for an expression language (e.g., arithmetic expressions) EMFText's standard mechanisms for specifying syntax can lead to structures that can not be optimally handled by an interpreter or evaluator. Furthermore, the underlying parser generator technology used by EMFText causes problems if left recursive rules are required to build an optimal expression tree, which is the case for all expression languages with left-associative binary operators (e.g., -). Therefore, EMFText provides a special feature called operator precendence annotations (@Operator). These annotations can be added to all rules, which refer to expression metaclasses with a common superclass. For example, the rule:

```
@Operator(type="binary_left_associative", weight="1", superclass="Expression")
Additive ::= left "+" right;
```

defines syntax for a metaclass Additive. The references left and right must be containment references and have the type Expression, which is the abstract supertype for all metaclasses of the expression metamodel.

The type attribute specifies the kind of expression at hand, which can be binary (either left\_associative or right\_associative), unary\_prefix, unary\_postfix or primitive.

The weight attribute specifies the priority of one expression type over another. For example, if a second rule:

```
@Operator(type="binary_left_associative", weight="2", superclass="Expression")
Multiplicative ::= left "*" right;
```

is present, EMFText will create an expression tree, where Multiplicative nodes are created last (i.e., multiplicative expressions take precedence over additive expressions).

Unary expressions can be defined as follows:

```
@Operator(type="unary_prefix", weight="4", superclass="Expression")
Negation ::= "-" body;
```

There is also the option to define unary\_postfix rules.

Primitive expressions can be defined as follows:

```
@Operator(type="primitive", weight="5", superclass="Expression")
IntegerLiteralExp ::= intValue[INTEGER_LITERAL];
```

They should be used for literals (e.g., numbers, constants or variables).

For examples how to use @Operator annotations see the SimpleMath language in the EMF-Text Syntax Zoo<sup>1</sup> and the ThreeValuedLogic DSL<sup>2</sup>. These do also come with an interpreter which shows how expression trees can be evaluated.

#### 3.5 Suppressing warnings

To suppress warnings issued by EMFText in .cs files one can use the @SuppressWarnings annotation. This annotation can be added to rules, token definitions or complete syntax

<sup>&</sup>lt;sup>1</sup>http://www.emftext.org/language/simplemath

<sup>&</sup>lt;sup>2</sup>http://www.emftext.org/language/threevaluedlogic

definitions. One can either suppress all warnings or just specific types. To suppress all warning for a syntax use the following syntax:

```
@SuppressWarnings
YourMetaClass ::= "someKeyword";
```

A list of all warning types can be found in Appendix B. For example, to suppress warnings about features without syntax, you may use:

```
@SuppressWarnings(featureWithoutSyntax)
YourMetaClassWithAttribute ::= "someKeyword";
```

## 4 DSL Customization

#### 4.1 Customization Techniques

To adjust DSL plug-ins generated by EMFText to specific needs, there are three different customization techniques. Each of the subsequent sections describes one of them.

#### 4.1.1 Overriding Generated Artifacts

The most simple way to customize generated artifacts is to tell EMFText that it must not override a specific class or file, which needs to be changed. For all artifacts that are generated by EMFText there is a **override** option, which can be set to **false** to preserve such manual changes (see App. A for a complete list). For example, to customize the hover text shown when the mouse arrow points at an element in the editor, the **overrideHoverTextProvider** must be set to **false**.

For all files that do not depend on the rules defined in the .cs file, this customization technique is fine. These files do not change, if new rules are added or existing ones are changed. Thus, manual changes will not cause conflicts if the syntax evolves. Only when EMFText is updated and the code generators are replaced, one may want to compare the manually adjusted files with the ones generated by the new EMFText version to see whether all customizations are still correct. This does particularly apply to generated manifest files and plug-in descriptors. A list of all classes that are syntax dependent can be found in App. A.

#### 4.1.2 Overriding Meta Information Classes

For all files that do depend on the rules defined in the .cs file, another customization technique is more appropriate. Instead of setting the override option to false for the artifact that needs to be changed, one can set the override option for the meta information classes to false.

Each of the two generated resource plug-ins contains a meta information class. These are called XyzMetaInformation and XyzUIMetaInformation. Both classes provide factory methods to create instances of some important classes (e.g., createParser() or createPrinter()). To customize these classes (e.g., the printer) one can change the create methods to return instances of subclasses of the original classes. By using subclasses instead of overriding the classes directly, one can regenerate the resource plug-ins and thereby obtain new up-to-date classes, but still make customizations by overriding individual methods.

#### 4.1.3 Using Generated Extension Points

In addition to overriding generated classes—either directly or using the meta information factory methods—one can use the extension points that are generated by EMFText for all DSLs.

Currently EMFText generates two extension points for each DSL—default\_load\_options and additional\_extension\_parser.

The former can be used to customize how resources are loaded. For example, post processors can be registered which apply changes to the models that are created from their textual representation (see Sect. 4.2.3). Also, pre processors can be registered to process the input before it is actually passed to the parser. This is particularly useful to handle unicode characters (see the JaMoPP implementation<sup>1</sup> for an example how to use it).

The latter extension point can be used to register additional parsers which can handle a particular file extension. EMF on its own does map one file extension to one resource factory, but sometimes it is useful to have multiple resource types for the same file extension. An example for how to use this extension point can be found in the textual syntax for Ecore<sup>2</sup>.

#### 4.2 Concrete Customizations

#### 4.2.1 Customizing Token Resolving

To create models from their textual representation, it is necessary to convert the plain text found in Domain-specific Language (DSL) documents to attribute values (i.e., data types). For example, if the string "123" is found in a text file and shall be used as value for an attribute which has type EInt, the string needs to be converted to an int. Basic conversions, such as the one just mentioned, are handled by the generated class XyzDefaultTokenResolver (assuming the file extension of your DSL is xyz). However, if you want to use custom data types in your metamodels, or if you need to customize the default conversion, there are two ways to change the conversion of text to data types.

# **Customizing TokenResolver Classes**

The first option to customize the conversion of text, is to change the generated token resolver classes. EMFText generates one of these classes for each token that is defined in the .cs file. All classes end up in a package called analysis in the src folder of the generated resource plug-in.

Each token resolver class has two methods—resolve() and deResolve(). The first one is used to convert text to data types. The second one is used to perform the other way around. Consequently, resolve() is used when models are parsed, while deResolve() is used to print models to text.

The default implementation for both methods delegates calls to a default token resolver. However, this call can be replaced by custom code implementing different behavior. The code in the resolve() method must convert the text (given by the parameter lexem) to an object of the data type. This object must be set using result.setResolvedToken(). The deResolve() must implement the opposite behavior by returning a string representation of the object.

In the following a custom token resolver class is shown, which converts TEXT tokens to java.util.Date objects:

<sup>1</sup>http://www.jamopp.org

 $<sup>^2</sup> http://www.emftext.org/index.php/EMFText\_Concrete\_Syntax\_Zoo\_Ecore$ 

```
import java.text.ParseException;
import java.text.SimpleDateFormat;
import java.util.Date;
import java.util.Map;
import org.eclipse.emf.ecore.EObject;
import org.eclipse.emf.ecore.EStructuralFeature;
import org.emftext.language.xyz.resource.xyz.IXyzTokenResolveResult;
import org.emftext.language.xyz.resource.xyz.IXyzTokenResolver;
public class XyzTEXTTokenResolver implements IXyzTokenResolver {
  private SimpleDateFormat format = new SimpleDateFormat("dd.MM.yyyy");
  public String deResolve(Object value, EStructuralFeature feature,
      EObject container) {
   return format.format(value);
  }
  public void resolve(String lexem, EStructuralFeature feature,
      IXyzTokenResolveResult result) {
    try {
      Date date = format.parse(lexem);
      result.setResolvedToken(date);
    } catch (ParseException e) {
      result.setErrorMessage(lexem + "_is_not_a_valid_date.");
   }
  }
  public void setOptions(Map<?,?> options) {
    // can be left empty
  }
}
```

The difference between this kind of customization and the one below, is that the implemented conversion is local w.r.t. the textual syntax of the DSL. If you have multiple syntax definitions for your DSL, each can use completely different algorithms to convert data types.

#### **Customizing the EMF Data Type Handling**

Alternatively, you can customize the data type handling that is built into EMF. To do so, you need to define a custom data type in the metamodel (e.g., JavaDate). Then, the instance type name must be set to the actual Java class, which shall be used to represent instances of the data type (e.g., java.util.Date). When running the EMF code generation, the FactoryImpl class

will contain two methods—createJavaDateFromString() and convertJavaDateToString(). These need to be customized similar to the token resolver class before.

The following code is a snippet from the XyzFactoryImpl class and shows how to implement the same behavior as above using EMF's own data type handling facilities.

```
private SimpleDateFormat format = new SimpleDateFormat("yyyy-MM-dd");
/**
 * <!-- begin-user-doc -->
 * <!-- end-user-doc -->
 * @generated NOT
public Date createJavaDateFromString(EDataType eDataType,
    String initialValue) {
  try {
    return format.parse(initialValue);
  } catch (ParseException e) {
    // ignore
  return (Date)super.createFromString(eDataType, initialValue);
/**
 * <!-- begin-user-doc -->
 * <!-- end-user-doc -->
 * @generated NOT
 */
public String convertJavaDateToString(EDataType eDataType,
    Object instanceValue) {
 return format.format(instanceValue);
}
```

#### 4.2.2 Customizing Reference Resolving

If metamodels expose non-containment references (i.e., EReferences where the containment attribute is set to false), EMFText needs to resolve these references. This basically means that symbolic identifiers, which are used to reference other EObjects must be replaced by actual references to the respective objects.

Thus, EMFText generates one reference resolver class for each non-containment reference that is found in the metamodel of your DSL and that is actually used in the concrete syntax definition. All reference resolver classes end up in a package called **analysis** in the **src** folder of the generated resource plug-in.

The default implementation delegates calls to the **DefaultResolverDelegate** class. This class uses the following strategy to find objects that are referenced by identifiers:

- 1. the resource is searched for objects that have the correct type (i.e., the type of the non-containment reference)
- 2. if the objects having the correct type have an ID attribute, or a name attribute, or a single attribute of type EString, the value of this attribute is compared to the symbolic identifier. If the identifier matches the value of the attribute, the object is considered to be referenced.
- 3. if no matching object is found and the symbolic identifier is a valid URI, EMFText tries to load the resource at the URI. If the resource contains a root object with the correct type, this object is assumed to be referenced.

In cases, where this default resolving strategy is not sufficient, you can customize the resolver classes by changing the bodies of the methods resolve() and deResolve(). These methods are similar to the ones generated for the token resolver classes (see Sect. 4.2.1). The first one is used to find the object referenced by an identifier. The second one does the opposite—it creates a symbolic identifier for a referenced object. Again, the former is used after parsing. The latter is called when printing models.

The resolve() method must call result.addMapping(identifier, object) to set the referenced object, if one is found. The deResolve() method can simply return the textual representation of the referenced object as string.

To enable code completion for references, the resolve() method must be extended to take care of the resolveFuzzy parameter. If this parameter is true, the resolver class is used for code completion and must add all referenceable object to the result. Thus, instead of checking, whether identifier actually references an object, resolve() can simply add all objects that have the correct type to the result by calling result.addMapping(). However, in this case, the first argument, which is passed to addMapping() should not be identifier, but rather the string representation of the object.

#### 4.2.3 Implementing Post Processors

Another quite common customization task is to implement post processors. Post processors basically provide the possibility to modify the model that is created when text is parsed. This way one can add default elements which are not represented in the model's textual representation or normalize models if multiple concrete syntax is allowed for the same DSL concept.

Registered post processors are automatically called by the generated DSL tooling whenever a model is created from text. This does also include the case where the editor parses text in the background to show errors immediately. Thus, post processors must be able to deal with partial models or explicitly abort their execution if errors (e.g., syntactical problems) have been detected beforehand.

Post processors should not be used to solely implement semantic checks (i.e., to validate models). This should rather be done using the EMF Validation Framework as this allows checks to be available in all editors rather than a single one that was generated by EMFText.

To register a post processor for your DSL, the generated default\_load\_options extension point must be used. This extension point allows to register classes that provide default load options, which are used whenever resources are loaded by the generated DSL tooling.

Such classes must implement the IXyzOptionProvider interface, which has one method—getOptions(). To register a post processor, this method must return a map that has an entry where the key is IXyzOptions.RESOURCE\_POSTPROCESSOR\_PROVIDER and the value is an instance of a class that implements the IXyzResourcePostProcessorProvider interface. The latter object is used by the generated DSL tooling to instantiate post processors by calling getResourcePostProcessor().

To illustrate this procedure consider the case where you want to add some default model elements to all models that are created from text. To do so, you need a plugin.xml which registers the option provider using the following code snippet:

This plugin.xml can be part of a separate plug-in (i.e., it does not need to be part of the generated resource plug-ins). The respective post processor class can be as follows.

```
package org.emftext.language.xyz.post;
import java.util.Collections;
import java.util.Map;
import org.eclipse.emf.ecore.EObject;
import org.emftext.language.xyz.resource.xyz.IXyzOptionProvider;
import org.emftext.language.xyz.resource.xyz.IXyzOptions;
import org.emftext.language.xyz.resource.xyz.IXyzResourcePostProcessor;
import org.emftext.language.xyz.resource.xyz.IXyzResourcePostProcessorProvider;
import org.emftext.language.xyz.resource.xyz.mopp.XyzResource;
public class PostProcessorExample implements IXyzOptionProvider,
  IXyzResourcePostProcessorProvider,
  IXyzResourcePostProcessor {
  public Map<?, ?> getOptions() {
    return Collections.singletonMap(
      IXyzOptions.RESOURCE_POSTPROCESSOR_PROVIDER,
      this
    );
  }
  public IXyzResourcePostProcessor getResourcePostProcessor() {
    return this;
  }
```

```
public void process(XyzResource resource) {
   EObject root = resource.getContents().get(0);
   // perform model modifications here
}
```

One can see that this class implements all three interfaces that are required to register a post processor. The actual post processing must be implemented in the **process()** method. Here, the model can be modified in arbitrary ways. However, one must be aware that any modification will yield different textual representations when the model is printed.

#### 4.2.4 Implementing Quick Fixes

If a problem is added to a resource (e.g., by a post processor, cf. Section 4.2.3), problem markers are automatically created in the editor. Markers are a convenient way to inspect the cause of the problem directly from the editor. By providing an instance of <code>IXyzQuickFix</code> while creating an <code>IXyzProblem</code>, actions are specified that can automatically solve the reported problem.

To implement a custom quick fix CustomQuickFix for a specific problem, XyzQuickFix must be subclassed. Normally, the context object (i.e., the object where the action is applied to) is provided as a parameter to the constructor of CustomQuickFix. The method applyChanges() performs the actual fix of the problem on the context object.

This context object is also passed to the constructor of <code>XyzQuickFix</code> along with a brief description of the quick fix and an image key that references an image for the quick fix. The image key is used by the <code>XyzImageProvider</code> that either takes a key of one of the standard Eclipse images or a path to the image relative to the UI project. In case a more sophisticated means for providing images is needed, the <code>XyzImageProvider</code> can be manually extended after the option <code>overrideImageProvider</code> has been set to <code>false</code>.

The following listing shows a simple quick fix, which removes a given element from the resource.

```
public class RemoveElementQuickFix extends XyzQuickFix
   implements IXyzQuickFix {

   private EObject objectToRemove;

   public RemoveElementQuickFix(String message, EObject objectToRemove) {
        super(message, "IMG_ETOOL_DELETE", objectToRemove);
        this.objectToRemove = objectToRemove;
   }

   @Override
   public void applyChanges() {
        EcoreUtil.delete(objectToRemove);
   }
}
```

```
}
```

#### 4.2.5 Implementing Builders

To implement a custom builder for your DSL, you can basically set the code generation option overrideBuilder to false:

```
OPTIONS {
    overrideBuilder = "false";
}
```

After regenerating the resource plug-ins (see Sect. 2.3), you will find a new class XyzBuilder in the src folder of the generated resource plug-in (assuming the file extension of your DSL is xyz). If you face compilation errors, make sure to the delete the XyzBuilder class from the src-gen folder.

The generated builder class contains two methods—isBuildingNeeded() and build(). The first one is called to let the builder decide, which resources need to be included in the build process. The default implementation returns false to avoid unnecessary loading of resources. To include all textual resources that contain models of your DSL, change the method to return true.

The second method is called whenever the content of a resource changes. You can implement arbitrary behavior here. Usually, builders create some kind of derived artifact, for example a transformed or compiled version of the DSL model. Since build() retrieves the resource as method parameter, you can easily access the contents of the resource. To save the derived artifact it is good practice to use the URI of the original resource to derive a new URI. This can for example be done by removing segments and adding new ones.

The following listing shows a simple builder, which copies the contents of the resource to a new resource without making any changes.

```
import java.io.IOException;
import java.util.Collection;

import org.eclipse.core.runtime.IProgressMonitor;
import org.eclipse.core.runtime.IStatus;
import org.eclipse.core.runtime.Status;
import org.eclipse.emf.common.util.EList;
import org.eclipse.emf.common.util.URI;
import org.eclipse.emf.ecore.EObject;
import org.eclipse.emf.ecore.resource.Resource;
import org.eclipse.emf.ecore.util.EcoreUtil;
import org.emftext.language.xyz.resource.xyz.IXyzBuilder;

public class XyzBuilder implements IXyzBuilder {
    public boolean isBuildingNeeded(URI uri) {
        return true;
    }
}
```

```
}
  public IStatus build(XyzResource resource, IProgressMonitor monitor) {
    // get contents and create copy
    EList<EObject> contents = resource.getContents();
    Collection<EObject> contentsCopy = EcoreUtil.copyAll(contents);
    // create new resource with different name
    URI newUri = URI.createURI("copy.xyz").resolve(resource.getURI());
    Resource newResource = resource.getResourceSet().createResource(newUri);
    // add copy of original content to new resource
    newResource.getContents().addAll(contentsCopy);
    // save new resource
    try {
      newResource.save(null);
    } catch (IOException e) {
      // handle exception
    return Status.OK_STATUS;
  }
}
```

Alternatively, you can also register builders for your DSL in other plug-ins.

#### 4.2.6 Implementing Interpreters

To ease the implementation of interpreters for your DSL, EMFText generates an interpreter stub. Assuming the file extension of your DSL is xyz, the abstract stub class will be named AbstractXyzInterpreter. To implement concrete interpreters, you can create subclasses of this stub class.

For each metaclass found in the metamodel of your DSL, the interpreter stub contains a **interprete\_Classname** method. These methods can be overridden in concrete interpreter classes to implement the desired interpretation for the objects of each type.

After implementing the methods for the classes which shall be interpreted, the interpreter can be used in different modes. First, models can be interpret using a stack. In this case, the interprete\_Classname methods must perform the interpretation, but should not call other interprete methods. This is automatically performed by the interpreter. One can put objects on the interpretation stack by calling addObjectToInterprete() and then start interpretation by calling interprete(). Interpretation ends when all objects from the stack are consumed.

Second, the interpretation can be performed without using the stack. In this case, the interprete\_Classname methods call other interprete methods to continue interpretation. The traversal of the model is more explicit than using the interpreter with the stack in this mode.

The first, stack-based interpretation mode is useful to traverse models in a bottom-up fashion. One can simply put all models elements (using eAllContents() on the model root element)

on the stack and then start interpretation. The second, stack-independent interpretation mode is useful to traverse models top-down.

The interpreter stub class has two type parameters—ResultType and ContextType, which concrete subclasses must bind. The former parameter (i.e., ResultType) specifies the return type of the interprete methods. The latter parameter (i.e., ContextType) defines the type of the parameter that is passed to the interprete methods. By binding the type parameters one can use arbitrary classes to pass interpretation results.

Examples for interpreters can be found in the EMFText Syntax Zoo. Both SimpleMath<sup>3</sup> and the ThreeValuedLogic DSL<sup>4</sup> use the generated interpreter stubs.

#### 4.2.7 Customizing Text Hovers

To implement custom text hovers for your DSL, basically set the code generation option overrideHoverTextProvider to false:

```
OPTIONS {
    overrideHoverTextProvider = "false";
}
```

After regenerating the resource plug-ins (see Sect. 2.3), a new class XyzHoverTextProvider can be found in the src folder of the generated resource UI plug-in (assuming the file extension of your DSL is xyz). If you face compilation errors, make sure to the delete the XyzHoverTextProvider class from the src-gen folder.

The generated hover text provider class contains one method—getHoverText(). The default implementation of this method delegates calls to a default provider. To customize the hover text you can inspect the EObject passed to the method and return arbitrary HTML code. The following listing shows a simple customized provider, which returns the type of the EObject.

```
import org.eclipse.emf.ecore.EObject;
import org.emftext.language.xyz.resource.xyz.IXyzHoverTextProvider;

public class XyzHoverTextProvider implements IXyzHoverTextProvider {
    public String getHoverText(EObject object) {
        return "An_object_of_type_" + object.eClass().getName();
    }
}
```

#### 4.2.8 Customizing Code Completion Proposals

The DSL tooling generated by EMFText does equip the DSL editor with default code completion facilities. If you find the completion proposals to be not sufficient, or you want to adjust them w.r.t. the text that is displayed for specific proposals or the icons that are shown, you can

<sup>&</sup>lt;sup>3</sup>http://www.emftext.org/language/simplemath

<sup>&</sup>lt;sup>4</sup>http://www.emftext.org/language/threevaluedlogic

customize the proposals. To do so, set the overrideProposalPostProcessor option to false. After regenerating the resource plug-ins, you will find a class XyzProposalPostProcessor in the src folder of the UI resource plug-in. The class with the same name in the src-gen folder can then be deleted.

The default implementation of the only method in this class (i.e., process()) does return the list of proposals as they are. However, you can make arbitrary changes to this list. For example, you can remove proposals if you find them not useful or modify proposals if you want to change the displayed string or icon. You can also add new proposals if needed.

The proposals that are passed to the <code>process()</code> method provide information such as which structural feature they complete (<code>getStructuralFeature())</code>, which image they are associated with (<code>getImage())</code> or which text is inserted if the respective proposal is selected by a user (<code>getInsertString())</code>. To modify proposals, new instances of the <code>XyzCompletionProposal</code> must be created, because this class is immutable.

# List of Figures

2.1	Iterative EMFText language development process	3
2.2	EMFText Project wizard	4
2.3	Projects generated by EMFText to implement language tooling	10

# List of Listings

2.1	Metamodel for the exemplary forms language written in text.ecore	
2.2	Concrete syntax specification for the exemplary forms language written in the	
	cs-language	8

## **A Code Generation Options**

EMFText currently supports 215 code generation options. However, most of them (181) are only used to specify which generated artifacts shall be customized. Subsequently, a list of all options and their description can be found.

#### additionalDependencies

A list of comma separated plug-in IDs, which will be added to the manifest of the generated resource plug-in. The default value for this option is an empty list.

### additionalExports

A list of comma separated packages, which will be added as exports to the manifest of the generated resource plug-in. The default value for this option is an empty list.

### additionalUIDependencies

A list of comma separated plug-in IDs, which will be added to the manifest of the generated resource UI plug-in. The default value for this option is an empty list.

### additionalUIExports

A list of comma separated packages, which will be added as exports to the manifest of the generated resource UI plug-in. The default value for this option is an empty list.

### antlrPluginID

Sets the ID for the generated common ANTLR runtime plug-in. The default value for this option is org.emftext.commons.antlr3\_2\_0.

### $autofix {\tt SimpleLeftrecursion}$

If set to **true**, EMFText will try to fix rules that contain simple left recursion. The default value for this option is **false**. This is a non-standard option, which might be removed in future releases of EMFText.

#### backtracking

If set to false, the ANTLR-backtracking is deactivated for parser generation. The default value for this option is true.

### basePackage

The name of the base package EMFText shall store the generated classes or the resource plug-in in. If this option is not set, the default value is determined by adding the suffix resource.FILE\_EXTENSION to the base package of the generator model.

### baseResourcePlugin

The plug-in containing the resource implementation for the DSL (if different from the generated resource plug-in). By default this option is not set, which means that the generated resource plug-in provides the resource implementation.

#### defaultTokenName

This option can be used to specify the name of the token that is used when no token is given for attributes or non-containment references in syntax rules. Declarations like featureX[] in CS rules will automatically be expanded to featureX[TOKEN\_Y] if the value of this option is TOKEN\_Y. The default value for this option is TEXT, which makes the predefined token TEXT the default token.

#### disableBuilder

If set to **true**, the builder that is generated and registered by default will not be registered anymore. The default value for this option is **false**.

### disableEMFValidationConstraints

If set to **true**, constraint validation using the EMF Validation Framework is disabled. The default value for this option is **false**.

#### disableEValidators

If set to false, constraint validation using registered EValidators will be enabled. The default value for this option is true.

### disableTokenSorting

Disables the automatic sorting of tokens. The default value for this option is false.

#### forceEOF

If set to false, EMFText will generate a parser that does not expect an EOF signal at the end of the input stream. The default value for this option is true.

### generateCodeFromGeneratorModel

If set to true, EMFText automatically generates the model code using the generator model referenced in the CS specification. The default value for this option is false.

### generateTestAction

If set to true, EMFText generates a UI action that can be used to test parsing and printing of files containing textual syntax. The default value for this option is false. This is a non-standard option, which might be removed in future releases of EMFText.

### generateUIPlugin

If set to false, EMFText will not generate the resource UI plug-in. The default value for this option is true.

### licenceHeader

A URI pointing to a text file that contains a header which shall be added to all generated Java files. This option is useful to include copyright statements in the generated classes. If this option is not set, a default (empty) header is added to all generated Java classes.

#### memoize

If set to false, the ANTLR-memoize is deactivated for parser generation. The default value for this option is true.

#### overrideAbstractExpectedElement

If set to false, the AbstractExpectedElement class will not be overridden. The default value for this option is true.

### overrideAbstractInterpreter

If set to false, the AbstractInterpreter class will not be overridden. The default value for this option is true.

#### overrideAdditionalExtensionParserExtensionPointSchema

If set to false, the extension point schema for additional parsers is not overridden. The default value for this option is true.

#### overrideAnnotationModel

If set to false, the AnnotationModel class will not be overridden. The default value for this option is true.

#### overrideAnnotationModelFactory

If set to false, AnnotationModelFactory class will not be overridden. The default value for this option is true.

### overrideAntlrPlugin

If set to false, no ANTLR common runtime plug-in is generated. The default value for this option is true.

### overrideAntlrTokenHelper

If set to false, the AntlrTokenHelper class will not be overridden. The default value for this option is true.

#### overrideAttributeValueProvider

If set to false, the AttributeValueProvider class will not be overridden. The default value for this option is true.

#### overrideBooleanTerminal

If set to false, the BooleanTerminal class will not be overridden. The default value for this option is true.

### overrideBracketInformationProvider

If set to false, the BracketInformationProvider class will not be overridden. The default value for this option is true.

### overrideBracketPreferencePage

If set to false, the BracketPreferencePage class will not be overridden. The default value for this option is true.

### overrideBracketSet

If set to false, the BracketSet class will not be overridden. The default value for this option is true.

#### overrideBrowserInformationControl

If set to false, the BrowserInformationControl class will not be overridden. The default value for this option is true.

#### overrideBuildProperties

If set to false, the build properties file will not be overridden. The default value for this option is true.

### overrideBuilder

If set to false, the Builder class will not be overridden. The default value for this option is true.

### overrideBuilderAdapter

If set to false, the BuilderAdapter class will not be overridden. The default value for this option is true.

### overrideCardinality

If set to false, the Cardinality class will not be overridden. The default value for this option is true.

#### overrideCastUtil

If set to false, the CastUtil class will not be overridden. The default value for this option is true.

#### overrideChoice

If set to false, the Choice class will not be overridden. The default value for this option is true.

### overrideClasspath

If set to false, the .classpath file of the resource plug-in will not be overridden. The default value for this option is true.

### overrideCodeCompletionHelper

If set to false, the CodeCompletionHelper class will not be overridden. The default value for this option is true.

### overrideCodeFoldingManager

If set to false, the CodeFoldingManager class will not be overridden. The default value for this option is true.

### overrideColorManager

If set to false, the ColorManager class will not be overridden. The default value for this option is true.

### overrideCompletionProcessor

If set to false, the CompletionProcessor class will not be overridden. The default value for this option is true.

#### overrideCompletionProposal

If set to false, the CompletionProposal class will not be overridden. The default value for this option is true.

### overrideCompound

If set to false, the Compound class will not be overridden. The default value for this option is true.

#### overrideContainment

If set to false, the Containment class will not be overridden. The default value for this option is true.

### overrideContextDependentURIFragment

If set to false, the ContextDependentUriFragment class will not be overridden. The default value for this option is true.

### overrideContextDependentURIFragmentFactory

If set to false, the ContextDependentUriFragmentFactory class will not be overridden. The default value for this option is true.

### overrideCopiedEList

If set to false, the CopiedEList class will not be overridden. The default value for this option is true.

#### overrideCopiedEObjectInternalEList

If set to false, the CopiedEObjectInternalEList class will not be overridden. The default value for this option is true.

#### overrideDefaultHoverTextProvider

If set to false, the DefaultHoverTextProvider class will not be overridden. The default value for this option is true.

### override Default Load Options Extension Point Schema

If set to false, the extension point schema for default load options is not overridden. The default value for this option is true.

### overrideDefaultResolverDelegate

If set to false, the default resolver class will not be overridden. The default value for this option is true.

#### overrideDefaultTokenResolver

If set to false, the DefaultTokenResolver class will not be overridden. The default value for this option is true.

### overrideDelegatingResolveResult

If set to false, the DelegatingResolveResult class will not be overridden. The default value for this option is true.

### override Doc Browser Information Control Input

If set to **false**, the DocBrowserInformationControlInput class will not be overridden. The default value for this option is **true**.

### overrideDummyEObject

If set to **false**, the DummyEObject class will not be overridden. The default value for this option is **true**.

### overrideDynamicTokenStyler

If set to false, the DynamicTokenStyler class will not be overridden. The default value for this option is true.

#### overrideEClassUtil

If set to false, the EClassUtil class will not be overridden. The default value for this option is true.

#### overrideEObjectSelection

If set to false, the EObjectSelection class will not be overridden. The default value for this option is true.

### overrideEObjectUtil

If set to false, the EObjectUtil class will not be overridden. The default value for this option is true.

### overrideEProblemType

If set to false, the EProblemType class will not be overridden. The default value for this option is true.

#### overrideEditor

If set to false, the Editor class will not be overridden. The default value for this option is true.

### overrideEditorConfiguration

If set to **false**, the EditorConfiguration class will not be overridden. The default value for this option is **true**.

### overrideElementMapping

If set to false, the ElementMapping class will not be overridden. The default value for this option is true.

#### overrideExpectedBooleanTerminal

If set to false, the ExpectedBooleanTerminal class will not be overridden. The default value for this option is true.

### overrideExpectedCsString

If set to false, the ExpectedCsString class will not be overridden. The default value for this option is true.

### override Expected Structural Feature

If set to false, the ExpectedStructuralFeature class will not be overridden. The default value for this option is true.

### overrideExpectedTerminal

If set to false, the ExpectedTerminal class will not be overridden. The default value for this option is true.

### overrideFoldingInformationProvider

If set to false, the FoldingInformationProvider class will not be overridden. The default value for this option is true.

#### overrideFollowSetProvider

If set to false, the FollowSetProvider class will not be overridden. The default value for this option is true.

### overrideFormattingElement

If set to false, the FormattingElement class will not be overridden. The default value for this option is true.

### override Fuzzy Resolve Result

If set to false, the FuzzyResolveResult class will not be overridden. The default value for this option is true.

### override Grammar Information Provider

If set to false, the GrammarInformationProvider class will not be overridden. The default value for this option is true.

### overrideHTMLPrinter

If set to false, the HtmlPrinter class will not be overridden. The default value for this option is true.

### overrideHighlighting

If set to false, the Highlighting class will not be overridden. The default value for this option is true.

#### overrideHoverTextProvider

If set to false, the HoverTextProvider class will not be overridden. The default value for this option is true.

#### overrideHyperlink

If set to false, the Hyperlink class will not be overridden. The default value for this option is true.

### overrideHyperlinkDetector

If set to false, the HyperlinkDetector class will not be overridden. The default value for this option is true.

### overrideIBackgroundParsingListener

If set to false, the IBackgroundParsingListener class will not be overridden. The default value for this option is true.

#### overrideIBracketHandler

If set to false, the IBracketHandler class will not be overridden. The default value for this option is true.

#### overrideIBracketPair

If set to false, the IBracketPair class will not be overridden. The default value for this option is true.

### overrideIBuilder

If set to false, the IBuilder class will not be overridden. The default value for this option is true.

#### overrideICommand

If set to false, the ICommand class will not be overridden. The default value for this option is true.

### overrideIConfigurable

If set to **false**, the IConfigurable class will not be overridden. The default value for this option is **true**.

### overrideIContextDependentURIFragment

If set to false, the IContextDependentUriFragment class will not be overridden. The default value for this option is true.

#### overrideIContextDependentURIFragmentFactory

If set to false, the IContextDependentUriFragmentFactory class will not be overridden. The default value for this option is true.

### overrideIElementMapping

If set to false, the IElementMapping class will not be overridden. The default value for this option is true.

### overrideIExpectedElement

If set to false, the IExpectedElement class will not be overridden. The default value for this option is true.

#### overrideIHoverTextProvider

If set to false, the IHoverTextProvider class will not be overridden. The default value for this option is true.

### override IInput Stream Processor Provider

If set to false, the IInputStreamProcessorProvider class will not be overridden. The default value for this option is true.

### overrideILocationMap

If set to false, the ILocationMap class will not be overridden. The default value for this option is true.

#### overrideIMetaInformation

If set to false, the IMetaInformation class will not be overridden. The default value for this option is true.

### overrideIOptionProvider

If set to false, the IOptionProvider class will not be overridden. The default value for this option is true.

### overrideIOptions

If set to false, the IOptions class will not be overridden. The default value for this option is true.

### overrideIParseResult

If set to false, the IParseResult class will not be overridden. The default value for this option is true.

#### overrideIProblem

If set to false, the IProblem class will not be overridden. The default value for this option is true.

#### overrideIQuickFix

If set to false, the IQuickFix class will not be overridden. The default value for this option is true.

### overrideIReferenceCache

If set to false, the IReferenceCache class will not be overridden. The default value for this option is true.

### $override IR eference {\tt Mapping}$

If set to false, the IReferenceMapping class will not be overridden. The default value for this option is true.

### overrideIReferenceResolveResult

If set to false, the IReferenceResolveResult class will not be overridden. The default value for this option is true.

### overrideIReferenceResolver

If set to false, the IReferenceResolver class will not be overridden. The default value for this option is true.

#### overrideIReferenceResolverSwitch

If set to false, the IReferenceResolverSwitch class will not be overridden. The default value for this option is true.

#### overrideIResourcePostProcessor

If set to false, the IResourcePostProcessor class will not be overridden. The default value for this option is true.

#### overrideIResourcePostProcessorProvider

If set to false, the IResourcePostProcessorProvider class will not be overridden. The default value for this option is true.

### overrideITextDiagnostic

If set to false, the ITextDiagnostic class will not be overridden. The default value for this option is true.

#### overrideITextParser

If set to false, the ITextParser class will not be overridden. The default value for this option is true.

#### overrideITextPrinter

If set to false, the ITextPrinter class will not be overridden. The default value for this option is true.

#### overrideITextResource

If set to **false**, the ITextResource class will not be overridden. The default value for this option is **true**.

### overrideITextResourcePluginPart

If set to false, the ITextResourcePluginPart class will not be overridden. The default value for this option is true.

#### overrideITextScanner

If set to false, the ITextScanner class will not be overridden. The default value for this option is true.

### overrideITextToken

If set to **false**, the ITextToken class will not be overridden. The default value for this option is **true**.

#### overrideITokenResolveResult

If set to false, the ITokenResolveResult class will not be overridden. The default value for this option is true.

#### overrideITokenResolver

If set to false, the ITokenResolver class will not be overridden. The default value for this option is true.

### override IToken Resolver Factory

If set to false, the ITokenResolverFactory class will not be overridden. The default value for this option is true.

### overrideITokenStyle

If set to false, the ITokenStyle class will not be overridden. The default value for this option is true.

### overrideIURIMapping

If set to false, the IUriMapping class will not be overridden. The default value for this option is true.

### overrideImageProvider

If set to false, the ImageProvider class will not be overridden. The default value for this option is true.

### overrideInputStreamProcessor

If set to false, the InputStreamProcessor class will not be overridden. The default value for this option is true.

### overrideKeyword

If set to false, the Keyword class will not be overridden. The default value for this option is true.

### overrideLayoutInformation

If set to false, the LayoutInformation class will not be overridden. The default value for this option is true.

### overrideLayoutInformationAdapter

If set to false, the LayoutInformationAdapter class will not be overridden. The default value for this option is true.

### overrideLineBreak

If set to false, the LineBreak class will not be overridden. The default value for this option is true.

#### overrideListUtil

If set to false, the ListUtil class will not be overridden. The default value for this option is true.

#### overrideLocationMap

If set to false, the LocationMap class will not be overridden. The default value for this option is true.

### overrideManifest

If set to **false**, the manifest of the resource plug-in will not be overridden. The default value for this option is **true**.

### overrideMapUtil

If set to false, the MapUtil class will not be overridden. The default value for this option is true.

### overrideMarkerAnnotation

If set to false, the MarkerAnnotation class will not be overridden. The default value for this option is true.

### $override {\tt MarkerHelper}$

If set to false, the MarkerHelper class will not be overridden. The default value for this option is true.

#### overrideMarkerResolutionGenerator

If set to false, the MarkerResolutionGenerator class will not be overridden. The default value for this option is true.

#### overrideMetaInformation

If set to false, the MetaInformation class will not be overridden. The default value for this option is true.

#### overrideMinimalModelHelper

If set to false, the MinimalModelHelper class will not be overridden. The default value for this option is true.

#### overrideNature

If set to false, the Nature class will not be overridden. The default value for this option is true

#### overrideNewFileContentProvider

If set to false, the NewFileContentProvider class will not be overridden. The default value for this option is true.

#### overrideNewFileWizard

If set to false, the new file wizard class will not be overridden. The default value for this option is true.

### overrideNewFileWizardPage

If set to false, the NewFileWizardPage class will not be overridden. The default value for this option is true.

### overrideOccurrence

If set to false, the Occurrence class will not be overridden. The default value for this option is true.

### overrideOccurrencePreferencePage

If set to false, the OccurrencePreferencePage class will not be overridden. The default value for this option is true.

### overrideOutlinePage

If set to false, the OutlinePage class will not be overridden. The default value for this option is true.

### override Outline Page Tree Viewer

If set to false, the OutlinePageTreeViewer class will not be overridden. The default value for this option is true.

#### overridePair

If set to false, the Pair class will not be overridden. The default value for this option is true.

### overrideParseResult

If set to false, the ParseResult class will not be overridden. The default value for this option is true.

#### overrideParser

If set to false, the Parser class will not be overridden. The default value for this option is true.

### overrideParsingStrategy

If set to false, the ParsingStrategy class will not be overridden. The default value for this option is true.

#### overridePixelConverter

If set to false, the PixelConverter class will not be overridden. The default value for this option is true.

#### overridePlaceholder

If set to **false**, the Placeholder class will not be overridden. The default value for this option is **true**.

### $override {\tt PluginActivator}$

If set to false, the PluginActivator class will not be overridden. The default value for this option is true.

### overridePluginXML

If set to **true**, the plugin.xml file will be overridden. The default value for this option is **true**.

### overridePositionCategory

If set to false, the PositionCategory class will not be overridden. The default value for this option is true.

### overridePositionHelper

If set to false, the PositionHelper class will not be overridden. The default value for this option is true.

#### overridePreferenceConstants

If set to false, the PreferenceConstants class will not be overridden. The default value for this option is true.

#### overridePreferenceInitializer

If set to false, the PreferenceInitializer class will not be overridden. The default value for this option is true.

### overridePreferencePage

If set to false, the PreferencePage class will not be overridden. The default value for this option is true.

#### overridePrinter

If set to false, the printer will not be overridden. The default value for this option is true.

### overridePrinter2

If set to false, the Printer2 class will not be overridden. The default value for this option is true.

### overrideProblemClass

If set to false, the problem class will not be overridden. The default value for this option is true.

### overrideProjectFile

If set to false, the .project file of the resource plug-in will not be overridden. The default value for this option is true.

### overridePropertySheetPage

If set to false, the PropertySheetPage class will not be overridden. The default value for this option is true.

#### overrideProposalPostProcessor

If set to false, the ProposalPostProcessor class will not be overridden. The default value for this option is true.

### overrideQuickAssistAssistant

If set to false, the QuickAssistAssistant class will not be overridden. The default value for this option is true.

### overrideQuickAssistProcessor

If set to false, the QuickAssistProcessor class will not be overridden. The default value for this option is true.

#### overrideQuickFix

If set to false, the QuickFix class will not be overridden. The default value for this option is true.

#### overrideReferenceResolveResult

If set to false, the ReferenceResolveResult class will not be overridden. The default value for this option is true.

### overrideReferenceResolverSwitch

If set to false, the reference resolver switch will not be overridden. The default value for this option is true.

#### overrideReferenceResolvers

If set to **true**, the reference resolver classes will be overridden. The default value for this option is **false**.

### overrideResourceFactory

If set to **false**, the resource factory class will not be overridden. The default value for this option is **true**.

### over ride Resource Factory Delegator

If set to false, the ResourceFactoryDelegator class will not be overridden. The default value for this option is true.

### overrideResourceUtil

If set to false, the ResourceUtil class will not be overridden. The default value for this option is true.

### overrideScanner

If set to false, the Scanner class will not be overridden. The default value for this option is true.

### overrideSequence

If set to false, the Sequence class will not be overridden. The default value for this option is true.

#### overrideStreamUtil

If set to false, the StreamUtil class will not be overridden. The default value for this option is true.

### overrideStringUtil

If set to false, the StringUtil class will not be overridden. The default value for this option is true.

### overrideSyntaxColoringHelper

If set to false, the SyntaxColoringHelper class will not be overridden. The default value for this option is true.

### override Syntax Coloring Preference Page

If set to false, the SyntaxColoringPreferencePage class will not be overridden. The default value for this option is true.

### overrideSyntaxCoverageInformationProvider

If set to false, the SyntaxCoverageInformationProvider class will not be overridden. The default value for this option is true.

### overrideSyntaxElement

If set to false, the SyntaxElement class will not be overridden. The default value for this option is true.

### overrideSyntaxElementDecorator

If set to false, the SyntaxElementDecorator class will not be overridden. The default value for this option is true.

#### overrideTerminal

If set to false, the Terminal class will not be overridden. The default value for this option is true.

#### overrideTerminateParsingException

If set to false, the TerminateParsingException class will not be overridden. The default value for this option is true.

### overrideTextHover

If set to false, the TextHover class will not be overridden. The default value for this option is true.

#### overrideTextResource

If set to false, the text resource class will not be overridden. The default value for this option is true.

### overrideTextResourceUtil

If set to false, the TextResourceUtil class will not be overridden. The default value for this option is true.

### overrideTextToken

If set to false, the TextToken class will not be overridden. The default value for this option is true.

#### overrideTokenResolveResult

If set to false, the TokenResolveResult class will not be overridden. The default value for this option is true.

### overrideTokenResolverFactory

If set to false, the token resolver factory class will not be overridden. The default value for this option is true.

#### overrideTokenResolvers

If set to **true**, the token resolver classes will be overridden. The default value for this option is **false**.

#### overrideTokenScanner

If set to false, the TokenScanner class will not be overridden. The default value for this option is true.

### overrideTokenStyle

If set to false, the TokenStyle class will not be overridden. The default value for this option is true.

#### overrideTokenStyleInformationProvider

If set to false, the TokenStyleInformationProvider class will not be overridden. The default value for this option is true.

### overrideUIBuildProperties

If set to false, the build properties file of the resource UI plug-in will not be overridden. The default value for this option is true.

### overrideUIDotClasspath

If set to false, the .classpath file of the resource UI plug-in will not be overridden. The default value for this option is true.

### overrideUIDotProject

If set to **false**, the .project file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

### overrideUIManifest

If set to false, the manifest of the resource UI plug-in will not be overridden. The default value for this option is true.

#### overrideUIMetaInformation

If set to false, the MetaInformation class of the resource UI plug-in will not be overridden. The default value for this option is true.

#### overrideUIPluginActivator

If set to false, the plug-in activator class of the resource UI plug-in will not be overridden. The default value for this option is true.

### overrideUIPluginXML

If set to **false**, the plugin.xml file of the resource UI plug-in will not be overridden. The default value for this option is **true**.

### overrideURIMapping

If set to false, the UriMapping class will not be overridden. The default value for this option is true.

### overrideUnexpectedContentTypeException

If set to false, the UnexpectedContentTypeException class will not be overridden. The default value for this option is true.

#### overrideUnicodeConverter

If set to false, the UnicodeConverter class will not be overridden. The default value for this option is true.

### overrideWhiteSpace

If set to false, the WhiteSpace class will not be overridden. The default value for this option is true.

### parserGenerator

The name of the parser generator to use. The default value for this option is **antlr**, which is also the only valid value. This is a non-standard option, which might be removed in future releases of EMFText.

#### reloadGeneratorModel

If set to true, EMFText reloads the generator model before loading it. This is particular useful, when the meta model (i.e., the Ecore file) is changing a lot during language development. The default value for this option is false.

### resolveProxyElementsAfterParsing

If set to false, the generated resource class will not resolve references after parsing. The default value for this option is true.

#### resourcePluginID

The ID of the generated resource plug-in. The resource plug-in is stored in a folder that is equal to this ID.

### resourceUIPluginID

The ID of the generated resource UI plug-in. The resource UI plug-in is stored in a folder that is equal to this ID.

### saveChangedResourcesOnly

If set to true, the generated EMF resource will save only resource when their content (text) has actually changed. The default value for this option is false.

### srcFolder

The name of the folder where EMFText shall store the customizable classes of the resource plug-in in. All classes for which the **override** option is set to **false** will be stored in this folder.

### srcGenFolder

The name of the folder where EMFText shall store the generated classes of the resource plug-in in. All classes for which the **override** option is set to **true** will be stored in this folder.

### tokenspace

The (numerical) value of this option defines how many whitespace should be printed between tokens if no whitespace information is given in CS rules. This option should only be used with the classic printer. The default value of this option is 1 if the classic printer is used (see option useClassicPrinter) and automatic otherwise.

### uiBasePackage

The package where to store all classes of the resource UI plug-in in. If this option is not set, the default value is determined by adding the suffix resource.FILE\_EXTENSION.ui to the base package of the generator model.

### uiSrcFolder

The name of the folder where EMFText shall store the customizable classes of the resource UI plug-in in. All classes for which the **override** option is set to **false** will be stored in this folder.

#### uiSrcGenFolder

The name of the folder EMFText shall store the generated classes of the resource UI plug-in in. All classes for which the **override** option is set to **true** will be stored in this folder.

#### useClassicPrinter

If set to false, the classic printer (i.e., the one used before EMFText 1.3.0) will be used. Otherwise the new printer implementation is used. In any case both printers are generated, but only one is used. The default value for this option is false.

#### usePredefinedTokens

If set to false, EMFText does not automatically provide predefined tokens (TEXT, WHITESPACE, LINEBREAK). The default value for this option is true.

# **B** Types of Warnings

- abstractSyntaxHasStartSymbols
- collectInTokenUsedInRule
- duplicateOptionWithSameValue
- duplicateTokenStyle
- explicitSyntaxChoice
- featureWithoutSyntax
- generationWarning
- leftRecursiveRule
- licenceHeaderNotFound
- maxOccurenceMismatch
- minOccurenceMismatch
- multipleFeatureUse
- noRuleForMetaClass
- nonContainmentOpposite
- nonStandardOption
- oppositeFeatureWithoutSyntax
- optionalKeyword
- $\bullet \ reference To Abstract Class Without Concrete Subtypes In Abstract Syntax \\$
- styleReferenceToNonExistingToken
- tokenOverlapping
- tokenPriorizationUselessWhenTokenSortingEnabled
- unusedResolverClass
- unusedToken

# **A Syntax Dependent Artifacts**

The following artifacts depend on the .cs specification. Overriding them does therefore require special care.

- ANTLR grammar
- ullet AbstractInterpreter
- BracketInformationProvider
- BuilderAdapter
- $\bullet \ \ Folding Information Provider$
- GrammarInformationProvider
- MetaInformation
- Nature
- NewFileContentProvider
- Printer
- Printer2
- ReferenceResolverSwitch
- Resource
- ScannerlessParser
- SyntaxCoverageInformationProvider
- TokenResolverFactory
- TokenStyleInformationProvider

# **Bibliography**

- [Obj02] Object Management Group. Human Usable Textual Notation (HUTN) Specification. Final Adopted Specification ptc/02-12-01, 2002.
- [SBPM08] Dave Steinberg, Frank Budinsky, Marcelo Paternostro, and Ed Merks. *Eclipse Modeling Framework, 2nd Edition*. Pearson Education, 2008.