# **Documentation Cashregister Sales.**

Sales.

## **Database cashregister:**

Schema	Name	Туре	Owner
public	accounts	table	postgres
public	articles	table	postgres
public	buttons	table	postgres
public	params	table	postgres
public	payments	table	postgres
public	purchases	table	postgres
public	sales	table	postgres

### cashregister=# \d accounts

	Table	"public.accou	ınts"	
Column	Type	Collation	Nullable	Default
barcodeID	character varying(8)	1	not null	
firstname	character varying(20)	ĺ		''::character varying
lastname	character varying(30)			''::character varying
access	integer			1
callname	character varying(20)	1		''::character varying
Indovest				

"barcodeID\_pkey" PRIMARY KEY, btree ("barcodeID")

Column	Туре	Collation	Nullable	Default
parcode	character varying(13)		not null	
description	character varying(50)			''::character varying
item_price	double precision			0
item_stock	double precision		(1)	0
item_unit	character varying(6)			''::character varying
minimum_stock	double precision			0
order_size	double precision			0
location_warehouse	character varying(8)			''::character varying
article_group	character varying(40)			''::character varying
thumbnail	character varying(50)			''::character varying
photo	character varying(50)			''::character varying
category	integer			0
order_balance	double precision			0
order_status	boolean			true
mutation_date	character varying(10)			''::character varying
annual_consumption_1	double precision			0
annual_consumption_2	double precision		ĺ	0
VAT	character varying(4)			'hoog'::character varying
ndexes:				

### cashregister=# \d buttons

	Table	"public.buttons"	
Column	Туре	Collation   Nullable	Default
buttonID	integer	not null	
buttontext	character varying(20)		''::character varying
barcode	character varying(13)	not null	''::character varying

### Indexes:

	Table	"public.sales	"	
Column	Туре	Collation	Nullable	Default
ID	integer		not null	
receiptnumber	integer	İ	140 140 141	0
barcode	character varying(13)	1	1	''::character varying
description	character varying(40)	1		''::character varying
number	double precision			0
item_price	double precision	1	1	0
sub_total	double precision	1		0
sub_vat	double precision	1		0
callname	character varying(20)			''::character varying
mutation_date	character varying(10)	ĺ		''::character varying
ndexes:		Ē 116		

Column	Туре	Collation	Nullable	Default
payID	integer	† 	not null	 
kind	character varying(25)			''::character varying
amount	double precision	ĺ	ĺ	0
bookdate	character varying(10)	ĺ		''::character varying
paydate	character varying(10)	ĺ		''::character varying
instance	character varying(25)	Ì	ĺ	''::character varying
accountnumber	character varying(25)	İ	ĺ	''::character varying
ovorderID	integer	Ì	Ì	0
ndexes:			ž.	±10.775

#### Accounts.

The system detects if a logon barcode or a product barcode is scanned.

When no logon is established processing is blocked.

The message above the 'Exit' button show 'Logged out'

By valid login the message show <callname> logged in.

<sup>&</sup>quot;buttonID\_pkey" PRIMARY KEY, btree ("buttonID")

With the logon from barcode accesslevel 3 (10000014 for testing) a Administration button is activated. With this button and it's menuline 4 it is possible to generate other barcodes for logon purposes.

The barcodefield will be generated as 7 random digits by the program. (The 8th digit is a check number). The program will check and correct for duplicates. Access is default set on level 1, change if desired. The barcodelabel is saved in folder . /Barcodes/Accounts/

The callname field will be printed on the saleslip, it's also saved in the sales table.

When the account switch from level 1 to level 2 or level 3 or back the orderlines remains. If the account switches back the spinbox is reset to it's original state. When the login employee logs the barcode a second time, the employee is logged out.

When another employee logs his barcode, the logon is switched towards this employee.

Accesslevel 1. Normal operation. (No administration and no plusminbutton visible)

Accesslevel 2 . Expose an checkable button  $\pm$  for return products. The spinrange from the spinbox changes from 1, 99 to -1, -99 with button checked.

Accesslevel 3. Expose the Administration button. Pressing this button reveals a combobox with 10 menulines. The items are:

Articles request
Sales request
Payments request/paying
Accounts insert
Buttons define
Articles insert
Articles-list import
Write off loss
Purchase products
Parameters insert/change

#### **Articles**

The table articles helds a column barcode (String 13 positions).

By inserting a new article a ean 13 barcode is generated. The first 2 numbers is the country code. The next 5 numbers are the company numbers, the following 5 numbers is the product number en the last number is a validity check number.

In this module is a image saved of the barcode in the folder ./Barcodes/Articles

This image can be printed for labeling the product or storage bin in the warehouse, so it's enabled for scanning.

With the program Sales, the sales can be established by scanning barcodes.

The amount can be set with the little spinbox. The amount can be filled with the little arrows, or turning the mouseweheel on the field. The amount can be set from 1 to 99. The amount is default set to 1.

The module scans the barcode, looks up in the database the articlenumber, description, price and counts the subtotals and VAT. When scanning is completed, a orderlist can be printed.

If scanning is not possible, in case of a damaged barcode, the barcode can be filled manually.

In this case the <Enter> must be pressed on the keyboard.

The program checks if 13 numbers are filled and checks the validy check number.

The module provides a display with heading and 17 product lines.

The lines are scrolling, if more then 17 lines are added.

Below the display screen the totals including VAT and total VAT is displayed.

If the thirst scan is established the close button is blocked, until next client button is pressed.

Printing of the order is possible until the button next client is pressed.

In the print module the total price and total VAT is counted and printed in the tail heading. After the next client button is pressed the print button and the next client button is blocked, until the first scan for the next client is established. By scanning the table sales filled with the order receipt number, article number, description, amount, price, subtotal and subVAT, also in the table articles the stock data is updated.

With pressing the next client button the table afdrachten (payments) is filled with the totals and VAT.

By scanning is checked on 4 error conditions:

- 1. The checksum of the barcode is wrong. (wrong barcode or damaged)
- 2. The product is not in the range of the company.
- 3. Too little stock for the orderline.
- 4. Error message if not logged on.

The errors are showed below the product display in the color red.

With choise 3, also the amount of current stock is showed.

For return goods  $a \pm button$  is added.

This button is visible if the logon barcode is valid as code 2 or code 3 . See **Accounts.** If the button (checkable) is set on – the spinbox range change from -1 to -99.

### **Articles Request**

With this menuchoice a tableview from the articles table sorted on barcode is shown.

### **Sales Request**

With this menuchoice a tableview from the sales sorted on receiptnumber is shown.

### **Payments Request/Paying**

With this menuchoice a tableview from the payments towards instances sorted on not payed and receiptnumber is shown.

With this menuchoice is it also possible to book a payment towards instances by clicking on the thirst field from the payments request tableview. This action opens a payform whith a checkbox pay. By checking this box the payment is booked with the paydata. After this booking is done the checkbox is disabled for checking and the text from the box is changed in payed.

### Importing.

### **Programmable Buttons.**

Accessable with the admin button (security level 3)

There are 32 programmable buttons.

With the menuchoice Buttons define you will get a submenu 'New barcode' or 'Existing barcode' The thirst choice calls a form there a new barcode is generated and fields for a new article must be filled in, also in this form the buttontext (max 2 rows with 10 positions and 9 positions) and buttonnumber (1-32) must be inserted. If a button with a existing text is choosen the text is replaced and the button is linked towards the new barcodenumber. Minimal the fields description, price, buttonnumber and buttontext must be completed.

The second choice displays the barcode table. By browsing to the barcodeproduct and clicking on the thirst field a form is opened for inserting buttonnumber and buttontext. By accepting the buttonnumber with it's text the button linked to the chosen barcodenumber. The new buttontext become visible after a restart of the program.

P	11	rc	h	as	es.

Parameters.