Common

Library version:	RENAT 0.1.7
Library scope:	global
Named arguments:	supported

Introduction

Common library for RENAT

It loads config files and create necessary varibles. The file should be the 1st library included from any test case.

Table of Contents

Configuration file

Global configuration

There are 2 kinds of configuration files. The global configuration files (aka master files) include device information, authentication etc that are used for all the test cases in the suite. The local configuration file `local.yaml` includes information about nodes, tester ports etc. that are used in a specific test case.

At the beginning, the module makes a local copy the master files and initialize necessary variables.

The master files folder is defined by `renat-master-folder` in `$RENAT_PATH/config/config.yaml`. Usually, users do not need to modify the master files. The most common case is when new device is deployed, the `device.yaml` need to be update so that device could be used in the test cases.

- device.yaml: contains global device information

```
device:
  apollo:
    type: ssh-host
    description: main server
    ip: 10.128.3.101
  artermis:
    type: ssh-host
    description: second server
    ip: 10.128.3.91
  vmx11:
    type: juniper
    description: r1
    ip: 10.128.64.11
  vmx12:
    type: juniper
    description: r2
    ip: 10.128.64.12
```

- auth.yaml: contains authentication information

```
auth:
  plain-text:
    default:
      user: user
      pass: nttXXX
    flets:
      user: user
      pass: lpcoXXXX
    arbor:
      user: admin
      pass: nttXXX

  public-key: # for Public Key authentication
    default:
      user: robot
      key: /home/user/.ssh/robot_id_rsa
    test:
      user: jenkins
      key:  /var/lib/jenkins/.ssh/id_rsa
```

- template.yaml: contains devvice template information

```
access-template:
  ssh-host:
    access: ssh
    auth: public-key
    profile: default
    prompt: \$
```

```
      append:
      init: unalias -a
    juniper:
      access: telnet
      auth: plain-text
      profile: default
      prompt: "(#|>) "
      append: ' | no-more'
      init:
    cisco:
      access: ssh
      auth: plain-text
      profile: default
      prompt: "\@.*(#|>) "
      append:
      init:
snmp-template:
    juniper:
        mib: ./mib-Juniper.json
        community: public
        poller: renat
    cisco:
        mib: ./mib-Cisco.json
        community: public
        poller: renat
```

Local Configuration

Local configuration (aka `local.yaml`) was used by a test case of its sub test cases. Test cases could includes several test cases (the sub level is not limited). The local configuration is defined by `local.yaml` in the `config` folder of each test case. If a test case does not has the `local.yaml` in its `config` folder, it will use the `local.yaml` file in its parent test case and so on. This will help users to share the test information for related test case without having the same `local.yaml` for each test case (**Note:** this feature is enabled from RENAT 0.1.4). The `local.yaml` that is really used for the test is called `active local.yaml`.

When user used the wizard `case.sh` to create a new test case, they have the ability to crete new `local.yaml` or not. `local.yaml` could be edited and inserted new information later to hold more informations for the test case.

When a test is run, it will display its current active `local.yaml`

- <testcase>/config/local.yaml: contains local data for a test case

```
node:
  vmx11:
    device: vmx11
    snmp_polling: yes
  vmx12:
    device: vmx11
    snmp_polling: yes
  apollo:
    device: vmx11
    snmp_polling: yes

tester:
  tester01:
    type: ixnet
    ip: 10.128.32.70
    config: vmx_20161129.ixncfg

port-mapping:
  uplink01:
    device: vmx11
    port: ge-0/0/0
  downlink01:
    device: vmx12
    port: ge-0/0/2

default:
  ignore_dead_node: yes
  terminal:
    width: 80
    height: 32
  result_folder: result
```

Variables

The module automatically create `GLOBAL` & `LOCAL` variable for other libraries. It also creates global list variables *GLOBAL,LOCAL and `NODE` that could be accessed from* Robot Framework` test cases.

The GLOBAL variable holds all information defined by the master files and LOCAL variable holds all variables defined by active `local.yaml`. And `NODE` is a list that hold all active nodes defined in the `local.yaml`.

Users could access to the information of a key in `local.yaml` by `${LOCAL['key']}`, information of a node by `${LOCAL['node']['vmx11']}` or simply `$NODE['vmx']`. When a keyword need a list of current node, `@{NODE}` could be used.

Notes: By default, RENAT will stop and raise an exception if connection to a node is failed. But if `ignore_dead_node` is defined as `yes` (default) is the current active `local.yaml`, RENAT will omit an warning but keep running the test and remove the node from its active node list.

Shortcuts

Change Mod · **C**leanup Result · **C**onvert Html To Pdf · **C**ount Keyword · **C**ount Keyword Line · **C**ount Match Regexp · **C**reate Sequence · **C**sv Concat · **C**sv Merge · **C**sv Select · **D**iff File · **E**rr · **E**rror Line Should Not Be Bigger Than · **E**rror Should Not Be Bigger Than · **F**ile Md5 · **F**old Str · **F**ollow Syslog And Trap · **G**et Config Path · **G**et File Without Error · **G**et Item Config Path · **G**et Item Name · **G**et Renat Path · **G**et Result Folder · **G**et Result Path · **G**et Test Device · **I**s Stable · **K**eyword Line Should Not Be Bigger Than · **K**eyword Should Not Be Bigger Than · **L**og · **L**oop For Node Tag · **M**d 5 · **M**erge Files · **M**ib For Node · **N**ode With Attr · **N**ode With Tag · **N**ode Without Tag · **P**ause · **P**ing Until Ok · **R**andom Name · **R**andom Number · **R**enat Version · **S**et Multi Item Variable · **S**et Result Folder · **S**tr 2 Seq · **V**ersion

Keywords

Keyword	Arguments	Documentation
Change Mod	*name*, *mod*, *relative=False*	Changes file mod, likes Unix chmod `mod` is a string specifying the privilege mode `relative` is `False` or `True` Examples: Common.*Change Mod* | tmp | 0775
Cleanup Result	*ignore=^(log.html|output.xml|report.html)$*	Cleans up the result folder Deletes all files in current active folder that does not match the `ignore` expression and are older than the time the test has started. **Note**: The keyword only removes files but not folders
Convert Html To Pdf	*html_file*, *pdf_file*	Converts html file to pdf file
Count Keyword	*keyword*, **pattern_list*	Count the keyword in files. Keyword is not case-sensitive
Count Keyword Line	*keyword*, **pattern_list*	Count the number of lines contains the `keyword` **Notes:** Keyword is matched partially. For example, `error` or *`errorXXX* will be matched by *`error* keyword.
Count Match Regexp	*regexp*, **pattern_list*	Count the number of `regex` found in `pattern_list` Examples: ${err_num}= | *Count Match RegExp* | .*error.* | result/*.csv | result/*.txt
Create Sequence	*start*, *end*, *interval*, *option=float*	Creates a list with number from `start` to `end` with `interval` Example: @{list}= | *Create Sequence* | 10 | 15 | 0.5 will create a list of `[11.0, 11.5, 12.0, 12.5, 13.0, 13.5, 14.0, 14.5]`
Csv Concat	*src_pattern*, *dst_name*, *has_header=None*	Concatinates CSV files vertically If the CSV files has header, set `has_header` to `${TRUE}` Examples: Commmon.*CSV Merge* \| config/data0[3,4].csv \| result/result2.csv \| Commmon.*CSV Merge* \| config/data0[3,4].csv \| result/result2.csv \| has_header=${TRUE}
Csv Merge	*src_pattern*, *dst_name*, *on_key=0*, *has_header=None*	Merges all CSV files horizontally by `on_key` key from `src_pattern` `on_key` is the order of key column that is used as key when merging the files. Default is zero. When `has_header` is not `None` (default value), it is the order of the row used to make the column name. Returns `False` if only one file was found, no merging happend Examples: Common.*CSV Merge* | config/data0[3,4].csv | result/result2.csv | Common.*CSV Merge* | config/data0[3,4].csv | result/result2.csv | has_header=${TRUE}
Csv Select	*src_file*, *dst_file*, *str_row=:*, *str_col=:*, *has_header=None*	Select part of the CSV file and write it to other file `str_row` and `str_col` are used to specify necessary rows and columns. They are using the same format with slice for Python list. ▪ : and : means all rows and columns ▪ :2 and : means first 2 rows and all columns ▪ : and 1,2 means all rows and 2nd and 3rd columns ▪ 0:3 and 1 means 3 rows from the 1st one(0,1,2) and second column ▪ 0:5:2 and 1 means 3 rows(0,3,5) and second column

		Notes: ▪ Rows and columns are indexed from zero ▪ When ':' is used, the string has format: <start>:<stop> or <start>:<stop>:<step> For convenience, ':' means all the data, ':x' means first 'x' data Examples: *CSV Select* result/data05.csv result/result3.csv 0,1,2 0,1 *CSV Select* result/data05.csv result/result4.csv : 0,1 *CSV Select* result/data05.csv result/result5.csv :2 : *CSV Select* result/data05.csv result/result6.csv 0:3 : *CSV Select* result/data05.csv result/result7.csv 0:5:2 :
Diff File	*path1*, *path2*, *newline=True*	Shows difference between files Returns the diff result (multi lines) `path1` , `path2` are absolute paths.
Err	*msg*	Prints error `msg` to console
Error Line Should Not Be Bigger Than	*num*, **pattern_list*	Checks whether the number of lines that contains `error` be less than a number
Error Should Not Be Bigger Than	*num*, **pattern_list*	Checks whether the number of `error` be less than a number
File Md5	*path*	Returns MD5 hash of a file `path` is an absolute path
Fold Str	*str*	Folds a string by adding Non-Width-Space char (0x200b) at 6th char
Follow Syslog And Trap	*pattern*, *log_file_name=syslog-trap.log*, *delay_str=1s*	Pauses the execution and wait for the pattern is matched if the file *log_file_name* located in the current result folder. By default the *log_file_name* is *./result/syslog-trap.log* which is created by *Follow Syslog and Trap* keyword. The keyword should be in tests between *Follow Syslog adn Trap Start* and *Follow Syslog and Trap Stop* keywords.
Get Config Path		Returns absolute path of RENAT config folder path
Get File Without Error	*file_path*	Get content of the file and return null string if the file does not exist
Get Item Config Path		Returns absolute path of current item config folder
Get Item Name		Returns the name of the running item
Get Renat Path		Returns the absolute path of RENAT folder
Get Result Folder		Returns current result folder name. Default is `result` in current test case. **Note**: the keyword only returns the `name` of the result folder not its absolue path.
Get Result Path		Returns absolute path of the current result folder
Get Test Device		Return a list of all test device that is used in this test **Notes:** Device number could less than node number
Is Stable	*seq*, *threshold*, *percentile=90*	Checks if the value sequence is stable or not
Keyword Line Should Not Be Bigger Than	*num*, *keyword*, **pattern_list*	Checks whether the number of line containing the keyword be less than a number
Keyword Should Not Be Bigger Than	*num*, *keyword*, **pattern_list*	Checks whether the number of keyword be less than a number
Log	*msg*	Logs `msg` to the current log file
Loop For Node Tag	*var*, *tags*, **keywords*	Repeatly executes RF `keyword` for nodes that has tag `tags` multi tags are separated by *:* keywords has same meaning with `keywords` used by *Run Keywords* of RobotFramework (keyword and its arguments are separated by `AND` with the others. Example: *Loop For Node Tag* \${node} tag1 ... *Switch* \${node} AND ... *Cmd* show system user AND ... *Cmd* show system uptime **Note:** `$` in variable name must be escaped
Md 5	*str*	Returns MD5 hash of a string
Merge Files	*path_name*, *file_name*	Merges all the text files defined by `path_name` to `file_name` Example: *Merge Files* ./result/*.csv ./result/test.csv

Mib For Node	*node*	Returns the mib file name for this `node` mib file is define by `mib` keyword under the `node` in `local.yaml`
		
		`...`
		`node:`
		`  vmx11:`
		`  device: vmx11`
		`  snmp_polling: yes`
		`  mib: mib11.txt`
		`...`
		
		Default value is defined by `mib` keyword from global `config/snmp-template.yaml` for the `type` of the node
		
		Example:
		
		`${mib}=` `Common.MIB For Node` `vmx11`

Node With Attr	*attr_name*, *value*	Returns a list of nodes which have attribute `attr_name` with value `value`

Node With Tag	**tag_list*	Returns list of `node` from `local.yaml` that has **ALL** tags defined by `tag_list`
		
		Tag was defined like this in local.yaml
		
		`vmx11:`
		`  device: vmx11`
		`  snmp_polling: yes`
		`  tag:`
		`  - tag1`
		`  - tag2`
		
		Examples:
		
		`${test3}=` `Common.Node With Tag` `tag1` `tag3`

Node Without Tag	**tag_list*	Returns list of `node` from `local.yaml` that **does not has ANY** tags defined by `tag_list`
		
		Tag was defined like this in local.yaml
		
		`vmx11:`
		`  device: vmx11`
		`  snmp_polling: yes`
		`  tag:`
		`  - tag1`
		`  - tag2`
		
		Examples:
		
		`${test3}=` `Common.Node Without Tag` `tag1` `tag3`

Pause	*msg=*, *time_out=1s*, *default_input=*, *error_on_timeout=False*	Displays the message `msg` and pauses the test execution and wait for user input
		
		In case of `error_on_timeout` is False(default), the keyword will return with `default_input` and the test will be continued wihout error. Otherwise, the keyword will raise an error and stop.
		
		If the variable `${RENAT_BATCH}` was defined, the keyword will print out the message and keeps running without pausing.
		
		Examples:
		
		`Common.Pause` `Waiting...` `10s` `default` `error_on_timeout=${TRUE}`
		`Common.Pause` `Waiting...` `10s`

Ping Until Ok	*node*, *wait_str=5s*, *extra=-c 3*	Ping a `node` until it gets response. Then wait for more `wait_str` Default `extra` option is `-c 3`
Random Name	*base*, *a=0*, *b=99*	Returns a random name by a *base* and a random number between [a,b] Example: `${FOLDER}=` `Random Name` `capture_%05d` `0` `99`
Random Number	*a=0*, *b=99*	Returns a random number between [a,b]
Renat Version		Returns RENAT version string
Set Multi Item Variable	**vars*	Set multiple varibles to be *suite variable* at the same time Suite variables (or item variable) could be access anywhere in all the item scenario.
Set Result Folder	*folder*	Sets the result folder to `folder` and return the old result folder. The result folder contains all output files from the test likes tester ouput, config file ... `folder` is a folder name that under current test case folder The system will create a new folder if it does not exist and set its mode to *0775* **Note:** Result folder should be set at the begining of the test. Changing result folder only has effect on up comming connection
Str 2 Seq	*str_index*, *size*	Returns a sequence from string format

		Samples: *Str2Seq* :: 5 # (0,1,2,3,4) *Str2Seq* :2 5 # (0,1) *Str2Seq* 1:3 5 # (1,2) *Str2Seq* 0:5:2 5 # (0,2,4)
Version		Returns the current version of RENAT

Altogether 45 keywords.
Generated by Libdoc on 2018-03-20 02:58:08.