Common

Library version: RENAT 0.1.8g1

Library scope: global **Named arguments:** supported

Introduction

Common library for RENAT

It loads config files and create necessary varibles. The file should be the 1st library included from any test case.

Table of Contents

- Configuration file
- Variables
- Shortcuts
- Keywords

Configuration file

Global configuration

There are 2 kinds of configuration files. The global configuration files (aka master files) include device information, authentication etc that are used for all the test cases in the suite. The local configuration file local.yaml includes information about nodes, tester ports etc. that are used in a specific test case.

At the beginning, the module makes a local copy the master files and initialize necessary variables.

The RENAT framework utilized the YAML format for its configurations file.

The master files folder is defined by renat-master-folder in \$RENAT_PATH/config/config.yaml. Usually, users do not need to modify the master files. The most common case is when new device is deployed, the device.yaml need to be update so that device could be used in the test cases.

1. device.yaml: contains global device information

Each device information is store under device block and has the following format:

```
<node_name>
type: <device type>
description: <any useful description>
ip: <the IPv4 address of the device
```

Where <node_name> is the name of the device. It could be the name of a switch, router or a web appliance box and should be uniq between the devices. <description> is any useful information and <ip> is the IP that RENAT uses to access the device.

<type> is important because it will be used as the ky of the access_template in template file. Usually users do not need to invent a new type but should use the existed type. When a new platform need to be supported, a new type will be introduced with the correspon template and authentication information.

Samples:

```
device:
  apollo:
    type: ssh-host
    description: main server
    ip: 10.128.3.101
  artermis:
    type: ssh-host
    description: second server
    ip: 10.128.3.91
  vmx11:
    type: juniper
    description: r1
    ip: 10.128.64.11
  vmx12:
    type: juniper
    description: r2
    ip: 10.128.64.12
```

2. template.yaml: contains device template information

The template file contains information about how to access to the device and how it should polling information (SNMP only for now). Each template has the following format:

<type>: access: <ssh or telnet> auth: <plaint-text or public-key> profile: <authentication profile name> prompt: <a regular expression for the PROMPT of the CLI device> (optional) login_prompt: <a login PROMPT for CLI device> (optional) password_prompt:<a PROMPT for asking password of CLI device> (optional) append: <a pharase to append automatically for every CLI command that executes> on this device (optional> init: <an array of command that will be executed automatically after a sucessful login of CLI device> (optional)

Note: Becareful about the prompt field. Usually RENAT will wait until it could see the prompt in its output. A wrong prompt will halt the system until it is timed out.

Samples:

```
access-template:
 ssh-host:
    access: ssh
    auth: public-key
    profile: default
    prompt: \$
    append:
    init: unalias -a
 iuniper:
    access: telnet
    auth: plain-text
    profile: default
    prompt: "(#|>) "
    append: ' | no-more'
    init:
 cisco:
    access: ssh
    auth: plain-text
    profile: default
    prompt: "\@.*(#|>) "
    append:
    init:
snmp-template:
   juniper:
      mib: ./mib-Juniper.json
      community: public
      poller: renat
   cisco:
      mib: ./mib-Cisco.json
      community: public
```

3. auth.yaml: contains authentication information

The file contains authentication information that system uses when access to a device. Each authencation type has follwing format:

Where <profile> is the name of the authentication profile specificed in the access template of the device

Sample:

```
auth:
 plain-text:
    default:
      user: user
      pass: nttXXX
    flets:
      user: user
      pass: lpcoXXXX
    arbor:
      user: admin
      pass: nttXXX
 public-key: # for Public Key authentication
   default:
      user: robot
      key: /home/user/.ssh/robot_id_rsa
      user: jenkins
      key: /var/lib/jenkins/.ssh/id_rsa
```

Local Configuration

Local configuration (aka local.yaml) was used by a test case of its sub test cases. Test cases could includes several test cases (the sub level is not limited). The local configuration is defined by local.yaml in the config folder of each test case. If a test case does not has the local.yaml in its config folder, it will use the local.yaml file in its parent test case and so on. This will help users to share the test information for related test case without having the same local.yaml for each test case (**Note:** this feature is enabled from RENAT 0.1.4). The local.yaml that is really used for the test is called active local.yaml.

When user used the wizard item.sh to create a new test case, they have the ability to crete new local.yaml or not. local.yaml could be edited and inserted new information later to hold more informations for the test case.

When a test is run, it will display its current active local.yaml

The local configuration file of each test item is stored in the config folder of the item as `local.yaml

Usually the local.yaml has following parts:

- CLI node information: started by node keyword
- WEB node information: started by webapp keyword
- Tester device information: started by tester keyword
- Default information: automatically created and started by default keyword
- And other neccessary information for the test by yaml format

Sample:

```
# CLI node
node:
  vmx11:
    device: vmx11
    snmp_polling: yes
  vmx12:
    device: vmx11
    snmp_polling: yes
  apollo:
    device: vmx11
    snmp polling: yes
# web application information
webapp:
  arbor-sp-a:
    device: arbor-sp-a
    proxy:
      http: 10.128.8.210:8080
      ssl: 10.128.8.210:8080
      socks: 10.128.8.210:8080
# Tester information
tester:
  tester01:
    type: ixnet
    ip: 10.128.32.70
    config: vmx_20161129.ixncfg
# Other user information|
port-mapping:
  uplink01:
    device: vmx11
    port: ae-0/0/0
  downlink01:
    device: vmx12
    port: ge-0/0/2
# Default information
default:
  ignore_dead_node: yes
  terminal:
    width: 80
    height: 32
  result_folder: result
```

Variables

The module automatically create GLOBAL & LOCAL variable for other libraries. It also creates global list variables *GLOBAL,LOCAL* and *NODE* that could be accessed from Robot Framework` test cases.

The GLOBAL variable holds all information defined by the master files and LOCAL variable holds all variables defined by active local.yaml. And NODE is a list that hold all active nodes defined in the local.yaml.

Users could access to the information of a key in local.yaml by \${LOCAL["key]]}, information of a node by \${LOCAL["node][vmx11"]} or simply \$NODE[vmx]. When a keyword need a list of current node, @{NODE} could be used.

Notes: By default, RENAT will stop and raise an exception if connection to a node is failed. But if ignore_dead_node is defined as yes (default) is the current active local.yaml, RENAT will omit an warning but keep running the test and remove the node from its active node list.

Shortcuts

Change Mod · Cleanup Result · Convert Html To Pdf · Count Keyword · Count Keyword Line · Count Match Regexp · Create Sequence · Csv Concat · Csv Merge · Csv Select · Diff File · Err · Error Line Should Not Be Bigger Than · Error Should Not Be Bigger Than · Explicit Run · File Md5 · Fold Str · Follow Syslog And Trap · Get Config Path · Get File Without Error · Get Item Config Path · Get Item Name · Get Renat Path · Get Result Folder · Get Result Path · Get Test Device · Is Stable · Keyword Line Should Not Be Bigger Than · Keyword Should Not Be Bigger Than · Load Plugin · Log · Log To Console · Loop For Node Tag · Md 5 · Merge Files · Milb For Node · Node With Attr · Node With Tag · Node Without Tag · Pause · Ping Until Ok · Random Name · Random Number · Renat Version · Set Multi Item Variable · Set Result Folder · Slack · Str 2 Seq · Version

Keywords

| Keyword | Arguments | Documentation |
|---------|-----------|---------------|
| | | |

| Change Mod | name, mod, relative=False | Changes file mod, likes Unix chmod | | | |
|---|---|---|--|--|--|
| | | mod is a string specifying the privilege mode relative is False or True Examples: | | | |
| | | | | | |
| | | Common. <u>Change Mod</u> tmp 0775 | | | |
| Cleanup Result | ignore=^(log.html output.xml report.html)\$ | Cleans up the result folder | | | |
| | ignore (regiminifectionini) | Deletes all files in current active folder that does not match the ignore expression and are older than the time the test has started. | | | |
| | | Note: The keyword only removes files but not folders | | | |
| Convert Html To Pdf | html_file, pdf_file | Converts html file to pdf file | | | |
| Count Keyword | keyword, *pattern_list | Count the keyword in files. Keyword is not case-sensitive | | | |
| Count Keyword Line | keyword, *pattern list | Count the number of lines contains the keyword | | | |
| · | , , , = | Notes: Keyword is matched partially. For example, error or errorXXX will be matched by error keyword. | | | |
| Count Match Regexp | regexp, *pattern_list | Count the number of regex found in pattern_list | | | |
| | | Examples: | | | |
| | | \${err_num}= Count Match RegExp .*error.* result/*.csv result/*.txt | | | |
| Create Sequence | start and interval ention-float | | | | |
| oreate Sequence | start, end, interval, option=float | Creates a list with number from start to end with interval | | | |
| | | Example: | | | |
| | | @{list}= Create Sequence 10 15 0.5 | | | |
| | | will create a list of [11.0, 11.5, 12.0, 12.5, 13.0, 13.5, 14.0, 14.5] | | | |
| Csv Concat | src_pattern, dst_name, has_header=None | Concatinates CSV files vertically If the CSV files has header, set has_header to \$\{TRUE\} | | | |
| | | Examples: | | | |
| | | Commmon. <u>CSV</u> config/data0[3,4].csv result/result2.csv | | | |
| | | Merge Commmon. CSV config/data0[3,4].csv result/result2.csv has_header=\${TRUE Merge | | | |
| Csv Merge | src_pattern, dst_name, on_key=0, | Merges all CSV files horizontally by on_key key from src_pattern | | | |
| - | has_header=None | on_key is the order of key column that is used as key when merging the files. Default is zero. | | | |
| | | When has_header is not None (default value), it is the order of the row used to make the column name. Returns False if only one file was found, no merging happend | | | |
| | | Examples: | | | |
| | | Common. <u>CSV</u> config/data0[3,4].csv result/result2.csv | | | |
| | | Merge Common.CSV config/data0[3,4].csv result/result2.csv has header=\${TRUE} | | | |
| | | Common. <u>CSV</u> config/data0[3,4].csv result/result2.csv has_header=\${TRUE | | | |
| Csv Select | src_file, dst_file, str_row=:, str_col=:, has_header=None | Select part of the CSV file and write it to other file str_row and str_col are used specify necessary rows and columns. They are using the same format with slice for Python list. | | | |
| | | : and : means all rows and columns | | | |
| | | :2 and : means first 2 rows and all columns | | | |
| | | : and 1,2 means all rows and 2nd and 3rd columns 0:3 and 1 means 3 rows from the 1st one(0,1,2) and second column 0:5:2 and 1 means 3 rows(0,3,5) and second column | | | |
| | | Notes: | | | |
| | | Rows and columns are indexed from zero | | | |
| | | When ':' is used, the string has format: <start>:<stop> or <start>:<stop>:</stop></start></stop></start> | | | |
| | | <step> For convenience, ':' means all the data, ':x' means first 'x' data</step> | | | |
| | | Examples: | | | |
| | | CSV Select result/data05.csv result/result3.csv 0,1,2 0,1 | | | |
| | | CSV Select result/data05.csv result/result4.csv : 0,1 | | | |
| | | CSV Select result/data05.csv result/result5.csv :2 : | | | |
| | | CSV Select result/data05.csv result/result6.csv 0:3 : CSV Select result/data05.csv result/result7.csv 0:5:2 : | | | |
| Diff File | nath1 nath2 newline_True | | | | |
| Diff File path1, path2, newline=True Shows difference between files | | Returns the diff result (multi lines) path1, path2 are absolute paths. | | | |
| | | | | | |

| Err Error Line Should Not Be Bigger Than | msg num, *pattern_list | Prints error msg to console Checks whether the number of lines that contains error be less than a number | | | | |
|--|--|--|--|--|--|--|
| Error Should Not Be Bigger Than | num, *pattern_list | Checks whether the number of error be less than a number | | | | |
| Explicit Run | | skip the test case if global_variable RUN_ME is not defined | | | | |
| • | | Sample scenario: | | | | |
| | | 00. Cabling | | | | |
| | | Common. Explicit Run Log To Console cabling | | | | |
| | | run.sh will bypass 00. Cabling by default. In other to run this test case \${FORC} needs declared globally run.sh -X -v FORCE | | | | |
| File Md5 | path | Returns MD5 hash of a file | | | | |
| | | path is an absolute path | | | | |
| Fold Str | str | Folds a string by adding Non-Width-Space char (0x200b) at 6th char | | | | |
| Follow Syslog And Trap | pattern, log_file_name=syslog-trap.log, delay_str=1s | Pauses the execution and wait for the pattern is matched if the file <code>log_file_nam</code> located in the current result folder. | | | | |
| | | By default the <i>log_file_name</i> is ./result/syslog-trap.log which is created by <u>Folksyslog and Trap</u> keyword. | | | | |
| | | The keyword should be in tests between Follow Syslog adn Trap Start and I Syslog and Trap Stop keywords. | | | | |
| Get Config Path | | Returns absolute path of RENAT config folder path | | | | |
| Get File Without Error | file_path | Get content of the file and return null string if the file does not exist | | | | |
| Get Item Config Path | | Returns absolute path of current item config folder | | | | |
| Get Item Name | | Returns the name of the running item | | | | |
| Get Renat Path | | Returns the absolute path of RENAT folder | | | | |
| Get Result Folder | | Returns current result folder name. Default is result in current test case. | | | | |
| | | Note: the keyword only returns the name of the result folder not its absolue pat | | | | |
| Get Result Path | | Returns absolute path of the current result folder | | | | |
| Get Test Device | | Return a list of all test device that is used in this test Notes: Device number could less than node number | | | | |
| Is Stable | seq, threshold, percentile=90 | Checks if the value sequence is stable or not | | | | |
| Keyword Line Should Not Be Bigger Than | num, keyword, *pattern_list | Checks whether the number of line containing the keyword be less than a number | | | | |
| Keyword Should Not Be Bigger Than | num, keyword, *pattern_list | Checks whether the number of keyword be less than a number | | | | |
| Load Plugin | | Load plugin in renat/plugin folder | | | | |
| Log | msg, level=1 | Logs msg to the current log file (not console) | | | | |
| | | The msg will logged only if the level is bigger than the global level \${DEBUG} which could be defined at runtime. If \${DEBUG} is not defined, it will be considered as the default level as 1. | | | | |
| | | Examples: | | | | |
| | | Common. <u>Log</u> XXX # this always be logged | | | | |
| | | Common. <u>Log</u> AAA level=2 # this will not be logged with common run.sh | | | | |
| | | Common. <u>Log</u> BBB level=2 # /run.sh -v DEBUG:2 will log the message | | | | |
| | | Notes: For common use level 1: is default level 2: is debug mode | | | | |
| Log To Console | msg, level=1 | ■ level 3: is very informative mode Logs a message to console | | | | |
| | - | See Common. Print for more details about debug level | | | | |
| Loop For Node Tag | var, tags, *keywords | Repeatly executes RF keyword for nodes that has tag tags | | | | |
| | multi tags are separated by : keywords has same meaning with keywords used Run Keywords of RobotFramework (keyword and its arguments are separated by | | | | | |

| | | Example: | | | | |
|------------------|--|--|------------|------------------------|---------------------------|--|
| | | Loop For Node Tag | \\${node} | tag1 | | |
| | | | Switch | \\${node} | AND | |
| | | | Cmd | show system user | AND | |
| | | | Cmd | show system uptime | | |
| | | Note: \$ in variable na | | t be escaped | | |
| Md 5 | str | Returns MD5 hash of | a string | | | |
| Merge Files | path_name, file_name | Merges all the text files defined by path_name to file_n: Example: | | file_name | | |
| | | Merge Files ./result/ | *.csv ./re | sult/test.csv | | |
| Mib For Node | node | the node in local.yam | | his node mib file is | define by mib keyword | |
| | | node: vmx11: device: vmx11 snmp_polling: yes mib: mib11.txt | | | | |
| | | Default value is defined by mib keyword from global config/snmp-template.ya the type of the node | | | | |
| | | Example: | | | | |
| | | \${mib}= Common. <u>M</u> | IIB For No | vmx11 | | |
| Node With Attr | attr_name, value | Returns a list of node | s which l | nave attribute attr_na | ame with value value | |
| Node With Tag | *tag_list | Returns list of node or webapp from local.yaml that has ALL tags defined by tag_list | | | | |
| | | vmx11: device: vmx11 snmp_polling: yes tag: - tag1 - tag2 | | | | |
| | | Examples: | | | | |
| | | \${test3}= Common. Node With Tag tag1 tag3 | | | | |
| Node Without Tag | *tag_list | Returns list of node from local.yaml that does not has ANY tags defined by tag_list | | | | |
| | | Tag was defined like this in local.yaml | | | | |
| | | vmx11: device: vmx11 snmp_polling: ye tag: - tag1 - tag2 | S | | | |
| | | Examples: | | | | |
| | | \${test3}= Common. | Node Wit | hout Tag tag1 tag3 | | |
| Pause | msg=, time_out=3h, | | | | xecution and wait for use | |
| . 4435 | msg=, time_out=3n, error_on_timeout=True, default_input= | Displays the message msg and pauses the test execution and wait for user in case of error_on_timeout is True(default), the keyword will raise an error w timeout occurs. Otherwise, it will continue the test. | | | | |
| | | Notes: If the variable \${RENAT_BATCH} was defined, the keyword will print of message and keeps running without pausing. | | | | |
| | | Examples: | | | | |
| | | Common. Pause Waiting 10s error_on_timeout=\${TRUE} default input Common. Pause Waiting 10s | | | | |
| Ping Until Ok | node, wait_str=5s, extra=-c 3 | Ping a node until it g | ets respo | nse. Then wait for n | nore wait_str Default ext | |
| Random Name | base, a=0, b=99 | Returns a random nar | ne by a | base and a random r | number between [a,b] | |
| | | Example: | | | | |
| | | \${FOLDER}= Rand | om Name | capture_%05d 0 9 | 9 | |
| | | - | | | | |

| Random Number Renat Version | a=0, b=99 | Returns a random number between [a,b] Returns RENAT version string | | |
|--------------------------------|---|--|--|--|
| Set Multi Item | *vars | Set multiple varibles to be suite variable at the same time | | |
| Variable | | Suite variables (or item variable) could be access anywhere in all the item scenario. | | |
| Set Result Folder | folder | Sets the result folder to folder and return the old result folder. The result folder contains all output files from the test likes tester ouput, config file | | |
| | | folder is a folder name that under current test case folder | | |
| | | The system will create a new folder if it does not exist and set its mode to 0775 | | |
| | | Note: Result folder should be set at the begining of the test. Changing result folder only has effect on up comming connection | | |
| Slack | msg, channel=#automation_dev, user=renat, host=127.0.0.1 | Post a message to Slack | | |
| Str 2 Seq | str_index, size | Returns a sequence from string format | | |
| | | Samples: | | |
| | | <u>Str2Seq</u> :: 5 # (0,1,2,3,4) | | |
| | | <u>Str2Seq</u> :2 5 # (0,1) | | |
| | | <u>Str2Seq</u> 1:3 5 # (1,2) | | |
| | | <u>Str2Seq</u> 0:5:2 5 # (0,2,4) | | |
| Version | Returns the current version of RENAT | | | |

Altogether 49 keywords.
Generated by <u>Libdoc</u> on 2018-06-01 21:39:28.

