



z/OS Introduction and Workshop

Operating System Overview




Unit Objectives

After completing this unit, you should be able to:

- Describe an address space
- Describe virtual storage
- Describe paging
- List 3 types of address spaces
- List 3 types of memory storage
- Describe system integrity using key-controlled protection



z/OS Environment





System Tasks – No need to know it all

How the operating system works is not required to develop, maintain and port business applications

Pages, Frames and Slots

PSA DAT

CVT RSM

ASTE ASM VSM

ASCB Virtual Storage

CSA WLM

Master Scheduler SVC

PCAUTH Protect Keys

RASP



What is z/OS?

System z 'flagship' operating system

64-bit operating system

Ideally suited for processing large workloads for many concurrent users

Designed for:

- 1) Serving 1000s of users concurrently
- 2) I/O intensive computing
- 3) Processing very large workloads
- 4) Running mission critical applications securely



Operating System

Comprised of modules, system programs (macros), system components

Information about the system, resources, and tasks are in *control blocks*

Management of physical storage:

- 1) Real storage
- 2) Auxiliary storage
- 3) Virtual storage



System Tasks are known as <u>Address Spaces</u>

z/OS and its related subsystems require **address spaces** of their own to provide a functioning operating system.

System **address spaces** are started after initialization of the master scheduler. These address spaces perform functions for all the other types of **address spaces** that start in z/OS.


Middleware **address spaces** exist for major system functions and middleware such as DB2, CICS, and WebSphere Application Server.

TSO/E address spaces are created for every user who logs on to z/OS

Address spaces are created for every batch job that runs on z/OS.



The address space concept requires addressable memory




"Bar" (31 bit) max address 2 GB of address locations


"Line" (24 bit) max address 16 MB of address locations



64-bit address space map









Middleware for z/OS are a collection of address spaces

- Middleware is typically something between the operating system and an end user or end-user applications.
- Middleware supplies major functions not provided by the operating system.
- Typical z/OS middleware includes:
 - Database systems
 - Web servers
 - Message queuing and routing functions
 - Transaction managers
 - Java virtual machines
 - XML processing functions



Defining characteristics of z/OS

- Uses address spaces to ensure isolation of private areas
- Ensures *data integrity*, regardless of how large the user population might be.
- Can process a large number of concurrent batch jobs, with automatic workload balancing
- Allows security to be incorporated into applications, resources, and user profiles.
- Allows multiple communications subsystems at the same time
- Provides extensive recovery, making unplanned system restarts very rare.
- Can manage mixed workloads
- Can manage large I/O configurations of 1000s of disk drives, automated tape libraries, large printers, networks of terminals, etc.
- Can be controlled from one or more operator terminals, or from application programming interfaces (APIs) that allow automation of routine operator functions.



Address Spaces – SDSF display active

70 o								
3 Class - svscmvx								
File Edit View Communication Actions Window Help								
<u>D</u> isplay <u>F</u> ilter	<u>V</u> iew <u>P</u> rint	<u>O</u> ptions	<u>H</u> elp					
		O CPU 6	1	L	INE 1-26			
COMMAND INPUT ===:					St	CROLL ===	> CSR	
PREFIX=* DEST=(AI		SYSNAME=		6 6	DD D 1	ъ .	6.16	
	pName ProcStep	STC00367	Owner .		DP Real		SIO	
MASTER PCAUTH PCAI	UTU	2100367	+MH21EK+		FF 2954 FF 141	0.00 0.00	0.00	
RASP RASI					FF 243	0.00	0.00	
TRACE TRAC					FF 364	0.00	0.00	
	PSRV DUMPSRV				FF 369	0.00	0.00	
XCFAS XCF					FF 2140	0.00	0.00	
GRS GRS					FF 2020	0.00	0.00	
SMSPDSE SMSI	PDSE			NS	FF 4776	0.00	0.00	
CONSOLE CONS	SOLE			NS	FF 2199	0.00	0.00	
WLM WLM	IEFPROC				FF 1582	0.00	0.00	
	MAIN IEFPROC				FF 1395	0.00	0.00	
	AS000 IEFPROC				C1 1285	0.00	0.00	
DEVMAN DEVI					FF 426	0.00	0.00	
OMVS OMV:					FF 14T	0.00	0.00	
IEFSCHAS IEFS					FF 90	0.00	0.00	
JESXCF JES					FF 648 FF 2795	0.00 0.00	0.00	
ALLOCAS ALLO SMS SMS	OCAS IEFPROC				FE 375	0.00	0.00	
10SAS 10S					FF 422	0.00	0.00	
	LOGR IEFPROC				FF 5483	0.00	0.00	
AXR AXR					C1 477	0.00	0.00	
CEA CEA					FF 3041	0.00	0.00	
SMF SMF					FF 477	0.00	0.00	
LLA LLA					FE 3709	0.00	0.00	
JES2 JES:	2 IEFPROC			NS	FE 8661	0.00	0.00	
VLF VLF	VLF			NS	FE 9135	0.00	0.00	
M <u>A</u> a								
ரு Connected to remote server/hos	st 204.90.115.184 using lu/poo	ol TCP00022 and po	rt 623				1	



Address Spaces – SDSF display active ...forward (F8)

3 Class - svscmvx								
File Edit View Communicat	tion Actions W	'indow Help						
<u>D</u> isplay <u>F</u> il	ter <u>V</u> iew	. <u>P</u> rint	<u>O</u> ptions	<u>H</u> elp				
SDSF DA SOW1 COMMAND INPUT :	S0W1	PAG 6	O CPU 6	,	'	LINE 27-9	02 (94) CROLL ==:	-> cep
		WNER=* S	SYSNAME=			31	KOLL	-/ CSK
		ProcStep		Owner	C. Pos	DP Real	Paging	SIO
	RSED	RSED	STC00428		IN	C1 8252	0.00	0.00
	SDSF	SDSF	STC00366		NS	F4 890	0.00	0.00
EPWFFST F	FFST	EPWFFST			NS	C1 354	0.00	0.00
EXITMVS E	EXITMVS	ST01	STC00380	STCOPER	LO	FF 227	0.00	0.00
TN3270	TN3270	TN3270	STC00379	TCPIP	NS	FE 2252	0.00	0.00
	VTAM	VTAM	STC00365		NS	FE 2946	0.00	0.00
	TCAS	TCAS	STC00381	STRTASK	LO	FF 279	0.00	0.00
	RRS	RRS			NS	C1 2566	0.00	0.00
		EZBREINI			NS	FE 329	0.00	0.00
	DAM	IEFPROC	0.7000077	0.70.7001/	NS	FE 673	0.00	0.00
II	RACF	RACF	STC00377	STRIHSK	NS	FE 562	0.00	0.00
	CATALOG	IEFPROC			NS	FF 2036	0.00	0.00
	ZFS JES2AUX	ZFZGO			NS NS	FE 24T FE 195	0.00 0.00	0.00 0.00
	JESZHON JESZMON	IEFPROC			NS	FF 555	0.00	0.00
		BPXOINIT			LO	FF 250	0.00	0.00
	TNF	IEFPROC			NS	FE 187	0.00	0.00
1	VMCF	IEFPROC			NS	FE 206	0.00	0.00
	STEP1	12	STC00383	TCPIP	LO	FF 336	0.00	0.00
FTPSERVE S			STC00384		LO	FF 391	0.00	0.00
DB9GMSTR I	DB9GMSTR	IEFPROC	STC00391	STCOPER	NS	FE 2241	0.00	0.00
DB9GIRLM I	DB9GIRLM		STC00392	STCOPER	NS	FE 2463	0.00	0.00
DB9GDBM1 (IEFPROC	STC00393		NS	FE 34T	0.00	0.00
DB9GDIST (STC00394		NS	FE 3630	0.00	0.00
	TCPIP	TCPIP	STC00397		NS	FE 6219	0.00	0.00
I BMUSER I	DBPROC9G	TCP00022	TSU00557	IBMUSER	IN	F4 808	0.00	0.00
M <u>A</u> a								
Connected to remote serve	er/host 204.90.11	.5.184 using lu/pod	ol TCP00022 and po	ort 623				11.



Address Spaces – SDSF display active ...shift right (F11)

⊉ ☐ Class - svscmvx								
File Edit View Communication Actions Window Help								
		iew <u>P</u> rint	Options	Help				
			-					
SDSF DA SOW1	SO₩		O CPU O		LINE 1-26 (54)			
COMMAND INPUT					SCROLL =	==> CSR		
PREFIX=* DES NP JOBNAME	T=(ALL)	OWNER=* ASID ASIDX	SYSNAME= EXCP-Cnt	CDU TALL C	CD C4-4 CN	en een		
MASTER		1 0001	18396	258.33	SR Status SysName S0W1	SPag SCP		
PCAUTH	0.00	2 0002	26	0.01	50W1	Θ		
RASP	0.00	3 0003	20	3.10	50W1	ĕ		
TRACE	0.00	4 0004	99	0.01	50W1	ŏ		
DUMPSRV	0.00	5 0005	253	0.04	50W1	ě		
XCFAS	0.00	6 0006	758755	195.21	S0W1	ŏ		
GRS	0.00	7 0007	34	555.28	S0W1	ŏ		
SMSPDSE	0.00	8 0008	3	25.02	SOW1	ō		
CONSOLE	0.00	9 0009	466	18.43	SOW1	Θ		
WLM	0.00	10 000A	117	1593.09	S0W1	Θ		
ANTMAIN	0.00	11 000B	1669	5.10	S0W1	Θ		
ANTAS000	0.00	12 000C	1296	0.09	S0W1	Θ		
DEVMAN	0.00	13 000D	550	0.74	S0W1	Θ		
OMVS	0.00	14 000E	2369	23.00	S0W1	Θ		
IEFSCHAS		16 0010	63	0.01	S0W1	Θ		
JESXCF	0.00	17 0011	1496	16.45	S0W1	Θ		
ALLOCAS	0.00	18 0012	72	0.02	SOW1	Θ		
SMS	0.00	19 0013	372646	40.96	S0W1	Θ		
IOSAS	0.00	20 0014	613	100.60	S0W1	Θ		
IXGLOGR	0.00	21 0015	177	13.96	S0W1	Θ		
AXR	0.00	22 0016	427	0.05	S0W1	9		
CEA	0.00	23 0017	492	0.09	S0W1	9		
SMF	0.00	25 0019	562	8.41	S0W1	Θ		
LLA JES2	0.00 0.00	26 001A 29 001D	16755 563924	0.55 134.55	S0W1 S0W1	Θ		
VLF	0.00	30 001E	963924 414	3.93	50W1 S0W1	Θ Θ		
MA a	0.00	JO OUIL	714	3.53	30w1			
	rver/host 204	90 115 184 usipa lu <i>l</i> a	ool TCP00022 and no	t 623				
Connected to remote server/host 204,90.115.184 using lu/pool TCP00022 and port 623								



Address Spaces – MVS command (D A,ALL) ..display of all address spaces – look up IEE115I

COMMA	SYSLOG AND INPUT: D A,ALL		SOW1 SOW1	02/14	1/201	L7 OW		5,247		NS 52- 131 ===> CSR
	IEE115I 1	4.38.00 2	017.045 A	CTTVTT	FY 94	41				
090	JOBS		S USERS	SYSA		INITS	ACTI	VE /MAX	X VTAM	OAS
			00001	0003		00018		01/00		00022
0090		*MASTER*		NSW		A=0001	PER=		SMC=000	****
0090						PGN=N/A			AFF=NONE	
0090						CT=004.9				
0090									ID=+MASTI	R+
090						WKL=SYST		SCL=S'		P=1
0090						RGP=N/A			NO QSC=I	
090	PCAUTH	PCAUTH		NSW	*	A=0002	PER=	NO S	SMC=000	
0090						PGN=N/A	DMN=		AFF=NONE	
0090						CT=000.0			.47.10	
0090						WKL=SYST		SCL=S'		P=1
0090						RGP=N/A			NO QSC=I	10
0090	RASP	RASP		NSW	*	A=0003	PER=	NO :	SMC=000	
0090						PGN=N/A	DMN=	NZA I	AFF=NONE	
0090						CT=000.0	000S	ET=24	.47.10	
0090						WKL=SYST	EM	SCL=S'	YSTEM I	P=1
0090						RGP=N/A		SRVR=I	NO QSC=I	10
0090	TRACE	TRACE		NSW	*	A=0004	PER=	NO :	SMC=000	
0090						PGN=N/A	DMN=		AFF=NONE	
0090						CT=000.0	000S	ET=24	.47.10	
0090						WKL=SYST	TEM .	SCL=S'	YSTEM I	P=1
0090						RGP=N/A		SRVR=I	NO QSC=I	10
0090	DUMPSRV	DUMPSRV	DUMPSRV	NSW	*	A=0005	PER=	:NO :	SMC=000	
0090						PGN=N/A	DMN=	NZA I	AFF=NONE	
0090						CT=000.0)15S	ET=24	.47.10	
0090						WKL=SYST	EM	SCL=S'	YSTEM I	P=1
0090						RGP=N/A			NO QSC=I	10
0090	XCFAS	XCFAS	IEFPR0C	NSW	*	A=0006	PER=	NO :	SMC=000	
0090						PGN=N/A	DMN=	NZA I	AFF=NONE	
0090						CT = 008.9			.47.10	
090						WKL=SYST		SCL=S'		P=1
090						RGP=N/A			NO QSC=I	10
090	GRS	GRS		NSW	*	A=0007	PER=		SMC=000	
090						PGN=N/A	DMN=		AFF=NONE	
090						CT=001.1			.47.10	
0090						WKL=SYST	TEM .	SCL=S'	YSTEM I	P=1



Address Spaces – SDSF command (D A) with PREFIX * and OWNER * ..display of all address spaces

SDSF DA SOW1	SOW1	. 1	PAG	1	CPU	0			LINE 1	-38 (64)	
COMMAND INPUT	===>									SCROLL =	
NP JOBNAME	CPU% A	SID	ASIDX	E	XCP-C	nt	CPU-Tim	e SR	Status	SysName	SPag SCF
MASTER	0.00		0001		66		8.4	2		SOW1	$\bar{1}$
PCAUTH	0.00		0002		;	26	0.0			SOW1	1
RASP	0.00		0003			2	0.2			SOW1	1
TRACE	0.00		0004			57	0.0			SOW1	1
DUMPSRV	0.00		0005			40	0.0			SOW1	1
XCFAS	0.00		0006		1127		10.2			SOW1	1
GRS	0.00	-	0007		:	33	21.5			SOW1	1
SMSPDSE	0.00	_	8000			3	2.0			SOW1	1
CONSOLE	0.00		0009			44	1.5			SOW1	1
WLM	0.00		000A			65	78.5			SOW1	1
ANTMAIN	0.00		000B			29	0.4			SOW1	1
ANTASO00	0.00		000C			31	0.0			SOW1	1
DEVMAN	0.00		000D			42	0.0			SOW1	1
GTZ	0.00		000E			35	0.0			SOW1	1
OMVS	0.00		000F		17		3.5			SOW1	1
IEFSCHAS	0.00		0011			9	0.0			SOW1	1
JESXCF	0.00		0012		12		1.4			SOW1	1
ALLOCAS	0.00		0013			81	0.0			SOW1	1
SMS	0.00		0014		665		3.2			SOW1	1
IOSAS	0.00		0015		10		1.2			SOW1	1
IXGLOGR	0.00		0016			21	0.9			SOW1	1
AXR	0.00		0017			02	0.0			SOW1	1
CEA	0.00		0018			91	0.0			SOW1	1
RESOLVER	0.00		0019			44	0.0			SOW1	1
SMF	0.00		001A			43	1.7			SOW1	1
LLA	0.00		001B		261		0.2			SOW1	1
JES2AUX	0.00		001D			63	0.0			SOW1	1
JES2	0.00		001E		1041		17.9			SOW1	1
VLF	0.00		001F			85	0.2			SOW1	1
TCPIP	0.00		0020		89		25.1			SOW1	1
SDSF	0.00		0021		_	48	1.2	_		SOW1	1
EPWFFST	0.00		0022		75		0.5			SOW1	1
RSED2	0.00		0023		424		5.0			SOW1	1
FTPSERVE	0.00		0024			02		1 DW		SOW1	1
HZSPROC	0.00		0025		71		2.5			SOW1	1
RSED3	0.00		0026			39		O DW		SOW1	1
VTAM	0.00		0027		27		1.9			SOW1	1
SSHD1	0.00	40	0028		47	27	7.9	12		SOW1	1



Address Space – A technical definition

- An address space is a consecutive sequence of integer numbers (virtual addresses), together with the specific transformation parameters which allow each number to be associated with a byte location in storage. The sequence starts at zero and proceeds left to right.
- When a virtual address is used by a CPU to access main storage, it is first converted, by means of dynamic address translation (DAT), to a real address



What is in an address space?

- z/OS provides each user with a unique address space and maintains the distinction between the **programs** and **data** belonging to each address space.
- While an address space includes **system code** as well as **user code** and **data**, it maps all of the <u>available</u> addresses. Thus, not all of the mapped addresses are available for user code and data.



System Tasks - Virtual storage concepts

- Virtual storage is an "illusion" created through z/OS management of real storage and auxiliary storage through tables.
- The running portions of a program are kept in real storage; the rest is kept in auxiliary storage
- A contiguous range of addressable virtual storage available to a user or program or the operating system is an *address space*
- Each user or separately running program is represented by an address space (each user gets a limited amount of private storage)



System Tasks - How virtual storage works

- Virtual storage is divided into 4-kilobyte pages
- Transfer of pages between auxiliary storage and real storage is called paging
- When a requested address is not in real storage, an interruption is signaled and the system brings the required page into real storage
- z/OS uses tables to keep track of pages
 - Dynamic address translation (DAT)
- **Frames**, *pages*, *slots* are all repositories for executable code and data.





System Tasks – Pages, Frames and Slots

- The pieces of a program executing in virtual storage must be moved between real and auxiliary storage:
 - A block of virtual storage is a page
 - A block of real storage is a *frame*
 - A block of auxiliary storage is a slot
- A *page*, *frame* and *slot* are all the same size: 4096 bytes (4 kilobytes 4K)
- To the programmer, the entire program appears to occupy contiguous space in real storage at all times.



Virtual Addresses Pages







Page Stealing

- > z/OS tries to keep an adequate supply of available real storage frames on hand.
- When this supply becomes low, z/OS uses page stealing to replenish it.
- Pages that have not been accessed for a relatively long time are good candidates for page stealing.
- > z/OS also uses various storage managers to keep track of all pages, frames, and slots in the system.



Swapping

- Swapping is one of several methods that z/OS uses to balance the system workload and ensure that an adequate supply of available real storage frames is maintained.
- Swapping has the effect of moving an entire address space into, or out of, real storage:
 - A swapped-in address space is active, having pages in real storage frames and pages in auxiliary storage slots.
 - A swapped-out address space is inactive; the address space resides on auxiliary storage and cannot execute until it is swapped in.



Structures for all 4K pages owned by the hardware, operating system address spaces, middleware address spaces and application address spaces such as TSO and Batch JOB



4K pages of system information

4K page of system information can reside in a 'frame' or 'slot'

Some 4K pages of system information are marked as a permanent resident in real storage – 'frame' only

27

Private	High User Region	16 EB
Shared {	Default Shared Memory Addressing	512TB
Area L	Low User Region	2TB
Private (Reserved	4G
}	Extended LSQA/SWA/229/230	2G
Extended Private	Extended User Region	
l y	E-11-1004	
	Extended CSA Extended PLPA/FLPA/MLPA	
Extended Common		
	Extended SQA	
Ų	Extended Nucleus	16 Mb
	Nucleus	
Common	SQA	
Common	PLPA/FLPA/MLPA	
U	CSA	
ĺ	LSQA/SWA/229/230	
Private	User Region	
		24K
Į,	System Region	8K
Common {	PSA	0



Key-Controlled protection ensures system wide integrity

A storage key is associated with each 4K-byte block of storage that is available in the configuration.

An execution key is associated with each running program

Program Status Word (PSW) Keys

- 0 system or authorized programs, can access all storage
- 1 MVS Scheduler, JES, APPC, TSO/E
- 2 WebSphere
- 5 Data Management O/C/EOV
- ▶ 6 VTAM, TCPIP
- > 7 IMS, DB2
- 8 Problem Program (Address Space Private Area)



MVS Storage Managers


- Real Storage is managed by RSM
- Virtual Storage is managed by VSM
- Auxiliary Storage is managed by ASM
- Dynamic Address Translation (DAT) converts a virtual-to-physical address




PSA>CVT>ASVT>ASCB

Prefixed Save Area

Address Space Control Block



IBM Manuals






PSA is at real address location 0 << represents a physical CPU

CVT is located at the address stored in x'10' offset in PSA

ASVT is located at the address stored in x'22C' offset in the CVT

ASCB list is located at the address stored in x'210' offset in the ASVT







z/OS Control Block Prefixed Save Area (PSA)

PSA Heading Information

Common Name: Prefixed Save Area

Macro ID: IHAPSA
DSECT Name: PSA

Owning Component: Supervisor Control (SC1C5)

Eye-Catcher ID: None

Storage Attributes: Subpool: 239

Key: 0

Residency: Below 16 MB line

Size: 4096 bytes Created by: IEAVFX00

> IEAVNIPO IEEVCPRA

Pointed to by: The PSA maps the storage that starts at location 0 for the

related processor.

Serialization: Disablement.

None needed for FLCFACL.

Function: Maps fixed hardware and software storage locations for the

related processor.



z/OS Control Block – Prefixed Save Area (PSA)

PSA Map

Dec	Hex	Type/Value	Len	Name (Dim)	Description			
0	(0)	STRUCTURE	0	PSA				
0	(0)	X'0'	0	FLC	***			
0	(0)	CHARACTER	8	FLCIPPSW (0)	- IPL PSW			
0	(0)	BITSTRING	4	FLCRNPSW	-RESTART NEW PSW (AFTER IPL) MDC001			
4	(4)	ADDRESS	4		"V(IEAVRSTR)" - SECOND HALF OF RESTART NEW PSW MDC128			
4	(4)	X'0'	0	IPLPSW	"FLCIPPSW" ALIAS			
8	(8)	CHARACTER	8	FLCICCW1 (0)	- IPL CCW1			
8	(8)	BITSTRING	8	FLCROPSW	- RESTART OLD PSW (AFTER IPL)			
16	(10)	CHARACTER	8	FLCICCW2 (0)	- IPL CCW2			
16	(10)	ADDRESS	4	FLCCVT	"V(IEACVT)" - ADDRESS OF CVT (AFTER IPL). THIS OFFSET FIXED BY ARCHITECTURE. (MDC450)			
20	(14)	BITSTRING	4		- RESERVED (AFTER IPL) (MDC431)			
24	(18)	BITSTRING	8	FLCEOPSW	- EXTERNAL OLD PSW			
24	(18)	X'18'	0	EXOPSW	"FLCEOPSW" ALIAS			
32	(20)	BITSTRING	8	FLCSOPSW	 SVC OLD PSW. THIS OFFSET FIXED BY ARCHITECTURE. (MDC451) 			
32	(20)	X'20'	0	SVCOPSW	"FLCSOPSW" ALIAS			
40	(28)	BITSTRING	8	FLCPOPSW	- PROGRAM CHECK OLD PSW			
40	(28)	X'28'	0	PIOPSW	"FLCPOPSW" ALIAS			
48	(30)	BITSTRING	8	FLCMOPSW	- MACHINE CHECK OLD PSW			
48	(30)	X'30'	0	MCOPSW	"FLCMOPSW" ALIAS			
56	(38)	BITSTRING	8	FLCIOPSW	- INPUT/OUTPUT OLD PSW			
56	(38)	X'38'	0	IOOPSW	"FLCIOPSW" ALIAS			
64	(40)	BITSTRING	8		- RESERVED			
72	(48)	DBL WORD	8	FLCCVT64 (0)	- 8-byte CVT address			
72	(48)	BITSTRING	4		- 1st 4 bytes are 0			
76	(4C)	ADDRESS	4	FLCCVT2	"V(IEACVT)" - ADDRESS OF CVT - USED BY DUMP ROUTINES ICB319			
80	(50)	BITSTRING	4		- RESERVED			
84	(54)	BITSTRING	4		- RESERVED - FLCTRACE DELETED DUE TO SYSTEM TRACE REDESIGN.			
88	(58)	BITSTRING	4	FLCENPSW	-EXTERNAL NEW PSW			
92	(5C)	ADDRESS	4		"V(IEAQEX00)" - SECOND HALF OF EXTERNAL NEW PSW			
92	(5C)	X'58'	0	EXNPSW	"FLCENPSW" ALIAS			



z/OS Control Block Communications Vector Table (CVT)

CVT Heading Information

Common Name: Communications Vector Table

Macro ID: CVT

DSECT Name: CVT(when DSECT=YES is coded and PREFIX=YES is not coded)

CVTFIX(when DSECT=YES and PREFIX=YES is coded)

CVTMAP(or name user coded in label field of CVT invocation)

CVTVSTGX(DSECT name of virtual storage extension)

CVTXTNT1(DSECT name of OS-OS/VS common extension)

CVTXTNT2(DSECT name of OS/VS1-OS/VS2 common extension)

Owning Component: Common Macros (SC101)

Eye-Catcher ID: CVT

Offset: 96

Length: 4

Storage Attributes: Subpool: Nucleus

Key: 0

Residency: Below 16M line

Size: Prefix: 256 bytes

CVT: 1280 bytes

Virtual storage address extension: 80 bytes OS - OS/VS common extension: 12 bytes OS/VS1 - OS/VS2 common extension: 132 bytes

Created by: IEAVCVT

Pointed to by: FLCCVT field of the PSA data area (location X'10')

FLCCVT2 field of the PSA data area

CVTSMEXT points to the Virtual address storage extension OS/VS - OS/VS extention is pointed to by CVTEXT1

OS/VS1 - OS/VS2 extention is pointed to by CVTEXT2

Serialization: Based on the individual fields being referenced.

Function: The CVT provides the means by which non-nucleus-resident

routines may refer to information in the nucleus of the control program. It contains addresses of other control blocks and tables used by the control program routines.



z/OS Control Block Address Space Vector Table (ASVT)

ASVT Heading Information

Common Name: Address Space Vector Table

Macro ID: IHAASVT DSECT Name: ASVT

Owning Component: Supervisor Control (SC1C5)

Eye-Catcher ID: ASVTASVT

Offset: 512

Length: 4

Storage Attributes: Subpool: 245

Key: 0 1

Residency: Below 16M

Size: Offset of ASVTEND minus offset of ASVTBEGN plus

four times the value of ASVTMAXU.

Created by: IEAVNP09

Pointed to by: CVTASVT field of the CVT data area Serialization: General CMS lock and dispatcher lock

Function: Mapping for the Address Space Vector Table



z/OS Control Block Address Space Vector Table (ASVT)

ASVT Map

37

Offsets					
Dec	Hex	Type/Value	Len	Name (Dim)	Description
0	(0)	STRUCTURE	0	ASVT	
0	(O)	CHARACTER	472	ASVTPRFX	RESERVED FOR FUTURE EXPANSION
472	(1D8)	DBL WORD	8	ASVTBEGN (0)	- BEGINNING OF ASVT
472	(1D8)	ADDRESS	4	ASVTREUA	ADDRESS OF ASVTREUS BITS
476	(1DC)	ADDRESS	4	ASVTRAVL	ADDRESS OF FIRST AVAILABLE REUSABLE ASID SLOT
480	(1E0)	SIGNED	4	ASVTAAV	NUMBER OF FREE SLOTS ON THE ASVT AVAILABLE QUEUE.
484	(1E4)	SIGNED	4	ASVTAST	NUMBER OF FREE SLOTS ON THE START/SASI QUEUE.
488	(1E8)	SIGNED	4	ASVTANR	NUMBER OF FREE SLOTS ON THE NON-REUSABLE REPLACEMENT QUEUE.
492	(1EC)	SIGNED	4	ASVTSTRT	ORIGINAL SIZE OF START/SASI QUEUE.
496	(1F0)	SIGNED	4	ASVTNONR	ORIGINAL SIZE OF NON-REUSABLE REPLACEMENT QUEUE.
500	(1F4)	SIGNED	4	ASVTMAXI	 ORIGINAL MAX USERS COUNT AS INPUT TO IEAVNP09. OWNERSHIP - SUPERVISOR CONTROL SERIALIZATION - NIP RIM PROCESS
504	(1F8)	BITSTRING	8		- RESERVED, WAS ASVTRSHD/DSHD
512	(200)	CHARACTER	4	ASVTASVT	- ACRONYM IN EBCDIC -ASVT-
516	(204)	SIGNED	4	ASVTMAXU	- MAXIMUM NUMBER OF ADDRESS SPACES
520	(208)	SIGNED	4	ASVTMDSC	MAXUSER DEFICIT SLOT COUNT. ASVTMDSC = ASVTMAXI - ASVTAAV - NUMBER OF ACTIVE A.S. INCREMENTED WHEN WE TRY TO TAKE A REPLACEMENT SLOT BUT THERE ARENT ANY. DECREMENTED WHEN NON-ZERO AND A NONREUSEABLE ASID BECOMES REUSEABLE AND WE ADD A SLOT TO THE MAXUSER POOL WHEN AN ADDRESS SPACE BECOMES REUSEABLE.
524	(20C)	ADDRESS	4	ASVTFRST	- ADDRESS OF FIRST AVAILABLE ASVT ENTRY (MDC300)
		1		ASVTAVAI	"X'80" - BIT ONE IF ASID IS AVAILABLE AND ZERO IF ASÍD IS ASSIGNED MDC002
528	(210)	ADDRESS	4	ASVTENTY	 ENTRY FOR EACH POSSIBLE ASID. IF ADDRESS SPACE ASSIGNED, ENTRY CONTAINS ADDRESS OF ASCB. IF NOT ASSIGNED, ENTRY CONTAINS EITHER ADDRESS OF NEXT AVAILABLE ASID OR ZEROS WITH HIGH-ORDER BIT ON IF LAST ENTRY. (MDC301) IF THE ADDRESS SPACE IS MARKED NON-REUSABLE, THE ENTRY CONTAINS THE ADDRESS OF MASTER'S ASVT ENTRY WITH THE HIGH BIT ON.



z/OS Control Block PSA > CVT > ASVT > ASCB

©₫ Class - svscmvx	
File Edit View Communication Actions Window Help	
test 'sys1.linklib(iefbr14)' TEST l 10.	
00000010. 00FDC7C0 TEST L 10.%	0000000
00FDC7C0. 00000218 TEST l 10.%+22c	0000000
00FDC9EC. 00FB15F0 TEST L 10.%+22c%	0000000
00FB15F0. E2F0E6F1 TEST L 10.%+22c% c L(16)	0000000
00FB15F0. S0W1 TEST L 10.%+22c%+210	0000000
00FB1800. 00FDA500 TEST L 10.%+22c%+210%	0000000
00FDA500. C1E2C3C2 TEST	0000000
l 10.%+22c%+210% c l(16) 00FDA500. ASCB TEST	0000000
l 10.%+22c%+218% c l(16) 00F56300.	0000000
l 10.%+22c%+204 l(8) 00FB17F4. 0000018B 00000000 *** _	0000000
MA a	
Connected to remote server/host 204.90.115.185 using lu/pool TCP	1.



z/OS Control Block Address Space Control Block (ASCB)

ASCB Heading Information

Common Name: ADDRESS SPACE CONTROL BLOCK

Macro ID: IHAASCB DSECT Name: ASCB

Owning Component: SUPERVISOR CONTROL (SC1C5)

Eye-Catcher ID: ASCB

Offset: 0 Length: 4

Storage Attributes: Subpool: 245

Key: 0 Residency: Below 16M

Size: 384 bytes
Created by: IEAMSWCB, IEAVEMRQ

Pointed to by: CVTASCBH and CVTASCBL fields of the CVT data area

PSAANEW field of the PSA data area

PSAAOLD field of the PSA data area (Master's ASCB)

ASVTENTY field of the ASVT data area

ASCBFWDP, ASCBBWDP and ASCBTRQP fields of the ASCB data area

ASMASCBP field of the ASMVT data area JSELASCB field of the JSEL data area LCTASCBA field of the LCT data area LDAASCB field of the LDA data area LWAPASCB field of the LWA data area PCBASCB field of the PCB data area RSMASCB field of the RSMHD data area SMCAASCB field of the SMCA data area SRBASCB field of the SRB data area

SSENASCB and SSETASCB fields of the SSOB data area

TCASASCB field of the TCAST data area TQEASCB field of the TQE data area TSBASCBA field of the TSB data area TVCSASCB field of the TVCS data area TWAASCB field of the TWAR data area UCMASCB field of the UCM data area OUCBASCB field of the OUCB data area WEBHASCB field of the WEB data area WEBLSQP field of the WEB data area

Serialization: Serialization of the ASCB is dependent on

the field being referenced. Some serialization techniques

used here are local lock, compare and swap (CS), compare

double and swap, and global intersect.

Function: Contain information and pointers needed for

Address Space Control. The ASCB is non-swappable.



z/OS Control Block Address Space Control Block (ASCB)

ASCB Map

Officets

Deo	Hex	Type/Value	Len	Name (Dim)	Description
0	(0)	STRUCTURE	0	ASCS	
0	(0)	DBL WORD	8	ASCBEGIN (0)	- BEGINNING OF ASCB
0	(0)	CHARACTER	4	ASCBASCB	- ACRONYM IN EBCDIC -ASCB-
4	(4)	ADDRESS	4	ASCBFWDP	- ADDRESS OF NEXT ASCS ON ASCS READY QUEUE
8	(8)	ADDRESS	4	ASCBBWDP	- ADDRESS OF PREVIOUS ASCE ON ASCE READY QUEUE



z/OS Control Block Address Space Control Block (ASCB)

41

Offsets		_			
Deo	Hex	Type/Value	Len	Name (DIm)	Description
12	(C)	ADDRESS	4	ASCBLTCS	TCB and preemptable-class SRB Local lock suspend service queue. Serialization: ASCB CML promotion WEB lock.
16	(10)	DBL WORD	8	ASCBSUPC (0)	- SUPERVISOR CELL FIELD (MDC309)
16	(10)	ADDRESS	<u> </u>	ASCBSVRB	- SVRB POOL ADDRESS. THIS OFFSET FIXED BY
					ARCHITECTURE. (MDC310)
20	(14)	SIGNED	4	ASCBSYNC	 COUNT USED TO SYNCHRONIZE SVRB POOL. THIS OFFSET FIXED BY ARCHITECTURE. (MDC311)
24	(18)	ADDRESS	4	ASCBIOSP	 POINTER TO IOS PURGE INTERFACE CONTROL BLOCK (IPIB) (MDC308)
28	(1C)	BITSTRING	4	ASCBWQLK (0)	WEB QUEUE LOCK WORD SERIALIZATION: COMPARE AND SWAP OWNERSHIP: SUPERVISOR CONTROL
28	(1C)	BITSTRING	2	ASCBR01C	RESERVED, MUST BE ZERO
30	(1E)	SIGNED	2	ASCBWQID	LOGICAL CPU ID OF THE PROCESSOR HOLDING THE WE QUEUE LOCK OWNERSHIP: SUPERVISOR CONTROL
32	(20)	ADDRESS	4	ASCBR020 (0)	Reserved as of z/OS 1.11
32	(20)	ADDRESS	4	ASCBSAWQ_PREZ	0811
					- ADDRESS OF ADDRESS SPACE SRB WEB QUEUE
					SERIALIZATION: WEB QUEUE LOCK OWNERSHIP: SUPERVISOR CONTROL Not set as of z/OS 1.11
		1		ASCBURRQ_PREZO	0811
					"X'80" - SYSEVENT USER READY REQUIRED
					SERIALIZATION: WEB QUEUE LOCK OWNERSHIP:
					SUPERVISOR CONTROL Not set as of z/OS 1.11
36	(24)	SIGNED	2	ASCBASN (D)	- SAME AS ASCBASID
36	(24)	SIGNED	2	ASCBASID	- ADDRESS SPACE IDENTIFIER FOR THE ASCE
38	(26)	BITSTRING	1	ASCBR026	- RESERVED
39	(27)	BITSTRING	1	ASCBSRMFLAGS ASCBVCMOVERRIE	- SRM flags Ownership: SRM Serialization: SRMLOCK
				/ COD FORM OF LIGHT	"X'80" - This bit indicates that this address space should not
					follow the standard SRM management in an VCM-on
					environment. Instead of trying to assign the work this address
					space to the same affinity node for cache efficiency concerns,
					assign this work to any affinity node, ignore any cache
					concerns. Ownership: SRM
		.1		ASCRBROKENUP	"X'40" - This bit indicates that this address space has been
					broken up by SRM. Ownership: SRM
		1		ASCBVCMGIVEPRE	
					"X'20" - This bit indicates that this address space should get fu
					preemption. Ownership: SRM
		1		ASCBVCMGIVESIG	
					"X'10" - This bit indicates that this address space can SIGP ar
					waiting CPUs to process its work. Ownership: SRM
40	(28)	BITSTRING	1	ASCBLL5	- FLAGS, SERIALIZATION - LOCAL LOCK
	(20)	1		ASCBS3S	"X'20" - STAGE II EXIT EFECTOR HAS SCHEDULED AN RG
					OR IQE AND STAGE III EXIT EFFECTOR SHOULD BE INVOKED



Work Load Management (WLM) – Performance Tuning Parameters

With workload management, you define performance goals and assign a business importance to each goal.

Goals:

Response-Time
Execution Velocity
Discretionary
Importance level (1-5)

Goal is 1 or below (meeting goals)
All is well

Goal is above 1 (failing to meet goals)

Revise performance goals or increase capacity



- Each Batch Job, TSO and Started Task are a separate address space
- Types of Address Spaces
 - 1. Batch Jobs identified by JOBID JOB#####
 - 2. Started Tasks identified by JOBID STC#####
 - 3. Time Sharing Tasks identified by JOBID TSU#####

where ##### is a uniquely assigned number

Address Space is a contiguous range of virtual addresses divided into blocks of 4K pages. The pages are stored in both real and auxiliary storage. Paging is the movement of pages between real and auxiliary storage.



- A PAGE is a 4K area of processing storage
- A PAGE is also considered to be a 4K block of virtual addresses
- All processing storage is contained in PAGES
- A 4K FRAME of central storage can hold a PAGE
- A 4K SLOT of auxiliary storage can hold a PAGE
- Movement of a PAGE between a FRAME and a SLOT is called PAGING



- All programs operate with an assigned protection key
- All discrete storage areas have an assigned protection key
- System integrity is maintained through a requirement for program and storage area keys to match
- Program operating with key 0 can access any discrete storage areas regardless of the assigned storage area protect key



- Virtual storage is managed by Virtual Storage Manager (VSM)
- Real storage is managed by Real Storage Manager (RSM)
- Auxiliary storage is managed by Auxiliary Storage Manager (ASM)
- System workload is managed and prioritized by Work Load Manager (WLM)



Professional Manuals and Documentation



z/Architecture Principle of Operations



MVS Bookshelf



Unit Summary

Having completed this unit, you should be able to:

- ✓ Describe an address space
- ✓ Describe virtual storage
- ✓ Describe paging
- ✓ List 3 types of address spaces
- ✓ List 3 types of memory storage
- ✓ Describe system integrity using key-controlled protection