The NCBI C++ Toolkit

22: Debugging, Exceptions, and Error Handling

Last Update: July 18, 2010.

Overview

The overview for this chapter consists of the following topics:

- Introduction
- · Chapter Outline

Introduction

This chapter discusse the debugging mechanisms available in the NCBI C++ toolkit. There are two approaches to getting more information about an application, which does not behave correctly:

- Investigate the application's log without recompiling the program,
- Add more diagnostics and recompile the program.

Of course, there is always the third method which is to run the program under an external debugger. While using an external debugger is a viable option, this method relies on an external program and not on a log or diagnostics produced by the program itself which in many cases is customized to reflect the program behavior, and can, therefore, more quickly reveal the source of errors.

Chapter Outline

The following is an outline of the topics presented in this chapter:

- Extracting Debug Data
 - Command Line Parameters
 - Getting More Trace Data
 - ♦ Tracing
 - ♦ <u>Diagnostic Messages</u>
 - Tracing in the Connection Library
 - NCBI C++ Toolkit Diagnostics
 - Object state dump
 - Exceptions
- NCBI C++ Error Handling and Diagnostics
 - Debug-mode for Internal Use
 - C++ Exceptions
 - ♦ <u>Standard C++ Exception Classes</u>, and Two Useful NCBI Exception <u>Classes (CErrnoTemplException, CParseTemplException)</u>
 - ♦ <u>Using STD_CATCH_*(...) to catch and report exceptions</u>
 - ♦ <u>Using THROW* TRACE(...) to throw exceptions</u>
 - ♦ THROWS*(...) -- Exception Specification
 - Standard NCBI C++ Message Posting

- ♦ Formatting and Manipulators
- ♦ ERR POST macro
- ♦ Turn on the Tracing
- DebugDump: Take an Object State Snapshot
 - Terminology
 - Requirements
 - Architecture
 - Implementation
 - ♦ CDebugDumpable
 - ♦ CDebugDumpContext
 - ♦ CDebugDumpFormatter
 - Examples
- Exception Handling (*) in the NCBI C++ Toolkit
 - NCBI C++ Exceptions
 - ♦ Requirements
 - ♦ Architecture
 - **♦** Implementation
 - <u>CException</u>
 - Derived exceptions
 - Reporting an exception
 - <u>CExceptionReporter</u>
 - Choosing and analyzing error codes
 - **♦** Examples
 - Throwing an exception
 - Reporting an exception
 - The CErrnoTemplException Class
 - The CParseTemplException Class
 - Macros for Standard C++ Exception Handling
 - Exception Tracing

Extracting Debug Data

The C++ Toolkit has several mechanisms which can be used by a programmer to extract information about the program usage, printing trace and diagnostic messages, and examining the object state dump. The following sections discuss these topics in more detail:

- Command Line Parameters.
- Getting More Trace Data.
- Tracing in the Connection Library
- NCBI C++ Toolkit Diagnostics
- Object state dump

Exceptions

Command Line Parameters

There are several command line parameters (see Table 1), which are applicable to any program which utilizes NCBI C++ toolkit, namely CNcbiApplication class. They provide with the possibility

- to obtain a general description of the program as well as description of all available command line parameters (-h flag),
- to redirect the program's diagnostic messages into a specified file (-logfile key),
- to read the program's configuration data from a specified file (-conffile key).

Getting More Trace Data

All NCBI C++ toolkit libraries produce a good deal of diagnostic messages. Still, many of them remain "invisible" - as long as the tracing is disabled. Some tracing data is only available in debug builds - see _TRACE macro for example. Other - e.g., the one produced by ERR_POST or LOG_POST macros - could be disabled. There are three ways to manipulate these settings, that is enable or disable tracing, or set the severity level of messages to print:

- from the application itself,
- · from the application's configuration file,
- with the help of environment variables.

The following additional topics relating to trace data are presented in the subsections that follow:

- Tracing
- Diagnostic Messages

Tracing

There are two ways to post trace messages: using either the _TRACE macro or the ERR_POST macro. Trace messages produced with the help of _TRACE macro are only available in debug mode, while those posted by ERR_POST are available in both release and debug builds. By default, tracing is disabled. See Table 2 for settings to enable tracing.

Please note, when enabling trace from a configuration file, some trace messages could be lost: before configuration file is found and read the application may assume that the trace was disabled. The only way to enable tracing from the very beginning is by setting the environment variable.

Diagnostic Messages

Diagnostic messages produced by ERR_POST macro are available both in debug and release builds. Such messages have a severity level, which defines whether the message will be actually printed or not, and whether the program will be aborted or not. To change the severity level threshold for posting diagnostic messages, see Table 3.

Only those messages, which severity is equal or exceeds the threshold will be posted. By default, messages posted with Fatal severity level also abort execution of the program. This can be changed by SetDiagDieLevel(EDiagSev dieSev) API function.

Tracing in the Connection Library

The connection library has its own tracing options. It is possible to print the connection parameters each time the link is established, and even log all data transmitted through the socket during the life of the connection (see Table 4).

NCBI C++ Toolkit Diagnostics

NCBI C++ toolkit provides with a sophisticated <u>diagnostic mechanism</u>. Diagnostic messages could be redirected to different output channels. It is possible to set up what additional information should be printed with a message, for example date/time stamp, file name, line number etc. Some macros are defined only in debug mode:_TRACE,_ASSERT,_TROUBLE. Others are also defined in release mode as well: _VERIFY, THROW*_TRACE.

Object state dump

Potentially useful technique in case of trouble is to use <u>object state dump API</u>. In order to use it, the object's class must be derived from <u>CDebugDumpable</u> class, and implementation of the class should supply meaningful dump data in its DebugDump function. Debug dump gives an object's state snapshot, which can help in identifying the cause of problem at run time.

Exceptions

NCBI C++ toolkit defines its own type of C++ exceptions. Unlike standard ones, this class

- makes it possible to define error codes (specific to each exception class), which could be analyzed from a program,
- provides with more information about where a particular exception has been thrown from (file name and line number),
- gives the possibility to create a stack of exceptions to accumulate a backlog of events (unfinished jobs) which caused the problem,
- · has elaborated, customizable reporting mechanism,
- supports using standard diagnostic mechanism with all the configuration options it provides.

NCBI C++ Error Handling and Diagnostics

The following topics are discussed in this section:

- Debug-mode for Internal Use
- <u>C++ Exceptions</u>
- Standard NCBI C++ Message Posting

Debug-mode for Internal Use

#include <corelib/ncbidbg.hpp> [also included in <corelib/ncbistd.hpp>]

There are four preprocessor macros (_TROUBLE, _ASSERT, _VERIFY and _TRACE) to help the developer to catch some (logical) errors on the early stages of code development and to hardcode some assertions on the code and data behaviour for internal use. All these macros gets disabled in the non-debug versions lest to affect the application performance and functionality; to turn them on, one must #define the _DEBUG preprocessor variable. Developer must be careful and do not use any code with side effects in _ASSERT or _TRACE as this will cause a discrepancy in functionality between debug and non-debug code. For example, _ASSERT(a++) and _TRACE("a++ = " << a++) would increment "a" in the debug version but do nothing in the non-debug one).

- _TROUBLE -- Has absolutely no effect if _DEBUG is not defined; otherwise, unconditionally halt the application.
- _ASSERT(expr) -- Has absolutely no effect if _DEBUG is not defined; otherwise, evaluate expression expr and halt the application if expr resulted in zero(or "false").
- _VERIFY(expr) -- Evaluate expression expr; if _DEBUG is defined and expr resulted in zero(or "false") then halt the application.
- _TRACE(message) -- Has absolutely no effect if _DEBUG is not defined; otherwise, it outputs the message using <u>Standard NCBI C++ message posting</u>. NOTE: as a matter of fact, the tracing is turned off by default, even if _DEBUG is defined, and you still have to do a special configuration to really turn it on.

All these macros automatically report the file name and line number to the diagnostics. For example, this code located in file "somefile.cpp" at line 333:

```
int x = 100;
_TRACE( "x + 5 = " << (x + 5) );
will output:
"somefile.cpp", line 333: Trace: x + 5 = 105</pre>
```

C++ Exceptions

#include <corelib/ncbiexpt.hpp> [also included in <corelib/ncbistd.hpp>]

The following additional topics are discussed in this section:

- Standard C++ Exception Classes, and Two Useful NCBI Exception Classes (CErrnoTemplException, CParseTemplException)
- Using STD_CATCH_*(...) to catch and report exceptions
- Using THROW* TRACE(...) to throw exceptions
- THROWS*(...) -- Exception Specification

Standard C++ Exception Classes, and Two Useful NCBI Exception Classes (CErrnoTemplException, CParseTemplException)

One must use <u>CException</u> as much as possible. When not possible, standard C++ exceptions should be used. There are also a couple of auxiliary exception classes derived from std::runtime error that may be used if necessary.

- CErrnoTemplException -- to report failure in a standard C library function; it automatically appends to the user message a system-specific description reported by errno
- CParseTemplException -- to report an erroneous position (passed in the additional constructor parameter) along with the user message

Then, it is **strongly recommended** that when <u>CException</u> can't be used, and when the basic functionality provided by standard C++ exceptions is insufficient for some reason, one must derive new ad hoc exception classes from one of the standard exception classes. This provides a more uniform way of exception handling, because most exceptions can be caught and appropriately handled using the STD_CATCH_*(...) preprocessor macros as described below.

Using STD_CATCH_*(...) to catch and report exceptions

You can use the STD_CATCH_*(...) macros to catch exceptions potentially derived from the standard exception class std::exception when you just want to print out a given error name, subcode, and message along with the information returned from std::exception::what().

The STD_CATCH_X(subcode, message) and STD_CATCH_XX(name, subcode, message) macros only catch exceptions derived from std::exception, and post the given error name, subcode, and message along with the information returned from std::exception::what().

The STD_CATCH_ALL_X(subcode, message) and STD_CATCH_ALL_XX(name, subcode, message) macros first try to catch a std::exception-derived exception (using the STD_CATCH_X and STD_CATCH_XX macros, respectively), and if the thrown exception was not caught (i.e. if it is not derived from std::exception) then they catch all exceptions and post the given error name, subcode, and message.

The name argument must match one of the pre-defined values in the error_codes.hpp header for the relevant module (e.g. connect), and the subcode argument must be within the range specified in the same place. The message argument can be of any form acceptable by the <u>diagnostic class CNcbiDiag</u>.

Using these macros makes dealing with exceptions in NCBI C++ code easy:

```
class foreign_exception { ..... };
class exception_derived_user : public exception { ..... };
char arg1 = "qqq";
int arg2 = 888;
try {
   SomeFunc(arg1, arg2);
} catch (foreign_exception& fe) {
   // do something special with the particular "non-standard"
   // (not derived from "std::exception") exception "foreign_exception"
} catch (exception_derived_user& eu) {
   // do something special with the particular "standard"
   // do something special with the particular "standard"
   // do something special with the particular "standard"
   // handle all other "standard" exceptions in a uniform way
STD_CATCH_X( 1, "in SomeFunc(" << arg1 << "," << arg2 << ")" );</pre>
```

Here, if SomeFunc() executes throw std::runtime_error("Invalid Arg2"); then the application will print out (to its diagnostic stream) something like:

```
Error: (101.1) [in SomeFunc(qqq,888)] Exception: Invalid Arg2
```

In this output, the (101.1) indicates the error code (defined in the module's error_codes.hpp header) and the subcode passed to STD_CATCH_X.

Using THROW*_TRACE(...) to throw exceptions

If you use one of THROW*_TRACE(...) macros to throw an exception, and the source was compiled in a debug mode (i.e. with the preprocessor _DEBUG defined), then you can turn on the following features that proved to be very useful for debugging:

• If the <u>tracing is on</u>, then the location of the throw in the source code and the thrown exception will be printed out to the current diagnostic stream, e.g.:

```
THROW_TRACE(CParseException, ("Failed parsing(at pos. 123)", 123));

"coretest.cpp", line 708: Trace: CParseException: {123}
Failed parsing(at pos. 123)

------

strtod("1e-999999", 0);
THROW1_TRACE(CErrnoException, "Failed strtod('1e-999999', 0)");
```

"coretest.cpp", line 718: Trace: CErrnoException: Failed strtod('le-999999', 0): Result too large

• Sometimes, it can be convenient to just abort the program execution at the place where you throw an exception, e.g. in order to examine the program stack and overall state that led to this throw. By default, this feature is not activated. You can turn it on for your whole application by either setting the environment variable \$ABORT_ON_THROW to an arbitrary non-empty string, or by setting the application's registry entry ABORT_ON_THROW (in the [DEBUG] section) to an arbitrary non-empty value. You also can turn it on and off in your program code, calling function SetThrowTraceAbort().

NOTE: if the source was not compiled in the debug mode, then the THROW*_TRACE(...) would just throw the specified exception, without doing any of the "fancy stuff" we just described.

THROWS*(...) -- Exception Specification

One is discouraged from writing exception specifications - either with throw() or the THROWS* macros.

Standard NCBI C++ Message Posting

#include <corelib/ncbidiag.hpp> [also included in <corelib/ncbistd.hpp>]

Standard diagnostics is provided with the CNcbiDiag class. A given application can have as many objects of this class as needed. An important point to remember is that each instance of the CNcbiDiag class actually stores (and allows to append to) only one message at a time. When the message controlled by an instance of CNcbiDiag is complete, CNcbiDiag invokes the Post() method of a global handler object (of type CDiagHandler) and passes the message (along with its severity level) as the method's argument.

Usually, this global object would merely dump the message to a diagnostic stream, and there is an auxiliary function SetDiagStream() that can be used to specify the output stream for the diagnostics. One can call SetDiagStream(&NcbiCerr) to dump the diagnostics to the standard error output stream:

```
/// Set diagnostic stream.
///
/// Error diagnostics are written to output stream "os"
/// This uses the SetDiagHandler() functionality.
NCBI_XNCBI_EXPORT
extern void SetDiagStream
(CNcbiOstream* os,
bool quick flush = true,///< Do stream flush after every message</pre>
```

```
FDiagCleanup cleanup = 0, ///< Call "cleanup(cleanup_data)" if diag.
void* cleanup_data = 0 ///< Stream is changed (see SetDiagHandler)
);</pre>
```

Using SetDiagHandler(), one can install a custom handler object of type CDiagHandler to process the messages posted via CNcbiDiag. The implementation of the CStreamDiagHandler in "ncbidiag.cpp" is a good example of how to do this.

```
///
/// CDiagHandler --
111
/// Base diagnostic handler class.
class NCBI XNCBI EXPORT CDiagHandler
public:
/// Destructor.
virtual ~CDiagHandler(void) {}
/// Post message to handler.
virtual void Post(const SDiagMessage& mess) = 0;
/// Set the diagnostic handler using the specified diagnostic handler class.
NCBI XNCBI EXPORT
extern void SetDiagHandler(CDiagHandler* handler,
bool can delete = true);
/// Get the currently set diagnostic handler class.
NCBI XNCBI EXPORT
extern CDiagHandler* GetDiagHandler(bool take ownership = false);
where:
/// SDiagMessage --
111
/// Diagnostic message structure.
/// Defines structure of the "data" message that is used with message handler
/// function("func"), and destructor("cleanup").
/// The "func(..., data)" to be called when any instance of "CNcbiDiagBuffer"
/// has a new diagnostic message completed and ready to post.
/// "cleanup(data)" will be called whenever this hook gets replaced and
/// on the program termination.
/// NOTE 1: "func()", "cleanup()" and "g SetDiagHandler()" calls are
/// MT-protected, so that they would never be called simultaneously
/// from different threads.
/// NOTE 2: By default, the errors will be written to standard error stream.
```

```
struct SDiagMessage {
/// Initalize SDiagMessage fields.
SDiagMessage (EDiagSev severity, const char* buf, size t len,
const char* file = 0, size t line = 0,
TDiagPostFlags flags = eDPF Default, const char* prefix = 0,
int err code = 0, int err subcode = 0,
const char* err text = 0);
mutable EDiagSev m_Severity; ///< Severity level</pre>
const char* m Buffer; ///< Not guaranteed to be '\0'-terminated!</pre>
size t m BufferLen; ///< Length of m Buffer
const char* m File; ///< File name</pre>
size t m Line; ///< Line number in file
 int m ErrCode; ///< Error code</pre>
 int m ErrSubCode; ///< Sub Error code
TDiagPostFlags m Flags; ///< Bitwise OR of "EDiagPostFlag"
const char* m Prefix; ///< Prefix string</pre>
const char* m ErrText; ///< Sometimes 'error' has no numeric code,</pre>
 ///< but can be represented as text
 // Compose a message string in the standard format(see also "flags"):
 // "<file>", line <line>: <severity>: [<prefix>] <message> [EOL]
 // and put it to string "str", or write to an output stream "os".
 /// Which write flags should be output in diagnostic message.
 enum EDiagWriteFlags {
 fNone = 0x0, ///< No flags
 fNoEndl = 0x01 ///< No end of line
 typedef int TDiagWriteFlags; /// Binary OR of "EDiagWriteFlags"
/// Write to string.
void Write(string& str, TDiagWriteFlags flags = fNone) const;
 /// Write to stream.
CNcbiOstream& Write(CNcbiOstream& os, TDiagWriteFlags flags = fNone) const;
```

Installing a new handler typically destroys the previous handler, which can be a problem if you need to keep the old handler around for some reason. There are two ways to address this issue:

- Declare an object of class CDiagRestorer at the top of the block of code in which you
 will be using your new handler. This will protect the old handler from destruction, and
 automatically restore it -- along with any other diagnostic settings -- when the block
 exits in any fashion. As such, you can safely use the result of calling GetDiagHandler
 () at the beginning of the block even if you have changed the handler within the block.
- Call GetDiagHandler(true) and then destroy the old handler yourself when done with it. This works in some circumstances in which CDiagRestorer is unsuitable, but places much more responsibility on your code.

For compatibility with older code, the diagnostic system also supports specifying simple callbacks:

```
/// Diagnostic handler function type.
typedef void (*FDiagHandler) (const SDiagMessage& mess);

/// Diagnostic cleanup function type.
typedef void (*FDiagCleanup) (void* data);

/// Set the diagnostic handler using the specified diagnostic handler class.
NCBI_XNCBI_EXPORT
extern void SetDiagHandler(CDiagHandler* handler,
bool can_delete = true);
```

However, it is better to use the object-based interface for new code.

The following additional topics are discussed in this section:

- Formatting and Manipulators
- ERR POST macro
- Turn on the Tracing

Formatting and Manipulators

To compose a diagnostic message with CNcbiDiag you can use the formatting operator "<<". It works practically the same way as operator "<<" for standard C++ output streams. CNcbiDiag class also has some CNcbiDiag-specific manipulators to control the message severity level:

- Info -- set severity level to eDiag_Info
- Warning -- set severity level to eDiag Warning
- Error -- set severity level to eDiag Error [default]
- Fatal -- set severity level to eDiag Fatal
- Trace -- set severity level to eDiag Trace

NOTE: whenever the severity level is changed, CNcbiDiag also automatically executes the following two manipulators:

- Endm -- means that the message is complete and to be flushed(via the global callback as described above)
- Reset -- directs to discard the content of presently composed message

The Endm manipulator also gets executed on the CNcbiDiag object destruction.

For example, this code:

```
int iii = 1234;
CNcbiDiag diag1;

diag1 << "Message1_Start " << iii;
    // message 1 is started but not ready yet
{ CNcbiDiag diag2; diag2 << Info << "Message2"; }
    // message 2 flushed in destructor
diag1 << "Message1_End" << Endm;
    // message 1 finished and flushed by "Endm"
diag1 << "Message1_1"; // will be flushed by the following "Warning"
diag1 << Warning << "Discard this warning" << ++iii << Reset;
    // message discarded</pre>
```

```
diag1 << "This is a warning " << iii;
diag1 << Endm;</pre>
```

will write to the diagnostic stream(if the latter was set with SetDiagStream()):

```
Error: Message1_Start 1234
Info: Message2
Error: Message1_End
Error: Message1_1
Warning: This is a warning 1235
```

ERR POST macro

There is an ERR_POST(message) macro that can be used to shorten the error posting code. This macro is discussed in the chapter on Core Library.

Turn on the Tracing

The tracing (messages with severity level eDiag_Trace) is considered to be a special, debugoriented feature, and therefore it is not affected by SetDiagPostLevel() and SetDiagDieLevel (). To turn the tracing on or off in your code you can use function SetDiagTrace().

By default, the tracing is off -- unless you assign environment variable \$DIAG_TRACE to an arbitrary non-empty string (or, alternatively, you can set DIAG_TRACE entry in the [DEBUG] section of your registry to any non-empty value).

DebugDump: Take an Object State Snapshot

The following topics are discussed in this section:

- Terminology
- Requirements
- Architecture
- Implementation
- <u>Examples</u>

Debugging is an inevitable part of software development. When it comes to a "mystical" problem, one can spend days and days hunting for a glitch. So, being prepared is not just a "nice thing to have", it is a requirement.

When a system being developed crashes consistently, debugging is easy in the sense that the problem is reproducable. Were that all bugs like this! It is much more "fun", when the system crashes intermittently, under circumstances about which we have only a vague idea, if any, of the symptoms or the cause. What the developer needs in this case is information - the more the better. One short message ("Assertion failed") is good and a coredump is better, but we typically need a more user-friendly reporting of the program status at the point of failure.

One possible idea is to make the object tell about itself. That is, in case of trouble (but not necessarily trouble), an object could call a function that would report as much as possible about itself and other object it contains or to which it refers. During such operation the object should not do anything important, something that could potentially cause other problems. The diagnostic must of course be safe - it should only take a snapshot of an object's state and never alter that data.

Sure, DebugDump may cause problems by itself, even if everything is "correct". Let us say there are two objects, which "know" each other: Object A refers to Object B, while Object B refers to Object A (very common scenario in fact). Now dumping contents of Object A will cause dumping of Object B, which in turn will cause dumping of Object A, and so on until the stack overflows.

Terminology

So, dumping the object contents should look as a single function call, i.e. something like this:

```
Object name;
...
name.DebugDump(?);
```

The packet of information produced by such operation we call bundle. The class Object is most likely derived from other classes. The function should be called sequentially for each subclass, so it could print its data members. The piece of information produced by the subclass we call frame. The object may refer to other objects. Dumping of such object produces a sub-bundle, which consists of its own frames. To help fight cyclicity, we introduce depth of the dump. When an object being dumped wants to dump other objects it refers to, it should reduce the depth by one. If the depth is already zero, other objects should not be dumped.

Requirements

- The dump data should be separated from its representation. That is, the object should
 only supply data, something else should format it. Examples of formatting may include
 generating human-readable text or file in a special format (HTML, XML), or even
 transmitting the data over the network.
- Debug and release libraries should be compatible.
- It should be globally configurable as to whether the dump produces any output or not,

Architecture

Class CDebugDumpable is a special abstract base class. Its purpose is to define a virtual function DebugDump, which any derived class should implement. Another purpose is to store any global dump options. Any real dump should be initiated through a non-virtual function of this class - so, global option could be applied. Class CObject is derived from this class. So, any classes based on CObject may benefit from this functionality right away. Other classes may use this class as a base later on (e.g. using multiple inheritance).

Class CDebugDumpContext provides a generic dump interface for dumpable objects. The class has nothing to do with data representation. Its purpose is the ability to describe the location of where the data comes from, accept it from the object and transfer to the data formatter.

Class CDebugDumpFormatter defines the dump formatting interface. It is an abstract class.

Class CDebugDumpFormatterText is derived from CDebugDumpFormatter. Based on incoming data, it generates a human-readable text and passes it into any output stream (ostream).

In general, the system works like this:

 Client creates DebugDump formatter object (it could be an object of class CDebugDumpFormatterText or any other class derived from CDebugDumpFormatter) and passes it to a proper, non-virtual function of the object

- to be dumped. Bundle name is to be defined here it can be anything, but a reasonable guess would be to specify the location of the call and the name of the object being dumped.
- CDebugDumpable analyses global settings, creates CDebugDumpContext object and calls virtual DebugDump() function of the object.
- DebugDump function of each subclass defines a frame name (which must be the type
 of the subclass), calls DebugDump function of a base class and finally logs its own
 data members. From within the DebugDump(), the object being dumped "sees" only
 CDebugDumpContext. It does not know any specifics about target format in which
 dump data will be eventually represented.

Implementation

The following topics are discussed in this section:

- CDebugDumpable
- CDebugDumpContext
- CDebugDumpFormatter

CDebugDumpable

The class is an abstract one. Global options are stored as static variable(s).

```
public:
    // Enable/disable debug dump
    static void EnableDebugDump(bool on);

    // Dump using text formatter
    void DebugDumpText(ostream& out,
    const string& bundle,
    unsigned int depth) const;

    // Dump using external dump formatter
    void DebugDumpFormat(CDebugDumpFormatter& ddf,
    const string& bundle,
    unsigned int depth) const;

// Function that does the dump - to be overloaded
    virtual void DebugDump(CDebugDumpContext ddc,
    unsigned int depth) const = 0;
```

Any derived class must impelement a relevant DebugDump function.

CDebugDumpContext

The class defines a public dump interface for a client object. It receives the data from the object and decides when and what functions of dump formatter to call.

The dump interface looks like this:

```
public:
   CDebugDumpContext(CDebugDumpFormatter& formatter,
   const string& bundle);
   // This is not exactly a copy constructor -
```

```
// this mechanism is used internally to find out
 // where are we on the Dump tree
CDebugDumpContext(CDebugDumpContext& ddc);
CDebugDumpContext(CDebugDumpContext& ddc, const string& bundle);
public:
// First thing in DebugDump() function - call this function
// providing class type as the frame name
void SetFrame(const string& frame);
// Log data in the form [name, data, comment]
// All data is passed to a formatter as string, still sometimes
// it is probably worth to emphasize that the data is REALLY a
// string
void Log(const string& name,
const string& value,
bool is string = true,
const string& comment = kEmptyStr
void Log(const string& name,
bool value,
const string& comment = kEmptyStr
);
void Log(const string& name,
long value,
const string& comment = kEmptyStr
);
void Log(const string& name,
unsigned long value,
const string& comment = kEmptyStr
void Log(const string& name,
double value,
const string& comment = kEmptyStr
);
void Log(const string& name,
const void* value,
const string& comment = kEmptyStr
void Log(const string& name,
const CDebugDumpable* value,
unsigned int depth
```

A number of overloaded Log functions is provided for convenience only.

CDebugDumpFormatter

);

This abstract class defines dump formatting interface:

```
public:
    virtual bool StartBundle(unsigned int level, const string& bundle) = 0;
    virtual void EndBundle( unsigned int level, const string& bundle) = 0;
```

```
virtual bool StartFrame( unsigned int level, const string& frame) = 0;
virtual void EndFrame( unsigned int level, const string& frame) = 0;
virtual void PutValue( unsigned int level, const string& name, const string& value, bool is_string, const string& comment) = 0;
```

Examples

Supposed that there is an object m_ccObj of class CSomeObject derived from CObject. In order to dump it into the standard cerr stream, one should do one of the following:

```
m_ccObj.DebugDumpText(cerr, "m_ccObj", 0);

or

{
   CDebugDumpFormatterText ddf(cerr);
   m_ccObj.DebugDumpFormat(ddf, "m_ccObj", 0);
}
```

The DebugDump function should look like this:

```
void CSomeObject::DebugDump(CDebugDumpContext ddc, unsigned int depth) const
{
    ddc.SetFrame("CSomeObject");
    CObject::DebugDump(ddc,depth);
    ddc.Log("m_1", m_1);
    ddc.Log("m_2", m_2);
    ... etc for each data member
}
```

Exception Handling (*) in the NCBI C++ Toolkit

The following topics are discussed in this section:

- NCBI C++ Exceptions
- The CErrnoTemplException Class
- The CParseTemplException Class
- Macros for Standard C++ Exception Handling
- Exception Tracing

NCBI C++ Exceptions

C++ exceptions is a standard mechanism of communicating abnormal or unexpected events to a higher execution context. By throwing an exception a piece of code says it was unable to complete the task and it is up to others to decide what to do next.

What the standard mechanism lacks is backlog, history of unfinished tasks and its consequences. Say for instance, a program tries to load some data from a database. An exception occurs, which says a connection to some port could not be created -- so what? How

meaningfull is it? What did the program try to do? Where did the request for the connection come from?

Another problem is analyzing and handling exceptions in a program. When an exception is caught, what is known for sure is only that something bad has happened -- but what exactly? The standard exception has only type (exception class) and a text message. The latter probably makes sense for a human, but not for a program. The former does not seem to be clear enough.

The following topics are discussed in this section:

- Requirements
- Architecture
- Implementation
- Examples

Requirements

In order for exceptions to be more useful, they should meet the following requirements:

- Exceptions should contain information about where exactly has it been thrown -- for a human.
- Exceptions should have a numeric id -- for a program.
- It should be possible to create a stack of exceptions -- to accumulate a backlog of events (unfinished jobs) which caused the problem. Still, for a client, it should look like a single exception. That is, a client should be able to ignore completely the compound structure of the exception being thrown and still get some meaningful information.
- The system should provide for the ability to analyze the exception backlog and possibly print information about each exception separately.
- It should be possible to report the exception data into an arbitrary output channel and possibly format it differently for each channel.

Architecture

Each subsystem (library) has its own type of exceptions. It may have several types, if necessary, but all of them should be derived from a single base class (which in turn is derived from a system-wide base class). So, the type of an exception uniquely identifies the library which produced it.

Each exception has a numeric id, which is unique throughout the subsystem. Such an id gives an unambiguous description of the problem occurred. Each id is associated with a text message. Strictly speaking, there is only one message associated with a given id, so there is no need to include the message in the exception itself -- it could be taken from an external source. Still, we suggest using the message -- it serves as an additional comment. Also, it does not restrict us from using an external source of messages in the future.

Each exception has information about the location where it has been thrown -- file name and line number.

An exception can have a reference to the "lower level" one, which makes it possible to analyze the backlog. Naturally, such a backlog cannot be created automatically - it is a developer's responsibility. The system only provides the mechanism, it does not solve problems by itself. The developer is supposed to catch exceptions in proper places and re-throw them with the backlog information added.

The exception constructor's mandatory parameters include location information, exception id and a message. This constructor is to be used at the lower level, when the exception is thrown initially. At higher levels we need a constructor, which would accept the exception from the lower level as one of its parameters.

The NCBI exception mechanism has a sophisticated reporting mechanism -- the standard exception::what() function is definitely not enough. There are three groups of reporting mechanisms:

- exception formats its data by itself and either returns the result as a string or puts it into an output stream;
- client provides an external exception data formatter;
- · NCBI standard diagnostic mechanism is used.

Implementation

The following topics are discussed in this section:

- CException
- Derived exceptions
- Reporting an exception
- CExceptionReporter
- Choosing and analyzing error codes

CException

There is a single system-wide exception base class -- CException. Each subsystem **must** implement its own type of exceptions, which must be derived from this class. The class defines basic requirements of an exception construction, backlog and reporting mechanisms.

The CException constructor includes location information, exception id and a message. Each exception class defines its own error codes. So, the error code "by itself" is meaningless -- one should also know the the exception class, which produced it.

```
/// Constructor.
///
/// When throwing an exception initially, "prev_exception" must be 0.
CException(const char* file, int line,
  const CException* prev_exception,
  EErrCode err_code,const string& message) throw();
```

To make it easier to throw/re-throw an exception, the following macros are defined:

```
NCBI_THROW(exception_class, err_code, message)
NCBI_RETHROW(prev_exception, exception_class, err_code, message)
NCBI_RETHROW SAME(prev_exception, message)
```

The last one (NCBI_RETHROW_SAME) re-throws the same exception with backlog information added.

The CException class has numerous reporting methods (the contents of reports is defined by diagnostics post flags):

```
/// Standard report (includes full backlog).
virtual const char* what (void) const throw();
/// Report the exception.
///
/// Report the exception using "reporter" exception reporter.
/// If "reporter" is not specified (value 0), then use the default
/// reporter as set with CExceptionReporter::SetDefault.
void Report(const char* file, int line,
const string& title, CExceptionReporter* reporter = 0,
TDiagPostFlags flags = eDPF Trace) const;
/// Report this exception only.
///
/// Report as a string this exception only. No backlog is attached.
string ReportThis(TDiagPostFlags flags = eDPF Trace) const;
/// Report all exceptions.
///
/// Report as a string all exceptions. Include full backlog.
string ReportAll (TDiagPostFlags flags = eDPF Trace) const;
/// Report "standard" attributes.
/// Report "standard" attributes (file, line, type, err.code, user message)
/// into the "out" stream (this exception only, no backlog).
void ReportStd(ostream& out, TDiagPostFlags flags = eDPF Trace) const;
/// Report "non-standard" attributes.
/// Report "non-standard" attributes (those of derived class) into the
/// "out" stream.
virtual void ReportExtra(ostream& out) const;
/// Enable background reporting.
111
/// If background reporting is enabled, then calling what() or ReportAll()
/// would also report exception to the default exception reporter.
/// @return
/// The previous state of the flag.
static bool EnableBackgroundReporting(bool enable);
```

Also, the following macro is defined that calls the CExceptionReporter::ReportDefault() method to produce a report for the exception:

```
NCBI REPORT EXCEPTION(title,e)
```

Finally, the following data access functions help to analyze exceptions from a program:

```
/// Get class name as a string.
virtual const char* GetType(void) const;
```

```
/// Get error code interpreted as text.
virtual const char* GetErrCodeString(void) const;

/// Get file name used for reporting.
const string& GetFile(void) const;

/// Get line number where error occurred.
int GetLine(void) const;

/// Get error code.
EErrCode GetErrCode(void) const;

/// Get message string.
const string& GetMsg (void) const;

/// Get "previous" exception from the backlog.
const CException* GetPredecessor(void) const;
```

Derived exceptions

The only requirement for a derived exception is to define error codes as well as its textual representation. Implementation of several other functions (e.g. constructors) are, in general, pretty straightforward -- so we put it into a macro definition, NCBI_EXCEPTION_DEFAULT. Please note, this macro can only be used when the derived class has no additional data members. Here is an example of an exception declaration:

```
class CSubsystemException : public CException
{
public:
 /// Error types that subsystem can generate.
 enum EErrCode {
eType1, ///< Meaning of eType1
 eType2 ///< Meaning of eType2
 };
 /// Translate from the error code value to its string representation.
virtual const char* GetErrCodeString(void) const
 {
 switch (GetErrCode()) {
 case eType1: return "eType1";
 case eType2: return "eType2";
 default: return CException::GetErrCodeString();
 }
 }
 // Standard exception boilerplate code.
NCBI EXCEPTION DEFAULT (CSubsystemException, CException);
};
```

In case the derived exception has data members not found in the base class, it should also implement its own ReportExtra method -- to report this non-standard data.

Reporting an exception

There are several way to report an NCBI C++ exception:

• An exception is capable of formatting its own data, returning a string (or a pointer to a string buffer). Each exception report occupies one line. Still, since an exception may contain a backlog of previously thrown exceptions, the resulting report could contain several lines of text - one for each exception thrown. The report normally contains information about the location from which the exception has been thrown, the text representation of the exception class and error code, and a description of the error. The content of the report is defined by diagnostics post flags. The following methods generate reports of this type:

```
/// Standard report (includes full backlog).
virtual const char* what(void) const throw();
/// Report the exception.
/// Report the exception using "reporter" exception reporter.
/// If "reporter" is not specified (value 0), then use the default
/// reporter as set with CExceptionReporter::SetDefault.
void Report(const char* file, int line,
const string& title, CExceptionReporter* reporter = 0,
TDiagPostFlags flags = eDPF Trace) const;
/// Report this exception only.
/// Report as a string this exception only. No backlog is attached.
string ReportThis(TDiagPostFlags flags = eDPF Trace) const;
/// Report all exceptions.
/// Report as a string all exceptions. Include full backlog.
string ReportAll (TDiagPostFlags flags = eDPF_Trace) const;
/// Report "standard" attributes.
///
/// Report "standard" attributes (file, line, type, err.code, user message)
/// into the "out" stream (this exception only, no backlog).
void ReportStd(ostream& out, TDiagPostFlags flags = eDPF Trace) const;
```

Functions what() and ReportAll() may also generate a background report - the one generated by a default exception reporter. This feature can be disabled by calling the static method

CException::EnableBackgroundReporting(false);

- A client can provide its own exception reporter. An object of this class may either use
 exception data access functions to create its own reports, or redirect reports into its
 own output channel(s). While it is possible to specify the reporter in the
 CException::Report() function, it is better if the same reporting functions are used for
 exceptions, to install the reporter as a default one instead, using
 CExceptionReporter::SetDefault(const CExceptionReporter* handler); static
 function, and use the standard NCBI_REPORT_EXCEPTION macro in the program.
- Still another way to report an exception is to use the standard diagnostic mechanism provided by NCBI C++ toolkit. In this case the code to generate the report would look

```
like this:
try {
...
} catch (CException& e) {
ERR_POST_X(1, Critical << "Your message here." << e);
}</pre>
```

CExceptionReporter

One of possible ways to report an exception is to use an external "reporter" modeled by the CExceptionReporter abstract class. The reporter is an object that formats exception data and sends it to its own output channel. A client can install its own, custom exception reporter. This is not required, though. In case the default was not set, the standard NCBI diagnostic mechanism is used.

The CExceptionReporter is an abstract class, which defines the reporter interface:

```
/// Set default reporter.
static void SetDefault(const CExceptionReporter* handler);
/// Get default reporter.
static const CExceptionReporter* GetDefault(void);
/// Enable/disable using default reporter.
///
/// @return
/// Previous state of this flag.
static bool EnableDefault(bool enable);
/// Report exception using default reporter.
static void ReportDefault(const char* file, int line,
const string& title, const CException& ex,
TDiagPostFlags flags = eDPF Trace);
/// Report exception with this reporter
virtual void Report (const char* file, int line,
const string& title, const CException& ex,
TDiagPostFlags flags = eDPF Trace) const = 0;
```

Choosing and analyzing error codes

Choosing and interpreting error codes can potentially create some problems because each exception class has its own error codes, and interpretation. Error codes are implemented as an enum type, EErrCode, and the enumerated values are stored internally in a program as numbers. So, the same number can be interpreted incorrectly for a different exception class than the one in which the enum type was defined. Say for instance, there is an exception class, which is derived from CSubsystemException -- let us call it CBiggersystemException -- which also defines two error codes: eBigger1 and eBigger2:

```
class CBiggersystemException : public CSubsystemException
{
public:
   /// Error types that subsystem can generate.
```

```
enum EErrCode {
  eBigger1, ///< Meaning of error code, eBigger1
  eBigger2 ///< Meaning of error code, eBigger2
};

/// Translate from the error code value to its string representation.
  virtual const char* GetErrCodeString(void) const
{
    switch (GetErrCode()) {
        case eBigger1: return "eBigger1";
        case eBigger2: return "eBigger2";
        default: return CException::GetErrCodeString();
    }
}

// Standard exception boilerplate code.
    NCBI_EXCEPTION_DEFAULT(CBiggersystemException, CSubsystemException);
};</pre>
```

Now, suppose an exception CBiggersystemException has been thrown somewhere. On a higher level it has been caught as CSubsystemException. It is easy to see that the error code returned by the CSubsystemException object would be completely meaningless: the error code of CBiggersystemException cannot be interpreted in terms of CSubsystemException.

One reasonable solution seems to be isolating error codes of different exception classes -- by assigning different numeric values to them. And this has to be done by the developer. Such isolation should only be done within each branch of derivatives only. Another solution is to make sure that the exception in question does belong to the desired class, not to any intermediate classes in the derivation hierarchy. The template function UppermostCast() can be used to perform this check:

```
/// Return valid pointer to uppermost derived class only if "from" is
_really_
/// the object of the desired type.
///
/// Do not cast to intermediate types (return NULL if such cast is
attempted).
template <class TTo, class TFrom>
const TTo* UppermostCast(const TFrom& from)
{
   return typeid(from) == typeid(TTo) ? dynamic_cast<const TTo*>(&from) : 0;
}
```

UppermostCast() utilizes the runtime information using the typeid() function, and dynamic cast conversion to return either a pointer to "uppermost" exception object or NULL.

The following shows how UppermostCast() can be used to catch the correct error types:

```
try {
    ...
NCBI_THROW(CBiggersystemException,eBigger1,"your message here");
    ...
```

It is possible to use the runtime information to do it even better. Since GetErrCode function is non-virtual, it might check the type of the object, for which it has been called, against the type of the class to which it belongs. If these two do not match, the function returns invalid error code. Such code only means that the caller did not know the correct type of the exception, and the function is unable to interpret it.

Examples

The following topics are discussed in this section:

- Throwing an exception
- · Reporting an exception

Throwing an exception

It is important to remember that the system only provides a mechanism to create a backlog of unfinished tasks, it does not create this backlog automatically. It is up to developer to catch exceptions and re-throw them with the backlog information added. Here is an example of throwing <u>CSubsystemException</u> exception:

```
... // your code
NCBI_THROW(CSubsystemException,eType1,"your message here");
```

The code that catches, and possibly re-throws the exception might look like this:

```
try {
    ... // your code
} catch (CSubsystemException& e) {
    if (e.GetErrCode() == CSubsystemException::eType2) {
        ...
} else {
    NCBI_RETHROW(e, CSubsystemException, eType1, " your message here")
```

```
} catch (CException& e) {
  NCBI_RETHROW(e, CException, eUnknown, "your message here")
}
```

Reporting an exception

There are a <u>number of ways</u> to report CException, for example:

```
try {
    ... // your code
} catch (CSubsystemException& e) {
    NCBI_REPORT_EXCEPTION("your message here", e);
    ERR_POST_X(CMyException::eMyErrorXyz, Critical << "message" << e);
    cerr << e.ReportAll();
    cerr << e.what();
    e.Report(__FILE__, __LINE__, "your message here");
}</pre>
```

We suggest using NCBI_REPORT_EXCEPTION(title,e) macro (which is equivalent to calling e.Report(__FILE__,__LINE__,title)) - it redirects the output into standard diagnostic channels and is highly configurable.

The CErrnoTemplException Class

The CErrnoTemplException class is a template class used for generating error exception classes:

```
/// CErrnoTemplException --
/// Define template class for easy generation of Errno-like exception
template < class TBase > class CErrnoTemplException :
public CErrnoTemplExceptionEx<TBase, CStrErrAdapt::strerror>
public:
/// Parent class type.
typedef CErrnoTemplExceptionEx<TBase, CStrErrAdapt::strerror> CParent;
 /// Constructor.
 CErrnoTemplException<TBase>(const char* file,int line,
 const CException* prev exception,
 typename CParent::EErrCode err code,const string& message) throw()
 : CParent(file, line, prev_exception,
 (typename CParent::EErrCode) CException::eInvalid, message)
NCBI EXCEPTION DEFAULT IMPLEMENTATION TEMPL(CErrnoTemplException<TBase>,
CParent)
};
```

The template class is derived form another template class, the ErrnoTemplExceptionEx which implements a parent class with the template parameter TBase. The parent ErrnoTemplExceptionEx class implements the basic exception methods such as ReportExtra (), GetErrCode(), GetErrno(), GetType(). The ErrnoTemplExceptionEx class has an int data member called m_Errno. The constructor automatically adds information about the most recent error state as obtained via the global system variable errno to this data member.

The constructor for the derived CErrnoTemplException class is defined in terms of the NCBI_EXCEPTION_DEFAULT_IMPLEMENTATION_TEMPL macro which defines the program code for implementing the constructor.

The TBase template parameter is an exception base class such as CException or CCoreException, or another class similar to these. The CStrErrAdapt::strerror template parameter is a function defined in an adaptor class for getting the error description string. The CErrnoTemplException has only one error core - eErrno defined in the parent class, ErrnoTemplExceptionEx. To analyze the actual reason of the exception one should use GetErrno() method:

```
int GetErrno(void) const;
```

The CErrnoTemplException is used to create exception classes. Here is an example of how the CExecException class is created from CErrnoTemplException. In this example, the TBase template parameter is the exception base class CCoreException:

```
///
/// CExecException --
///
/// Define exceptions generated by CExec.
/// CExecException inherits its basic functionality from
/// CErrnoTemplException<CCoreException> and defines additional error codes
/// for errors generated by CExec.
class NCBI_XNCBI_EXPORT CExecException :
public CErrnoTemplException<CCoreException>
public:
 /// Error types that CExec can generate.
 enum EErrCode {
eSystem, ///< System error
 eSpawn ///< Spawn error
 };
 /// Translate from the error code value to its string representation.
 virtual const char* GetErrCodeString(void) const
 switch (GetErrCode()) {
 case eSystem: return "eSystem";
 case eSpawn: return "eSpawn";
 default: return CException::GetErrCodeString();
```

```
}

// Standard exception boilerplate code.
NCBI_EXCEPTION_DEFAULT(CExecException,
CErrnoTemplException<CCoreException>);
};
```

The CParseException Class

The CParseTemplException is a template class whose parent class is the template parameter TBase. The CParseTemplException class includes an additional int data member, called m_Pos. This class was specifically defined to support complex parsing tasks, and its constructor requires that positional information be supplied along with the description message. This makes it impossible to use the standard NCBI_THROW macro to throw it, so we defined two additional macros:

```
/// Throw exception with extra parameter.
///
/// Required to throw exceptions with one additional parameter
/// (e.g. positional information for CParseException).
#define NCBI_THROW2(exception_class, err_code, message, extra) \
    throw exception_class(__FILE__, __LINE__, \
    0,exception_class::err_code, (message), (extra))

/// Re-throw exception with extra parameter.
///
/// Required to re-throw exceptions with one additional parameter
/// (e.g. positional information for CParseException).
#define NCBI_RETHROW2(prev_exception, exception_class, err_code, message, extra) \
    throw exception_class(__FILE__, __LINE__, \
    &(prev exception), exception class::err code, (message), (extra))
```

Macros for Standard C++ Exception Handling

The C++ throw() statement provides a mechanism for specifying the types of exceptions that may be thrown by a function. Functions that do **not** include a throw() statement in their declaration can throw any type of exception, but where the throw() statement **is** used, undeclared exception types that are thrown will cause std::unexpected() to be raised. Various compilers handle these events differently, and the first two macros listed in Table 5, (THROWS (()), THROWS_NONE, are provided to support platform-independent exception specifications.

The catch macros provide uniform, routine exception handling with minimal effort from the programmer. We provide convenient STD_CATCH_*() macros to print formatted messages to the application's diagnostic stream. For example, if F() throws an exception of the form:

```
throw std::runtime_error(throw-msg)
then
try {F();}
STD CATCH X(1, catch-msg); // here 1 is the error subcode
```

will generate a message of the form:

```
Error: (101.1) [catch-msg] Exception: throw-msg
```

In this output, the (101.1) indicates the error code (defined in the module's error_codes.hpp header) and the subcode passed to STD_CATCH_X.

In this example, the generated message starts with the Error tag, as that is the severity level for the default diagnostic stream. User-defined classes that are derived from std::exception will be treated uniformly in the same manner. The throw clause in this case creates a new instance of std::runtime_error whose data member desc is initialized to throw-msg. When the exception is then caught, the exception's member function what() can be used to retrieve that message.

The STD_CATCH_ALL_X macro catches all exceptions. If however, the exception caught is **not** derived from std::exception, then the catch clause cannot assume that what() has been defined for this object, and a default message is generated of the form:

```
Error: (101.1) [catch-msg] Exception: Unknown exception
```

Again, the (101.1) indicates the error code (defined in the module's error_codes.hpp header) and the subcode passed to STD_CATCH_ALL_X.

Exception Tracing

Knowing exactly where an exception first occurs can be very useful for debugging purposes. <u>CException</u> class has this functionality built in, so it is highly recommended to use exceptions derived from it. In addition to this a set of THROW*_TRACE() macros defined in the NCBI C++ Toolkit combine exception handling with trace mechanisms to provide such information.

The most commonly used of these macros, THROW1_TRACE(class_name, init_arg), instantiates an exception object of type class_name using init_arg to initialize it. The definition of this macro is:

```
/// Throw trace.
///
/// Combines diagnostic message trace and exception throwing. First the
/// diagnostic message is printed, and then exception is thrown.
///
/// Arguments can be any exception class with the specified initialization
/// argument. The class argument need not be derived from std::exception as
/// a new class object is constructed using the specified class name and
/// initialization argument.
///
/// Example:
/// - THROW1_TRACE(runtime_error, "Something is weird...");
# define THROW1_TRACE(exception_class, exception_arg) \
throw NCBI_NS_NCBI::DbgPrint(DIAG_COMPILE_INFO, \
exception class(exception arg), #exception class)
```

From the throw() statement here, we see that the object actually being thrown by this macro is the value returned by DbgPrint(). DbgPrint() in turn calls DoDbgPrint(). The latter is an overloaded function that simply creates a diagnostic stream and writes the file name, line

number, and the exception's what() message to that stream. The exception object (which is of type class name) is then the value returned by DbgPrint().

More generally, three sets of THROW* TRACE macros are defined:

- THROW0 TRACE(exception object)
- THROW0p_TRACE(exception_object)
- THROW0np TRACE(exception object)
- THROW1_TRACE(exception_class, exception_arg)
- THROW1p_TRACE(exception_class, exception_arg)
- THROW1np TRACE(exception class, exception arg)
- THROW TRACE(exception class, exception args)
- THROWp TRACE(exception class, exception args)
- THROWnp_TRACE(exception_class, exception_args)

The first three macros (THROW0*_TRACE) take a single argument, which may be a newly constructed exception, as in:

```
THROW0 TRACE(runtime error("message"))
```

or simply a printable object to be thrown, as in:

```
THROWO TRACE("print this message")
```

The THROW0_TRACE macro accepts either an exception object or a string as the argument to be thrown. The THROW0p_TRACE macro generalizes this functionality by accepting any printable object, such as complex(1,3), as its single argument. Any object with a defined output operator is, of course, printable. The third macro generalizes this one step further, and accepts aggregate arguments such as vector<T>, where T is a printable object. Note that in cases where the object to be thrown is not a std::exception, you will need to use STD_CATCH_ALL_{X|XX} or a customized catch statement to catch the thrown object.

The remaining six macros accept two arguments: an "exception" class name and an initialization argument, where both arguments are also passed to the trace message. The class argument need not actually be derived from std::exception, as the pre-processor simply uses the class name to construct a new object of that type using the initialization argument. All of the THROW1*_TRACE macros assume that there is a single initialization argument. As in the first three macros, THROW1_TRACE(), THROW1p_TRACE() and THROW1np_TRACE() specialize in different types of printable objects, ranging from exceptions and numeric and character types, to aggregate and container types.

The last three macros parallel the previous two sets of macros in their specializations, and may be applied where the exception object's constructor takes multiple arguments. (See also the discussion on Exception handling).

It is also possible to specify that execution should abort immediately when an exception occurs. By default, this feature is not activated, but the SetThrowTraceAbort() function can be used to activate it. Alternatively, you can turn it on for the entire application by setting either the \$ABORT_ON_THROW environment variable, or the application's registry ABORT_ON_THROW entry (in the [DEBUG] section) to an arbitrary non-empty value.

Table 1. Command line parameters available for use to any program that uses CNcbiApplication

| Flag | Description | Example |
|-----------|---|-----------------------------|
| -h | Print description of the application's command line parameters. | theapp -h |
| -logfile | Redirect program's log into the specified file | theapp -logfile theapp_log |
| -conffile | Read the program's configuration data from the specified file | theapp -conffile theapp_cfg |

Table 2. Enabling Tracing

| C++ toolkit API | Configuration file | Environment |
|--|--------------------|---|
| call: SetDiagTrace(eDT_Enable); define DIAG_TRACE entry in the DEBUG section. [DEBUG] DIAG_TRACE=1 | | define DIAG_TRACE environment variable: set DIAG_TRACE=1 |

Table 3. Changing severity level for diagnostic messages

| C++ toolkit API | Configuration file | Environment |
|--|---|---|
| call: SetDiagPostLevel(EDiagSev postSev); Valid arguments are eDiag_Info, eDiag_Warning, eDiag_Error, eDiag_Critical, eDiag_Fatal. | define DIAG_POST_LEVEL entry in the DEBUG section: [DEBUG] DIAG_POST_LEVEL=Info Valid values are Info, Warning, Error, Critical, Fatal. | define DIAG_POST_LEVEL environment variable: set DIAG_POST_LEVEL=Info Valid values are Info, Warning, Error, Critical, Fatal. |

Table 4. Setting up trace options for connection library

| | Configuration file | Environment |
|------------------------|---|---|
| Connection parameters: | define DEBUG_PRINTOUT entry in the CONN section: [CONN] DEBUG_PRINTOUT=TRUE Valid values are TRUE, or YES, or SOME. | define CONN_DEBUG_PRINTOUT environment variable: set CONN_DEBUG_PRINTOUT=TRUE Valid values are TRUE, or YES, or SOME. |
| All data: | define DEBUG_PRINTOUT entry in the CONN section: [CONN] DEBUG_PRINTOUT=ALL Valid values are ALL, or DATA. | define CONN_DEBUG_PRINTOUT environment variable: set CONN_DEBUG_PRINTOUT=ALL Valid values are ALL, or DATA. |

Table 5. Platform Independent Exception Macros

| Macro | C++ Equivalent | Synopsis |
|--|-----------------------|--|
| THROWS((types)) | throw(types) | Defines the type of exceptions thrown by the given function. types may be a single object type or a comma delimited list. |
| THROWS_NONE | throw() | Specifies that the given function throws no exceptions. |
| STD_CATCH_X(subcode, message) | catch(std::exception) | Calls STD_CATCH_XX() using the currently selected error code name. |
| STD_CATCH_XX(name, subcode, message) | catch(std::exception) | Provides uniform handling of all exceptions derived from std::exception using the given error code name, subcode, and message. Does not catch exceptions <i>not</i> derived from std::exception. |
| STD_CATCH_ALL_X(subcode, message) | catch() | Calls STD_CATCH_ALL_XX() using the currently selected error code name. |
| STD_CATCH_ALL_XX(name, subcode, message) | catch() | Applies STD_CATCH_XX() to std::exception derived objects. Catches non-standard exceptions and generates an "Unknown exception" message using the given error code name, subcode, and message. |