MA2252 Introduction to Computing Lecture 9 Representation of Numbers

Sharad Kumar Keshari

School of Computing and Mathematical Sciences
University of Leicester

Learning outcomes

At the end of lecture, students will be able to understand

- Base-N numbers
- Binary numbers
- Floating Point Numbers

Motivation

Sometimes, MATLAB gives unexpected outputs. Consider these examples:

- $\exp(i*pi)+1==0$
- sin(pi), cos(pi/2)
- 5+8e-17>5
- \bullet 1 3*(4/3 1)
- 2⁻¹⁰⁷³==0. 2⁻¹⁰⁷⁵==0
- \bullet sqrt(1e-16 + 1) 1

The goal of this lecture is to understand the reason behind these strange results.

Base-N numbers

Base: Number of unique digits to represent a number.

Example:

Decimal number (Base-10 number)

- ① Uses digits from 0 to 9. So, base is 10.
- 2 Decimal number can be expanded in powers of 10.

Examples:

$$582 = 5 \times 10^2 + 8 \times 10 + 2 \times 10^0,$$

$$25.36 = 2 \times 10^{1} + 5 \times 10^{0} + 3 \times 10^{-1} + 6 \times 10^{-2}$$
.

Base-N numbers (contd.)

Other examples:

- Binary number: Uses only two digits: 0 and 1.
- Octal number: Uses digits from 0 to 7.
- Hexadecimal number: Uses 16 digits: 0-9 followed by A-F or a-f.

Binary numbers

- Binary numbers are represented by only 0s and 1s. So, the base is 2.
- A digit in binary number is called a bit.
- Example: The number 1001000110.

This number can be converted to a decimal number as follows:

$$1x2^9 + 0x2^8 + 0x2^7 + 1x2^6 + 0x2^5 + 0x2^4 + 0x2^3 + 1x2^2 + 1x2^1 + 0x2^0 = 582$$

Binary numbers (contd.)

Pros

- Easier for a computer to store and work with.
- A computer can do all arithmetic operations with them.
- A 32-bit computer can represent upto 2²³ binary numbers.

Binary numbers (contd.)

Cons

- Harder for humans to do binary algebra.
- Limited range and precision to perform all mathematical calculations.

Floating Point Numbers

MATLAB uses **floating point** numbers or **floats** to achieve the desired range and precision required to perform mathematical calculations.

Note: Floating point numbers are always **rational**. MATLAB approximates irrational numbers (e.g. π) by rational numbers.

Types of float:

- single precision (32 bits)
- double precision (64 bits)

Single precision float

In the IEEE754 standard for single precision, a float which is represented as

$$n = -1^s 2^{e-127} (1+f)$$

Here, s, e and f are sign indicator, exponent and fraction respectively.

32 bits are allocated as follows:

- s has 1 bit so it takes values of 0 or 1.
- e has 8 bits so it can take 2⁸ values.
- f has 23 bits so it can take 2^{23} values. $0 \le f < 1$.

Example:

Convert the number

1 10000011 110000000000000000000 (IEEE754)

into decimal (base 10) number.

Solution:

$$\begin{split} s &= 1, \\ e &= 1 \times 2^7 + 0 + 0 + 0 + 0 + 0 + 0 + 1 \times 2^1 + 1 \times 2^0 = 131, \\ f &= 1 \times 2^{-1} + 1 \times 2^{-2} + \dots = 0.75. \end{split}$$

$$n = -1^{1}2^{131-127}(1+0.75) = -2^{4} \times 1.75 = -28.$$

Gaps between numbers

Not every decimal (base 10) number can be represented by double precision float. This causes gaps between numbers in MATLAB.

To find the gap, use MATLAB's eps function. eps(x) gives the gap between number x and next representable number.

Example:

eps(5)=8.881784197001252e-16.

The gap increases as numbers get large because the factor 2^{e-127} grows in size.

Special cases

• e=0 (00000000(base 2))
In this case, the float is calculated using

$$n = -1^s 2^{-126} f$$

- 2 e=255 (11111111(base 2))
 - $f \neq 0$: n=NaN (Not a Number)
 - f=0 and s=0: n=Inf
 - f=0 and s=1: n=-Inf

Single precision float interesting facts

Note: Use MATLAB functions realmax('single') and realmin('single') to find the above results

 $\mbox{\bf Note:}\ \mbox{\bf Use}\ \mbox{\bf MATLAB}\ \mbox{\bf single}()\ \mbox{\bf function to represent a number in single}\ \mbox{\bf precision.}$

Double precision float

MATLAB uses default double precision of **IEEE754** standard. A double precision is represented as

$$n = -1^s 2^{e-1023} (1+f)$$

Again, s, e and f are sign indicator, exponent and fraction respectively.

64 bits are allocated as follows:

- s has 1 bit so it takes values of 0 or 1.
- e has 11 bits so it can take 2¹¹ values.
- f has 52 bits so it can take 2^{52} values. $0 \le f < 1$.



The special cases for double precision float are similar to single-precision float.

Double precision float interesting facts

- Largest defined number
 1.797693134862316e+308 (type realmax in command window)
- Smallest defined positive 'normal' number
 2.225073858507201e-308 (type realmin in command window)
- Smallest defined subnormal number 4.940656458412465e-324 (2^-1074)

Activity

Typing 1e309 in the command window gives the output

- **1.0000e+309**
- Inf
- NaN
- Some error

To answer, please go to mentimeter link in the chat.

Overflow and Underflow

- Any number larger than the largest defined floating point number causes overflow. MATLAB assigns the result to Inf.
- Any number smaller than the smallest defined floating point number causes underflow. MATLAB assigns the result to 0.

End of Lecture 9

Please provide your feedback • here